COMP30040 - Assignment 2

Wireshark (Packet Analysis) and IP Address Configuration

Question 1

The following commands can be used to examine the IP configuration:

- ifconfig: configure or display statistics on a network interface, such as the IP address, netmask and MAC address
- route: show the IP routing table (with -n: show numerical addresses instead of host names), which is used to figure out a path to the destination network of a packet or to a gateway in the network, which will figure it out

```
[kimberley@promethei ~]$ ifconfig wlan0
wlan0: flags=4163<UP, BROADCAST, RUNNING, MULTICAST> mtu 1500
inet 137.43.68.127 netmask 255.255.255.0 broadcast 137.43.68.255
inet6 fe80::2b9:a5ff:fed2:cfbb prefixlen 64 scopeid 0x20<link>
ether e0:b9:a5:d2:cf:bb txqueuelen 1000
                                         (Ethernet)
RX packets 11769 bytes 5844746 (5.5 MiB)
RX errors 0 dropped 0 overruns 0 frame 0
TX packets 8188 bytes 1260157 (1.2 MiB)
TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
[kimberley@promethei ~]$ route -n
Kernel IP routing table
Destination
               Gateway
                               Genmask
                                               Flags Metric Ref
0.0.0.0
               137.43.68.1
                               0.0.0.0
                                               UG
                                                     0
                               255.255.255.0
137.43.68.0
               0.0.0.0
                                             IJ
                                                     0
                                                           0
```

Use I

0 w

0 w

From this we can tell the following:

• IP address: 137.43.68.127

• netmask: 255.255.255.0

• gateway: 137.43.68.1

• MAC address: e0:b9:a5:d2:cf:bb

Interestingly enough these two commands - and a related one, arp, which relates MAC addresses to IP addresses - state that they are obsolete in their respective man pages. Alright. Let's try the suggested replacement, ip:

```
[kimberley@promethei ~]$ ip
Usage: ip [ OPTIONS ] OBJECT COMMAND | help
        ip [ -force ] -batch filename
where OBJECT := link | addr | addrlabel | route | rule | neigh | ntable
```

```
tunnel | tuntap | maddr | mroute | mrule | monitor | x
netns | 12tp

OPTIONS := -V[ersion] | -s[tatistics] | -d[etails] | -r[esolve] |
-f[amily] inet | inet6 | ipx | dnet | link |
-l[oops] maximum-addr-flush-attempts |
-o[neline] | -t[imestamp] | -b[atch] [filename] |
-rc[vbuf] [size]
```

With -s, it will display different statistics depending on the objects specified. The relevant ones are addr, which gives similar information to ifconfig, and route, which unsurprisingly gives similar information to route.

```
[kimberley@promethei ~]$ ip -s addr
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 16436 qdisc noqueue state UNKNOWN
    link/loopback 00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
    inet6 ::1/128 scope host
        valid_lft forever preferred_lft forever
2: wlan0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP ql
    link/ether e0:b9:a5:d2:cf:bb brd ff:ff:ff:ff
    inet 137.43.68.127/24 brd 137.43.68.255 scope global wlan0
    inet6 fe80::e2b9:a5ff:fed2:cfbb/64 scope link
        valid_lft forever preferred_lft forever
```

Note: instead of specifying the netmask in dotted decimal notation, it is given in something called CIDR notation. The number after the slash in 137.43.68.127/24 is the number of bits allocated to the network prefix (the part of the IP address which specifies the network), with the remaining bits identifying the specific host on the network. /24 is equivalent to the subnet mask 255.255.25.0.

```
[kimberley@promethei ~]$ ip -s route
default via 137.43.68.1 dev wlan0 proto static
137.43.68.0/24 dev wlan0 proto kernel scope link src 137.43.68.127
```

Once again we can see that the default gateway is 137.43.68.1.

Question 2

After editing /etc/network/interfaces:

Before reconfiguration, my Ubuntu VM's IP address is 10.0.2.15 (assignment 1).

```
root@tempe:/home/kimberley# cat /etc/network/interfaces
auto lo
iface lo inet loopback
auto eth0
iface eth0 inet static
address 10.0.2.14
netmask 255.255.255.0
gateway 10.0.2.2
dns-nameservers 137.43.116.19
Switch to static network configuration:
root@tempe:/home/kimberley# service network-manager stop
network-manager stop/waiting
root@tempe:/home/kimberley# ifdown eth0
root@tempe:/home/kimberley# ifup eth0
Test connectivity:
root@tempe:/home/kimberley# ping google.com -q -c5
PING google.com (74.125.24.101) 56(84) bytes of data.
--- google.com ping statistics ---
5 packets transmitted, 0 received, 100% packet loss, time 4033ms
root@tempe:/home/kimberley# telnet google.com 80
Trying 74.125.24.139...
```

```
telnet> quit
```

^]

Connection closed.

Connected to google.com. Escape character is '^]'.

```
root@tempe:/home/kimberley# ping 137.43.68.127 -q -c5 PING 137.43.68.127 (137.43.68.127) 56(84) bytes of data.
```

```
--- 137.43.68.127 ping statistics --- 5 packets transmitted, 5 received, 0% packet loss, time 3999ms rtt min/avg/max/mdev = 0.178/0.480/1.282/0.407 ms
```

I have no idea why it won't let me ping google - but I can connect to my host machine as well as telnet to google.com, so I clearly still have a connection to the outside world and DNS is working.


Question 3

Address Resolution Protocol (ARP) is used to map MAC addresses (of physical hardware) to IP addresses.

Generate ARP packages by pinging another host on the network (machine with IP address 137.43.68.123). First confirm that there is no ARP entry for that IP address, meaning an ARP request will have to be sent.

[kimberley@promethei ~]\$ sudo arp -d 137.43.68.123 No ARP entry for 137.43.68.123

Start capturing ARP packages on wlan0 using Wireshark:




Now begin pinging the destination IP:

```
[kimberley@promethei ~]$ ping 137.43.68.123 -q -c5 PING 137.43.68.123 (137.43.68.123) 56(84) bytes of data.
```

```
--- 137.43.68.123 ping statistics --- 5 packets transmitted, 4 received, 20% packet loss, time 4004ms rtt min/avg/max/mdev = 2.443/12.598/41.103/16.462 ms
```

In Wireshark, filter out all but ARP packages:



You can also see the 5 pings and responses between the source machine (137.43.68.127) and the destination machine (137.43.68.123). Note that the destination is on the same network as the source, because it makes no sense to have ARP table entries for machines on a different network.

