

# Lease Cancellation Charges

## 1. Overview / Objective

The purpose of this document is to define the rules, system behavior, and financial treatment of **Lease Cancellation Fees** in BAT Connect.

A Cancellation Fee is a charge applied when a lease is **terminated early by BAT or the driver before the agreed lease end date**. This fee represents compensation for breaking the contract before completion.

This document does **not** cover:

- Natural lease expiry (end-of-term or completion of planned segments)
- Cancelled leases that never became Active (pre-activation cancellation)
- Automatic renewals or mid-cycle lease extensions

---

## 2. Scope

Included	Excluded
Leases that are in <b>Active</b> or <b>Suspended</b> status and terminated early	Leases in <b>In Progress</b> or <b>Cancelled (pre-activation)</b>
All Lease Types: DOV, Long-Term, Medallion-Only, True Weekly, etc.	Natural expiry / scheduled completion
Cancellation fee definition, validation, editing, and ledger posting	Deposit settlement, DTR generation, and refund rules (covered separately)

---

## 3. Key Business Rules – Lease Cancellation Fee

Rule	Description
------	-------------

<b>3.1 Fee Setup at Lease Creation</b>	A cancellation fee amount is recorded as part of the lease terms when the lease is created. No payment is taken at this stage.
<b>3.2 Fee Applicability</b>	The fee is only charged if the lease is terminated early (Lease Status = Active or Suspended). No fee applies if the lease expires naturally or is cancelled before activation.
<b>3.3 Default &amp; Editable on Termination</b>	At the time of termination confirmation, the system defaults the cancellation fee to the recorded amount but allows staff to edit it (e.g., based on negotiation or management decision).
<b>3.4 Ledger Posting Timing</b>	Once the termination is confirmed, the final cancellation fee is <b>immediately posted to the Ledger</b> . It is <b>not delayed</b> until deposit release or next DTR.
<b>3.5 Ledger Accounting Treatment</b>	The fee is recorded as income for BAT (e.g., “Cancellation Fee Revenue” ledger account). If deposit balance exists, fee is deducted against deposit balance first (if applicable).
<b>3.6 No Charge = No Posting</b>	If the final cancellation fee is set to 0, no financial posting is created.
<b>3.7 Audit &amp; Traceability</b>	Any fee change from the originally recorded amount must be logged with user, timestamp, and comments for audit purposes.
<b>3.8 Interaction with Deposit Hold</b>	Cancellation fee is <b>separate from the 30-day deposit hold logic</b> . Deposits are held for delayed charges; cancellation fees are charged immediately at termination.

## 4. Workflow & System Behavior – Cancellation Fee

### 4.1 Where It Appears in the Lease Termination Flow

Step	System Behavior
<b>Initiate Termination</b>	User selects <b>Terminate Lease</b> from Manage Leases (only available if lease is Active or Suspended).
<b>Pre-checks completed (Repairs/Loans posting)</b>	System ensures all Repair and Driver Loan installments are posted.
<b>Termination Details Screen</b>	The system displays a “ <b>Cancellation Fee</b> ” field with the amount recorded at lease creation (default value).
<b>User Interaction</b>	<ul style="list-style-type: none"> <li>• Field is editable.</li> <li>• User can adjust the amount (e.g., waive, reduce, or increase based on negotiation).</li> <li>• User can optionally add a note if modified.</li> </ul>
<b>Confirm Termination</b>	<p>On clicking Confirm:</p> <ul style="list-style-type: none"> <li>✓ Lease status → Terminated</li> <li>✓ Vehicle &amp; Medallion → Available for Lease</li> <li>✓ Deposit Hold is created (separate logic)</li> <li><b>✓ Cancellation Fee is immediately posted to the Ledger.</b></li> </ul>

### 4.2 System Actions When Confirmation Happens

System Action	Description
<b>Ledger Posting</b>	<p>A financial transaction is created in <b>Ledger_Postings</b> with:</p> <ul style="list-style-type: none"> <li>• Posting Type: Cancellation Fee</li> <li>• Amount = final fee value</li> <li>• Timestamp = Termination Confirmation Time</li> <li>• Linked to Lease ID &amp; Driver ID</li> </ul>
<b>Deposit Interaction (if applicable)</b>	If deposit exists, system may apply fee using deposit balance in Ledger (deducting from

	deposit credit).
<b>Lease History Logging</b>	System records: user, timestamp, original fee, final fee, and reason/comments.
<b>Visibility</b>	The fee is visible in: <ul style="list-style-type: none"> <li>• Lease Financial Summary</li> <li>• Driver Ledger Statement</li> <li>• DTR (if included as part of balance adjustment)</li> </ul>
<b>Audit Trail</b>	Any changes to fee amount are logged for compliance.

#### 4.3 User Interface – Minimum Fields Required

Field	Default Value	Editable?
Cancellation Fee	Pulled from Lease Creation data	<input checked="" type="checkbox"/> Yes
Final Fee Amount	Same as default	<input checked="" type="checkbox"/> Yes
Notes / Comments	Empty	Optional (required if fee changed)

---

#### 5. Ledger Posting Logic – Cancellation Fee

##### 5.1 When is the Fee Posted?

- The **cancellation fee is posted immediately** when the user confirms termination.
- It is **not delayed to DTR generation and not part of the deposit 30-day hold logic.**

##### 5.2 Ledger Posting Details

Field	Description
<b>Posting Trigger</b>	Lease termination confirmation
<b>Posting Table</b>	Ledger_Postings
<b>Posting Type / Category</b>	Cancellation Fee

<b>Debit Account</b>	Driver Ledger Balance (Amount owed by driver)
<b>Credit Account</b>	BAT Revenue → “Cancellation Fee Income” (or equivalent GL account)
<b>Posting Date</b>	Termination Confirmation Date
<b>Reference Fields</b>	Lease ID, Driver ID, Vehicle ID, Termination ID (if applicable)
<b>Amount</b>	Final cancellation fee value entered by the user
<b>Notes / Narration</b>	“Cancellation Fee for Lease [Lease ID] – Early Termination”

### 5.3 Interaction with Deposit

Scenario	System Behavior
Deposit exists and fee $\leq$ deposit amount	Fee is deducted from deposit balance (internal ledger offset).
Deposit exists but fee $>$ deposit	Deposit is used first; remaining balance posted as payable by the driver.
No deposit available	Entire fee amount is posted as a payable balance in driver ledger.
No fee (final amount = 0)	No ledger posting created.

### 5.4 Impact on Driver Trip Report (DTR)

- Cancellation Fee will **appear as an immediate charge** if the termination occurs before the next DTR.
- If termination is already confirmed, the DTR reflects an **adjusted balance (carry-forward)** rather than computing this fee separately.
- It is **not calculated as part of trip-based earnings** — it is a direct ledger transaction.

### 5.5 Audit & Traceability

Requirement	Behavior

Fee Modification Tracking	Original fee (from lease creation) vs. Final fee is stored.
Change Logging	System logs User, Timestamp, Reason/Comments for edits.
Financial Transparency	Posting is visible in Driver Ledger, Lease Financial Summary & Admin Reports.

## 6. Fields & Data Capture – Cancellation Fee

Field Name	Description / Purpose	When Captured	Editable?	Stored In
<b>Cancellation Fee (Base Value)</b>	Fee amount agreed at lease creation; used as default during termination.	Lease Creation	No	Lease Master Record
<b>Final Cancellation Fee</b>	Actual fee charged at termination. Defaults to base value, but editable.	Lease Termination (Confirmation screen)	<input checked="" type="checkbox"/> Yes	Lease Termination Record & Ledger Posting
<b>Fee Modified Flag</b>	Indicates if the fee was changed from the originally recorded value.	Auto-set on change	Auto	System Log / Audit
<b>Fee Modification Reason / Comments</b>	Notes to justify waiver/reduction/increase of fee.	Lease Termination (if fee edited)	Optional (Mandatory if fee ≠ base value)	Lease Termination Log

<b>Ledger Posting ID</b>	Unique reference for the financial posting.	Auto on termination confirmation	No	Ledger_Postings
<b>Debit Account</b>	Driver ledger balance (money owed).	Auto	No	Ledger_Postings
<b>Credit Account</b>	Cancellation Fee Revenue / BAT Income account.	Auto	No	Ledger_Postings
<b>Posting Timestamp</b>	Date & time when the fee is officially charged.	Auto on termination confirmation	No	Ledger_Postings
<b>User / Staff Name</b>	Who confirmed the termination.	Auto	No	Lease History / Audit Trail
<b>Linked Lease ID</b>	Lease reference for tracking.	Auto	No	Ledger_Postings / Lease History
<b>Linked Driver ID</b>	Driver responsible for fee.	Auto	No	Ledger_Postings

#### 7. Assumptions & Notes (Table Format)

#	Assumption / Note
1	Cancellation fee is only <b>recorded at lease creation</b> , not collected or posted at that stage.
2	Fee applies <b>only when a lease in Active or Suspended status is terminated early</b> .
3	<b>No cancellation fee</b> is applied if the lease is cancelled before activation (In Progress / Cancelled status).
4	<b>Fee is posted to Ledger immediately</b> when termination is confirmed — not during DTR and not after the 30-day deposit hold.

5	The fee <b>defaults to the recorded amount</b> during termination but is <b>editable by staff</b> before confirmation.
6	<b>Cancellation fee and Deposit are treated separately</b> — deposits follow the 30-day hold; cancellation fee is charged instantly.
7	Any change to the fee amount must be <b>logged with user, timestamp, and comment (if modified)</b> for audit.
8	<b>Finance confirmation is required</b> to determine if the cancellation fee is taxable or needs a separate tax component.
9	If the final cancellation fee is set to <b>0</b> , system will <b>not create a ledger posting</b> .
10	The fee should be <b>visible in Driver Ledger, Lease Financial Summary, and Admin Reports.</b>

#### 8. Validations – Cancellation Fee

Validation ID	Validation Rule	Condition / Logic	System Behavior / Message
<b>Eligible Lease Status</b>	Cancellation fee can only be applied if the lease is eligible for termination	Lease.Status ∈ {Active, Suspended}	If not eligible → “ <i>Cancellation fee cannot be applied. Lease is not Active or Suspended.</i> ”
<b>Cancellation Fee Exists</b>	A cancellation fee value must exist from lease creation	Lease.CancellationFee Amount is not null	If null → prevent termination and show: “ <i>Cancellation fee not defined in lease terms.</i> ”
<b>Fee Amount Cannot Be Negative</b>	Final fee value cannot be less than zero	FinalCancellationFee ≥ 0	If < 0 → “ <i>Cancellation fee cannot be negative.</i> ”

<b>Fee Change Justification</b>	If final fee is modified from originally recorded value, user must provide a reason/comment	If FinalFee ≠ RecordedFee	System prompts for comment before allowing confirmation
<b>Pre-Termination Ledger Completion</b>	All Repair and Driver Loan installments must be posted before applying fee or terminating lease	Repairs.Posted = True AND Loans.Posted = True	If not → block termination until resolved
<b>Posting at Confirmation</b>	Cancellation fee must be posted immediately on confirmation	On Confirm Termination	Failure to post results in validation error and rollback of termination
<b>No Direct Deduction from Deposit at Posting</b>	Cancellation fee posting should not directly reduce deposit balance at time of posting	On posting of cancellation fee	Deposit remains in "Hold" until separate deposit settlement logic applies
<b>Prevent Duplicate Fee Posting</b>	Fee cannot be applied twice for the same lease	If Lease.Status = Terminated AND CancellationFeePosted = True	Hide fee field and prevent posting again
<b>Valid Termination Date</b>	Termination date must be valid and is required for fee posting	TerminationDate ≤ Today AND ≥ Lease.StartDate	Show error if invalid date is selected