
# **Main Memory Management**





# **Memory Management**

- Background
- Contiguous Memory Allocation
- Paging
- Structure of the Page Table
- Swapping





# **Objectives**

- To provide a detailed description of various ways of organizing memory hardware
- To discuss various memory-management techniques,





## **Background**


- Program must be brought (from disk) into memory and placed within a process for it to be run
- Main memory and registers are only storage CPU can access directly
- Memory unit only sees a stream of:
  - addresses + read requests, or
  - address + data and write requests
- Register access is done in one CPU clock (or less)
- Main memory can take many cycles, causing a stall
- Cache sits between main memory and CPU registers
- Protection of memory required to ensure correct operation





#### **Protection**

- Need to censure that a process can access only access those addresses in its address space.
- We can provide this protection by using a pair of base and limit registers define the logical address space of a process








#### **Hardware Address Protection**

 CPU must check every memory access generated in user mode to be sure it is between base and limit for that user



the instructions to loading the base and limit registers are privileged





## **Address Binding**

- Programs on disk, ready to be brought into memory to execute form an input queue
  - Without support, must be loaded into address 0000
- Inconvenient to have first user process physical address always at 0000
  - How can it not be?
- Addresses represented in different ways at different stages of a program's life
  - Source code addresses usually symbolic
  - Compiled code addresses bind to relocatable addresses
    - ▶ i.e., "14 bytes from beginning of this module"
  - Linker or loader will bind relocatable addresses to absolute addresses
    - i.e., 74014
  - Each binding maps one address space to another






# **Binding of Instructions and Data to Memory**

- Address binding of instructions and data to memory addresses can happen at three different stages
  - Compile time: If memory location known a priori, absolute code can be generated; must recompile code if starting location changes
  - Load time: Must generate relocatable code if memory location is not known at compile time
  - Execution time: Binding delayed until run time if the process can be moved during its execution from one memory segment to another
    - Need hardware support for address maps (e.g., base and limit registers)





## **Multistep Processing of a User Program**







# Logical vs. Physical Address Space


- The concept of a logical address space that is bound to a separate physical address space is central to proper memory management
  - Logical address generated by the CPU; also referred to as virtual address
  - Physical address address seen by the memory unit
- Logical and physical addresses are the same in compile-time and load-time address-binding schemes; logical (virtual) and physical addresses differ in execution-time address-binding scheme
- Logical address space is the set of all logical addresses generated by a program
- Physical address space is the set of all physical addresses generated by a program





# **Memory-Management Unit (MMU)**

Hardware device that at run time maps virtual to physical address



Many methods possible, covered in the rest of this chapter





# **Memory-Management Unit (Cont.)**


- Consider simple scheme. which is a generalization of the baseregister scheme.
- The base register now called relocation register
- The value in the relocation register is added to every address generated by a user process at the time it is sent to memory
- The user program deals with logical addresses; it never sees the real physical addresses
  - Execution-time binding occurs when reference is made to location in memory
  - Logical address bound to physical addresses





# **Memory-Management Unit (Cont.)**

- Consider simple scheme. which is a generalization of the baseregister scheme.
- The base register now called relocation register
- The value in the relocation register is added to every address generated by a user process at the time it is sent to memory







## **Dynamic Loading**

- The entire program does need to be in memory to execute
- Routine is not loaded until it is called
- Better memory-space utilization; unused routine is never loaded
- All routines kept on disk in relocatable load format
- Useful when large amounts of code are needed to handle infrequently occurring cases
- No special support from the operating system is required
  - Implemented through program design
  - OS can help by providing libraries to implement dynamic loading





## **Dynamic Linking**

- Static linking system libraries and program code combined by the loader into the binary program image
- Dynamic linking –linking postponed until execution time
- Small piece of code, stub, used to locate the appropriate memoryresident library routine
- Stub replaces itself with the address of the routine, and executes the routine
- Operating system checks if routine is in processes' memory address
  - If not in address space, add to address space
- Dynamic linking is particularly useful for libraries
- System also known as shared libraries
- Consider applicability to patching system libraries
  - Versioning may be needed





## **Contiguous Allocation**

- Main memory must support both OS and user processes
- Limited resource, must allocate efficiently
- Contiguous allocation is one early method
- Main memory usually split into two partitions:
  - Resident operating system, usually held in low memory with interrupt vector
  - User processes then held in high memory
  - Each process contained in single contiguous section of memory






# **Contiguous Allocation (Cont.)**

- Relocation registers used to protect user processes from each other, and from changing operating-system code and data
  - Base register contains value of smallest physical address
  - Limit register contains range of logical addresses each logical address must be less than the limit register
  - MMU maps logical address dynamically
  - Can then allow actions such as kernel code being transient and kernel changing size



# Hardware Support for Relocation and Limit Registers








#### **Variable Partition**

- Multiple-partition allocation
  - Degree of multiprogramming limited by number of partitions
  - Variable-partition sizes for efficiency (sized to a given process' needs)
  - Hole block of available memory; holes of various size are scattered throughout memory
  - When a process arrives, it is allocated memory from a hole large enough to accommodate it
  - Process exiting frees its partition, adjacent free partitions combined
  - Operating system maintains information about:
    a) allocated partitions
    b) free partitions (hole)







How to satisfy a request of size *n* from a list of free holes?

- First-fit: Allocate the first hole that is big enough
- Best-fit: Allocate the smallest hole that is big enough; must search entire list, unless ordered by size
  - Produces the smallest leftover hole
- Worst-fit: Allocate the *largest* hole; must also search entire list
  - Produces the largest leftover hole

First-fit and best-fit better than worst-fit in terms of speed and storage utilization





## **Fragmentation**

- External Fragmentation total memory space exists to satisfy a request, but it is not contiguous
- Internal Fragmentation allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used
- First fit analysis reveals that given N blocks allocated, 0.5 N blocks lost to fragmentation
  - 1/3 may be unusable -> 50-percent rule





# Fragmentation (Cont.)

- Reduce external fragmentation by compaction
  - Shuffle memory contents to place all free memory together in one large block
  - Compaction is possible only if relocation is dynamic, and is done at execution time
  - I/O problem
    - Latch job in memory while it is involved in I/O
    - Do I/O only into OS buffers
- Now consider that backing store has same fragmentation problems





# **Paging**

- Physical address space of a process can be noncontiguous; process is allocated physical memory whenever the latter is available
  - Avoids external fragmentation
  - Avoids problem of varying sized memory chunks
- Divide physical memory into fixed-sized blocks called frames
  - Size is power of 2, between 512 bytes and 16 Mbytes
- Divide logical memory into blocks of same size called pages
- Keep track of all free frames
- To run a program of size N pages, need to find N free frames and load program
- Set up a page table to translate logical to physical addresses
- Backing store likewise split into pages
- Still have Internal fragmentation





#### **Address Translation Scheme**

- Address generated by CPU is divided into:
  - Page number (p) used as an index into a page table which contains base address of each page in physical memory
  - Page offset (d) combined with base address to define the physical memory address that is sent to the memory unit


page number	page offset
p	d
m -n	n

For given logical address space 2<sup>m</sup> and page size 2<sup>n</sup>





# **Paging Hardware**







#### Paging Model of Logical and Physical Memory

page 0

page 1

page 2

page 3

logical memory


frame number 0 1 page 0 3 page 2 4 page 1 5 6 page 3 physical memory






## **Paging Example**

 Logical address: n = 2 and m = 4. Using a page size of 4 bytes and a physical memory of 32 bytes (8 pages)



0	5	
1	6	
2	1	
3	2	
page table		









#### Paging -- Calculating internal fragmentation

- Page size = 2,048 bytes
- Process size = 72,766 bytes
- 35 pages + 1,086 bytes
- Internal fragmentation of 2,048 1,086 = 962 bytes
- Worst case fragmentation = 1 frame 1 byte
- On average fragmentation = 1 / 2 frame size
- So small frame sizes desirable?
- But each page table entry takes memory to track
- Page sizes growing over time
  - Solaris supports two page sizes 8 KB and 4 MB





#### **Free Frames**



Before allocation

After allocation





## Implementation of Page Table

- Page table is kept in main memory
  - Page-table base register (PTBR) points to the page table
  - Page-table length register (PTLR) indicates size of the page table
- In this scheme every data/instruction access requires two memory accesses
  - One for the page table and one for the data / instruction
- The two-memory access problem can be solved by the use of a special fast-lookup hardware cache called translation look-aside buffers (TLBs) (also called associative memory).





#### **Translation Look-Aside Buffer**

- Some TLBs store address-space identifiers (ASIDs) in each TLB entry – uniquely identifies each process to provide addressspace protection for that process
  - Otherwise need to flush at every context switch
- TLBs typically small (64 to 1,024 entries)
- On a TLB miss, value is loaded into the TLB for faster access next time
  - Replacement policies must be considered
  - Some entries can be wired down for permanent fast access





#### **Hardware**

Associative memory – parallel search


Page #	Frame #

- Address translation (p, d)
  - If p is in associative register, get frame # out
  - Otherwise get frame # from page table in memory





## **Paging Hardware With TLB**







#### **Effective Access Time**

- Hit ratio percentage of times that a page number is found in the TLB
- An 80% hit ratio means that we find the desired page number in the TLB 80% of the time.
- Suppose that 10 nanoseconds to access memory.
  - If we find the desired page in TLB then a mapped-memory access take 10 ns
  - Otherwise we need two memory access so it is 20 ns
- Effective Access Time (EAT)

 $EAT = 0.80 \times 10 + 0.20 \times 20 = 12$  nanoseconds

implying 20% slowdown in access time

Consider amore realistic hit ratio of 99%,

$$EAT = 0.99 \times 10 + 0.01 \times 20 = 10.1 \text{ns}$$

implying only 1% slowdown in access time.






# **Memory Protection**


- Memory protection implemented by associating protection bit with each frame to indicate if read-only or read-write access is allowed
  - Can also add more bits to indicate page execute-only, and so on
- Valid-invalid bit attached to each entry in the page table:
  - "valid" indicates that the associated page is in the process' logical address space, and is thus a legal page
  - "invalid" indicates that the page is not in the process' logical address space
  - Or use page-table length register (PTLR)
- Any violations result in a trap to the kernel





#### Valid (v) or Invalid (i) Bit In A Page Table









### **Structure of the Page Table**


- Memory structures for paging can get huge using straight-forward methods
  - Consider a 32-bit logical address space as on modern computers
  - Page size of 4 KB (2<sup>12</sup>)
  - Page table would have 1 million entries (2<sup>32</sup> / 2<sup>12</sup>)
  - If each entry is 4 bytes → each process 4 MB of physical address space for the page table alone
    - Don't want to allocate that contiguously in main memory
  - One simple solution is to divide the page table into smaller units
    - Hierarchical Paging
    - Hashed Page Tables





#### **Hierarchical Page Tables**

- Break up the logical address space into multiple page tables
- A simple technique is a two-level page table
- We then page the page table







### **Two-Level Paging Example**

- A logical address (on 32-bit machine with 4K page size) is divided into:
  - a page number consisting of 20 bits
  - a page offset consisting of 12 bits
- Since the page table is paged, the page number is further divided into:
  - a 10-bit page number
  - a 10-bit page offset
- Thus, a logical address is as follows:


page number		page offset
$p_1$	$p_2$	d
10	10	12

- where  $p_1$  is an index into the outer page table, and  $p_2$  is the displacement within the page of the inner page table
- Known as forward-mapped page table





#### **Address-Translation Scheme**







## 64-bit Logical Address Space

- Even two-level paging scheme not sufficient
- If page size is 4 KB (2<sup>12</sup>)
  - Then page table has 2<sup>52</sup> entries
  - If two level scheme, inner page tables could be 2<sup>10</sup> 4-byte entries
  - Address would look like

outer page	inner page	offset
$p_1$	$p_2$	d
42	10	12

- Outer page table has 2<sup>42</sup> entries or 2<sup>44</sup> bytes
- One solution is to add a 2<sup>nd</sup> outer page table
- But in the following example the 2<sup>nd</sup> outer page table is still 2<sup>34</sup> bytes in size
  - And possibly 4 memory access to get to one physical memory location



# **Three-level Paging Scheme**

outer page	inner page	offset	
$p_1$	$p_2$	d	
42	10	12	

2nd outer page	outer page	inner page	offset
$p_1$	$p_2$	$p_3$	d
32	10	10	12






#### **Hashed Page Tables**

- Common in address spaces > 32 bits
- The virtual page number is hashed into a page table
  - This page table contains a chain of elements hashing to the same location
- Each element contains (1) the virtual page number (2) the value of the mapped page frame (3) a pointer to the next element
- Virtual page numbers are compared in this chain searching for a match
  - If a match is found, the corresponding physical frame is extracted
- Variation for 64-bit addresses is clustered page tables
  - Similar to hashed but each entry refers to several pages (such as 16) rather than 1
  - Especially useful for sparse address spaces (where memory references are non-contiguous and scattered)





### **Hashed Page Table**







#### **Swapping**

- A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution
  - Total physical memory space of processes can exceed physical memory
- Backing store fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images
- Roll out, roll in swapping variant used for priority-based scheduling algorithms; lower-priority process is swapped out so higher-priority process can be loaded and executed
- Major part of swap time is transfer time; total transfer time is directly proportional to the amount of memory swapped
- System maintains a ready queue of ready-to-run processes which have memory images on disk







# **Swapping (Cont.)**

- Does the swapped out process need to swap back in to same physical addresses?
- Depends on address binding method
  - Plus consider pending I/O to / from process memory space
- Modified versions of swapping are found on many systems (i.e., UNIX, Linux, and Windows)
  - Swapping normally disabled
  - Started if more than threshold amount of memory allocated
  - Disabled again once memory demand reduced below threshold





#### **Schematic View of Swapping**



main memory





- If next processes to be put on CPU is not in memory, need to swap out a process and swap in target process
- Context switch time can then be very high
- 100MB process swapping to hard disk with transfer rate of 50MB/sec
  - Swap out time of 2000 ms
  - Plus swap in of same sized process
  - Total context switch swapping component time of 4000ms (4 seconds)
- Can reduce if reduce size of memory swapped by knowing how much memory really being used
  - System calls to inform OS of memory use via request memory() and release memory()






# **Context Switch Time and Swapping (Cont.)**

- Other constraints as well on swapping
  - Pending I/O can't swap out as I/O would occur to wrong process
  - Or always transfer I/O to kernel space, then to I/O device
    - Known as double buffering, adds overhead
- Standard swapping not used in modern operating systems
  - But modified version common
    - Swap only when free memory extremely low





#### **Swapping with Paging**

