## Strategy Studio: SpeedRouteExecutionHandler (Execution Handler)

SpeedRouteExecutionHandler is Strategy Studio's FIX4.2 interface to SpeedRoute's exchange gateway.

This execution handler may be selected by including the following line in the server's main configuration file:

## EXECUTION\_HANDLER\_MODE=SpeedRouteExecutionHandler

## Session Level Settings

Many of the session-level settings are specified in the file execution\_handler-conf/speed\_route.config. Notable settings include:

- > StartTime=HH:MM:SS
- > EndTime=HH:MM:SS
  - Required. Sets the window of time that the execution handler will attempt a connection.
     Connection will begin at StartTime, and end at EndTime. Times are in UTC.
- > SocketConnectHost=host
  - Required. Specifies the IP of the SpeedRoute server for this session. This must be an IP address, and not a domain name.
- > SocketConnectPort=port number
  - Required. Specifies the IP port of the SpeedRoute server for this session.
- > ReconnectInterval=seconds
  - Sets the wait period before a disconnected session attempts a reconnect.
- > TargetCompID=targetCompID
  - Required. Required. This will be provided by SpeedRoute.
- > SenderCompID=senderCompID
  - Required. This corresponds to a SpeedRoute account and will be provided by SpeedRoute.
- > SenderSubID=senderSubID
  - Required. This corresponds to a SpeedRoute account and will be provided by SpeedRoute.
- > StrategyStudioAccount=accountName
  - Required. Sets the Strategy Studio account that will be associated with this session. This
    value must be unique for each session.
- > LocateBroker=MPID
  - Required if selling short. This is the MPID of the broker to be used for locates of short-sold stocks.