Strategy Studio: NanexAdapter

The NanexAdapter currently supports both Nanex's historical equities data tape files for backtesting as well as their live equities feed for live simulation and production.

The following main server configuration file settings apply:

> BACKTEST_SOURCE= Nanex

Enables Nanex as the source for backtest server

PRIMARY_ADAPTER=Nanex

Enables Nanex as the source for live simulation or production server

> NANEX_DIR=path

Optional. Directory containing Nanex historical data tape files. Default is "./bin/nanex".

Historical data tape file names must conform to the naming convention specified by Nanex.

> NANEX_TRADES_ONLY=true/false

 Optional. Boolean flag indicating whether or not quotes are ignored. This directly corresponds to the Nanex API's NxCF_EXCLUDE_QUOTES and NxCF_EXCLUDE_QUOTES2 options. Default is "false".

NANEX_IGNORE_MMQUOTES=true/false

Optional. Boolean flag indicating whether or not market maker quotes are ignored. This
directly corresponds to the Nanex API's NxCF_EXCLUDE_QUOTES2 option. L2 events will be
sent to OnDepth, and if adapter is not ignoring these events, it will flag Depth as best
available quote feed type for Nasdaq. Default is "true".

> NANEX_CORE_PROCESS_NAME=name

 Optional. String specifying the Nanex process name servicing live connections. The adapter will fail to start if a process by this name is not running. Specifying an empty string bypasses this check. Default is "NxCoreAccess.exe".

> USE_SOURCE_TIME_AS_ADAPTER_TIME=true/false

 Optional. For the backtest reader, toggles whether to use the source time (NxCoreHeader.nxExgTimestamp) as the adapter/event time. Otherwise uses NxCoreSystem.nxTime collection time. Default is "false"