

Database Reference Manual

Proactive Risk Manager™
Release 9.0.2.0

17 September 2020



ACI Worldwide

Offices in principal cities throughout the world

www.aciworldwide.com

Americas +1 402 390 7600

Asia Pacific +65 6334 4843

Europe, Middle East, Africa +44 (0) 1923 816393

Publish Date: 17 September 2020

© Copyright ACI Worldwide, Inc. 2020

All information contained in this documentation, as well as the software described in it, is confidential and proprietary to ACI Worldwide, Inc., or one of its subsidiaries, is subject to a license agreement, and may be used or copied only in accordance with the terms of such license. Except as permitted by such license, no part of this documentation may be reproduced, stored in a retrieval system, or transmitted in any form or by electronic, mechanical, recording, or any other means, without the prior written permission of ACI Worldwide, Inc., or one of its subsidiaries.

ACI, ACI Worldwide, the ACI logo, ACI Universal Payments, UP, the UP logo and all ACI product/solution names are trademarks or registered trademarks of ACI Worldwide, Inc., or one of its subsidiaries, in the United States, other countries or both. Other parties' trademarks referenced are the property of their respective owners.

Contents

Contents.....	3
Section 1: Introduction.....	17
Section 2: What's new in this publication	18
Section 3: Root and Tenant Table List	29
Section 4: Analytic Gateway Process and Analysis/Review Tables.....	40
Overview	40
Data Modification	41
Primary Database Tables	41
Account_Master Table	42
Act Table	43
Action_Level Table	48
Alerts Table	53
Alerts_Tracking Table	59
Capability_Config Table	64
Master the RTR Master Tables.....	67
DASHB_AP_ACT Table	109
Detail Table	110
Employee_Master Table.....	173
FraudDetail Table.....	173
Merchant_Master Table	175
PRM_Heritage_Pass Table.....	176
PRM_Ref_Data Table	176
RT_Account_Master Table.....	177
RT_Card_Master Table.....	178
RT_Employee_Master Table	179
RT_Merchant_Master Table.....	179
RT_PRM_Install Table.....	180
RT_PRM_Install_Log Table.....	181
RT_PRM_Ref_Data Table	182

RT_Shortwindow Table	184
RT_Terminal_Master Table	185
RT_UAID_Master Table	186
RT_UAN_Master Table	187
ShortWindow Table	187
Std_Profile_Status Table	189
Terminal_Master Table	191
UAID_Master Table	192
UAN_Master Table	192
Analysis Tables	194
Alert_Category Table	194
APR_Mark_History Table	197
APR_Statistic Table	199
Category_History Table	201
DASHB_QST_ALERT_CATEGORY Table	202
Detail_Alerted_Rule Table	204
Detail_Flag Table	208
Forward Table	212
QueueHistory Table	214
Rules_OP_Events_KPI Table	216
RULES_OP_EVENTS_LOG Table	218
RvQuAISum Table	219
TEMP_APR_APR_INCBLK Table	221
TEMP_APR_APR_LOSS Table	222
TEMP_APR_APR_LOSSPREV Table	222
TEMP_APR_APR_LOSS_BLK Table	222
TEMP_APR_APR_MISSED Table	223
TEMP_APR_USERS_AL_AC_BK Table	223
TEMP_APR_USERS_BLK Table	223
TEMP_APR_USERS_INCBLK Table	224
TEMP_APR_USERS_LOSS Table	224
TEMP_APR_USERS_MARK Table	225
Rule/Queue System Tables	225
AutoActionsRule Table	226
Pending_Aggregates Table	229
Rqa Table	231
RQCategories Table	232

RQDisposition Table	233
RQOrder Table	234
RQPortAssign Table	235
RQVarDefAssign Table	237
RqVariables Table.....	239
RuleDefTemplateLink Table	240
RULEPERFMONITOR_DEF Table	241
RULEPERFMONITOR_LOG Table.....	242
RuleQueue Table	243
RuleSubTypes Table	249
RuleSubtypeTemplate Table	250
RuleTypes Table	250
Rule_Tester_Alerted Table	251
Rule_Tester_Dataset Table.....	253
Templates Table.....	256
Template_Types Table	257
Action/External Message Tables	258
ActionsText Table	259
ActionTypes Table	263
AddBlockCode_Action_Level Table.....	266
Auto_Action_Pending Table.....	267
CONTACT_STRATEGY Table	270
CONTACT_STRATEGY_ACTION_LEVEL Table.....	271
EMM_Status_Type Table	272
External_Message_Data Table.....	273
Security System Tables.....	281
Action_Level_User Table.....	281
FilterLayout Table.....	283
Locks Table.....	283
PasswordHistory Table.....	286
Portfolios Table	287
PRM_Filters Table.....	288
PRM_Keys Table.....	290
PRM_Tenants Table	291
PRM_Tenants_Config Table	295
PRM_Users Table	296
RT_Filterlayout Table.....	300

TeamPortfolioLinks Table	301
Teams Table	303
Trans_Category_Filter_Field Table	305
UserConfig Table.....	306
UserLockout Table.....	307
Dynamic Screen Tables.....	308
ActionTypes_Review_Screen Table	308
Cross_Action_Level Table.....	309
System Tables.....	310
Accnt_Routing Table.....	315
ACMAddInUsers Table	316
ActionTypes_Action_Level Table	317
ActionTypes_Action_Level_Emm Table.....	321
ActionTypes_Feature Table	322
ActionTypes_Permission Table.....	323
Action_Level_Alert_Order_List Table.....	323
Action_Level_Memo Table.....	325
Action_Level_Profile_Table Table.....	327
Action_Level_Record_Source Table.....	328
AddBlockCodes Table	329
AddResponseCodes Table	331
AddResponseCodes_Action_Level Table.....	331
AG_Composite_Field Table.....	332
AG_Comp_Fields_Selector Table	334
AG_Data_Sanitizer Table.....	335
AG_Field Table.....	335
AG_Field_Composition Table	337
AG_Field_Selection Table.....	337
AG_Field_Transformation Table	338
AG_KPI_DEF Table	339
AG_KPI_LOG Table.....	340
AG_KPI_SLA_Report_Result Table	342
AG_KPI_SLA_Report_Statistics Table	344
AG_NACHA_Batch_Statistics Table	346
AG_NACHA_File_Statistics Table.....	348
AG_Services Table.....	349
AG_Transformation_Param Table.....	351

Application_Data_Type Table	352
Assgnd_ActionsType_ActionLevel Table.....	353
AuthConfig Table.....	356
AutoText Table.....	356
Autotext_Action_Level Table	358
Auto_Add_In_Config Table	359
Auto_Add_In_Rule_Config Table	362
Batch_Statistics Table.....	363
Check_Index_Columns Table	364
Cleanup_Tables Table	366
Config Table	368
DASHB_AP_SYSAUD Table	370
DD_Routing Table	371
Detail_MarkSelection Table	372
DE_Filter_Fields Table	374
External_Connection_Map Table.....	375
External_Procedure Table	377
External_Procedure_Purpose Table.....	378
External_Procedure_Type Table.....	379
Extrcnct_Service Table.....	380
Feature Table.....	383
Field_Action_Level Table.....	384
Filter_Fields Table	385
Flags Table	386
Flags_Action_Level Table	388
Multi_Team_Access Table	389
Notification_Actions Table.....	390
Notification_Additional_Fields Table.....	392
Notification_NewTran_Filter Table	393
NOTIFICATION_REQUEST_ADDTL Table.....	393
NOTIFICATION_STATUS Table	395
Notification_Subscriptions Table	395
Notification_Types Table	396
NRT_Group_Link Table	397
PrinterAreas Table.....	398
PrinterPortfolios Table.....	398
Printers Table.....	399

PRMJNLPCfg Table	400
PRM_Batch Table	401
PRM_Batch_History Table	404
PRM_Batch_Job Table	406
PRM_Install Table.....	407
PRM_Install_Log Table	408
PRM_Permission Table.....	410
PRM_Permission_Grp Table.....	411
Profile_Alerted_Rule Table	412
Profile_To_RT_Batch Table.....	414
Queue_Link Table	416
Record_Source Table.....	416
Record_Source_Column_Mapping Table.....	418
Record_Source_Field Table	420
Record_Source_Mapping Table.....	422
Record_Source_Routing Table.....	424
RQAggregateTypes Table	425
RQ_Fields Table	426
RT_Group_Link Table	427
RuleAggregateLink Table	428
RuleDef Table	429
Service_Additional_Fields Table.....	430
Service_RQ_Filter Table.....	432
Settings Table	432
Shortwindow_Group Table	434
SystemAudit Table.....	436
SystemAuditSubTypes Table.....	438
SystemAuditTSec Table.....	439
SystemAuditTypes Table	440
SystemConfig Table.....	441
SystemFields Table.....	442
SystemSql Table.....	443
SystemTableMap Table	444
Task_Semaphore Table	444
TCR_Group Table	445
TCR_Run_Log Table	448
TCR_Statistic Table.....	449

TFL_Report_Last_DD_Date Table	450
Timer_Lock Table	451
Tips Table.....	452
TipTypes Table.....	453
Tip_Action_Level Table	454
Tip_PRMroles Table	455
Travel_Locations Table.....	456
Travel_Notifications Table	457
Travel_Notification_Countries Table	459
Travel_Notification_Method Table	460
Travel_Notification_Regions Table	461
Travel_Notification_Type Table	462
TRENDS_1_BIMONTHLY Table	462
TRENDS_1_MONTHLY Table	465
TRENDS_1_WEEKLY Table	468
TRENDS_2_BIMONTHLY Table	471
TRENDS_2_DAILY Table	475
TRENDS_2_WEEKLY Table	478
TRENDS_3_BIMONTHLY Table	481
TRENDS_3_MONTHLY Table	484
TRENDS_3_WEEKLY Table	486
TRENDS_4_BIMONTHLY Table	489
TRENDS_4_DAILY Table	492
TRENDS_4_WEEKLY Table	495
TRENDS_5_BIMONTHLY Table	498
TRENDS_5_MONTHLY Table	501
TRENDS_5_WEEKLY Table	504
TRENDS_6_BIMONTHLY Table	507
TRENDS_6_MONTHLY Table	510
TRENDS_6_WEEKLY Table	513
TRENDS_7_BIMONTHLY Table	516
TRENDS_7_MONTHLY Table	519
TRENDS_7_WEEKLY Table	522
TRENDS_FIELDS Table	525
TRENDS_GROUPING Table	527
TRENDS_GROUPING_RANGE Table	528
TRENDS_YAXIS_DISPLAY Table	529

UserRecentHistory Table	530
UserRecentHistory_Cross_AL Table.....	532
UserSessions Table.....	534
Letter Generator Tables	535
LetterColumns Table.....	535
LetterPostClass Table.....	537
LetterPrintLocation Table	538
LetterSelect Table	539
LetterSignatures Table.....	541
LetterTags Table.....	542
LetterTemplates Table	544
Letter_Config Table	546
User Interface Tables	547
Active_AL_Report Table	548
AL_Last_AP_Date Table.....	550
Available_Locale Table.....	552
ConfigSortOptions Table	552
FieldConfig Table.....	554
L10N_Property Table	555
L10N_Property_Additional_Info Table	556
L10N_Property_Range Table	557
MasterDisp Table.....	559
MasterDisp_Temp Table.....	561
PrmMenu Table	564
PRM_Dictionary Table.....	567
PRM_Field Table.....	567
PRM_UI_Component Table	570
PRM_UI_Component_Type Table.....	573
PRM_UI_Datasource Table.....	574
PRM_UI_Field Table	575
PRM_UI_Field_Format Table	578
PRM_UI_Field_Search Table.....	580
PRM_UI_Gridbag_Config Table.....	581
PRM_UI_Grid_Config Table	583
PRM_UI_Masking Table	589
PRM_UI_Panel Table	590
ReportCategory Table.....	591

ReportCategoryLink Table	592
ReportFonts Table	593
Reports Table.....	596
ReportWizardPanellink Table	597
RT_Masterdisp Table	598
RT_Masterdisp_Temp Table	601
SelectListValues Table.....	603
Titanium_Port_Total Table	605
Titanium_Reports_Categories Table.....	606
Titanium_RT_Rule_Perf Table	607
Titanium_Rule_Perf Table	608
ToolbarButtons Table.....	609
Txns_Processed_Rpt Table	613
UI_External_View_Config Table.....	614
UI_KPI Table.....	616
UserTableParams Table.....	617
User_Date_Patterns Table.....	619
WizardPanels Table	619
Profile Tables	620
Enh_Profile_Cycle_Type Table	621
ENH_Profile_Frequency Table	622
ENH_Profile_Mark_Types Table	623
ENH_Profile_New_Txns Table	624
ENH_Profile_Setup Table	625
ENH_Profile_Type Table.....	630
ENH_Temp Table.....	631
EP_Dummy Table	632
Profile_Lookup Table	634
Role Configuration Tables	635
PrmRolePerms Table.....	636
PrmRoles Table	637
Role_Template Table	639
Role_Template_Permission Table.....	640
Role_Tran_Type Table.....	641
Tran_Type Table.....	641
Translation Tables	642
TransLookup Table	643

Trans_Category Table	644
Point of Compromise Tables.....	644
PocAlerts Table	645
PocSelect Table	648
Universal Scoring Engine Tables	651
Scoring_Event Table	651
Scoring_Feature Table	652
Scoring_Model Table	653
Scoring_Models_Mapping Table.....	654
Temporary Tables.....	655
TT_Add_Dflt_NRT_Queue_Procs Table	655
TT_Add_Dflt_Profile_Queue_Procs Table	656
TT_AlertTimeout Table	657
TT_Auto_Actions Table	659
TT_Detail_Cleanup_Job Table	664
TT_GenPOCAAlerts Table.....	664
TT_OpenAcctTimeout Table	667
TT_SessionLockExpired Table.....	669
Data Extensibility Tables	671
DE_Action_Level Table	673
DE_Action_Level_Record_Source Table.....	676
DE_AG_Class_Field Table.....	677
DE_AG_Composite_Field Table.....	678
DE_AG_Services Table.....	681
DE_Application_Data_Type Table	682
DE_Column Table.....	684
DE_Compatible_SQL_Data_Type Table	685
DE_Configuration Table	686
DE_Configuration_Type Table	687
DE_Demo_Caption Table	687
DE_PIM_Mappings Table	688
DE_Record_Source Table.....	690
DE_Record_Source_Attr Table.....	692
DE_Record_Source_Format Table.....	694
DE_Record_Source_Mapping Table.....	695
DE_Record_Source_Type Table	696
DE_SQL_Data_Type Table.....	697

DE_SQL_Data_Type_MSQ Table	697
DE_SQL_Data_Type_ORA Table	698
DE_Table Table	698
DE_UI_Component Table.....	699
DE_UI_Field Table.....	701
DE_UI_Field_Format Table.....	703
DE_UI_Field_Search Table	704
DE_UI_GridBag_Config Table.....	705

Section 5: Profile and Peer Profile tables 708

Account action level	708
Acct_31_Days_Profile Table	708
Acct_3_Days_Profile Table	713
Acct_Daily_Profile Table.....	718
Card action level	724
Card_31_Days_Peer_Profile Table	724
Card_31_Days_Profile Table.....	728
Card_3_Days_Peer_Profile Table	732
Card_3_Days_Profile Table	736
Card_Daily_Peer_Profile Table.....	740
Card_Daily_Profile Table	744
RT_Card_31_Days_Peer_Prof Table	749
RT_Card_31_Days_Profile Table.....	753
TT_Card_31_Days_Peer_Prof Table	757
TT_RT_Card_31_Days_Peer_Prof Table	761
Employee action level.....	765
Employee_30_Days_Peer_Profile Table	766
Employee_30_Days_Profile Table	767
Employee_7_Days_Peer_Profile Table.....	768
Employee_7_Days_Profile Table	769
Employee_90_Days_Peer_Profile Table	770
Employee_90_Days_Profile Table	771
Employee_Daily_Peer_Profile Table	772
Employee_Daily_Profile Table.....	773
Merchant action level	775
Merchant_30_Days_Peer_Profile Table	775
Merchant_30_Days_Profile Table.....	779
Merchant_7_Days_Peer_Profile Table	782

Merchant_7_Days_Profile Table.....	786
Merchant_90_Days_Peer_Profile Table	789
Merchant_90_Days_Profile Table.....	793
Merchant_Daily_Peer_Profile Table.....	796
Merchant_Daily_Profile Table	800
Terminal action level	804
Term_3_Days_Peer_Profile Table.....	804
Term_3_Days_Profile Table.....	808
Term_7_Days_Peer_Profile Table.....	813
Term_7_Days_Profile Table.....	817
Term_Daily_Peer_Profile Table	821
Term_Daily_Profile Table	826
UAID action level	831
UAID_31_Days_Profile Table.....	831
UAID_3_Days_Profile Table.....	832
UAID_Daily_Profile Table	834
UAN action level.....	835
LinkDetail Table	836
UAN_31_Days_Peer_Profile Table.....	837
UAN_31_Days_Profile Table	842
UAN_3_Days_Peer_Profile Table.....	847
UAN_3_Days_Profile Table.....	852
UAN_Daily_Peer_Profile Table	857
UAN_Daily_Profile Table	863
Device ID view.....	868
Device_3_Days_Profile Table	868
Device_7_Days_Profile Table	870
Device_Daily_Profile Table	871
IP Address view	872
IP_3_Days_Profile Table	872
IP_7_Days_Profile Table	873
IP_Daily_Profile Table.....	874
Payee view	875
Payee_3_Days_Profile Table.....	876
Payee_7_Days_Profile Table.....	877
Payee_Daily_Profile Table	878

Section 6: BASE24 Files Maintenance Considerations 880

Logical Network Configuration File (LCONF) Assigns and Params.....	880
Assigns.....	880
Params.....	883
Process Configuration.....	884
XPNET 3.0 Userdata Example	884
XPNET 3.0 Process NCPCOM Obey File	884
XPNET 3.0 Device Obey File.....	885
XPNET 3.0 Input Station Obey File	885
XPNET 3.0 Output Station Obey File.....	886
XPNET 3.0 Input Line File	886
XPNET 3.0 Output Line File.....	887
XPNET 3.0 Node Parameter Example.....	887
ACI Proactive Risk Manager Data Files.....	887
ACI Proactive Risk Manager Tokens	890
ACI Proactive Risk Manager Token ID - 28.....	890
ACI Proactive Risk Manager Real Time Token - 32.....	892
Real Time Scoring Table	893
Sample RTSFIIDS Table.....	893
Pathway Configuration.....	894
Pathconf Entries.....	894
Pathway Screen Layouts	895
Credit/Debit Master File (CDMF).....	896
SEMF Screen 1	896
SEMF Screen 2.....	900
SEMF Refresh and Extract Processing	903
SEMF from Host Maintenance Processing.....	904
Interchange Configuration File (ICF)	904
Operating Modes.....	904
ICF Screen 1.....	906
ICF Screen 2.....	906
ICF Screen 3.....	907
ICF Screen 7.....	908
ICF Screen 9.....	909
ICF Screen 10.....	909
ICF Screen 12.....	910
Merchant Master File (MMF)	915
MMF Screen 1	915

MMF Screen 2	919
MMF Refresh and Extract Processing	923
ACI Proactive Risk Manager Routing Table (PTBL)	923
PTBL Screen 1.....	924
PTBL Screen 2.....	924
PTBL Screen 3.....	925
PTBL Screen 4.....	927
Proactive Risk Manager Startup and Control.....	928
Network and Control Commands.....	928
Network Control Point Communications (NCPCOM) Utility	928
NCPCOM Commands	928
Network Control Supervisor (NCS) Screen.....	930
Establish and Start the TCP/IP Processes.....	930
HP NonStop Scoring Engine Environment	930
Starting the ACI Proactive Risk Manager System	934

Section 1: Introduction

Following are descriptions of the remaining sections of this manual:

Section 2: What's new in this publication – Contains information on changes to the documentation of the tables, columns, and indexes since the last publication.

Section 3: Root and Tenant Table List – Contains a list of all the PRM tables. It identifies which tables belong to the Tenant schema, which tables belong to the Root (or Master schema), and which tables are used in both schemas.

Section 4: Analytic Gateway Process and Analysis/Review Tables - Provides a detailed description of the tables that are used by the Analytic Gateway process throughout the Proactive Risk Manager processing cycle.

Section 5: Profile and Peer Profile Tables - Provides descriptions of the profile and peer profile tables for the following action levels: Account, Card, Employee, Merchant, Terminal, UAN, and UAID. It also provides descriptions of the profile tables for the following views: Device ID, IP Address, and Payee.

Section 6: BASE24 Files Maintenance Considerations - Describes the installation and configuration of the BASE24 files and the PRM Interface Process operating under an HP NonStop platform

Section 7: SystemConfig table parameters – Provides descriptions of the SystemConfig table parameters.

Section 8: Config table parameters – Provides descriptions of the Config table parameters.

Section 9: FieldConfig table parameters – Provides descriptions of the FieldConfig table parameters.

Section 2: **What's new in this publication**

The LSTATUS column was added to the Acct_Daily_Profile table with the following definition:

Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

0 - unassigned

1 - assigned

3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

The PRCSID column was added to the Acct_Daily_Profile table with the following definition:

Web server process that the row is assigned to for roll-up rules processing.

The STANDARD_PROFILE_CONFIG column was added to the Action_Level table with the following definition:

Configuration for Standard Profiles Jobs for each action level in JSON format

The PK_ALERT_PROPERTY key was added to the Alert_Property table.

The PK_ALERTS_TRACKING_STATUS key was added to the Alerts_Tracking_Status table.

The LCREATED_BY column was added to the AutoText table with the following definition:

The users's ID who added the auto text.

The DCREATED_TIME column was added to the AutoText table with the following definition:

The date and time when the auto text was added

The LLAST_MODIFIED_BY column was added to the AutoText table with the following definition:

The user's ID who last applied changes to the auto text

The DLAST_MODIFIED_TIME column was added to the AutoText table with the following definition:

- Date and time when the auto text was added or updated for the respective action.

The LSTATUS column was added to the Card_Daily_Profile table with the following definition:

Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

0 - unassigned

1 - assigned

3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

The PRCSID column was added to the Card_Daily_Profile table with the following definition:

Web server process that the row is assigned to for roll-up rules processing.

The JSON column was added to the DE_Column table with the following definition:

Flag that indicates whether this column is a JSON formatted string.

The COMPONENT_NAME column on the DE_UI_Component table was modified. The description was changed to: The name of the component used in the user interface.

The LSTATUS column was added to the Employee_Daily_Profile table with the following definition:

Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

0 - unassigned

1 - assigned

3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them

to the current PRM Server process and change their status.

The PRCSID column was added to the Employee_Daily_Profile table with the following definition:
Web server process that the row is assigned to for roll-up rules processing.

The CYCLE_FIELD column on the ENH_Profile_Setup table was modified. The data type was changed from varchar(61) to varchar(512).

The PRIMARY_FIELD column on the ENH_Profile_Setup table was modified. The data type was changed from varchar(61) to varchar(512).

The AMOUNT_FIELD column on the ENH_Profile_Setup table was modified. The data type was changed from varchar(61) to varchar(512).

The SOPTIONS column was added to the External_Connection_Map table with the following definition:

This column is in JSON format and can hold multiple configurations. At the moment, it only can be used to specify if the rows that belong to a specific entry in EXTERNAL_CONNECTION_MAP table should send PII Data in clear instead of encrypted/hashed. This currently only applies to PAN.

The PrcsID column on the External_Message_Data table was modified. The name was changed from PrcsID to PROCSID.

The PrcsID column on the External_Message_Data table was modified. The code was changed from PRCSID to PROCSID.

The PrcsID column on the External_Message_Data table was modified. The checkconstraintname was changed from CKC_PRCSID_EXTERNAL to CKC_PROCSID_EXTERNAL.

The TRACKING_ID column was added to the External_Message_Data table with the following definition:

Tracking id of the OEI instance processing the transaction

The LSTATUS column was added to the Merchant_Daily_Profile table with the following definition:
Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

- 0 - unassigned
- 1 - assigned
- 3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

The PRCSID column was added to the Merchant_Daily_Profile table with the following definition:
Web server process that the row is assigned to for roll-up rules processing.

The SD_PT_SRV_ENTRY_MDE column was added to the POC_FraudDetail table with the following definition:

The transaction entry mode. The first two bytes of this column indicate how the transaction entered the system.

The following are examples of valid values:

- 00 = Unspecified
- 01 = Manually
- 02 = Magnetic stripe
- 03 = Bar code
- 04 = OCR (optical character reader)
- 05 = Integrated circuit card
- 06–60 = Reserved for ISO use
- 61–80 = Reserved for national use
- 81–99 = Reserved for private use

The third byte indicates the capability of the terminal where the transaction was performed. The following are examples of valid values:

- 0 = Unspecified
- 1 = PIN entry capability
- 2 = No PIN entry capability
- 3–5 = Reserved for ISO use
- 6–7 = Reserved for national use
- 8–9 = Reserved for private use

The SD_PT_SRV_COND_CDE column was added to the POC_FraudDetail table with the following definition:

Indicates a special condition that exists at the time a transaction is initiated.

The following are examples of valid values:

- 00 = Normal presentment
- 01 = Customer not present
- 02 = Unattended terminal, able to retain card
- 03 = Merchant suspicious
- 04 = Electronic cash register interface
- 05 = Customer present but card not present
- 06 = Preauthorization transaction request
- 07 = Telephone device request
- 08 = Mail order or telephone order
- 09 = Security alert
- 10 = Customer identity verified
- 11 = Suspected fraud
- 12 = Security reasons
- 13 = Presentment of items
- 14 = Public utility terminal
- 15 = Customer terminal (home terminal)
- 16 = Administration terminal
- 17 = Returned items (chargeback)
- 18 = No check in envelope or all returned
- 19 = Deposit out-of-balance returned
- 20 = Payment out-of-balance (all returned)
- 21 = Manual reversal
- 22 = terminal error (counted)
- 23 = terminal error (not counted)
- 24 = Deposit out-of-balance/applied contents
- 25 = Payment out-of-balance/applied contents
- 26 = Withdrawal had error/reversed
- 27 = Unattended terminal, unable to retain card
- 28-40 = Reserved for ISO use
- 41-50 = Reserved for national use
- 51 = Address verification

52–99 = Reserved for private use

The PRM_Heritage_Pass table was added to the database with the following definition:

Keeps encrypted password

The columns in the PRM_Heritage_Pass table (PRM_HERITAGE_PASS) are listed below with the data type.

Column Name	Data Type
ENC_KEY	varchar(512)
ENC_PASS	varchar(512)

The DTLASTFAILLOGIN column was added to the PRM_Users table with the following definition:

Date and Time of the logged in user's last unsuccessful login attempt

The DTPREVIOUSLOGIN column was added to the PRM_Users table with the following definition:

Date and Time of the logged in user's previous successful login

The DTREATED column was added to the RQDisposition table with the following definition:

The date when the Real-Time disposition was created

The LCREATEDBY column was added to the RQDisposition table with the following definition:

The user ID for the person who created this Real-Time disposition

The SD_ACCT_TYP column was added to the RT_Shortwindow table with the following definition:

The account type affected by this transaction

The SD_CLIENT_LANGUAGE column was added to the RT_Shortwindow table with the following definition:

The language for which the user's client has been localized, which can be parsed from the User-Agent string.

The SD_CVD_PRESENT_FLG column was added to the RT_Shortwindow table with the following definition:

A code indicating whether the manual Card Verification Value is printed on the card. This field is used in POS transactions only.

The SD_CLIENT_IP column was added to the RT_Shortwindow table with the following definition:

The client's IP, which can be parsed from the X-Forwarded-For string.

The Rules_OP_Events_KPI table was added to the database with the following definition:

The RULES_OP_EVENTS_KPI table is a configuration table and is used to obtain Operational Events reports.

The columns in the Rules_OP_Events_KPI table (RULES_OP_EVENTS_KPI) are listed below with the data type.

Column Name	Data Type
BDEBUG	integer
DB_LOG	integer
EMAIL_ADDRESS	nvarchar(2000)
EMAIL_LOG	integer
KPI_ID	integer
LOCALE_ID	nvarchar(10)
NSTATUS	integer
POLL_INTERVAL	integer
RULE_TYPE	varchar(20)
SSQL	nvarchar(2000)
THRESHOLD	integer

Index Name: **PK_RULES_OP_EVENTS_KPI**

Fields: KPI_ID

The RULES_OP_EVENTS_LOG table was added to the database with the following definition:

RULES_OP_EVENTS_LOG contains recorded information related to operation events for rule's performance.

The columns in the RULES_OP_EVENTS_LOG table (RULES_OP_EVENTS_LOG) are listed below with the data type.

Column Name	Data Type
END_DATE	datetime
KPI_ID	integer
LOG_ID	integer
RULE_COUNT	integer
RULE_ID	integer
RULE_NAME	nvarchar(500)
START_DATE	datetime

Index Name: **IDX_RULES_OP_EVENTS_LOG**

Fields: LOG_ID

The Std_Profile_Status table was added to the database with the following definition:

Table STD_PROFILE_STATUS holds the standard profiles jobs for all the action levels. It is set to be cleaned up by default after 30 days.

The columns in the Std_Profile_Status table (STD_PROFILE_STATUS) are listed below with the data type.

Column Name	Data Type
ACTIONLEVELID	integer
ENDTIME	datetime
FAILEDKEYS	integer
ID	integer
LASTUPDATED	datetime
PRCSID	varchar(50)
PREVIOUSSTATUSES	varchar(1000)
RECOMMENDATION	varchar(254)
RQBYPRCSID	varchar(50)
RUNDATE	date
STARTTIME	datetime
STATUS	varchar(50)
SUCCESSFULKEYS	integer

Index Name: PK_STD_PROFILE_STATUS

Fields: ACTIONLEVELID
RUNDATE

Index Name: IDX_STD_PROFILE_STATUS_ID

Fields: ID

The LSTATUS column was added to the Term_Daily_Profile table with the following definition:

Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

0 - unassigned

1 - assigned

3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

The PRCSID column was added to the Term_Daily_Profile table with the following definition:

Web server process that the row is assigned to for roll-up rules processing.

The TOTAL_AMT1 column was deleted from the Titanium_Port_Total table and removed from the documentation.

The LSTATUS column was added to the UAID_Daily_Profile table with the following definition:

Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

0 - unassigned

1 - assigned

3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

The PRCSID column was added to the UAID_Daily_Profile table with the following definition:

Web server process that the row is assigned to for roll-up rules processing.

The LSTATUS column was added to the UAN_Daily_Peer_Profile table with the following definition:

Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

- 0 - unassigned
- 1 - assigned
- 3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

The PRCSID column was added to the UAN_Daily_Peer_Profile table with the following definition:

Web server process that the row is assigned to for roll-up rules processing.

The UI_KPI table was modified. The clusterobject was changed from IDX_UI_KPI_END_TIME to <None>

The SESSIONID column was added to the UI_KPI table with the following definition:

The session under which a certain servlet was called. Available for calls from the swing application and from AR. For BSI, it writes the consumer ID, since we use no sessions for BSI calls.

The END_TIME column was deleted from the IDX_UI_KPI_END_TIME index.

The documentation for the SystemConfig table parameters, Config table parameters, and FieldConfig table parameters has been moved from this manual to appendices in the *Application Administrator User Guide*.

Section 3: Root and Tenant Table List

The following table lists all PRM tables in alphabetical order. An "X" indicates that the corresponding table belongs to the group of tables identified in the column header.

All PRM90 Tables	NRT Tenant Tables	RT Tenant Tables	Tenant Tables	NRT Root Tables	RT Root Tables	Root Tables
ACCNT_ROUTING	X	X	X			
ACCOUNT_MASTER	X		X			
ACCT_31_DAYS_PROFILE	X		X			
ACCT_3_DAYS_PROFILE	X		X			
ACCT_DAILY_PROFILE	X		X			
ACT	X		X			
ACTIONSTEXT	X		X			
ACTIONSTYPE	X		X			
ACTIONSTYPE_ACTION_LEVEL	X		X			
ACTIONSTYPE_ACTION_LEVEL_EMM	X		X			
ACTIONSTYPE_FEATURE	X		X			
ACTIONSTYPE_PERMISSION	X		X			
ACTIONSTYPE_REVIEW_SCREEN	X		X			
ACTION_LEVEL	X	X	X	X	X	X
ACTION_LEVEL_ALERT_ORDER_LIST	X		X			
ACTION_LEVEL_MEMO	X		X			
ACTION_LEVEL_PROFILE_TABLE	X		X			
ACTION_LEVEL_RECORD_SOURCE	X	X	X			
ACTION_LEVEL_USER	X		X			
ACTIVE_AL_REPORT	X		X			
ACTSESS	X	X	X			
ACTSESS2	X	X	X			
ADDBLOCKCODES	X		X			
ADDBLOCKCODE_ACTION_LEVEL	X		X			
ADDRRESPONSECODES	X		X			
ADDRRESPONSECODES_ACTION_LEVEL	X		X			
ADMLOGIN	X	X	X			
ADMNSBGP	X	X	X			
ADMNUGRP	X	X	X			
AG_COMPOSITE_FIELD	X	X	X			
AG_COMP_FIELDS_SELECTOR	X	X	X			
AG_DATA_SANITIZER	X	X	X			
AG_FIELD	X	X	X			
AG_FIELD_COMPOSITION	X	X	X			

All PRM90 Tables	NRT Tenant Tables	RT Tenant Tables	Tenant Tables	NRT Root Tables	RT Root Tables	Root Tables
AG_FIELD_SELECTION	X	X	X			
AG_FIELD_TRANSFORMATION	X	X	X			
AG_KPI_DEF	X	X	X			
AG_KPI_LOG	X	X	X			
AG_KPI_SLA_REPORT_RESULT	X	X	X			
AG_KPI_SLA_REPORT_STATISTICS	X	X	X			
AG_NACHA_BATCH_STATISTICS	X		X			
AG_NACHA_FILE_STATISTICS	X		X			
AG_SERVICES	X	X	X			
AG_TRANSFORMATION_PARAM	X	X	X			
ALERTS	X		X			
ALERT_CATEGORY	X		X			
ALERT_PROPERTY	X		X			
ALERTS_TRACKING	X		X			
ALERTS_TRACKING_STATUS	X		X			
AL_LAST_AP_DATE	X		X			
APPLCNFG	X	X	X			
APPLCNFG_REPOS	X	X	X			
APPLCNFG_SEED	X	X	X			
APPLDSRC	X	X	X			
APPLICATION_DATA_TYPE	X	X	X			
APR_MARK_HISTORY	X		X			
APR_STATISTIC	X		X			
AR_NODE_PERMISSION	X		X			
ASSGND_ACTIONSTYPE_ACTIONLEVEL	X		X			
AUTHCONFIG	X		X			
AUTOACTIONSRULE	X		X			
AUTOTEXT	X		X			
AUTOTEXT_ACTION_LEVEL	X		X			
AUTO_ACTION_PENDING	X		X			
AUTO_ADD_IN_CONFIG	X		X			
AUTO_ADD_IN_RULE_CONFIG	X		X			
AVAILABLE_LOCALE	X		X			
BATCH_STATISTICS	X		X			
CAPABILITY_CONFIG	X		X			
CARD_31_DAYS_PEER_PROFILE	X		X			
CARD_31_DAYS_PROFILE	X		X			
CARD_3_DAYS_PEER_PROFILE	X		X			
CARD_3_DAYS_PROFILE	X		X			
CARD_DAILY_PEER_PROFILE	X		X			
CARD_DAILY_PROFILE	X		X			
CARD_MASTER	X		X			
CATEGORY_HISTORY	X		X			
CHECK_INDEX_COLUMNS	X	X	X			

All PRM90 Tables	NRT Tenant Tables	RT Tenant Tables	Tenant Tables	NRT Root Tables	RT Root Tables	Root Tables
CLEANUP_TABLES	X	X	X			
CONFIG	X		X	X		X
CONFIGSORTOPTIONS	X		X			
CONTACT_STRATEGY	X		X			
CONTACT_STRATEGY_ACTION_LEVEL	X		X			
CROSS_ACTION_LEVEL	X		X	X		X
DASHB_AP_ACT	X		X			
DASHB_AP_MAXDATE	X		X			
DASHB_AP_PQ	X		X			
DASHB_AP_SYSAUD	X		X			
DASHB_AP_USRSESEXP	X		X			
DASHB_QST_ALRT	X		X			
DASHB_QST_ALRT_OLD	X		X			
DASHB_QST_MAXDATE	X		X			
DASHB_QST_USRSESEXP	X		X			
DATASRC	X	X	X			
DD_ROUTING	X	X	X			
DETAIL	X		X			
DETAIL_ALERTED_RULE	X		X			
DETAIL_FLAG	X		X			
DETAIL_MARKSELECTION	X		X			
DEVICE_3_DAYS_PROFILE	X		X			
DEVICE_7_DAYS_PROFILE	X		X			
DEVICE_DAILY_PROFILE	X		X			
DE_ACTION_LEVEL	X		X			
DE_ACTION_LEVEL_RECORD_SOURCE	X		X			
DE_AG_CLASS_FIELD	X		X			
DE_AG_COMPOSITE_FIELD	X		X			
DE_AG_SERVICES	X		X			
DE_APPLICATION_DATA_TYPE	X		X			
DE_COLUMN	X		X			
DE_COMPATIBLE_SQL_DATA_TYPE	X		X			
DE_CONFIGURATION	X		X			
DE_CONFIGURATION_TYPE	X		X			
DE_DEMO_CAPTION	X		X			
DE_FILTER_FIELDS	X		X			
DE_PIM_MAPPINGS	X		X			
DE_RECORD_SOURCE	X		X			
DE_RECORD_SOURCE_ATTR	X		X			
DE_RECORD_SOURCE_FORMAT	X		X			
DE_RECORD_SOURCE_MAPPING	X		X			
DE_RECORD_SOURCE_TYPE	X		X			
DE_SQL_DATA_TYPE	X		X			
DE_SQL_DATA_TYPE_MSQ	X		X			

All PRM90 Tables	NRT Tenant Tables	RT Tenant Tables	Tenant Tables	NRT Root Tables	RT Root Tables	Root Tables
DE_SQL_DATA_TYPE_ORA	X		X			
DE_TABLE	X		X			
DE_UI_COMPONENT	X		X			
DE_UI_FIELD	X		X			
DE_UI_FIELD_FORMAT	X		X			
DE_UI_FIELD_SEARCH	X		X			
DE_UI_GRIDBAG_CONFIG	X		X			
EMM_STATUS_TYPE	X		X			
EMPLOYEE_30_DAYS_PEER_PROFILE	X		X			
EMPLOYEE_30_DAYS_PROFILE	X		X			
EMPLOYEE_7_DAYS_PEER_PROFILE	X		X			
EMPLOYEE_7_DAYS_PROFILE	X		X			
EMPLOYEE_90_DAYS_PEER_PROFILE	X		X			
EMPLOYEE_90_DAYS_PROFILE	X		X			
EMPLOYEE_DAILY_PEER_PROFILE	X		X			
EMPLOYEE_DAILY_PROFILE	X		X			
EMPLOYEE_MASTER	X		X			
ENH_PROFILE_CYCLE_TYPE	X		X			
ENH_PROFILE_FREQUENCY	X		X			
ENH_PROFILE_MARK_TYPES	X		X			
ENH_PROFILE_NEW_TXNS	X		X			
ENH_PROFILE_SETUP	X		X			
ENH_PROFILE_TYPE	X		X			
ENH_TEMP	X		X			
EP_DUMMY	X		X			
EVENT	X	X	X			
EVENT_DOCUMENT	X	X	X			
EVNTLOG	X	X	X			
EXTERNAL_CONNECTION_MAP	X		X			
EXTERNAL_MESSAGE_DATA	X		X			
EXTERNAL_PROCEDURE	X	X	X			
EXTERNAL_PROCEDURE_PURPOSE	X	X	X			
EXTERNAL_PROCEDURE_TYPE	X	X	X			
EXTRCNCT	X	X	X			
EXTRCNCT_REPOS	X	X	X			
EXTRCNCT_SEED	X	X	X			
EXTRCNCT_SERVICE	X		X			
FEATURE	X		X	X		X
FIELDCONFIG	X		X	X		X
FIELDS	X	X	X			
FIELD_ACTION_LEVEL	X		X			
FILTERLAYOUT	X		X			
FILTERS	X	X	X			
FILTER_FIELDS	X	X	X			

All PRM90 Tables	NRT Tenant Tables	RT Tenant Tables	Tenant Tables	NRT Root Tables	RT Root Tables	Root Tables
FLAGS	X		X			
FLAGS_ACTION_LEVEL	X		X			
FLDVALS	X	X	X			
FLTXROLE	X	X	X			
FLXFLDVL	X	X	X			
FORBIDDEN_VERBS	X		X			
FORWARD	X		X			
FRAUDDetail	X		X			
FUNCTS	X	X	X			
HSMCNFG	X	X	X			
IP_3_DAYS_PROFILE	X		X			
IP_7_DAYS_PROFILE	X		X			
IP_DAILY_PROFILE	X		X			
L10N_PROPERTY	X		X	X		X
L10N_PROPERTY_ADDITIONAL_INFO	X		X	X		X
L10N_PROPERTY_RANGE	X		X	X		X
LANGUAG	X	X	X			
LETTERCOLUMNS	X		X			
LETTERPOSTCLASS	X		X			
LETTERPRINTLOCATION	X		X			
LETTERSELECT	X		X			
LETTERSIGNATURES	X		X			
LETTERTAGS	X		X			
LETTERTEMPLATES	X		X			
LETTER_CONFIG	X		X			
LINKDETAIL	X		X			
LISTENER	X	X	X			
LISTENER_REPOS	X	X	X			
LISTENER_SEED	X	X	X			
LOCKS	X		X	X		X
MASTERDISP	X		X			
MASTERDISP_TEMP	X		X			
MERCHANT_MASTER	X		X			
MER_30_DAYS_PEER_PROFILE	X		X			
MER_30_DAYS_PROFILE	X		X			
MER_7_DAYS_PEER_PROFILE	X		X			
MER_7_DAYS_PROFILE	X		X			
MER_90_DAYS_PEER_PROFILE	X		X			
MER_90_DAYS_PROFILE	X		X			
MER_DAILY_PEER_PROFILE	X		X			
MER_DAILY_PROFILE	X		X			
MSGCNTX	X	X	X			
MULTI_TEAM_ACCESS	X		X	X		X
NOTIFICATION_ACTIONS	X		X			

All PRM90 Tables	NRT Tenant Tables	RT Tenant Tables	Tenant Tables	NRT Root Tables	RT Root Tables	Root Tables
NOTIFICATION_ADDITIONAL_FIELDS	X		X			
NOTIFICATION_NEWTRAN_FILTER	X		X			
NOTIFICATION_REQUEST_ADDTL	X		X			
NOTIFICATION_STATUS	X		X			
NOTIFICATION_SUBSCRIPTIONS	X		X			
NOTIFICATION_TYPES	X		X			
NRT_GROUP_LINK	X		X			
PASSWORD	X	X	X			
PASSWORDHISTORY	X		X	X		X
PAYEE_3_DAYS_PROFILE	X		X			
PAYEE_7_DAYS_PROFILE	X		X			
PAYEE_DAILY_PROFILE	X		X			
PENDING_AGGREGATES	X		X			
PERMDET	X	X	X			
PERMGRP	X	X	X			
PERMS	X	X	X			
PERMTYPE	X	X	X			
PMGPXPRM	X	X	X			
POCALERTS	X		X			
POCSELECT	X		X			
PORTFOLIOS	X		X			
PRINTERAREAS	X		X			
PRINTERPORTFOLIOS	X		X			
PRINTERS	X		X			
PRMJNLPCONFIG				X		X
PRMMENU	X		X	X		X
PRMROLEPERMS	X		X	X		X
PRMROLES	X		X	X		X
PRM_BATCH	X		X			
PRM_BATCH_HISTORY	X		X			
PRM_BATCH_JOB	X		X			
PRM_FIELD	X		X			
PRM_FILTERS	X		X			
PRM_HERITAGE_PASS				X		
PRM_INSTALL	X		X	X		X
PRM_INSTALL_LOG	X		X	X		X
PRM_KEYS				X		X
PRM_PERMISSION	X		X	X		X
PRM_PERMISSION_GRP	X		X	X		X
PRM_REF_DATA	X		X			
PRM_TENANTS				X		X
PRM_TENANTS_CONFIG				X		X
PRM_UI_COMPONENT	X		X			
PRM_UI_COMPONENT_TYPE	X		X			

All PRM90 Tables	NRT Tenant Tables	RT Tenant Tables	Tenant Tables	NRT Root Tables	RT Root Tables	Root Tables
PRM_UI_DATASOURCE	X		X			
PRM_UI_FIELD	X		X			
PRM_UI_FIELD_FORMAT	X		X			
PRM_UI_FIELD_SEARCH	X		X			
PRM_UI_GRIDBAG_CONFIG	X		X			
PRM_UI_GRID_CONFIG	X		X			
PRM_UI_MASKING	X		X			
PRM_UI_PANEL	X		X			
PRM_USERS	X		X			
PROCESS	X	X	X	X		X
PROFILE_ALERTED_RULE	X		X			
PROFILE_LOOKUP	X		X			
PROFILE_TO_RT_BATCH	X		X			
PSWDGRP	X	X	X			
PSWDHIST	X	X	X			
QUE_CAT_TYPE	X		X			
QUEUEHISTORY	X		X			
QUEUE_LINK	X		X			
RECORD_SOURCE	X	X	X			
RECORD_SOURCE_COLUMN_MAPPING	X	X	X			
RECORD_SOURCE_FIELD	X	X	X			
RECORD_SOURCE_MAPPING	X	X	X			
RECORD_SOURCE_ROUTING	X	X	X			
REPORTCATEGORY	X		X	X		X
REPORTCATEGORYLINK	X		X	X		X
REPORTFONTS	X		X	X		X
REPORTS	X		X	X		X
REPORTWIZARDPANELLINK	X		X	X		X
ROLES	X	X	X			
ROLE_TEMPLATE	X		X			
ROLE_TEMPLATE_PERMISSION	X		X			
ROLE_TRAN_TYPE	X		X			
ROLXPMGP	X	X	X			
RQA	X		X			
RQAGGREGATETYPES	X		X			
RQCATEGORIES	X		X			
RQDISPOSITION	X		X			
RQORDER	X		X			
RQPORTASSIGN	X		X			
RQVARDEFASSIGN	X		X			
RQVARIABLES	X		X			
RQ_FIELDS	X		X			
RT_ACCOUNT_MASTER		X	X			
RT_CARD_31_DAYS_PEER_PROF		X	X			

All PRM90 Tables	NRT Tenant Tables	RT Tenant Tables	Tenant Tables	NRT Root Tables	RT Root Tables	Root Tables
RT_CARD_31_DAYS_PROFILE		X	X			
RT_CARD_MASTER		X	X			
RT_EMPLOYEE_MASTER		X	X			
RT_FILTERLAYOUT		X	X			
RT_GROUP_LINK	X		X			
RT_MASTERDISP		X	X			
RT_MASTERDISP_TEMP		X	X			
RT_MERCHANT_MASTER		X	X			
RT_PRM_INSTALL		X	X		X	X
RT_PRM_INSTALL_LOG		X	X		X	X
RT_PRM_REF_DATA		X	X			
RT_SHORTWINDOW		X	X			
RT_TERMINAL_MASTER		X	X			
RT_UAID_MASTER		X	X			
RT_UAN_MASTER		X	X			
RULEAGGREGATELINK	X		X			
RULEDEF	X		X			
RULEDEFTEMPLATELINK	X		X			
RULEPERFMONITOR_DEF	X		X			
RULEPERFMONITOR_LOG	X		X			
RULEQUEUE	X		X			
RULESUBTYPES	X		X			
RULESUBTYPETEMPLATE	X		X			
RULES_OP_EVENTS_KPI	X		X			
RULES_OP_EVENTS_LOG	X		X			
RULETYPES	X		X			
RULE_TESTER_ALERTED	X		X			
RULE_TESTER_DATASET	X		X			
RVQUALSUM	X		X			
SCORING_EVENT	X	X	X			
SCORING_FEATURE	X	X	X			
SCORING_MODEL	X	X	X			
SCORING_MODELS_MAPPING	X	X	X			
SECGRP	X	X	X			
SELECTLISTVALUES	X		X			
SERVICE_ADDITIONAL_FIELDS	X		X			
SERVICE_RQ_FILTER	X		X			
SETTINGS	X		X			
SHORTWINDOW	X		X			
SHORTWINDOW_GROUP	X		X	X		X
STD_PROFILE_STATUS	X		X			
SYSTEMAUDIT	X	X	X	X		X
SYSTEMAUDITSUBTYPES	X	X	X	X		X
SYSTEMAUDITTSEC	X		X	X		X

All PRM90 Tables	NRT Tenant Tables	RT Tenant Tables	Tenant Tables	NRT Root Tables	RT Root Tables	Root Tables
SYSTEMAUDITTYPES	X		X	X		X
SYSTEMCONFIG	X	X	X	X		X
SYSTEMFIELDS	X		X			
SYSTEMSQL	X		X	X		X
SYSTEMTABLEMAP	X		X			
TASKFLDS	X	X	X			
TASKFNCS	X	X	X			
TASKS	X	X	X			
TASK_SEMAPHORE	X		X			
TCR_GROUP	X		X			
TCR_RUN_LOG	X		X			
TCR_STATISTIC	X		X			
TEAMPORTFOLIOLINKS	X		X			
TEAMS	X		X	X		X
TEMP_APR_USERS_AL_AC_BK	X		X			
TEMP_APR_USERS_MARK	X		X			
TEMP_APR_APR_LOSSPREV	X		X			
TEMP_APR_USERS_LOSS	X		X			
TEMP_APR_APR_MISSED	X		X			
TEMP_APR_USERS_BLK	X		X			
TEMP_APR_USERS_INCBLK	X		X			
TEMP_APR_APR_INCBLK	X		X			
TEMP_APR_APR_LOSS	X		X			
TEMP_APR_APR_LOSS_BLK	X		X			
TEMPLATES	X		X			
TEMPLATE_TYPES	X		X			
TERMINAL_MASTER	X		X			
TERM_3_DAYS_PEER_PROFILE	X		X			
TERM_3_DAYS_PROFILE	X		X			
TERM_7_DAYS_PEER_PROFILE	X		X			
TERM_7_DAYS_PROFILE	X		X			
TERM_DAILY_PEER_PROFILE	X		X			
TERM_DAILY_PROFILE	X		X			
TFL_REPORT_LAST_DD_DATE	X		X			
TICKET	X	X	X			
TIMER_LOCK	X		X			
TIPS	X		X			
TIPTYPES	X		X			
TIP_ACTION_LEVEL	X		X			
TIP_PRMROLES	X		X			
TITANIUM_REPORTS	X		X			
TITANIUM_REPORTS_INPUT	X		X			
TITANIUM_REPORTS_INPUT_PROPS	X		X			
TITANIUM_REPORTS_OUTPUT	X		X			

All PRM90 Tables	NRT Tenant Tables	RT Tenant Tables	Tenant Tables	NRT Root Tables	RT Root Tables	Root Tables
TITANIUM_REPORTS_PARAM	X		X			
TOOLBARBUTTONS	X		X	X		X
TRANSLOOKUP	X		X			
TRANS_CATEGORY	X		X			
TRANS_CATEGORY_FILTER_FIELD	X		X			
TRAN_TYPE	X		X			
TRAVEL_LOCATIONS	X	X	X			
TRAVEL_NOTIFICATIONS	X	X	X			
TRAVEL_NOTIFICATION_COUNTRIES	X		X			
TRAVEL_NOTIFICATION_METHOD	X		X			
TRAVEL_NOTIFICATION_REGIONS	X		X			
TRAVEL_NOTIFICATION_TYPE	X		X			
TRENDS_1_BIMONTHLY	X		X			
TRENDS_1_MONTHLY	X		X			
TRENDS_1_WEEKLY	X		X			
TRENDS_2_BIMONTHLY	X		X			
TRENDS_2_DAILY	X		X			
TRENDS_2_WEEKLY	X		X			
TRENDS_3_BIMONTHLY	X		X			
TRENDS_3_MONTHLY	X		X			
TRENDS_3_WEEKLY	X		X			
TRENDS_4_BIMONTHLY	X		X			
TRENDS_4_DAILY	X		X			
TRENDS_4_WEEKLY	X		X			
TRENDS_5_BIMONTHLY	X		X			
TRENDS_5_MONTHLY	X		X			
TRENDS_5_WEEKLY	X		X			
TRENDS_6_BIMONTHLY	X		X			
TRENDS_6_MONTHLY	X		X			
TRENDS_6_WEEKLY	X		X			
TRENDS_7_BIMONTHLY	X		X			
TRENDS_7_MONTHLY	X		X			
TRENDS_7_WEEKLY	X		X			
TRENDS_FIELDS	X		X			
TRENDS_GROUPING	X		X			
TRENDS_GROUPING_RANGE	X		X			
TRENDS_YAXIS_DISPLAY	X		X			
TT_ADD_DFLT_NRT_QUEUE_PROCS	X		X			
TT_ADD_DFLT_PROFILE_QUEUE_PROC	X		X			
TT_ALERTTIMEOUT	X		X			
TT_AUTO_ACTIONS	X		X			
TT_CARD_31_DAYS_PEER_PROF	X		X			
TT_DETAIL_CLEANUP_JOB	X		X			
TT_GENPOCALERTS	X		X			

All PRM90 Tables	NRT Tenant Tables	RT Tenant Tables	Tenant Tables	NRT Root Tables	RT Root Tables	Root Tables
TT_OPENACCTTIMEOUT	X		X			
TT_RT_CARD_31_DAYS_PEER_PROF		X	X			
TT_SESSIONLOCKEXPIRED	X		X			
TXNS_PROCESSED_RPT	X		X			
UAID_31_DAYS_PROFILE	X		X			
UAID_3_DAYS_PROFILE	X		X			
UAID_DAILY_PROFILE	X		X			
UAID_MASTER	X		X			
UAN_31_DAYS_PEER_PROFILE	X		X			
UAN_31_DAYS_PROFILE	X		X			
UAN_3_DAYS_PEER_PROFILE	X		X			
UAN_3_DAYS_PROFILE	X		X			
UAN_DAILY_PEER_PROFILE	X		X			
UAN_DAILY_PROFILE	X		X			
UAN_MASTER	X		X			
UI_EXTERNAL_VIEW_CONFIG	X		X			
UI_KPI	X		X			
USERCONFIG	X		X	X		X
USERLOCKOUT	X		X	X		X
USERRECENTHISTORY	X		X	X		X
USERRECENTHISTORY_CROSS_AL	X		X	X		X
USERS	X	X	X			
USERSESSIONS	X		X	X		X
USERTABLEPARAMS	X		X			
USER_DATE_PATTERNS	X		X			
USRAULOG	X	X	X			
USRSTAT	X	X	X			
USRXFILT	X	X	X			
USRXROLE	X	X	X			
VERSIONS	X	X	X			
WEBAPPOPTS	X	X	X			
WEBAPPS	X	X	X			
WEBUSROPTS	X	X	X			
WIZARDPANELS	X		X	X		X

Section 4: **Analytic Gateway Process and Analysis/Review Tables**

The Analytic Gateway process is the server component of the Analysis and Review system. It provides the following four main functions:

- The server process interfaces with the host platform to access transactions, unless the Scoring Engine is present
- The server process interfaces with the host platform to access transactions, invoking (through messaging) the Scoring Engine to generate a suspicious activity score if it is present
- Assigns data to appropriate portfolio
- Generates rule-based alerts, based on end-user customer rules

The Analytic Gateway process also summarizes each day's transactions into a profile record and calculates summaries across time windows for each card and or account. This section provides a detailed description of the tables that are used by the Analytic Gateway process throughout the ACI Proactive Risk Manager processing cycle. These tables are grouped into the following categories:

- Primary Database Tables
- Analysis Tables
- Rule/Queue System Tables
- Action/External Message Tables
- Security System Tables
- Dynamic Screen Tables

Overview

This section describes the database layout of ACI Proactive Risk Manager. The tables are described in terms of the data contained and the functionality provided, as well as how they are managed from the front-end application and the database server.

Data Modification

ACI Worldwide Inc. strongly recommends against modifying table data directly by the end user. The database should be altered using the ACI Proactive Risk Manager application only. Any data alteration could render ACI Proactive Risk Manager inoperable and possibly unrecoverable.

Primary Database Tables

The primary database tables contain the account holder or cardholder information and the transaction information within the PRM system. The tables contain all the relevant information for the specified retention period and are used in the creation of alerts and in the display of information on the client workstations. The following tables make up the largest portion of the database in terms of bytes stored:

- Account_Master
- Act
- Action_Level
- Alerts
- Alerts_Tracking
- Capability_Config
- Card_Master
- DASHB_AP_ACT
- Detail
- Employee_Master
- FraudDetail
- Merchant_Master
- PRM_Heritage_Pass
- PRM_Ref_Data
- RT_Account_Master
- RT_Card_Master
- RT_Employee_Master
- RT_Merchant_Master
- RT_PRM_Install

- RT_PRM_Install_Log
- RT_PRM_Ref_Data
- RT_Shortwindow
- RT_Terminal_Master
- RT_UAID_Master
- RT_UAN_Master
- ShortWindow
- Std_Profile_Status
- Terminal_Master
- UAID_Master
- UAN_Master

Account_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor (Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the Account_Master table (ACCOUNT_MASTER).

Index Name: **ACCOUNT_MASTER_IX1**

Fields: SM_PRI_FIRST_NAM

 SM_SEC_FIRST_NAM

SM_PRI_LAST_NAM

SM_SEC_LAST_NAM

Index Name: ACCOUNT_MASTER_IX2

Fields: SM_USER_HOME_PHN

SM_USER_SEC_HOME_PHN

Index Name: ACCOUNT_MASTER_IX3

Fields: SM_USER_MOB_PHN

SM_USER_SEC_MOB_PHN

Index Name: PK_ACCOUNT_MASTER

Fields: SM_PRI_ACCT_NUM

Act Table

The Act table is used by the ACI Proactive Risk Manager Analysis and Review system. When an alert is viewed and the Actions and Memos tab is clicked, the system displays a list of analyst actions that have occurred over a configurable retention period.

This information is stored in the Act table.

A record is added to this table each time an analyst performs one of the following activities:

- Opens/closes an alert
- Open/closes an action level ID
- Marks
- Sends a letter
- Attaches a memo
- Blocks
- Places a watch
- Calls the accountholder
- Sets a reminder
- Ices
- Forwards the alert
- Sends an email
- Adds, edits, or deletes a travel notification
- Clicks the Export icon in the toolbar

- Clicks the Account History icon in the toolbar

An action is linked to the time and date of the most recent authorization that exists at the time of the action.

The columns in the Act table (ACT) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
ALERT_CATEGORY_ID	
ALERT_PROPERTY_ID	integer
DTACTDATEKEY	datetime
LACTIONID	int
LACTIONTYPE	int
LD_QUEID	int
LPORTFOLIOID	int
LSTATE	int
LSTATUS	int
MOST_RCNT_TRAN_DATE	datetime
NREVID	int
REVIEW_SCREEN_TYPE	int
RQPA_ID	

Column Name	Data Type
SACTACTION	int
SACTNOTES	nvarchar(255)
SACTNOTES2	nvarchar(255)
SREASON_CODE	nvarchar(5)
TDDATEKEY	varchar(21)
TRACKING_ID	bigint

Index Name: IDX_ACT_ACTIONID

Fields: LACTIONID

Index Name: IDX_ACT_CLUSTER

Fields: ACTION_LEVEL_KEY
 ACTION_LEVEL_ID
 DTACTDATEKEY

Index Name: IDX_ACT_DTACTDATEKEY

Fields: DTACTDATEKEY

Index Name: IDX_ACT_REVID

Fields: NREVID

Index Name: IDX_ACT_DASHB

Fields: LACTIONTYPE
 DTACTDATEKEY

Column Descriptions

The following are the descriptions of the Act table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

1 = CARD action level

- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the master tables. It can contain a SM_PAN, SM_UAN, SM_EMPLOYEE_ID, SM_RETL_ID, SM_TERM_ID. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and is used to determine what type of value is stored in ACTION_LEVEL_KEY.

ALERT_CATEGORY_ID — Set either to NULL to indicate that the alert generated for a given transaction was never closed from a category, or to the values (that is, the ALERT_CATEGORY.ALERT_CATEGORY_IDs) that specify the categories from which the alert was closed.

ALERT_PROPERTY_ID — Stores the alert property ID when the rule was defined

DTACTDATEKEY — The date the action was taken.

LACTIONID — The action ID. It links to the LID in the ActionsText table.

LACTIONTYPE — The action type.

LD_QUEID — The queue that sent the account if the account was opened as an alert when this was the most recent transaction. It links to the LID column in the RuleQueue table.

LPORTFOLIOID — This represents the identifier of the portfolio from which the action was taken on this account. In the case of Cross Action Level actions, this column is set to -1.

LSTATE — Contains the action state.

Valid values are as follows:

0 = Off

1 = On

LSTATUS — The action status. It is linked to the LSTATUS column in the ActionsText table.

Valid values are as follows:

0 = Completed

1 = Requested

2 = Failed

3 = Submitted

MOST_RCNT_TRAN_DATE — MOST_RCNT_TRAN_DATE represents the most recent transaction (date and time stamp) seen by user from the two transaction tabs (Txn-All or Txn-Summary).

NREVID — The ID of the analyst who took action. It links to the LID in the PRM_Users table.

REVIEW_SCREEN_TYPE — The value in The type of review screen for which the action was logged.

Valid values are:

0 = Action level

1 = Cross action level

RQPA_ID — Set either to NULL to indicate that the alert generated for a given transaction was never closed from a queue, or to the values (that is, the RQPORTASSIGN.LIDs) that specify the queues from which the alert was closed.

SACTACTION — The numeric identifier for the localized name of the action level. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

SACTNOTES — The first note field that is used to add or update notes on an account.

SACTNOTES2 — The second notes field that is used to add or update notes on an account.

SREASON_CODE — The Reason Code for an action. It is populated when a user performs a BLOCK action, and it is populated with values from the SBLOCKCODE column in the AddBlockCodes table.

TDDATEKEY — Contains the transaction date in YYYYMMDD HH:MM:SS.FFF format. It is displayed in the Transaction Date column on the Actions tab of the Review screen. The Transaction Date column displays n/a if the action taken was not against a specific transaction.

For the Mark action, the Transaction Date column displays the DD_DATE of the marked or unmarked transactions. As of PRM 8.4, Mark auditing inserts one row into the Act table per marked or unmarked transaction, instead of one row for all transactions affected by the entire Mark or Unmark operation.

For the Clear/Confirm, Alert, CloseAlert, and Forward/Remind an open alert action, the Transaction Date column displays the DD_DATE of the selected transaction.

For the OpenForward from user, OpenRemind, and all other actions that are not associated with a specific transaction, the Transaction Date column displays n/a.

TRACKING_ID — Stores the tracking id generated from ALERTS_TRACKING.

Action_Level Table

The Action_Level table is used by the Analysis and Review system. It defines the columns that appear for all action levels. The availability of an action level is contingent upon licensing. This table is used by all ACI Proactive Risk Manager action levels.

The columns in the Action_Level table (ACTION_LEVEL) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_DISPLAY_NAME	int
ACTION_LEVEL_ID	int
ACTION_LEVEL_LICENSE_NAME	nvarchar(12)
ACTIVE_REVIEW_TIMEOUT_IND	bit

Column Name	Data Type
ALERT_REVIEW_TIMEOUT_INTERVAL	smallint
ALERT_TIMEOUT_IND	bit
ALTERNATE_EXPORT_LOCATION	nvarchar(255)
ALTERNATE_PRINTER_LOCATION	nvarchar(255)
DEFAULT_EXPORT_LOCATION	nvarchar(255)
DEFAULT_PRINTER_LOCATION	nvarchar(255)
DETAIL_KEY_COLUMN_NAME	varchar(30)
DETAIL_PORTFOLIO_COLUMN_NAME	varchar(30)
DETAIL_TABLE_NAME	varchar(30)
DUAL_CONTROL_OVERRIDE_IND	bit
ENABLE_DUAL_CONTROL_IND	bit
FILTER_COLUMN_LENGTH	int
FUNDS_AT_RISK_PROCEDURE_NAME	varchar(30)
MANUAL_REVIEW_TIMEOUT_IND	bit
MASTER_KEY_COLUMN_NAME	varchar(30)
MASTER_TABLE_NAME	varchar(30)
MAX_FAILED_OVERRIDE_ATTEMPTS	smallint

Column Name	Data Type
NEGATIVE_FUNDS_AT_RISK_IND	bit
NRT_SHORTWINDOW_TAB_NAME	varchar(30)
OVERRIDE_CODE	nvarchar(255)
PROFILE_CALCULATION_IND	bit
RECALCULATE_FUNDS_AT_RISK_IND	bit
RT_SHORTWINDOW_TAB_NAME	varchar(30)
SOFT_DELETE_IND	bit
STANDARD_PROFILE_CONFIG	varbinary(250)
SYSTEM_DEFINED_IND	bit
XREF_COLUMN_NAME	nvarchar(30)
XREF_DETAIL_TAB_ID	int

Index Name: **PK_ACTION_LEVEL**

Fields: ACTION_LEVEL_ID

Index Name: **ACTION_LEVEL_AK**

Fields: ACTION_LEVEL_LICENSE_NAME

Column Descriptions

The following are the descriptions of the Action_Level table columns.

ACTION_LEVEL_DISPLAY_NAME — The numeric identifier for the localized name of the action level. The locale specific value for ACTION_LEVEL_DISPLAY_NAME can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_LICENSE_NAME — The value of the License Name.

ACTIVE_REVIEW_TIMEOUT_IND — Indicates that the system is not permitted to timeout the review in which the user is currently working on.

ALERT_REVIEW_TIMEOUT_INTERVAL — The time interval in minutes before a review times out.

ALERT_TIMEOUT_IND — Indicates that alerts will be timed out on the system. When activated, it allows users to edit the other settings for Alert Timeouts.

ALTERNATE_EXPORT_LOCATION — The alternate export location, relevant to the server, where the exported transactions will be stored.

ALTERNATE_PRINTER_LOCATION — The alternate printer location, relevant to the server, where the review page and reports will be printed.

DEFAULT_EXPORT_LOCATION — The default export location, relevant to the server, where the exported transactions will be stored.

DEFAULT_PRINTER_LOCATION — The default printer location, relevant to the server, where the review page and reports will be printed.

DETAIL_KEY_COLUMN_NAME — The name of the column to use as the key to the Detail table.

DETAIL_PORTFOLIO_COLUMN_NAME — Holds the name of this action level's detail table column which contains the ID of the portfolio associated with the action level to which the transaction belongs.

DETAIL_TABLE_NAME — The name of the Detail database table.

DUAL_CONTROL_OVERRIDE_IND — Indicates whether dual control override is enabled.

ENABLE_DUAL_CONTROL_IND — Indicates whether dual control is enabled.

FILTER_COLUMN_LENGTH — The number of characters considered significant for filtering.

FUNDS_AT_RISK_PROCEDURE_NAME — The name for the funds at risk calculation stored procedure.

MANUAL_REVIEW_TIMEOUT_IND — Indicates that the Action Level review pages manually opened by a user will be timed out as well as alerts. The Do Not Timeout Actively Working Review checkbox is enabled when this indicator is true.

MASTER_KEY_COLUMN_NAME — The name of the column to use as the key to the Master table.

MASTER_TABLE_NAME — The name of the Master (demographic data) database table.

MAX_FAILED_OVERRIDE_ATTEMPTS — The maximum number of failed Override Code entry attempts allowed per user, if Dual Control Override is enabled.

NEGATIVE_FUNDS_AT_RISK_IND — Indicates whether negative funds at risk is allowed within the system.

NRT_SHORTWINDOW_TAB_NAME — The name of the ShortWindow database table for Near Real Time processing.

VERRIDE_CODE — The code (similar to a password) that controls the ability to use override functionality.

PROFILE_CALCULATION_IND — Indicates whether inactive accounts are included for Profile calculation or not.

RECALCULATE_FUNDS_AT_RISK_IND — Indicates whether funds at risk is recalculated every time or not during Mark/Unmark functionality.

RT_SHORTWINDOW_TAB_NAME — The name of the ShortWindow database table for Real Time processing.

SOFT_DELETE_IND — Indicates the current delete status of the row.

STANDARD_PROFILE_CONFIG — Configuration for Standard Profiles Jobs for each action level in JSON format

SYSTEM_DEFINED_IND — Indicates that the row was added as one of the default PRM action levels.

XREF_COLUMN_NAME — The field name that will be used to perform cross reference on the Review screen tab that is used for cross reference.

XREF_DETAIL_TAB_ID — The identifier (COMPONENT_ID) field in the PRM_UI_Component table for the Cross Reference tab.

Alerts Table

The Alerts table is used by the Analytic Gateway process. One or more records are added to the Alerts table for each transaction that violated a user defined rule. Multiple alerts may be generated if the alert falls into more than one queue. A transaction is considered *alerted* if it matches a rule criterion or if the card has been changed to the status of *watch*.

The columns in the Alerts table (ALERTS) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
ALERT_CATEGORY_ID	int
ALERT_DATE	datetime
ALERT_PROPERTY_ID	integer
DD_DATE	datetime
DD_PARTITION_DATE	date
DD_TRAN_DAT_TIM	datetime
DTPICKUP	datetime
EMAIL_AFTER_TIME	datetime
EMAIL_NOTIFICATION_IND	bit
LPORTFOLIOID	int
LRQAID	int
MD_TRAN_AMT1	money
MM_ACCT_AVAIL_BAL	money
MM_OPEN_TO_BUY	money
ND_KEY_HASH	smallint

Column Name	Data Type
ND_NEAR_TIME_SCORE	int
NOTIFY_FLAG	smallint
RECORD_SOURCE_ID	smallint
REVIEWER_ID	int
RULE_SCORE	int
RULE_TYPE	varchar(1)
SD_CASH_IND	char(1)
SD_PIN_IND	char(1)
SD_TIEBREAKER	varchar(75)

Index Name: **IDX_ALERTS_CLUSTER**

Fields: ACTION_LEVEL_KEY
 ACTION_LEVEL_ID
 LRQAID
 ALERT_CATEGORY_ID

Index Name: **IDX_ALERTS_DATE**

Fields: DD_PARTITION_DATE

Index Name: **IDX_ALERTS_PORTFOLIO**

Fields: ACTION_LEVEL_ID
 LRQAID
 ALERT_CATEGORY_ID
 LPORTFOLIOID

Index Name: **IDX_ALERTS_CANDIDATE**

Fields: ACTION_LEVEL_KEY

ACTION_LEVEL_ID
LRQAID
ALERT_CATEGORY_ID
LPORTFOLIOID
DTPICKUP

Index Name: **IDX_ALERTS_LRQAID**

Fields: DD_PARTITION_DATE
 ND_KEY_HASH
 RECORD_SOURCE_ID
 SD_TIEBREAKER
 ACTION_LEVEL_ID
 LRQAID
 LPORTFOLIOID

Index Name: **IDX_ALERT_DASHB**

Fields: LRQAID
 ALERT_CATEGORY_ID
 ALERT_DATE

Column Descriptions

The following are the descriptions of the Alerts table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The action level key. It is linked to the ACTION_LEVEL_KEY in the Alerts

table.

ALERT_CATEGORY_ID — The name of the action level if selected during rule creation. The value is linked to the Alert_Category table.

ALERT_DATE — The date and time of the alert. It is linked to the Alerts table.

ALERT_PROPERTY_ID — Stores the alert property ID when the rule was defined.

DD_DATE — The authorization date.

DD_PARTITION_DATE — Derived from DD_DATE or DD_APDATE column and contain only date information.

DD_TRAN_DAT_TIM — The date and time the transaction occurred (local terminal time).

DTPICKUP — Used for forwards and reminders and is the date and time that must be exceeded before the forward or reminder should be retrieved by the system and presented to a user.

EMAIL_AFTER_TIME — The time in minutes after which an email will be sent when categories are available in Queue/Alert Category.

EMAIL_NOTIFICATION_IND — Determines whether email option is used for Rule (with matching queue or Alert Category ID), Queue, or Alert Category ID.

LPORTFOLIOID — The portfolio ID. It links each alert to a portfolio listed in the Portfolios table.

LRQAID — The queue ID. It is linked to the LID column in the RqPortAssign table.

MD_TRAN_AMT1 — The transaction amount requested, or if the transaction is a reversal, the amount originally requested.

Amount of money to be moved between the debtor and creditor, before deduction of charges,

expressed in the currency as ordered by the initiating party.

MM_ACCT_AVAIL_BAL — The available balance. If the account is a savings account, this is the available balance of the individual account.

MM_OPEN_TO_BUY — The maximum amount of funds available (at risk) at the time of the authorization.

ND_KEY_HASH — Enables sub-partitioning on two distinct columns. If it is not used for sub-partitioning, the column is populated by a constant (for example, a hashing function). If DD_DATE is used as the base for DD_PARTITION_DATE, then SD_PAN or SD_UAN is hashed. If AP_DATE is used as the base for DD_PARTITION_DATE, then SD_RETL_ID is hashed.

ND_NEAR_TIME_SCORE — The near real time score generated by the Scoring Engine.

NOTIFY_FLAG — Indicates whether the alert is notified. This column will contain a 0 if any of the transactions associated with the alert met at least one non-Notify rule. This column will contain 1 if the transaction or transactions associated with the alert met only Notify rules.

RECORD_SOURCE_ID — The identifier of the record source as defined in the Analytic Gateway.

REVIEWER_ID — The unique identifier of the individual reviewing the alert.

RULE_SCORE — Stores the rule score value for the alert, depending on which action level the alert was created on. For example, if a transaction triggers alerts for Card and Merchant action levels, for the Card alert the RULE_SCORE field will store the ND_CARD_NRT_RULE_SCR of the transaction and for the Merchant action level RULE_SCORE will store the ND_MERCHANT_NRT_RULE_SCR value.

RULE_TYPE — Contains the type of the rule (that is, standard, profile, or real-time).

SD_CASH_IND — The cash or non-cash indicator.

SD_PIN_IND — Indicates whether a PIN was associated with this transaction.

SD_TIEBREAKER — A transaction field that make a transaction unique when more than one transaction has the same date and time. It is defined at installation.

Alerts_Tracking Table

This table tracks the alert based on alert action, by saving the existing data from ALERTS table and completing with additional information like: user, log time, unique tracking id and alert grouping (USER_ID, STATUS, CREATE_DATETIME, CHANGE_DATETIME, TRACKING_ID, QUEUE_TRACKING, CATEGORY_TRACKING).

.

The columns in the Alerts_Tracking table (ALERTS_TRACKING) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
ALERT_CATEGORY_ID	int
ALERT_DATE	datetime
ALERT_PROPERTY_ID	integer
CATEGORY_TRACKING	integer
CHANGE_DATETIME	datetime
CREATE_DATETIME	datetime
DD_DATE	datetime
DD_PARTITION_DATE	date
DD_TRAN_DAT_TIM	datetime

Column Name	Data Type
DTPICKUP	datetime
EMAIL_AFTER_TIME	datetime
EMAIL_NOTIFICATION_IND	bit
LPORTFOLIOID	int
LRQAID	int
MD_TRAN_AMT1	money
MM_ACCT_AVAIL_BAL	money
MM_OPEN_TO_BUY	money
ND_KEY_HASH	smallint
ND_NEAR_TIME_SCORE	int
NOTIFY_FLAG	smallint
QUEUE_TRACKING	integer
RECORD_SOURCE_ID	smallint
REVIEWER_ID	int
RULE_SCORE	int
RULE_TYPE	varchar(1)
SD_CASH_IND	char(1)

Column Name	Data Type
SD_PIN_IND	char(1)
SD_TIEBREAKER	varchar(75)
STATUS	
TRACKING_ID	bigint
USER_ID	integer

Index Name: PK_ALERTS_TRACKING

Fields: ACTION_LEVEL_KEY
ACTION_LEVEL_ID
LRQAID
ALERT_CATEGORY_ID
USER_ID
ALERT_DATE

Index Name: IDX_ALERTS_TRACKING_DATE

Fields: DD_PARTITION_DATE

Index Name: IDX_ALERTS_TRACKING_ID

Fields: TRACKING_ID
ACTION_LEVEL_KEY

Column Descriptions

The following are the descriptions of the Alerts_Tracking table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level

- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The action level key. It is linked to the ACTION_LEVEL_KEY in the Alerts table.

ALERT_CATEGORY_ID — The name of the action level if selected during rule creation. The value is linked to the Alert_Category table.

ALERT_DATE — The date and time of the alert. It is linked to the Alerts table.

ALERT_PROPERTY_ID — Stores the alert property ID when the rule was defined.

CATEGORY_TRACKING — Description not available.

CHANGE_DATETIME — Stores the change datetime when the alert was tracked.

CREATE_DATETIME — Stores the insert datetime when the alert was tracked.

DD_DATE — The authorization date.

DD_PARTITION_DATE — Derived from DD_DATE or DD_APDATE column and contain only date information.

DD_TRAN_DAT_TIM — The date and time the transaction occurred (local terminal time).

DTPICKUP — Used for forwards and reminders and is the date and time that must be exceeded before the forward or reminder should be retrieved by the system and presented to a user.

EMAIL_AFTER_TIME — The time in minutes after which an email will be sent when categories are available in Queue/Alert Category.

EMAIL_NOTIFICATION_IND — Determines whether email option is used for Rule (with matching queue or Alert Category ID), Queue, or Alert Category ID.

LPORTFOLIOID — The portfolio ID. It links each alert to a portfolio listed in the Portfolios table.

LRQAID — The queue ID. It is linked to the LID column in the RqPortAssign table.

MD_TRAN_AMT1 — The transaction amount requested, or if the transaction is a reversal, the amount originally requested.

Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MM_ACCT_AVAIL_BAL — The available balance. If the account is a savings account, this is the available balance of the individual account.

MM_OPEN_TO_BUY — The maximum amount of funds available (at risk) at the time of the authorization.

ND_KEY_HASH — Enables sub-partitioning on two distinct columns. If it is not used for sub-partitioning, the column is populated by a constant (for example, a hashing function). If DD_DATE is used as the base for DD_PARTITION_DATE, then SD_PAN or SD_UAN is hashed. If AP_DATE is used as the base for DD_PARTITION_DATE, then SD_RETL_ID is hashed.

ND_NEAR_TIME_SCORE — The near real time score generated by the Scoring Engine.

NOTIFY_FLAG — Indicates whether the alert is notified. This column will contain a 0 if any of the transactions associated with the alert met at least one non-Notify rule. This column will contain 1 if the transaction or transactions associated with the alert met only Notify rules.

QUEUE_TRACKING — Stores the queue grouping for all alerts opened from UI

RECORD_SOURCE_ID — The identifier of the record source as defined in the Analytic Gateway.

REVIEWER_ID — The unique identifier of the individual reviewing the alert.

RULE_SCORE — Stores the rule score value for the alert, depending on which action level the alert was created on. For example, if a transaction triggers alerts for Card and Merchant action levels, for the Card alert the RULE_SCORE field will store the ND_CARD_NRT_RULE_SCR of the transaction and for the Merchant action level RULE_SCORE will store the ND_MERCHANT_NRT_RULE_SCR value.

RULE_TYPE — Contains the type of the rule (that is, standard, profile, or real-time).

SD_CASH_IND — The cash or non-cash indicator.

SD_PIN_IND — Indicates whether a PIN was associated with this transaction.

SD_TIEBREAKER — A transaction field that make a transaction unique when more than one transaction has the same date and time. It is defined at installation.

STATUS — Stores the status of the alert when is tracked.

TRACKING_ID — Unique identifier (autoincrement ID) for tracking alert.

USER_ID — User id that perform the action from UI

Capability_Config Table

The Capability_Config table is used by the RTR Action Disposition Update capability and the RTR Profile Data Access capability.

The columns in the Capability_Config table (CAPABILITY_CONFIG) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
CAPABILITY_NAME	varchar(50)
CONFIG_NAME	varchar(50)
CONFIG_VALUE	int

Column Descriptions

The following are the descriptions of the Capability_Config table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level. For the RTR Action Disposition Update capability and the RTR Profile Data Access capability, the value is 1 (CARD action level).

CAPABILITY_NAME — The capability name. The value depends on the capability:

The value is RTRActionDispUpdate for the Real-Time Rules (RTR) Action Disposition Update capability.

The value is RTRProfileDataAccess for the Real-Time Rules (RTR) Profile Data Access capability.

CONFIG_NAME — The configuration information for the capability. The valid configuration name or names depend on the capability:

The valid configuration names for the Real-Time Rules (RTR) Action Disposition Update capability are Status, Ice, Block, Watch, and Timer.

The valid configuration names for the Real-Time Rules (RTR) Profile Data Access capability are Status and Timer.

CONFIG_VALUE — This column contains the value for the configuration name or names. The valid

values depend on the capability and the configuration name:

For the Real-Time Rules (RTR) Action Disposition Update capability and the configuration names shown below, the valid values are:

For the configuration name Status:

- 0 = The capability is not enabled (the default value).
- 1 = The capability is enabled. It is set to 1 when the capability is enabled.

For the configuration names Ice, Watch, and Block:

- 0 = The capability is not enabled for the corresponding action (the default value).
- 1 = The capability is enabled for the corresponding action. It is set to 1 when the capability is enabled for the corresponding action.

For the configuration name Timer:

- 30 = The capability is not enabled (the default value).
- 1-3600 = The range of values to which the timer can be set after the capability is enabled. The timer configuration value specifies the interval at which the MasterDisp data is moved from the NRT database to the RT database.

Note: The RTR Action Disposition Update capability is configured on the Action Level Editor (Edit) window for the CARD action level.

For the Real-Time Rules (RTR) Profile Data Access capability and the configuration names shown below, the valid values are:

For the configuration name Status:

- 0 = The capability is not enabled (the default value).
- 1 = The capability is enabled. It is set to 1 when the capability is enabled.

For the configuration name Timer:

- 60 = The capability is not enabled (the default value).
- 1-1440 = The range of values to which the timer can be set after the capability is enabled. The timer configuration value specifies the interval at which the card 31 day profile data is moved from the NRT database to the RT database.

Note: The RTR Profile Data Access capability is configured on the Action Level Editor (Edit) window for the CARD action level.

Master the RTR Master Tables

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor (Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

The columns in the Master and RTR Master tables are listed below along with the data type and the action levels that use the column. An "X" in the NRT Only column means that the corresponding column is included in the Master table, but not in the RTR Master table. In the interest of space, the following abbreviations are used to describe the master tables for the ACI Proactive Risk Manager action levels:

CARD = ACI Proactive Risk Manager for the Card action level

MER = ACI Proactive Risk Manager for the Merchant action level

UAN = ACI Proactive Risk Manager for the UAN action level

TERM = ACI Proactive Risk Manager for the Terminal action level

EMP = ACI Proactive Risk Manager for the Employee action level

UAID = ACI Proactive Risk Manager for the User Account ID action level

ACCT = ACI Proactive Risk Manager for the Account action level

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
DM_ACCTMF_DAT_TIM		datetime27							X

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
DM_ACCT_CLS_DAT		date							X
DM_ACCT_OPN_DAT		date							X
		datetime			X				
DM_CASH_REFRESH_DAT		datetime				X			
DM_CDMF_DAT_TIM		datetime	X						
DM_CLOS_DAT		datetime		X					
DM_CRD_EMBOSS		datetime	X						
DM_CRD_LAST_ADDR_CHNG		datetime	X						
DM_CRD_LAST_CRV		datetime	X						
DM_CRD_LAST_ISS		datetime	X						
DM_CRD_LAST_STAT_CHNG		datetime	X						
DM_CRD_PIN_CHNG		datetime	X						
DM_CRD_RQST_DAT		datetime	X						
DM_CUST_MSTR_DAT		datetime	X	X	X				
DM_DISPDATE	X	datetime	X	X	X	X	X		
DM_EMPMF_DAT_TIM		datetime					X		

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
DM_EMP_HIRE_DATE		datetime					X		
DM_ERMF_DAT_TIM		datetime			X				
DM_FIRST_ACTV_DAT		datetime		X					
DM_FRAUD_EFFECTIVE_DAT		datetime	X						
DM_FRST_USE_DAT_TIM		datetime	X						
DM_LAST_ACTV_DAT		datetime		X					
DM_LAST_CAMERA_SVC_DAT		datetime				X			
DM_LAST_LOGIN_DAT_TIM		datetime						X	
DM_LAST_PMNT_DAT		datetime	X						
DM_LAST_SVC_DAT		datetime				X			
DM_MB_FIRST_LOGIN_DAT_T IM		datetime27						X	
DM_MB_LAST_LOGIN_DAT_TI M		datetime27						X	
DM_MMF_DAT_TIM		datetime		X					
DM_NEXT_ISS_DAT		datetime	X						
DM_OB_FIRST_LOGIN_DAT_T IM		datetime27						X	

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
DM_OPN_DAT		datetime	X	X					
DM_ORIG_FRAUDDATE	X	datetime	X	X	X	X	X	X	X
DM_OWN_CHNG_DAT		datetime		X					
DM_RCNT_FRAUDDATE	X	datetime	X	X	X	X	X	X	X
DM_TERMMF_DAT_TIM		datetime				X			
DM_TERM_OPN_DAT		datetime				X			
DM_UAIDMF_DAT_TIM		datetime						X	
DM_USER_ACTIVE_DAT		datetime						X	
DM_USER_DOB		date							X
		datetime			X				
DM_USER_PRI_DOB		datetime	X						
DM_USER_SEC_DOB		date							X
MM_ACCT_AVAIL_BAL		money			X				X
MM_ACCT_CREDIT_LINE		money							X
MM_ACCT_HOLD_BAL		money			X				
MM_ACCT_LEDG_BAL		money			X				X

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
MM_ACCT_OVERDRFT		money							X
MM_ACH_DAILY_AMT_LIMIT		money			X				
MM_ACH_TRAN_AMT_LIMIT		money			X				
MM_AUTH_BAL		money	X						
MM_AUTH_LMT		money	X						
MM_CUR_AUTH_AMT		money	X						
MM_CUST_MSTR_AMT		money	X	X	X				
MM_EXPECT_MM_VOL		money		X					
MM_EXPECT_YY_VOL		money		X					
MM_FLR_LMT		money		X					
MM_FUNDSATRISK		money	X	X	X	X	X	X	X
MM_LAST_DEP_REF_AMT		money		X					
MM_LAST_PMNT_AMT		money	X						
MM_LIFE_HIGH_BAL_AMT		money	X						
MM_LIFE_HIGH_BATCH_AMT		money			X				
MM_LIFE_HIGH_BATCH_TRAN_AMT		money			X				

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
MM_LIFE_HIGH_CASH_ADV_AMT		money	X						
MM_LIFE_HIGH_DEP_AMT		money			X				X
MM_LIFE_HIGH_PMNT_AMT		money			X				X
MM_LIFE_HIGH_PURCH_AMT		money	X						
MM_LIFE_HIGH_TRNSFR_AMT		money			X				X
MM_LIFE_HIGH_WDL_AMT		money			X				X
MM_MB_DAILY_LIMIT		money						X	
MM_MB_DAILY_TRAN_LIMIT		money						X	
MM_MNTR_CPY		money				X			
MM_OB_DAILY_LIMIT		money						X	
MM_OB_DAILY_TRAN_LIMIT		money						X	
MM_OPEN_TO_BUY		money	X						
MM_USER_PRI_INCOME		money							X
MM_USER_SEC_INCOME		money							X
MM_WIR_DAILY_AMT_LIMIT		money			X				
MM_WIR_SINGLE_AMT_LIMIT		money			X				

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
NM_ACCT_BRCH_MGR		int			X				
NM_ACCT_NUM_PROD		int			X				X
NM_ACCT_PEND_ACT		int			X				X
NM_CRD_NUM_ISS		int	X						
NM_DISPOSITION	X	int	X	X	X	X	X		
NM_DISPREVID	X	int	X	X	X	X	X		
NM_DISPSTATUS	X	int	X	X	X	X	X		
NM_EXPECT_MM_VOL_NUM		int		X					
NM_EXPECT_YY_VOL_NUM		int		X					
NM_INUSEREVID	X	int	X	X	X	X	X		
NM_PASSWD_CHNGS		smallint						X	
NM_PEND_AUTHS		bigint	X						
NM_TERM_STATUS		int				X			
NM_TERM_TYPE		int				X			
NM_WIR_MAX_DAILY_TRANS FERS		smallint			X				
SM_ACCTMF_UPDT_TYP		varchar(1)							X

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
SM_ACCT_BHVR_SCORE		varchar(5)		X					X
SM_ACCT_BIL_ADDR_1		nvarchar(100)							X
SM_ACCT_BIL_ADDR_2		nvarchar(100)							X
SM_ACCT_BIL_ADDR_3		nvarchar(100)							X
SM_ACCT_BIL_CITY		nvarchar(100)							X
SM_ACCT_BIL_CNTRY		nvarchar(3)							X
SM_ACCT_BIL_POSTAL_CDE		nvarchar(20)							X
SM_ACCT_BIL_STATE		nvarchar(100)							X
SM_ACCT_BNK_BRANCH_ID		nvarchar(35)							X
SM_ACCT_BUS_IND		char(1)		X					
		varchar(1)							X
SM_ACCT_CAT_CDE		char(3)		X					
SM_ACCT_CRNCY_CDE		nvarchar(3)							X
SM_ACCT_MRKT_SEG		varchar(5)		X					X
SM_ACCT_PROD_CAT		nvarchar(20)							X
SM_ACCT_PROD_TYPE		nvarchar(2)							X

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
SM_ACCT_RATE		char(1)		X					
		varchar(1)							X
SM_ACCT_STAT		nvarchar(4)		X					X
SM_ACCT_TAX_ID		nvarchar(20)							X
SM_ACQ_BANK_NAM		nvarchar(15)				X			
SM_ACTVTY_STAT		char(1)		X					
SM_ACTV_INDICATOR		varchar(1)	X						
SM_ACTV_METHOD		varchar(40)	X						
SM_ALT_EMAIL_ADDR		nvarchar(254)	X	X					X
SM_BIN		varchar(12)	X	X					X
SM_CARD_TECHNOLOGY		varchar(40)	X						
SM_CDMF_UPDT_TYP		char(1)	X						
SM_CLOS_RSN_CDE		char(2)		X					
SM_CNTCT_NAM		nvarchar(40)		X					
SM_CNTCT_PHN_1		varchar(50)		X					
SM_CNTCT_PHN_2		varchar(50)		X					

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
SM_CORP_ADDR_1		nvarchar(100)		X					
SM_CORP_ADDR_2		nvarchar(100)		X					
SM_CORP_CITY		nvarchar(100)		X					
SM_CORP_CNTRY		varchar(3)		X					
SM_CORP_CONTACT_FIRST_NAM		nvarchar(100)		X					
SM_CORP_CONTACT_LAST_NAM		nvarchar(100)		X					
SM_CORP_DBA_NAM		nvarchar(140)						X	
SM_CORP_EMAIL_ADDR		nvarchar(254)		X					
SM_CORP_ID		varchar(20)		X					
SM_CORP_NAM		nvarchar(140)		X				X	
SM_CORP_PHONE_1		varchar(20)		X					
SM_CORP_PHONE_2		varchar(20)		X					
SM_CORP_POSTAL_CDE		nvarchar(20)		X					
SM_CORP_ST		nvarchar(30)		X					
SM_CORP_TAX_ID		varchar(11)		X					
SM_CRD_BHVR_SCORE		char(4)	X						

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
SM_CRD_BLK_CDE		char(1)	X						
SM_CRD_PLASTIC_TYP		char(2)	X						
SM_CRD_PROD_TYP		char(2)	X						
SM_CRD_RECLASS_CDE		char(1)	X						
SM_CRD_STAT		char(1)	X						
SM_CRED_BUR_SCR		char(8)		X					
SM_CURRENCY_CODE		varchar(3)		X					
SM_CUST_MSTR_FLD1		char(2)	X	X	X				
SM_CUST_MSTR_FLD2		char(4)	X	X	X				
SM_CUST_NUM_1		varchar(20)		X					
SM_CUST_NUM_2		varchar(20)		X					
SM_DEFAULT_LANGUAGE		varchar(5)		X					
SM_EMPLOYEE_ID		varchar(50)					X		
SM_EMPMF_UPDT_TYP		char(1)					X		
SM_EMP_DEPT		nvarchar(50)					X		
SM_EMP_LOC		nvarchar(50)					X		

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
SM_EMP_PHN_NUM		varchar(50)					X		
SM_ERMF_UPDT_TYP		char(1)			X				
SM_EXP_DAT		char(4)	X		X				
SM_E_COM_IND		char(2)		X					
SM_FIID		varchar(50)	X		X			X	X
SM_FILTER		varchar(50)	X	X	X	X	X	X	X
SM_FILTER_FLD	X	char(15)		X					
SM_FI_IND		char(10)		X					
SM_ISS_MERCH_ID_NUM		varchar(35)	X						
SM_JOB_TITLE		nvarchar(50)					X		
SM_LINK		varchar(50)			X			X	
SM_LINKED_ACCT_1		varchar(20)	X						
SM_LINKED_ACCT_2		varchar(20)	X						
SM_LINKED_ACCT_3		varchar(20)	X						
SM_MBR_NUM		nvarchar(4)	X						
SM_MB_2FA_STAT		nvarchar(30)						X	

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
SM_MB_STAT		nvarchar(20)					X		
SM_MCC_LIMIT		varchar(10)	X						
SM_MGR_ID		nvarchar(20)				X			
SM_MGR_PHN_NUM		varchar(50)				X			
SM_MMF_UPDT_TYP		char(1)		X					
SM_NORM_BUS_HH_END		char(4)		X					
SM_NORM_BUS_HH_STRT		char(4)		X					
SM_NO_REISS_REASON		varchar(40)	X						
SM_OB_2FA_STAT		nvarchar(30)					X		
SM_OB_STAT		nvarchar(20)					X		
SM_OWN_GOVT_ID		varchar(20)		X					
SM_OWN_NAM		nvarchar(40)		X					
SM_OWN_TYP		char(1)		X					
SM_PAN		varchar(50)	X						
SM_PAN_HASHED	X	varchar(64)	X						
SM_PAYM_CARD_DESCR		varchar(128)	X						

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
SM_PAYM_INSTR_CRNCY		varchar(3)	X						
SM_PHN_NUM		varchar(50)						X	
SM_PRF_LANG		nvarchar(5)			X				
		varchar(5)			X				
SM_PRI_ACCT_NUM		varchar(50)							X
SM_PRI_AGENT		nvarchar(100)							X
SM_PRI_EMAIL_ADDR		nvarchar(254)	X	X		X	X	X	X
		nvarchar(256)			X				
SM_PRI_FIRST_NAM		nvarchar(100)	X		X		X	X	X
SM_PRI_LAST_NAM		nvarchar(100)	X		X		X	X	X
SM_PRI_MDL_INL		char(2)	X		X		X		
		nvarchar(2)							X
SM_PRI_NAM_SUFEX		char(2)	X		X		X		
SM_PROD_CATEG		varchar(20)	X						
SM_PROFILE	X	varchar(9)	X	X	X	X	X	X	
SM_RETL_ADDR_1		nvarchar(100)		X					

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
SM_RETL_ADDR_2		nvarchar(100)		X					
SM_RETL_BUS_NAM		nvarchar(40)		X					
SM_RETL_CITY		nvarchar(100)		X					
SM_RETL_CLAS		char(15)		X					
SM_RETL_CNTRY		char(3)		X					
SM_RETL_DBA_NAM		nvarchar(40)		X					
SM_RETL_ID		varchar(50)		X					
SM_RETL_POSTAL_CDE		nvarchar(20)		X					
SM_RETL_ST		nvarchar(35)		X					
SM_SEASNL_CDE		char(1)		X					
SM_SEC_ADDR_1		nvarchar(100)		X	X				
SM_SEC_ADDR_2		nvarchar(100)		X	X				
SM_SEC_AGENT		nvarchar(100)							X
SM_SEC_CITY		nvarchar(100)		X	X				
SM_SEC_CNTRY		char(3)		X					
		nvarchar(3)			X				

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
SM_SEC_CORP_NAM		nvarchar(40)		X					
SM_SEC_FIRST_NAM		nvarchar(100)	X		X				X
SM_SEC_LAST_NAM		nvarchar(100)	X		X				X
SM_SEC_MDL_INL		nvarchar(2)	X		X				X
SM_SEC_NAM_SUFEX		char(2)	X		X				
SM_SEC_POSTAL_CDE		nvarchar(20)		X	X				
SM_SEC_ST		nvarchar(30)		X	X				
SM_SETL_ACCT_DETL_1		varchar(25)		X					
SM_SETL_ACCT_DETL_2		varchar(25)		X					
SM_SIC_CDE		char(4)		X					
SM_STAT		char(1)		X					
SM_STORE_NUM		char(9)		X					
SM_TAX_ID_IND		char(1)			X				
SM_TERMMF_UPDT_TYP		char(1)				X			
SM_TERM_CITY		nvarchar(100)				X			
SM_TERM_CNTRY		char(3)				X			

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
SM_TERM_ID		varchar(50)				X			
SM_TERM_NAME_LOC		nvarchar(25)				X			
SM_TERM_OWNER		nvarchar(40)				X			
SM_TERM_OWNER_ID		varchar(15)				X			
SM_TERM_POSTAL_CDE		nvarchar(20)				X			
SM_TERM_ST		nvarchar(30)				X			
SM_TYP_GOOD_SERV		nvarchar(19)		X					
SM_UAIDMF_UPDT_TYP		char(1)						X	
		varchar(1)						X	
SM_UAN		varchar(50)			X				X
SM_USER_ACCT_ID		varchar(50)						X	
SM_USER_ADDR_1		nvarchar(100)	X		X			X	X
SM_USER_ADDR_2		nvarchar(100)	X		X			X	X
SM_USER_ADDR_3		nvarchar(100)							X
SM_USER_ADNL_NAM		nvarchar(40)	X		X				
SM_USER_ADV_COLLECT		char(1)			X				

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
SM_USER_CHK_BK_BL		char(1)			X				
SM_USER_CITY		nvarchar(100)	X		X			X	X
SM_USER_CNTRY		char(3)	X		X				
		nvarchar(3)							X
		varchar(3)						X	
SM_USER_DEBIT_RENEG		char(1)			X				
SM_USER_GENDER		char(1)			X				
		varchar(1)							X
SM_USER_GOV'T_ID		varchar(20)			X				
		varchar(35)							X
SM_USER_HOME_PHN		varchar(50)	X		X				X
SM_USER_ID		nvarchar(30)	X						
SM_USER_INDUSTRY		char(3)			X				
		varchar(6)							X
SM_USER_MOB_PHN		varchar(50)	X		X			X	X
SM_USER_OTHR_NAM		nvarchar(40)	X		X				

Column Name	NRT ONLY	Data Type	CARD	MER	UAN	TERM	EMP	UAID	ACCT
SM_USER_POSTAL_CDE		nvarchar(20)	X		X			X	X
SM_USER_PREV_CRD_NUM		varchar(50)	X						
SM_USER_PREV_UNI_ACCT_NUM		varchar(20)			X				
SM_USER_PRI_GOV_ID		varchar(35)	X						
SM_USER_PRI_NAM		nvarchar(40)	X		X				
SM_USER_RESIDENT_IND		char(1)			X				
		varchar(1)							X
SM_USER_SEC_EMAIL_ADDR		nvarchar(254)						X	X
SM_USER_SEC_GENDER		varchar(1)							X
SM_USER_SEC_GOV_ID		varchar(35)			X				X
SM_USER_SEC_HOME_PHN		varchar(50)							X
SM_USER_SEC_INDUSTRY		varchar(6)							X
SM_USER_SEC_MOB_PHN		varchar(50)						X	X
SM_USER_SEC_NAM		nvarchar(40)	X		X				
SM_USER_SEC_RESIDENT_IND		varchar(1)							X
SM_USER_ST		nvarchar(100)							X

<i>Column Name</i>	<i>NRT ONLY</i>	<i>Data Type</i>	<i>CARD</i>	<i>MER</i>	<i>UAN</i>	<i>TERM</i>	<i>EMP</i>	<i>UAID</i>	<i>ACCT</i>
		nvarchar(30)	X		X			X	
SM_USER_TIMEZONE		varchar(3)						X	
SM_USER_TYP		varchar(4)						X	
SM_USER_UND_MAIL		char(1)			X				
SM_USER_WRK_PHN		varchar(50)	X		X				

Column Descriptions

The columns listed in the preceding table are described below.

DM_ACCTMF_DAT_TIM — The date and time of the last demographic data update for the account.

DM_ACCT_CLS_DAT — The date the account was closed.

DM_ACCT_OPN_DAT — The date (Account Master table) or the date and time (UAN Master table) when the account was opened.

DM_CASH_REFRESH_DAT — The cash refresh date.

DM_CDMF_DAT_TIM — Contains the date and time the customer demographic data was last modified. This column is only used with the Card action level.

DM_CLOS_DAT — The date the key account was closed.

DM_CRD_EMBOSS — The emboss, or creation, date of the most recent card.

DM_CRD_LAST_ADDR_CHNG — The date of the address change for the card or statement.

DM_CRD_LAST_CRV — The date of the last card receipt verification (CRV) maintenance. It is the date when the customer called in to verify receipt of, and activate, the card.

DM_CRD_LAST_ISS — The date the last card was issued. This is also known as the begin or commence date.

DM_CRD_LAST_STAT_CHNG — The date of the last status change for this card.

DM_CRD_PIN_CHNG — The date of the last PIN change.

DM_CRD_RQST_DAT — The date of last card request.

DM_CUST_MSTR_DAT — A date field used to hold user defined customized master file dates.

DM_DISPDATE — The display date.

DM_EMPMF_DAT_TIM — The date and time the employee demographic data was last modified.

DM_EMP_HIRE_DATE — The date in which the employee was hired.

DM_ERMF_DAT_TIM — The date and time the customer demographic data was last modified. This column is only used with the UAN action level.

DM_FIRST_ACTV_DAT — The date of the first transaction in the merchant account.

DM_FRAUD_EFFECTIVE_DAT — The date the payment card was defined as fraudulent.

DM_FRST_USE_DAT_TIM — The date when the payment card was first used.

DM_LAST_ACTV_DAT — This field contains date of most recent transaction in the merchant account.

DM_LAST_CAMERA_SVC_DAT — The last camera service date.

DM_LAST_LOGIN_DAT_TIM — The date the user last logged in to the online banking application.

DM_LAST_PMNT_DAT — The date of the last payment or the last deposit to the account.

DM_LAST_SVC_DAT — The last service date.

DM_MB_FIRST_LOGIN_DAT_TIM — The date the user first logged into Mobile Banking.

DM_MB_LAST_LOGIN_DAT_TIM — The date of the last login via mobile device.

DM_MMF_DAT_TIM — The date and time the merchant demographic data was last modified. This column is only used for the Merchant action level.

DM_NEXT_ISS_DAT — The date (YYMM) when the next card will be issued for the PAN.

DM_OB_FIRST_LOGIN_DAT_TIM — The date the user first logged into Online Banking.

DM_OPN_DAT — The date when the cardholder or merchant account was opened. This will normally represent a “customer since” or similar concept.

For Cards, this value can differ from Card Issue Date as card(s) can be issued to an already active account. If card is requested as part of opening a new account, this value and Card Issue Date would be the same.

DM_ORIG_FRAUDDATE — The date of the first fraud marking of the account.

DM_OWN_CHNG_DAT — The date that the merchant ownership changed.

DM_RCNT_FRAUDDATE — The date of the most recent adjustment to the marked status of the account. This could be another transaction being marked fraud or a transaction being cleared of suspicious activity.

DM_TERM MF_DAT_TIM — The date and time the terminal demographic data was last modified. This column is only used for the Terminal action level.

DM_TERM_OPN_DAT — The date when the terminal was deployed and became active (the date when the terminal began processing transactions).

DM_UAIDMF_DAT_TIM — The date and time the terminal demographic data was last modified.

DM_USER_ACTIVE_DAT — The activation date of the user account ID.

DM_USER_DOB — The primary account owner's date of birth.

DM_USER_PRI_DOB — The primary cardholder's date of birth.

DM_USER_SEC_DOB — The date of birth of the secondary account owner.

MM_ACCT_AVAIL_BAL — The available balance in the account. The available balance equals the available funds minus the spent funds.

A bank may sometimes include checking account cash reserve in computing the available balance. Further restrictions on funds availability may apply in a context of a specific payment instrument such as ACH or international payment transaction. Other limits may apply in accordance to government regulations or agreement between customer and financial institution.

MM_ACCT_CREDIT_LINE — The total funds available to the account (maximum spending limit). This number is independent of the amount already spent. For example, if the credit line for the account is \$20,000, the accountholder can spend up to \$20,000.

MM_ACCT_HOLD_BAL — The total value of funds that are not available to the customer. This value is the sum of transactions that have been made but that have not yet posted to the

customer's account(s). A bank may sometimes include checking account cash reserve in computing the held balance. Further restrictions on funds availability may apply in a context of a specific payment instrument such as ACH or international payment transaction. Other limits may apply in accordance to government regulations or agreement between customer and financial institution.

MM_ACCT_LEDG_BAL — The ledger balance of the account. The ledger balance is different from the available balance, which is the amount of funds available for withdrawal. The ledger balance includes any and all transactions outstanding that have not yet cleared the account. The ledger balance equals available funds minus the sum of spent funds and pending transactions.

MM_ACCT_OVERDRFT — The overdraft limit, that is, the amount of money that can be withdrawn from the account, above the accountholder's funds. For example, if the account holds \$100, and if the account's overdraft limit is \$25, then the accountholder may have an additional \$25 available to spend through overdraft protection.

MM_ACH_DAILY_AMT_LIMIT — The customer's upper limit for the total sum amount of all ACH transactions in a given day.

MM_ACH_TRAN_AMT_LIMIT — The customer's upper limit on any single ACH transaction amount.

MM_AUTH_BAL — The authorization limit. For credit accounts, this is the authorized spending limit, or the total amount that can be charged to the account over a period of time. For debit accounts, the authorized spending limit is the sum of available funds and amount available through overdraft protection. Available funds are the sum of account balance and pending deposits less pending payments.

MM_AUTH_LMT — The available credit limit over a usage period for credit accounts or ledger balance for debit accounts. Ledger balance is found by subtracting from the card's account balance the balance amount of card's pending transaction(s) for the usage period.

MM_CUR_AUTH_AMT — The total amount of purchases or withdrawals and cash advances that were authorized against the credit account during the current usage period. Usage of this field does not apply to debit accounts.

MM_CUST_MSTR_AMT — An amount field used to hold any user defined customized amount.

MM_EXPECT_MM_VOL — The expected monthly volume amount.

MM_EXPECT_YY_VOL — The expected annual volume amount.

MM_FLR_LMT — The transaction floor limit. Transaction amounts below this limit are automatically considered pre-authorized.

MM_FUNDSATRISK — The amount of funds at risk when the account was marked suspicious, if the account was marked suspicious.

MM_LAST_DEP_REF_AMT — The amount of the last deposit or refund to the merchant account.

MM_LAST_PMNT_AMT — The amount of the last payment or deposit to the account.

MM_LIFE_HIGH_BAL_AMT — The lifetime high balance amount.

MM_LIFE_HIGH_BATCH_AMT — The customer's lifetime high total amount seen across all transactions within a single batch.

MM_LIFE_HIGH_BATCH_TRAN_AMT — The customer's lifetime high amount for a transaction within a batch, regardless of transaction type.

MM_LIFE_HIGH_CASH_ADV_AMT — The lifetime high cash advance amount.

MM_LIFE_HIGH_DEP_AMT — The account's lifetime high deposit amount.

MM_LIFE_HIGH_PMNT_AMT — The account's lifetime high payment amount.

MM_LIFE_HIGH_PURCH_AMT — The account's lifetime high purchase amount.

MM_LIFE_HIGH_TRNSFR_AMT — The account's lifetime high transfer amount.

MM_LIFE_HIGH_WDL_AMT — The account's lifetime high withdrawal amount.

MM_MB_DAILY_LIMIT — The daily limit for Mobile Banking User Account ID activity, that is, the total across accounts.

MM_MB_DAILY_TRAN_LIMIT — The daily limit per transaction for User Account ID activity via Mobile Banking. This is the total per transaction.

MM_MNTR_CPY — This field contains the monetary capacity amount for the terminal.

MM_OB_DAILY_LIMIT — The daily limit for Online Banking User Account ID activity, that is, the total across accounts.

MM_OB_DAILY_TRAN_LIMIT — The daily limit per transaction for User Account ID activity via Online Banking. This is the total per transaction.

MM_OPEN_TO_BUY — The amount of total available funds at the time of the authorization. For credit accounts, total available funds are equivalent to card's credit line less total amount of authorized purchases during the usage period. For debit accounts, total available funds are equivalent to last ledger balance less balance on pending deposits and payments.

MM_USER_PRI_INCOME — The income of the primary account owner.

MM_USER_SEC_INCOME — The income of the secondary account owner.

MM_WIR_DAILY_AMT_LIMIT — The customer's upper limit for the total sum amount of all wire transactions in a given day.

MM_WIR_SINGLE_AMT_LIMIT — The customer's upper limit on any single wire transaction amount.

NM_ACCT_BRCH_MGR — The employee code for the branch manager where customer's primary account is held. If the customer has only online accounts, this value may represent the manager of the branch closest to the customer's primary address or for the manager of online accounts at the customer's bank.

NM_ACCT_NUM_PROD — The number of cards issued to the account.

NM_ACCT_PEND_ACT — The count of pending actions for the customer. This value doesn't account for monetary transactions. Examples of pending actions are address changes, check-book requests, and so on.

NM_CRD_NUM_ISS — The number of cards issued with the same PAN as the card used for this transaction that are currently active.

NM_DISPOSITION — The disposition of the transaction.

NM_DISPREVID — This column was used in PRM 7.1. It is not being populated in the PRM 8.x releases.

NM_DISPSTATUS — The disposition status of the transaction.

NM_EXPECT_MM_VOL_NUM — The expected monthly number of sales.

NM_EXPECT_YY_VOL_NUM — The expected annual number of sales.

NM_INUSEREVID — This column is currently not used.

NM_PASSWD_CHNGS — The number of times the user has changed his/her password to the online banking application.

NM_PEND_AUTHS — The number of times the card has been used during the current usage period.

NM_TERM_STATUS — Used to determine whether the terminal is active.

Valid values are:

0 = Inactive

1 = Active

NM_TERM_TYPE — The terminal type identifier. Each identifier stands for a unique terminal type. Some valid terminal types differentiated through numeric identifiers are ATM, Point of Sale (POS), and MOBILE.

NM_WIR_MAX_DAILY_TRANSFERS — The customer's upper limit for the total number of transfer transactions in a given day.

SM_ACCTMF_UPDT_TYP — The update type of the last demographic data update for the account.

SM_ACCT_BHVR_SCORE — The account behavior score assigned to the customer/account by the financial institution or independent agency. Rules and procedures of customer behavior evaluation are usually unknown to the customer and/or financial institution. If this field is used, the valid values are 00000-99999.

SM_ACCT_BIL_ADDR_1 — Line 1 (street address) of the account billing address.

Billing address is the location where any bills for the account must be sent. The billing address and shipping address often, but not always, match. For example, when purchasing online, the billing address can be different from the shipping address. A shopper may buy a gift and request that the gift be shipped to location A and that the bill be sent to location B. Another example involves a corporation that has many offices. The corporation may purchase a printer and request that it be shipped to location A and that the bill be sent to the location B (the corporate headquarters). In both examples, location B is the billing address.

SM_ACCT_BIL_ADDR_2 — Line 2 of the account billing address. See SM_ACCT_BIL_ADDR_1 for a general description and examples of the billing address.

SM_ACCT_BIL_ADDR_3 — Line 3 of the account billing address. See SM_ACCT_BIL_ADDR_1 for a general description and examples of the billing address.

SM_ACCT_BIL_CITY — The city in the account billing address. See SM_ACCT_BIL_ADDR_1 for a general description and examples of the billing address.

SM_ACCT_BIL_CNTRY — The country in the account billing address. See SM_ACCT_BIL_ADDR_1 for a general description and examples of the billing address.

SM_ACCT_BIL_POSTAL_CDE — The postal code for the account billing address. See SM_ACCT_BIL_ADDR_1 for a general description and examples of the billing address.

SM_ACCT_BIL_STATE — The state or province in the account billing address. See SM_ACCT_BIL_ADDR_1 for a general description and examples of the billing address.

SM_ACCT_BNK_BRANCH_ID — The ID of the bank branch associated with the account.

SM_ACCT_BUS_IND — A code that identifies the type of account for tax purposes.

SM_ACCT_CAT_CDE — This field contains the category of the customer account, as defined by each FI.

SM_ACCT_CRNCY_CDE — The currency in which the account is held.

SM_ACCT_MRKT_SEG — A flag indicating whether the customer is a VIP. A VIP customer will have all velocity limits waived, except for Velocity Stand-in when the issuer is not available.

SM_ACCT_PROD_CAT — Identifies the account type (for example, checking, savings, money market, investment, and so on).

SM_ACCT_PROD_TYPE — A code for the product or member type associated with this account (for example, gold or classic).

SM_ACCT_RATE — The account rate.

SM_ACCT_STAT — This field contains a flag that indicates the account's activity status.

SM_ACCT_TAX_ID — Used for business accounts. It stores the tax ID of the account owner.

SM_ACQ_BANK_NAM — The name of the acquirer bank associated with this terminal.

SM_ACTVTY_STAT — The merchant activity status.

SM_ACTV_INDICATOR — The status of whether the payment card has been through the

activation process.

SM_ACTV_METHOD — The description of the method by which the payment card was activated (for example, phone, ATM, Point of Sale, online, etc.).

SM_ALT_EMAIL_ADDR — The primary account owner's alternate, or secondary, email address.

SM_BIN — The bank identification number.

Often, this value is the first four to six digits of a credit card. The bank identification number identifies the institution issuing the card. It is critical to the correct matching of transactions to the issuer of the charge card. This prefix system also applies to debit cards, charge cards, and electronic benefit cards.

Although it is called a bank identification number, BINs are also used by other institutions, such as American Express. As increasing numbers of issuers are opting into the BIN network, the term issuer identification number (IIN) is increasingly used interchangeably with BIN.

The prefix system is also used to help identify potential security breaches or identity theft, by comparing such things as the location of the issuing institution and the address of the cardholder.

In the context of UAN, BIN helps to identify, similarly to how that is done for cards, the financial institution where the customer banks. For example, debit cards are nothing more than representations of the customer's accounts at a particular financial institution.

SM_CARD_TECHNOLOGY — The type of payment card, for example whether the payment instrument is a chip card, presented by or inferred from the customer.

SM_CDMF_UPDT_TYP — The type of update made to the customer demographic data.

SM_CLOS_RSN_CDE — The reason code identifying why the account was closed.

SM_CNTCT_NAM — The name of the merchant contact.

SM_CNTCT_PHN_1 — The merchant contact telephone number.

SM_CNTCT_PHN_2 — The merchant contact alternate telephone number.

SM_CORP_ADDR_1 — The first line of the corporation's street address.

SM_CORP_ADDR_2 — The second line of the corporation's street address.

SM_CORP_CITY — The city where corporation is located.

SM_CORP_CNTRY — Alpha representation of the country where the corporation is located.

SM_CORP_CONTACT_FIRST_NAM — The first name of corporation contact. Corporation contact can be a person, or another organization empowered to act on the corporation's behalf. Examples of the corporation contact's role are, among others, the corporation's attorney, an officer of the corporation, or a board member of the corporation.

SM_CORP_CONTACT_LAST_NAM — The last name of corporation contact. Corporation contact can be a person, or another organization empowered to act on the corporation's behalf. Examples of the corporation contact's role are, among others, the corporation's attorney, an officer of the corporation, or a board member of the corporation.

SM_CORP_DBA_NAM — The “Doing Business As” name, which is the legal term for the corporation’s trade name, or the name under which the corporation operates and by which the corporation is known or referred to in the marketplace.

The “Doing Business As” scenario is especially popular with subsidiaries and franchises, that is, businesses that represent someone other than themselves.

SM_CORP_EMAIL_ADDR — The corporation’s email address.

SM_CORP_ID — The ID of the corporation. This value is how the state, or country, identifies a business. This identifier is assigned to a business at the time of incorporation by the location (state or country) where the business is being incorporated.

SM_CORP_NAM — The formal name of the corporation or other type of business. This is the corporation’s legal name.

SM_CORP_PHONE_1 — The first phone number for the corporation.

SM_CORP_PHONE_2 — The second phone number for the corporation.

SM_CORP_POSTAL_CDE — The postal or ZIP code for the corporation.

SM_CORP_ST — Alpha representation of the state, province or region where the corporation is located.

SM_CORP_TAX_ID — The tax ID number of the corporation. In U.S., this is the employer's federal tax number that a business applies for through IRS after incorporation. The employer's federal tax number is how IRS identifies a business. Generally, this value should be the tax ID in the country that corresponds to the customer's headquarters address.

SM_CRD_BHVR_SCORE — The cardholder's behavior score. If this field is used, the valid values are 0000-9999. Scores that range from 650-750 are good. If the score is less than 650, the risk is higher.

SM_CRD_BLK_CDE — A code that indicates that a card has been blocked and the reason why. These values are user defined.

SM_CRD_PLASTIC_TYP — The type of plastic card associated with the transaction (for example, Visa or MasterCard). Any values can be accommodated with a customer-specific data dictionary.

SM_CRD_PROD_TYP — A code for the product or member type associated with this card (for example, gold or classic). Any values can be accommodated with a customer-specific data dictionary.

SM_CRD_RECLASS_CDE — A reclassification code. This code is also known as the alternate block code. Values are user-defined.

SM_CRD_STAT — A code that indicates the status of the card (for example, lost or stolen).

SM_CRED_BUR_SCR — The Credit Bureau Score.

SM_CURRENCY_CODE — The merchant's transaction currency.

SM_CUST_MSTR_FLD1 — Used to hold user defined customized data.

SM_CUST_MSTR_FLD2 — Used to hold user defined customized data.

SM_CUST_NUM_1 — An internal defined customer number, electronic banking number, or checking account number.

SM_CUST_NUM_2 — An internal defined customer number, electronic banking number, or demand deposit account number.

SM_DEFAULT_LANGUAGE — The merchant's preferred language.

SM_EMPLOYEE_ID — The unique identifier for the employee.

SM_EMPMF_UPDT_TYP — The type of update made to the employee's demographic data.

Valid values are:

A = Add

C = Change

D = Delete

SM_EMP_DEPT — The employee's department.

SM_EMP_LOC — The employee's location.

SM_EMP_PHN_NUM — The employee's phone number.

SM_ERMF_UPDT_TYP — The type of update made to the customer demographic data.

SM_EXP_DAT — The expiration date of the card (in the format YYMM). It is also referred to as the ending date.

SM_E_COM_IND — Indicates whether the merchant can accept electronic commerce transactions.

SM_FIID — The financial institution identifier (FIID) of the bank associated with the cardholder or accountholder. This field differs from SM_BIN in that while the BIN may store the prefix for the identifier, the FIID may store the full institution identifier number. Alternatively, the BIN and FIID may be used to store different types of identifiers for the same financial institution.

SM_FILTER — The Masterfile field that defines the portfolio filter. It is often referred to as the FIID or BIN filter.

SM_FILTER_FLD — The Masterfile field that defines the portfolio filter. It is often referred to as the FIID or BIN filter.

SM_FI_IND — The merchant's financial indicator.

SM_ISS_MERCH_ID_NUM — The name of the merchant who issued the payment card. This value would be relevant only for merchant-branded cards.

SM_JOB_TITLE — The employee's job title

SM_LINK — All rows that have the same value in the SM_LINK column form a linked accounts group.

SM_LINKED_ACCT_1 — Identifies the primary funding source for the card.

A card can be connected to up to three funding sources. For example, a card can be connected to a personal checking account, a personal money market account, and credit account for the person's business. Rules define the conditions under which each funding source is debited or credited.

SM_LINKED_ACCT_2 — Identifies the secondary funding source for the card. Refer to SM_LINKED_ACCT_1 for more information.

SM_LINKED_ACCT_3 — Identifies the tertiary funding source for the card. Refer to SM_LINKED_ACCT_1 for more information.

SM_MBR_NUM — A value which uniquely identifies individual holders of the same card number when multiple cards are issued with the same card number. If an institution does not use member numbers, the value in this field is 000.

SM_MB_2FA_STAT — The status of two-factor authentication settings(registered, unregistered, temp exempt, permanent exempt, or suspended) for Mobile Banking sessions.

SM_MB_STAT — The status of the User login ID for Mobile Banking, for example: Blocked, Active, or Inactive.

SM_MCC_LIMIT — A code used to access a list of parameters that restrict the payment card usage based on a range of MCC codes and transaction limits.

SM_MGR_ID — The unique identifier for the manager.

SM_MGR_PHN_NUM — The phone number for the employee's manager.

SM_MMF_UPDT_TYP — The type of the last update of customer demographic data.

SM_NORM_BUS_HH_END — The closing time of normal business hours for this merchant.

SM_NORM_BUS_HH_STRT — The starting time of normal business hours for this merchant.

SM_NO_REISS_REASON — The reason why the card was not selected for reissue.

SM_OB_2FA_STAT — The status of two-factor authentication settings(registered, unregistered, temp exempt, permanent exempt, or suspended) for Online Banking sessions.

SM_OB_STAT — The status of the User login ID for Online Banking, for example: Blocked, Active, or Inactive.

SM_OWN_GOVT_ID — The merchant's tax or government ID number.

SM_OWN_NAM — The name of the owner of the business.

SM_OWN_TYP — The ownership type.

SM_PAN — The card number (PAN) that identifies the card.

SM_PAN_HASHED — Contains the hashed value of the SM_PAN column. The Secure Hash Algorithm 2 (SHA-2) algorithm, SHA-256 function is used.

SM_PAYM_CARD_DESCR — The description of the payment card.

SM_PAYM_INSTR_CRNCY — The currency associated with the payment instrument.

SM_PHN_NUM — The phone number of the user tied to the user account ID.

SM_PRF_LANG — The customer's preferred language.

SM_PRI_ACCT_NUM — The primary account number. It is the key to the Account Master table and to the Account RTR Master table.

SM_PRI_AGENT — Used for corporate accounts. It stores the full name of the corporation's primary agent.

An agent is the person authorized by the corporation to act legally on its behalf. This person is authorized to participate in legal and financial transactions.

SM_PRI_EMAIL_ADDR — The email address for the primary account owner.

SM_PRI_FIRST_NAM — The first name of the primary account owner.

SM_PRI_LAST_NAM — The last name of the primary account owner.

SM_PRI_MDL_INL — The middle initial of the primary account owner.

SM_PRI_NAM_SUFX — The primary account owner's name suffix (for example, Jr. or Sr.).

SM_PROD_CATEG — The card product category description (for example, debit, credit, pre-paid or store branded). Any values can be accommodated with a customer-specific data dictionary.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

SM_RETL_ADDR_1 — The first line of the retailer's street address.

SM_RETL_ADDR_2 — The second line of the retailer's street address.

SM_RETL_BUS_NAM — The merchant business name.

SM_RETL_CITY — The city in which the retailer is located.

SM_RETL_CLAS — An identifier used to group or classify retailers. It can be a concatenation of corporate, regional, principal, associate or chain.

SM_RETL_CNTRY — The country in which the retailer is located.

SM_RETL_DBA_NAM — The merchant doing business as name.

SM_RETL_ID — The unique identifier of the retailer.

SM_RETL_POSTAL_CDE — The postal or ZIP code where the retailer is located.

SM_RETL_ST — The state where the retailer is located.

SM_SEASNL_CDE — A seasonal code for billing information.

SM_SEC_ADDR_1 — The first line of the secondary street address.

SM_SEC_ADDR_2 — The second line of the secondary street address.

SM_SEC_AGENT — Used for corporate accounts. It stores the full name of the corporation's secondary agent.

An agent is the person authorized by the corporation to act legally on its behalf. This person is authorized to participate in legal and financial transactions. The secondary agent has potentially fewer authorized duties than the primary agent and is usually engaged if the primary agent is unavailable.

SM_SEC_CITY — The city for the secondary address.

SM_SEC_CNTRY — The country for the secondary address.

SM_SEC_CORP_NAM — The secondary or corporate name of the merchant. Most often, this would be the merchant name in legal and tax documents.

SM_SEC_FIRST_NAM — The first name of the secondary account owner.

SM_SEC_LAST_NAM — The last name of the secondary account owner.

SM_SEC_MDL_INL — The middle initial of the secondary account owner.

SM_SEC_NAM_SUFX — The name suffix (for example, Jr. or Sr.) of a secondary account owner.

SM_SEC_POSTAL_CDE — The postal or ZIP code for the address of the secondary account owner.

SM_SEC_ST — This field contains the state, province, or region for the street address of the secondary account owner.

SM_SETL_ACCT_DETL_1 — The bank and branch number of the settlement account.

SM_SETL_ACCT_DETL_2 — The bank and branch number of the settlement account.

SM_SIC_CDE — The Standard Industrial Classification (SIC) code indicating the retailer's line of business. Valid values are per industry standards.

SM_STAT — The merchant status. This value is independent of merchant activity status in that merchant can be open but inactive, merchant can be open and active, merchant can be closed and inactive, etc.

SM_STORE_NUM — The store number or identifier.

SM_TAX_ID_IND — This field contains the status indicating whether the customer's government ID is equivalent to the customer's Tax ID in the customer's country of residence.

SM_TERMMF_UPDT_TYP — The type of the last update of terminal demographic data.

Valid values are:

A = Add

C = Change

D = Delete

SM_TERM_CITY — The city in which the terminal is located.

SM_TERM_CNTRY — The ISO code for the country in which the terminal is located.

SM_TERM_ID — Identifies the terminal where the transaction originated.

SM_TERM_NAME_LOC — The name and location of the terminal from which this transaction originated. The name and location are printed on receipts to comply with Regulation E.

SM_TERM_OWNER — The name of the terminal owner. This is typically used to identify the principal owner of a terminal. The terminal may be owned by a bank or financial institution, or it may be owned by an independent service provider. Bank-owned processors normally support only bank-owned terminals, whereas the independent processors support merchant-owned terminals.

SM_TERM_OWNER_ID — The code that identifies the retailer card acceptor that owns or hosts this terminal.

SM_TERM_POSTAL_CDE — The postal or ZIP code where the terminal is located.

SM_TERM_ST — The state, province, or region in which the terminal is located.

SM_TYP_GOOD_SERV — The primary goods or services offered.

SM_UAIDMF_UPDT_TYP — The type of the last demographic data update.

SM_UAN — The Universal Account Number.

SM_USER_ACCT_ID — The user's account ID for the online banking application.

SM_USER_ADDR_1 — The first line of the residential address of the account owner.

SM_USER_ADDR_2 — The second line of the residential address of the account owner.

SM_USER_ADDR_3 — The third line of the residential address of the account owner.

SM_USER_ADNL_NAM — Accountholder's address for the other half of the transaction.

SM_USER_ADV_COLLECT — An indicator about whether the universal account (customer) has any accounts that are under review by a collection agency, such as for overdue debts.

SM_USER_CHK_BK_BL — The checkbook block indicator.

SM_USER_CITY — The city of residence of the account owner.

SM_USER_CNTRY — The country of residence of the account owner.

SM_USER_DEBIT_RENEG — The debt renegotiation indicator.

SM_USER_GENDER — A code that identifies the gender of the primary account owner.

SM_USER_GOV_T_ID — The Social Security Number (SSN) or government ID of the primary account owner.

SM_USER_HOME_PHN — The home phone number of the primary account owner.

SM_USER_ID — Another method for customer identification. It can be used for an ID number, password, place of birth etc.

SM_USER_INDUSTRY — The industry or occupation of the primary account owner.

SM_USER_MOB_PHN — The mobile phone number of the primary account owner.

SM_USER_OTHR_NAM — The primary cardholder's or accountholder's unique information. This column can also contain the name of an additional individual associated with the customer or cardholder. Examples of associates are an attorney, a guardian or a ward, or a spouse.

SM_USER_POSTAL_CDE — The postal or ZIP code of the residence of the account owner.

SM_USER_PREV_CRD_NUM — A card number (PAN), which was replaced by the card used for the current transaction.

SM_USER_PREV_UNI_ACCT_NUM — The customer's universal account number (UAN) that was replaced by the UAN associated with the current transaction. A customer's UAN may change due to suspicion of fraud against previous account number(s), due to customer's bank's merger into another institution, or due to a customer closing old account and opening a new account some time later at the same institution.

SM_USER_PRI_GOV_T_ID — The cardholder's or accountholder's social security number or government ID.

SM_USER_PRI_NAM — The cardholder's or accountholder's full name.

SM_USER_RESIDENT_IND — The indicator of whether the primary account owner is a resident of the country where his or her financial institution (as represented by the value in the SM_FIID field) is headquartered.

SM_USER_SEC_EMAIL_ADDR — The email address of the secondary account owner.

SM_USER_SEC_GENDER — A code that identifies the gender of the secondary account owner.

SM_USER_SEC_GOV_ID — The Social Security Number (SSN) or government ID of the secondary account owner.

SM_USER_SEC_HOME_PHN — The home phone number of the secondary account owner.

SM_USER_SEC_INDUSTRY — Identifies the industry or occupation of the secondary account owner.

SM_USER_SEC_MOB_PHN — The mobile phone number of the secondary account owner.

SM_USER_SEC_NAM — The full name of an additional cardholder or accountholder or the full name of a cardholder's or accountholder's associate.

SM_USER_SEC_RESIDENT_IND — The indicator of whether the secondary account owner is a resident of the country where his or her financial institution (as represented by the value in the SM_FIID field) is headquartered.

Valid values are:

R = Resident

N = Non-resident

SM_USER_ST — This field contains the state, province, or region of residence of the account owner.

SM_USER_TIMEZONE — The user's time zone.

SM_USER_TYP — Identifies a bank user vs. customer user.

SM_USER_UND_MAIL — Indicates whether customer correspondence is pending.

SM_USER_WRK_PHN — The cardholder's or accountholder's work telephone number.

DASHB_AP_ACT Table

The DASHB_AP_ACT table is a snapshot of ACT table and is used in dashboard Analyst Performance report

The columns in the DASHB_AP_ACT table (DASHB_AP_ACT) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ALERT_CATEGORY_ID	
DTACTDATEKEY	datetime
LPORTFOLIOID	int
NREVID	int
RQPA_ID	

Index Name: **IDX_DASHB_AP_ACT_CLUSTER**

Fields: LPORTFOLIOID
 DTACTDATEKEY

Column Descriptions

The following are the descriptions of the DASHB_AP_ACT table columns.

ALERT_CATEGORY_ID — Set either to NULL to indicate that the alert generated for a given transaction was never closed from a category, or to the values (that is, the ALERT_CATEGORY.ALERT_CATEGORY_IDs) that specify the categories from which the alert was

closed.

DTACTDATEKEY — The date the action was taken.

LPORTFOLIOID — This represents the identifier of the portfolio from which the action was taken on this account. In the case of Cross Action Level actions, this column is set to -1.

NREVID — The ID of the analyst who took action. It links to the LID in the PRM_Users table.

RQPA_ID — Set either to NULL to indicate that the alert generated for a given transaction was never closed from a queue, or to the values (that is, the RQPORTASSIGN.LIDs) that specify the queues from which the alert was closed.

Detail Table

The Detail table is used by the Analytic Gateway process. It contains the authorization history information that stores a 90 day history table for the purpose of executing rules and queues.

Proactive Risk Manager configures a variable for every input field. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing.

When a user wants to use an input variable in aggregate, rule, or queue creation, they can type the variable name or select a variable from the Variables dropdown list on any Aggregate, Rule, or Queue Editor (Add) screen. The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle. See the **ACI Proactive Risk Manager Team Administrator User Guide** for details.

Refer to the "Detail Table" topic for a list of the columns in the Detail table and for descriptions of those columns.

Listed below are the indexes for the Detail table.

Index Name: **IDX_DETAIL_CLUSTER**

Fields: ND_KEY_HASH
 RECORD_SOURCE_ID
 SD_TIEBREAKER

Index Name: **IDX_DETAIL_RT_RULE2**

Fields: ND_REAL_TIME_RULE_FIRED

Index Name: IDX_DETAIL_SM_CLIENT_IP

Fields: SD_CLIENT_IP

DD_DATE

ND_TRAN_ID

SD_TRAN_CDE

Index Name: IDX_DETAIL_SM_DEVICE_ID

Fields: SD_DEVICE_ID

DD_DATE

ND_TRAN_ID

SD_TRAN_CDE

Index Name: IDX_DETAIL_SM_EMPLOYEE_ID

Fields: SD_EMPLOYEE_ID

DD_DATE

ND_TRAN_ID

SD_TRAN_CDE

Index Name: IDX_DETAIL_SM_PAN

Fields: SD_PAN

DD_DATE

ND_TRAN_ID

SD_TRAN_CDE

Index Name: IDX_DETAIL_SM_PRI_ACCT_NUM

Fields: SD_PRI_ACCT_NUM

DD_DATE

ND_TRAN_ID

SD_TRAN_CDE

Index Name: IDX_DETAIL_SM_RETL_ID

Fields: SD_RETL_ID

DD_DATE

ND_TRAN_ID

SD_TRAN_CDE

Index Name: IDX_DETAIL_SM_SEC_ACCT_NUM

Fields: SD_SEC_ACCT_NUM

DD_DATE

ND_TRAN_ID

SD_TRAN_CDE

Index Name: IDX_DETAIL_SM_TERM_ID

Fields: SD_TERM_ID

DD_DATE

ND_TRAN_ID

SD_TRAN_CDE

Index Name: IDX_DETAIL_SM_UAN

Fields: SD_UAN

DD_DATE

ND_TRAN_ID

SD_TRAN_CDE

Index Name: IDX_DETAIL_SM_USER_ACCT_ID

Fields: SD_USER_ACCT_ID

DD_DATE

ND_TRAN_ID

SD_TRAN_CDE

Listed below are the column name and data type for each column in the Detail, FraudDetail, ShortWindow, and RT_ShortWindow tables. A check mark indicates that the table includes the corresponding column; a blank cell indicates that the table does not include the corresponding column.

In the interest of space, the following abbreviations are used in place of the full table names:

DTL = The Detail table

FDTL = The FraudDetail table

SW = The ShortWindow table

RTSW = The RT_ShortWindow table

Column Name	Data Type	DTL	FDTL	SW	RTSW
DD_ACH_BATCH_EFF_DAT	datetime				X
DD_ACH_BATCH_RELEASE_DAT_TIM	datetime	X	X	X	X
DD_ACQ_ICHG_SETL_DAT	datetime	X	X	X	
DD_APDATE	datetime	X	X	X	X
DD_CRD_EMOSS	datetime	X	X	X	
DD_CRD_LAST_ADDR_CHNG	datetime	X	X	X	X
DD_CRD_LAST_CRV	datetime	X	X	X	
DD_CRD_LAST_ISS	datetime	X	X	X	
DD_CRD_LAST_STAT_CHNG	datetime	X	X	X	
DD_CRD_PIN_CHNG	datetime	X	X	X	X
DD_CRD_RQST_DAT	datetime	X	X	X	X
DD_CREDITOR_ALIAS_LAST_UPDATE	datetime	X	X	X	X
DD_CREDITOR_ALIAS_REGISTER_DAT	datetime	X	X	X	X
DD_CUST_TRAN_DAT	datetime	X	X	X	X
DD_DATE	datetime	X	X	X	X
DD_DDAY	datetime	X	X		

Column Name	Data Type	DTL	FDTL	SW	RTSW
DD_EXP_DAT	datetime	X	X	X	X
DD_IP_FRAUD_FLG	datetime27	X	X	X	X
DD_IP_MAL_FLG	datetime27	X	X	X	X
DD_MAL_DEVICE_FLG	datetime27	X	X	X	X
DD_PARTITION_DATE	date	X	X	X	X
DD_POST_DAT	datetime	X	X	X	X
DD_RCV_DAT	datetime	X	X	X	
DD_REQ_EXECUTION_DATE	datetime	X	X	X	X
DD_RULEPROC_DATE	datetime27	X	X		
DD_TRAN_DAT_TIM	datetime	X	X	X	X
DD_USER_ACTIVE_DAT	datetime				X
DD_WIR_CREATION_DAT_TIM	datetime	X	X	X	X
DD_WIR_LAST_MODIFY_DAT_TIM	datetime	X	X	X	X
DD_WIR_RELEASE_DAT_TIM	datetime	X	X	X	X
MD_ACH_BATCH_CREDIT_AMT	money	X	X	X	X
MD_ACH_BATCH_DEBIT_AMT	money	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
MD_CHK_AMT	money	X	X	X	X
MD_CUST_TRAN_AMT1	money	X	X	X	X
MD_CUST_TRAN_AMT2	money	X	X	X	X
MD_CUST_TRAN_AMT3	money	X	X	X	X
MD_CUST_TRAN_AMT4	money	X	X	X	X
MD_TRAN_AMT1	money	X	X	X	X
MD_TRAN_AMT2	money	X	X	X	X
MD_TRAN_AMT3	money	X	X	X	
MD_TRAN_AMT4	money	X	X	X	X
MD_TRAN_AMT5	money	X	X	X	X
MM_ACCT_AVAIL_BAL	money				X
MM_AUTH_LMT	money				X
MM_OPEN_TO_BUY	money				X
ND_ACCOUNT_NRT_RULE_SCR	int	X	X	X	X
ND_ACH_CREDIT_TRANS_IN_BATCH	int	X	X	X	X
ND_ACH_DEBIT_TRANS_IN_BATCH	int	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
ND_ACH_NUM_TRANS_IN_BATCH	bigint	X	X	X	X
ND_AUTH_TRIES	smallint	X	X	X	X
ND_CARD_NRT_RULE_SCR	int	X	X	X	X
ND_CAVV_AAV	smallint	X	X	X	
ND_CHK_NUM	bigint	X	X	X	X
ND_CHK_RANGE_BEGIN	bigint	X	X	X	X
ND_CHK_RANGE_END	bigint	X	X	X	X
ND_CHK_ROUT_NUM	bigint	X	X	X	
ND_CRD_NUM_ISS	int	X	X	X	
ND_CRNCY_CONV_EXP	int	X	X	X	
ND_CRNCY_CONV_RATE	money	X	X	X	X
ND_CUST_SCORE	smallint	X	X	X	X
ND_EMPLOYEE_IS_KEY	int	X	X		
ND_EMPLOYEE_NRT_RULE_SCR	int	X	X	X	X
ND_EXCHANGE_RATE	float	X	X	X	X
ND_KEY_HASH	smallint	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
ND_MERCHANT_NRT_RULE_SCR	int	X	X	X	X
ND_NEAR_TIME_SCORE	int	X	X	X	
ND_NEAR_TIME_SCORE_2	int	X	X	X	
ND_NEAR_TIME_SCORE_3	int	X	X	X	
ND_NRT_REASON_CODE_1	int	X	X	X	
ND_NRT_REASON_CODE_2	int	X	X	X	
ND_NRT_REASON_CODE_2_1	int	X	X	X	
ND_NRT_REASON_CODE_2_2	int	X	X	X	
ND_NRT_REASON_CODE_2_3	int	X	X	X	
ND_NRT_REASON_CODE_3	int	X	X	X	
ND_NRT_REASON_CODE_3_1	int	X	X	X	
ND_NRT_REASON_CODE_3_2	int	X	X	X	
ND_NRT_REASON_CODE_3_3	int	X	X	X	
ND_PAN_IS_KEY	int	X	X		
ND_PIP_RESPONSE_REQUEST	int	X	X	X	X
ND_PRI_ACCT_NUM_IS_KEY	int	X	X		

Column Name	Data Type	DTL	FDTL	SW	RTSW
ND_REAL_TIME_RULE_FIRED	int	X	X	X	X
ND_REAL_TIME_SCORE	int	X	X	X	X
ND_REAL_TIME_SCORE_2	int	X	X	X	X
ND_REAL_TIME_SCORE_3	int	X	X	X	X
ND_RETL_IS_KEY	int	X	X		
ND_RTE_STAT	int	X	X	X	
ND_SRV_RESTR_CDE	smallint	X	X	X	X
ND_TERMINAL_NRT_RULE_SCR	int	X	X	X	X
ND_TERM_IS_KEY	int	X	X		
ND_TLR_APPR_CDE	int	X	X	X	
ND_TRAN_ID	bigint	X	X		
ND_UAID_NRT_RULE_SCR	int	X	X	X	X
ND_UAN_IS_KEY	int	X	X		
ND_UAN_NRT_RULE_SCR	int	X	X	X	X
ND_USER_ACCT_ID_IS_KEY	int	X	X		
ND_VISA_ADV_AUTH_SCORE	smallint	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
RECORD_SOURCE_ID	smallint	X	X	X	X
SD_ABA_NUM	varchar(12)	X	X	X	X
SD_ACCEPT	varchar(60)	X	X	X	
SD_ACCEPT_CHARSET	varchar(35)	X	X	X	
SD_ACCEPT_ENCODING	varchar(35)	X	X	X	
SD_ACCEPT_LANGUAGE	varchar(25)	X	X	X	
SD_ACCT_SEC_MOB_PHN	varchar(50)	X	X	X	X
SD_ACCT_STAT	char(1)	X	X	X	
SD_ACCT_TYP	char(3)	X	X	X	X
SD_ACH_APPLICATION	varchar(4)	X	X	X	
SD_ACH_BATCH_CO_DATE_DESCR	nvarchar(8)	X	X	X	
SD_ACH_BATCH_CO_ENTRY_DESCR	varchar(10)	X	X	X	X
SD_ACH_BATCH_OFFSET_TYP	varchar(1)	X	X	X	X
SD_ACH_BATCH_TYP	varchar(20)	X	X	X	X
SD_ACH_IAT_CNTRY_CDE	varchar(3)	X	X	X	X
SD_ACH_NUM	char(4)	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_ACQ_INST_ID_NUM	char(11)	X	X	X	X
SD_ADDENDA	varchar(80)	X	X	X	X
SD_ADDR_VRFY_FLG	char(1)	X	X	X	X
SD_AGENT_NAME	varchar(20)	X	X	X	
SD_AGENT_TYPE	varchar(15)	X	X	X	
SD_AGENT_VERSION	varchar(20)	X	X	X	
SD_APPRV_CDE	char(8)	X	X	X	X
SD_APP_SOURCE	varchar(2)	X	X	X	
SD_AUTH_RSN	varchar(1)	X	X	X	X
SD_AUTH_SRC	char(1)	X	X	X	X
SD_AUTH_TYPE	varchar(1)	X	X	X	X
SD_AUTH_UNAUTH_IND	char(1)	X	X	X	X
SD_B24_SRC	char(3)	X	X	X	X
SD_BATCH_ID	varchar(20)	X	X	X	X
SD_BATCH_ONLINE_IND	char(1)	X	X	X	X
SD_BATCH_TRAN_ID	varchar(20)	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_BEN_WIR_ACCT_ADDR1	nvarchar(40)	X	X	X	
SD_BEN_WIR_ACCT_ADDR2	nvarchar(40)	X	X	X	
SD_BEN_WIR_ACCT_IDENT	nvarchar(40)	X	X	X	X
SD_BEN_WIR_ACCT_NAM	nvarchar(40)	X	X	X	X
SD_BEN_WIR_CNTRY_CDE	varchar(3)	X	X	X	X
SD_BEN_WIR_CRNCY_CDE	varchar(3)	X	X	X	X
SD_BEN_WIR_INST_ADDR1	nvarchar(40)	X	X	X	
SD_BEN_WIR_INST_ADDR2	nvarchar(40)	X	X	X	
SD_BEN_WIR_INST_ID_NUM	varchar(11)	X	X	X	X
SD_BEN_WIR_INST_NAM	nvarchar(20)	X	X	X	
SD_BIN	char(12)				X
	varchar(12)	X	X	X	
SD_BRCH_ID_NUM	char(4)	X	X	X	
SD_BRCH_REGN	char(2)	X	X	X	
SD_BRCH_RSK_IND	char(1)	X	X	X	
SD_BTCH_ID	char(15)	X	X	X	

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_CASE_CREATOR	nvarchar(35)	X	X	X	X
SD_CASH_IND	char(1)	X	X	X	X
SD_CHK_ACCT_NUM	varchar(20)	X	X	X	X
SD_CHK_SERIAL_NUM	varchar(15)	X	X	X	X
SD_CHK_SERIAL_NUM_NEW	varchar(15)	X	X	X	X
SD_CHK_SERIAL_NUM_OLD	varchar(15)	X	X	X	X
SD_CLIENT_IP	varchar(39)	X	X	X	X
SD_CLIENT_LANGUAGE	varchar(5)	X	X	X	X
SD_COMPLETE_TRACK2_DATA	char(1)	X	X	X	
SD_CRD_ACCPT_ID_NUM	varchar(15)	X	X	X	X
SD_CRD_BLK_CDE	char(1)	X	X	X	
SD_CRD_PLASTIC_TYP	char(2)	X	X	X	
SD_CRD_PROD_TYP	char(2)	X	X	X	X
SD_CRD_SEQ_NUM	varchar(3)	X	X	X	X
SD_CRD_STAT	char(1)	X	X	X	
SD_CRD_VRFY_DIGITS	char(4)	X	X	X	

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_CRD_VRFY_FLG	char(1)	X	X	X	X
SD_CREDITOR_ALIAS	nvarchar(140)	X	X	X	X
SD_CREDITOR_ALIAS_ACCT_ID_TYPE	nvarchar(35)	X	X	X	X
SD_CREDITOR_ALIAS_ACCT_ISSUER	nvarchar(35)	X	X	X	X
SD_CREDITOR_ALIAS_SHORT_NAME	nvarchar(140)	X	X	X	X
SD_CREDITOR_ALIAS_TYPE	nvarchar(35)	X	X	X	X
SD_CR_DB_IND	char(1)	X	X	X	X
SD_CUST_HEADER	varchar(30)	X	X	X	
SD_CUST_TRAN_FLD	char(4)	X	X	X	
	varchar(4)				X
SD_CVD_PRESENT_FLG	char(1)	X	X	X	X
SD_DATEKEY	varchar(21)	X	X	X	X
SD_DEVICE_BRWS_PLGIN	nvarchar(200)	X	X	X	X
SD_DEVICE_COOKIE	nvarchar(255)	X	X	X	X
SD_DEVICE_COOKIE_ENBL	varchar(1)	X	X	X	X
SD_DEVICE_CPU_TYPE	nvarchar(15)	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_DEVICE_DISPL	nvarchar(50)	X	X	X	X
SD_DEVICE_DOTNET	nvarchar(50)	X	X	X	X
SD_DEVICE_FLASH	nvarchar(50)	X	X	X	X
SD_DEVICE_FONT	nvarchar(1000)	X	X	X	X
SD_DEVICE_HTTP	nvarchar(1000)	X	X	X	X
SD_DEVICE_ID	nvarchar(50)	X	X	X	X
SD_DEVICE_IMEI	nvarchar(16)	X	X	X	X
SD_DEVICE_IMSI	nvarchar(15)	X	X	X	X
SD_DEVICE_JAVA	nvarchar(50)	X	X	X	X
SD_DEVICE_MEM	nvarchar(20)	X	X	X	X
SD_DEVICE_MSISDN	nvarchar(15)	X	X	X	X
SD_DEVICE_NAME	varchar(20)	X	X	X	X
SD_DEVICE_PDF	nvarchar(50)	X	X	X	X
SD_DEVICE_RISK_SCORE	nvarchar(20)	X	X	X	X
SD_DEVICE_SILVERLIGHT	nvarchar(50)	X	X	X	X
SD_DEVICE_STOR	nvarchar(50)	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_DEVICE_SUPERCOOKIE	varchar(100)	X	X	X	X
SD_DEVICE_VERSION	varchar(20)	X	X	X	
SD_EMPLOYEE_ID	varchar(50)	X	X	X	X
SD_EMV_CRD_VRFY_RSLTS	varchar(11)	X	X	X	X
SD_EMV_TERM_TYPE	char(2)	X	X	X	X
SD_EMV_TVR	varchar(19)	X	X	X	X
SD_EMV_USER_FILLER	char(15)	X	X	X	X
SD_END_TO_END_IDENT	nvarchar(35)	X	X	X	X
SD_EVENT_DETAIL1	varchar(40)	X	X	X	X
SD_EVENT_DETAIL2	varchar(40)	X	X	X	X
SD_EVENT_TYP	varchar(3)	X	X	X	X
SD_EXT_AUTH_RESULT	nvarchar(20)	X	X	X	X
SD_EXT_AUTH_TYPE	nvarchar(20)	X	X	X	X
SD_E_COM_FLG	char(1)	X	X	X	X
SD_FIID	char(50)				X
	varchar(50)	X	X	X	

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_FILLER_FIELD	nvarchar(40)	X	X	X	
SD_FRGN_FLG	char(1)	X	X	X	
SD_FRWD_INST_ID_NUM	char(11)	X	X	X	
SD_HOST_DECISION	varchar(8)	X	X	X	X
SD_IBK1_ACCT_IDENT	varchar(40)	X	X	X	X
SD_IBK1_CNTRY_CDE	varchar(3)	X	X	X	X
SD_IBK1_CRNCY_CDE	varchar(3)	X	X	X	X
SD_IBK1_INST_ADDR1	nvarchar(40)	X	X	X	
SD_IBK1_INST_ADDR2	nvarchar(40)	X	X	X	
SD_IBK1_INST_ID_NUM	varchar(11)	X	X	X	X
SD_IBK1_INST_NAM	nvarchar(40)	X	X	X	
SD_IBK2_ACCT_IDENT	varchar(40)	X	X	X	
SD_IBK2_CNTRY_CDE	varchar(3)	X	X	X	
SD_IBK2_CRNCY_CDE	varchar(3)	X	X	X	
SD_IBK2_INST_ADDR1	nvarchar(40)	X	X	X	
SD_IBK2_INST_ADDR2	nvarchar(40)	X	X	X	

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_IBK2_INST_ID_NUM	varchar(11)	X	X	X	
SD_IBK2_INST_NAM	nvarchar(40)	X	X	X	
SD_INSTRUCTED_AGT	nvarchar(35)	X	X	X	X
SD_INSTRUCTED_REIMB_AGT	nvarchar(35)	X	X	X	X
SD_INSTRUCTING_AGT	nvarchar(35)	X	X	X	X
SD_INSTRUCTING_REIMB_AGT	nvarchar(35)	X	X	X	X
SD_INSTRUCTION_IDENT	nvarchar(35)	X	X	X	X
SD_INSTR_CREDITOR_AGT	nvarchar(4)	X	X	X	X
SD_INSTR_NEXT_AGT	nvarchar(4)	X	X	X	X
SD_INST_ID_NUM	char(11)	X	X	X	
SD_INTERNTL_IND	varchar(1)	X	X	X	X
SD_INVESTIGATION_TEXT	nvarchar(140)	X	X	X	X
SD_INVESTIGATION_TYPE	nvarchar(35)	X	X	X	X
SD_IP_CITY	nvarchar(100)	X	X	X	X
SD_IP_CNTRY	nvarchar(3)	X	X	X	X
SD_IP_DOM	nvarchar(63)	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_IP_FRAUD_FLG	varchar(1)	X	X	X	X
SD_IP_LAT	varchar(12)	X	X	X	X
SD_IP_LONG	varchar(12)	X	X	X	X
SD_IP_MAL_CAT	nvarchar(35)	X	X	X	X
SD_IP_MAL_FLG	varchar(1)	X	X	X	X
SD_IP_MAL_TYPE	nvarchar(35)	X	X	X	X
SD_IP_POSTAL_CDE	varchar(20)	X	X	X	X
SD_IP_PROXY_CAT	nvarchar(35)	X	X	X	X
SD_IP_PROXY_FLG	varchar(1)	X	X	X	X
SD_IP_RISK_SCORE	nvarchar(20)	X	X	X	X
SD_IP_STATE	nvarchar(100)	X	X	X	X
SD_IP_TYP	varchar(1)	X	X	X	X
SD_ISP_NAM	nvarchar(100)	X	X	X	X
SD_LOGIN_TOKEN_FLG	varchar(1)	X	X	X	X
SD_MAL_DEVICE_CAT	nvarchar(35)	X	X	X	X
SD_MAL_DEVICE_FLG	varchar(1)	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_MAL_DEVICE_TYPE	nvarchar(35)	X	X	X	X
SD_MBR_NUM	char(4)	X	X	X	X
SD_MODEL_CLIENT_ID	char(3)	X	X	X	
SD_MODEL_STATUS	char(1)	X	X	X	
SD_MODEL_SUBN	char(1)	X	X	X	
SD_MODEL_TYPE	char(1)	X	X	X	
SD_MODEL_VERSION	char(1)	X	X	X	
SD_MSG_ID	varchar(35)	X	X	X	X
SD_MSG_SRC	varchar(20)	X	X	X	X
SD_MSG_TYP	char(4)	X	X	X	X
SD_NRT_MODEL_1_ID	varchar(64)	X	X	X	
SD_NRT_MODEL_2_ID	varchar(64)	X	X	X	
SD_NRT_MODEL_3_ID	varchar(64)	X	X	X	
SD_OFAC	varchar(1)	X	X	X	
SD_OFFSET_LIVE_IND	varchar(1)	X	X	X	X
SD_ORG_CDE	char(3)	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_ORIG_CRNCY_CDE	char(3)	X	X	X	X
SD_ORIG_WIR_ACCT_ADDR1	nvarchar(40)	X	X	X	
SD_ORIG_WIR_ACCT_ADDR2	nvarchar(40)	X	X	X	
SD_ORIG_WIR_ACCT_IDENT	varchar(40)	X	X	X	X
SD_ORIG_WIR_ACCT_NAM	nvarchar(40)	X	X	X	
SD_ORIG_WIR_CNTRY_CDE	varchar(3)	X	X	X	X
SD_ORIG_WIR_CRNCY_CDE	varchar(3)	X	X	X	X
SD_ORIG_WIR_INST_ADDR1	nvarchar(40)	X	X	X	
SD_ORIG_WIR_INST_ADDR2	nvarchar(40)	X	X	X	
SD_ORIG_WIR_INST_ID_NUM	varchar(11)	X	X	X	X
SD_ORIG_WIR_INST_NAM	nvarchar(40)	X	X	X	
SD_OS_NAME	varchar(20)	X	X	X	
SD_OS_VERSION	varchar(20)	X	X	X	
SD_PAN	varchar(50)	X	X	X	X
SD_PAYEE_ADDR	nvarchar(80)	X	X	X	
SD_PAYEE_CITY	nvarchar(35)	X	X	X	

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_PAYEE_COUNTRY	nvarchar(35)	X	X	X	
SD_PAYEE_POSTAL_CDE	nvarchar(16)	X	X	X	
SD_PAYEE_ST	nvarchar(35)	X	X	X	
SD_PAYMENT_INFO_IDENT	nvarchar(35)	X	X	X	X
SD_PAY_TYPE	nvarchar(2)	X	X	X	
SD_PIN_IND	char(1)	X	X	X	X
SD_PIN_TRIES	char(1)	X	X	X	X
SD_PRI_ACCT_NAM	nvarchar(140)	X	X	X	X
SD_PRI_ACCT_NUM	varchar(50)	X	X	X	X
SD_PRI_ACCT_OTHR_CDE	char(3)	X	X	X	
SD_PRI_ACCT_PROD_CDE	char(3)	X	X	X	X
SD_PRI_ACCT_TYP	char(3)	X	X	X	X
SD_PRI_BRCH_ID_NUM	char(4)	X	X	X	
SD_PRI_BRCH_RSK_IND	char(3)	X	X	X	
SD_PRI_INST_ID_NUM	char(11)	X	X	X	
	varchar(11)				X

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_PRM_MESSAGE_TYP	char(4)	X	X	X	X
SD_PROC_CDE	char(4)	X	X	X	
SD_PROD_IND	char(2)	X	X	X	X
SD_PROXY_1_IP	varchar(39)	X	X	X	
SD_PROXY_2_IP	varchar(39)	X	X	X	
SD_PT_SRV_COND_CDE	char(2)	X	X	X	X
SD_PT_SRV_ENTRY_MDE	char(3)	X	X	X	X
SD_PYMNT_INFO	nvarchar(80)	X	X	X	
SD_REAL_TIME_DISPOSITION	char(1)	X	X	X	X
SD_REAL_TIME_RULE_DISPOSITION	char(1)	X	X	X	X
SD_REAL_TIME_STATUS	char(1)	X	X	X	X
SD_REF_NUM	varchar(35)	X	X	X	X
SD_REGULATORY_REPORTING	nvarchar(10)	X	X	X	X
SD_RELEASE_TOKEN_IND	varchar(1)	X	X	X	X
SD_REMITTANCE_INFO_1	nvarchar(140)	X	X	X	X
SD_REMITTANCE_INFO_2	nvarchar(140)	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_REMOTE_IP	varchar(39)	X	X	X	X
SD_REOPEN_CASE_IND	nvarchar(1)	X	X	X	X
SD_RESP_CDE	char(3)	X	X	X	X
SD_RETL_ID	varchar(50)	X	X	X	X
SD_RETL_SIC_CDE	char(4)	X	X	X	X
SD_RSN_DESCR_CDE	char(2)	X	X	X	
SD_RT_MODEL_1_ID	varchar(64)	X	X	X	X
SD_RT_MODEL_2_ID	varchar(64)	X	X	X	X
SD_RT_MODEL_3_ID	varchar(64)	X	X	X	X
SD_SALES_RJCT_CDE	char(3)	X	X	X	
SD_SCORE_EVENT_TYPE	varchar(35)	X	X	X	X
SD_SECURITY_LEVEL	varchar(1)	X	X	X	
SD_SEC_ACCT_ACCT_TYP	char(3)	X	X	X	X
SD_SEC_ACCT_BANK_NAM	nvarchar(140)	X	X	X	X
SD_SEC_ACCT_CNTRY_CDE	char(3)	X	X	X	X
SD_SEC_ACCT_ID	nvarchar(50)	X	X	X	

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_SEC_ACCT_NAM	nvarchar(140)	X	X	X	
	varchar(140)				X
SD_SEC_ACCT_NUM	varchar(50)	X	X	X	X
SD_SEC_ACCT_OTHR_CDE	char(3)	X	X	X	X
SD_SEC_ACCT_PROD_CDE	char(3)	X	X	X	X
SD_SEC_BRCH_ID_NUM	char(4)	X	X	X	
SD_SEC_BRCH_RSK_IND	char(3)	X	X	X	
SD_SEC_CDE	varchar(3)	X	X	X	X
SD_SEC_CRNCY_CDE	nvarchar(3)	X	X	X	
SD_SEC_INST_ID_NUM	char(11)	X	X	X	
	varchar(11)				X
SD_SEC_OFAC	varchar(1)	X	X	X	
SD_SEC_PIN_IND	char(1)	X	X	X	
SD_SEC_PIN_TRIES	char(1)	X	X	X	
SD_SEQ_NUM	varchar(35)	X	X	X	X
SD_SEQ_NUM_NEW	varchar(15)				X

Column Name	Data Type	DTL	FDTL	SW	RTSW
	varchar(35)	X	X	X	
SD_SEQ_NUM_OLD	varchar(35)	X	X	X	X
SD_SESSION_ID	varchar(50)	X	X	X	X
SD_SETL_CRNCY_CDE	varchar(3)	X	X	X	X
SD_SIM	nvarchar(50)	X	X	X	X
SD_SPRVSR_OVRD_ID	char(9)	X	X	X	
SD_STATUS	varchar(8)	X	X	X	X
SD_TAX_ID_IND	char(1)	X	X	X	
SD_TERM_CITY	nvarchar(40)	X	X	X	X
SD_TERM_CITY_NEW	nvarchar(40)	X	X	X	X
SD_TERM_CITY_OLD	nvarchar(40)	X	X	X	X
SD_TERM_CNTRY	char(3)	X	X	X	X
SD_TERM_ID	varchar(50)	X	X	X	X
SD_TERM_NAME_LOC	nvarchar(25)	X	X	X	X
SD_TERM_POSTAL_CDE	varchar(16)	X	X	X	X
SD_TERM_ST	char(3)	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_TIEBREAKER	varchar(75)	X	X	X	X
SD_TRACK1_2_IND	char(1)	X	X	X	
SD_TRAN_CDE	char(4)	X	X	X	X
SD_TRAN_CDE_CAT	char(4)	X	X	X	X
SD_TRAN_RSN_CDE	char(8)	X	X	X	X
SD_TRAN_TYP	char(2)	X	X	X	X
SD_UAN	varchar(50)	X	X	X	X
SD_ULTIMATE_CREDITOR	nvarchar(140)	X	X	X	X
SD_ULTIMATE_DEBTOR	nvarchar(140)	X	X	X	X
SD_USER_ACCT_ID	varchar(50)	X	X	X	X
SD_USER_AGENT	varchar(200)	X	X	X	X
SD_USER_AGENT_TOKEN	varchar(30)	X	X	X	
SD_USER_TIMEZONE	varchar(3)				X
SD_USER_TYP	varchar(4)				X
SD_VISA_ADV_COND_CDE_1	char(2)	X	X	X	X
SD_VISA_ADV_COND_CDE_2	char(2)	X	X	X	X

Column Name	Data Type	DTL	FDTL	SW	RTSW
SD_VISA_ADV_COND_CDE_3	char(2)	X	X	X	X
SD_VISA_ADV_RSN_CDE_1	char(1)	X	X	X	X
SD_VISA_ADV_RSN_CDE_2	char(1)	X	X	X	X
SD_WIR_ID	varchar(20)	X	X	X	X
SD_WIR_PYMT_METHOD	varchar(15)	X	X	X	X
SD_WIR_TYPE	varchar(3)	X	X	X	X
SD_X_FWDED_FOR	varchar(120)	X	X	X	X
SM_ACCT_MRKT_SEG	varchar(5)				X
SM_ACCT_STAT	nvarchar(4)				X
SM_ACTVTY_STAT	char(1)				X
SM_EXP_DAT	char(4)				X
SM_RETL_CNTRY	char(3)				X
SM_RETL_POSTAL_CDE	nvarchar(16)				X
SM_STAT	char(1)				X
SM_USER_POSTAL_CDE	nvarchar(20)				X
SM_USER_TYP	varchar(4)				X

Column Descriptions

The columns listed in the preceding table are described below.

DD_ACH_BATCH_EFF_DAT — The effective date of the ACH batch.

DD_ACH_BATCH_RELEASE_DAT_TIM — The date the batch was released in the online banking application.

DD_ACQ_ICHG_SETL_DAT — The date when the transaction is to be reconciled (or settled) between the acquirer and the issuer (or between the acquirer and the network, for example, Visa). For Issuer transactions this field is zero-filled.

DD_UPDATE — The date and time that the transaction processing started in the database.

DD_CRD_EMOSS — The last emboss date of the card.

DD_CRD_LAST_ADDR_CHNG — The date of the last address change for the card.

DD_CRD_LAST_CRV — The date of the last CRV (card receipt validation) maintenance.

DD_CRD_LAST_ISS — The date the last card was issued. This is also known as the begin or commence date.

DD_CRD_LAST_STAT_CHNG — Contains the date of the last status change for this card.

DD_CRD_PIN_CHNG — The date of the last PIN change.

DD_CRD_RQST_DAT — The date of the last card request.

DD_CREDITOR_ALIAS_LAST_UPDATE — NPP:

If Addressing Service is used to look up the Creditor's bank and account information, this field is populated with the date that the Creditor alias was last updated.

DD_CREDITOR_ALIAS_REGISTER_DAT — NPP:

If Addressing Service is used to look up the Creditor's bank and account information, this field is populated with the date that the Creditor alias was registered.

DD_CUST_TRAN_DAT — A date field used to hold a user defined customized date.

DD_DATE — The date and time when the transaction occurred.

DD_DDAY — The transaction date in CCYYMMDD format.

DD_EXP_DAT — The expiration date (in the format YYMM) of the card. It is also referred to as the ending date.

Listing this value in transaction data protects against a chance of change to the expiration date of the card while the transaction(s) is still being approved/processed. Having this value in transaction data demonstrates that transaction occurred for a valid card.

DD_IP_FRAUD_FLG — The date on which this IP address was last marked as having a confirmed fraud case.

DD_IP_MAL_FLG — The date on which the IP address was last marked as malicious.

Note: This date is provided by an external data source; it is not calculated by PRM.

DD_MAL_DEVICE_FLG — The date on which this Device ID was last marked as malicious.

DD_PARTITION_DATE — Derived from DD_DATE or DD_APDATE column and contain only date information.

DD_POST_DAT — Date on which the amount of money ceases to be available to the agent that owes it and when the amount of money becomes available to the agent to which it is due.

DD_RCV_DAT — The date the chargeback or retrieval/copy request was received.

DD_REQ_EXECUTION_DATE — Date at which the initiating party requests the clearing agent to process the payment.

DD_RULEPROC_DATE — The date and time that the transaction was inserted into the Detail and FraudDetail tables after rule processing was completed.

DD_TRAN_DAT_TIM — The date and time (in the format DATETIME.MEDIUM.MEDIUM) at which the transaction occurred in locale terminal time.

If hundredths of a second is not available, substitute two zeroes (00).

In Real-Time processing, The date and time of the last card request.

DD_USER_ACTIVE_DAT — The activation date of the user account ID.

DD_WIR_CREATION_DAT_TIM — Date and time at which the message was created.

DD_WIR_LAST_MODIFY_DAT_TIM — The date and time the wire was last modified.

DD_WIR_RELEASE_DAT_TIM — The date and time the wire transaction was released.

MD_ACH_BATCH_CREDIT_AMT — The total amount of all credits in the batch.

MD_ACH_BATCH_DEBIT_AMT — The total debit amount of the ACH batch.

MD_CHK_AMT — The total amount of the actual check. It does not include any cash back or final amount, but the actual amount the check was written for.

MD_CUST_TRAN_AMT1 — Used to hold any user defined customized transaction amount.

MD_CUST_TRAN_AMT2 — Used to hold any user defined customized transaction amount.

MD_CUST_TRAN_AMT3 — Used to hold any user defined customized transaction amount.

MD_CUST_TRAN_AMT4 — Used to hold any user defined customized transaction amount.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

MD_TRAN_AMT4 — The current/final transaction amount or the amount of the reversal, in the original currency.

MD_TRAN_AMT5 — The original amount requested for the transaction, in the originating currency.

MM_ACCT_AVAIL_BAL — The available balance. If the account is a savings account, this is the available balance of the individual account.

MM_AUTH_LMT — The credit limit (for credit accounts) or current account balance (for debit accounts).

MM_OPEN_TO_BUY — The maximum amount of funds available (at risk) at the time of the authorization.

ND_ACCOUNT_NRT_RULE_SCR — The total (sum) score for all account rules that were alerted on the specified transaction.

ND_ACH_CREDIT_TRANS_IN_BATCH — The number of credit transactions that were sent to PRM in this batch.

ND_ACH_DEBIT_TRANS_IN_BATCH — The number of debit transactions that were sent to PRM in this batch.

ND_ACH_NUM_TRANS_IN_BATCH — The number of transactions that were sent to PRM in this batch.

ND_AUTH_TRIES — The number of authorization attempts made at the terminal when this transaction was being entered. This field might be left blank if the number of authorization attempts is unknown.

ND_CARD_NRT_RULE_SCR — The total (sum) score for all card rules that were alerted on the specified transaction.

ND_CAVV_AAV — Indicates if Visa CAVV or MC AAV was present.

ND_CHK_NUM — The serial number of the check, if used for this transaction.

ND_CHK_RANGE_BEGIN — The number to begin the range of the check numbers issued.

ND_CHK_RANGE_END — The number that ends the range of the check numbers issued.

ND_CHK_ROUT_NUM — The routing number and check digit of the DFI, Respondent, or Correspondent, as defined by the ACH operator.

ND_CRD_NUM_ISS — The number of cards issued with the same PAN as the card used for this transaction that are currently active.

ND_CRNCY_CONV_EXP — The conversion rate to convert the local currency to US dollars so the model has a single unit of measurement for the transaction amount.

ND_CRNCY_CONV_RATE — The currency conversion rate between the transaction's original, or local, currency and settlement currency.

ND_CUST_SCORE — A score from a third party or proprietary scoring engine.

ND_EMPLOYEE_IS_KEY — The Employee action level portfolio number for the transaction.

ND_EMPLOYEE_NRT_RULE_SCR — The total (sum) score for all employee/internal fraud rules that were alerted on the specified transaction.

ND_EXCHANGE_RATE — Factor used to convert an amount from one currency into another. This reflects the price at which one currency was bought with another currency.

ND_KEY_HASH — Enables sub-partitioning on two distinct columns. If it is not used for sub-partitioning, the column is populated by a constant (for example, a hashing function). If DD_DATE is used as the base for DD_PARTITION_DATE, then SD_PAN or SD_UAN is hashed. If AP_DATE is used as the base for DD_PARTITION_DATE, then SD_RETL_ID is hashed.

ND_MERCHANT_NRT_RULE_SCR — The total (sum) score for all merchant rules that were alerted on the specified transaction.

ND_NEAR_TIME_SCORE — The first near real-time score of the transaction generated by the optional Universal Scoring Engine or the near real-time score of the transaction generated by the optional PRM Scoring Engine.

ND_NEAR_TIME_SCORE_2 — The second near real-time score of the transaction generated by the optional Universal Scoring Engine.

ND_NEAR_TIME_SCORE_3 — The third near real-time score of the transaction generated by the optional Universal Scoring Engine.

ND_NRT_REASON_CODE_1 — Reason Code 1 associated with the Near real-time score produced by Model 1 of the Universal Scoring Engine.

ND_NRT_REASON_CODE_2 — Reason Code 2 associated with the Near real-time score produced by Model 1 of the Universal Scoring Engine.

ND_NRT_REASON_CODE_2_1 — Reason Code 1 associated with the Near real-time score produced by Model 2 of the Universal Scoring Engine.

ND_NRT_REASON_CODE_2_2 — Reason Code 2 associated with the Near real-time score

produced by Model 2 of the Universal Scoring Engine.

ND_NRT_REASON_CODE_2_3 — Reason Code 3 associated with the Near real-time score produced by Model 2 of the Universal Scoring Engine.

ND_NRT_REASON_CODE_3 — Reason Code 3 associated with the Near real-time score produced by Model 1 of the Universal Scoring Engine.

ND_NRT_REASON_CODE_3_1 — Reason Code 1 associated with the Near real-time score produced by Model 3 of the Universal Scoring Engine.

ND_NRT_REASON_CODE_3_2 — Reason Code 2 associated with the Near real-time score produced by Model 3 of the Universal Scoring Engine.

ND_NRT_REASON_CODE_3_3 — Reason Code 3 associated with the near real-time score produced by Model 3 of the Universal Scoring Engine.

ND_PAN_IS_KEY — The PAN action level portfolio number for the transaction.

ND_PIP_RESPONSE_REQUEST — Used to identify the type of response message to be sent back to the Authorization process for real-time scoring and or real-time rules processing.

ND_PRI_ACCT_NUM_IS_KEY — The Account action level portfolio number for the transaction.

ND_REAL_TIME_RULE FIRED — The first real-time rule number to fire for the transaction. It is filled in by the real-time rules Analytic Gateway process.

ND_REAL_TIME_SCORE — The first real-time score of the transaction generated by the optional Universal Scoring Engine or the real-time score of the transaction generated by the optional PRM Scoring Engine.

ND_REAL_TIME_SCORE_2 — The second real-time score of the transaction generated by the optional Universal Scoring Engine.

ND_REAL_TIME_SCORE_3 — The third real-time score of the transaction generated by the

optional Universal Scoring Engine.

ND_RETL_IS_KEY — The Merchant action level portfolio number for the transaction.

ND_RTE_STAT — The status of the message at a system level.

ND_SRV_RESTR_CDE — Provides information about a card's usage and restriction requirements.

ND_TERMINAL_NRT_RULE_SCR — The total (sum) score for all terminal rules that were alerted on the specified transaction.

ND_TERM_IS_KEY — The Terminal action level portfolio number for the transaction.

ND_TLR_APPR_CDE — The teller approval code.

ND_TRAN_ID — This column is for paginating performance purposes.

ND_UAID_NRT_RULE_SCR — The total (sum) score for all user account ID rules that were alerted on the specified transaction.

ND_UAN_IS_KEY — The UAN action level portfolio number for the transaction.

ND_UAN_NRT_RULE_SCR — The total (sum) score for all UAN rules that were alerted on the specified transaction.

ND_USER_ACCT_ID_IS_KEY — The UAID action level portfolio number for the transaction.

ND_VISA_ADV_AUTH_SCORE — The degree of risk associated with a transaction. This two-byte transaction risk score is represented by numeric value from 01 to 99.

RECORD_SOURCE_ID — The identifier of the record source as defined in the Analytic Gateway.

SD_ABA_NUM — The ABA transit routing number from the check.

SD_ACCEPT — The Accept string from the HTTP request header, which indicates the content types that are acceptable. Example: http://en.wikipedia.org/wiki/List_of_HTTP_header_fields.

SD_ACCEPT_CHARSET — The Accept-Charset string from the HTTP request header, which indicates the character sets that are acceptable. Example: http://en.wikipedia.org/wiki/List_of_HTTP_header_fields.

SD_ACCEPT_ENCODING — The Accept-Encoding string from the HTTP request header, which contains information about media types that are acceptable for the response. Example: <http://www.w3.org/Protocols/rfc2616/rfc2616-sec14.html>.

SD_ACCEPT_LANGUAGE — The Accept-Language string from the HTTP request header, which contains information about the languages that are acceptable for the response. Example: <http://www.w3.org/Protocols/rfc2616/rfc2616-sec14.html>.

SD_ACCT_SEC_MOB_PHN — The mobile phone number for the recipient account.

SD_ACCT_STAT — A code that indicates the current status of the account affected by this transaction (for example open, closed).

SD_ACCT_TYP — The account type affected by this transaction.

SD_ACH_APPLICATION — The ACH application.

SD_ACH_BATCH_CO_DATE_DESCR — A custom date field. It may represent multiple values depending on the data source.

Note: The field type is string (not date) because there are cases in which a word such as “auto-enroll” is populated into the field.

SD_ACH_BATCH_CO_ENTRY_DESCR — A description of the batch of transactions.

SD_ACH_BATCH_OFFSET_TYP — Identifies the offset type for the batch of transactions.

SD_ACH_BATCH_TYP — Identifies the batch type.

SD_ACH_IAT_CNTRY_CDE — Keeps country code value of destination country for IAT batches.

SD_ACH_NUM — The automated clearing house (ACH) number assigned by the Central Bank.

SD_ACQ_INST_ID_NUM — A code identifying the routing and transit number of the financial institution acting as the acquirer of this customer transaction. The acquirer is the member or system user that signed the merchant, installed the ATM, or dispensed cash. This field usually contains the BIN of the acquirer, but could be any other number assigned to it by the relevant authorities.

When a processing center operates for multiple acquirers, this field contains the code for the individual member or system user (acquirer institution), not a code for the processing center.

SD_ADDENDA — Additional information associated with the ACH transaction.

SD_ADDR_VRFY_FLG — A code identifying the result of comparing address verification information received in the transaction and address verification information contained in the processor's database.

SD_AGENT_NAME — The Agent Name, which can be parsed from the User-Agent string.

SD_AGENT_TYPE — The Agent Type, which can be derived from the information carried in the User-Agent string.

SD_AGENT_VERSION — The Agent Version, which can be parsed from the User-Agent string.

SD_APPRV_CDE — Contains an approval code associated with an approved transaction.

SD_APP_SOURCE — Identifies the message source if there are multiple applications for the online

banking system, for example a web application, a mobile application, a tablet application, etc.
Values provided by customer.

SD_AUTH_RSN — Provides additional information on the conditions under which authorization should be or was performed.

Valid values are:

- 0 = Unknown
- 1 = The transaction was authorized by the card issuer.
- 2 = Online stand-in. The transaction amount was below the local limits.
- 3 = Timeout stand-in. The Sink Node did not respond to a request.
- 4 = Offline stand-in. The Sink Node was not available.
- 5 = The use of this authorization type has been deprecated.
- 9 = The transaction was authorized by Visa.
- A = Declined by the Sink Node, not sent to the remote entity. This is not forwarded to the Source Node.
- B = Declined by the Sink Node after an approved response was received from the remote entity. This is not forwarded to the Source Node.

SD_AUTH_SRC — This field indicates which system authorized the transaction.

SD_AUTH_TYPE — Provides additional information on the conditions under which authorization should be or was performed.

Valid values are:

- 0 = Unknown
- 1 = Transaction authorized against cardholder record at card issuer.
- 2 = Transaction authorized using card issuer limits.
- 3 = Transaction authorized using card acceptor (merchant) limits.
- 4 = Transaction authorized using card issuer balances.
- 5 = Authorized using card issuer velocity limits.

SD_AUTH_UNAUTH_IND — Indicates whether the transaction was authorized or received using an offline posting file. A space in this field indicates the field is not used or the type of transaction

is unknown.

SD_B24_SRC — Indicates whether files were read by the Authorization process for balance and limit information. Values are added by the Authorization process and not by the user.

SD_BATCH_ID — A unique identifier for the ACH batch. This ID is used to link multiple messages sent to PRM for the same batch.

SD_BATCH_ONLINE_IND — Indicates whether the authorization was passed in using an online message or by a batch process.

SD_BATCH_TRAN_ID — A unique identifier for a transaction within an ACH batch. This ID is used to link multiple messages sent to PRM for the same ACH transaction.

SD_BEN_WIR_ACCT_ADDR1 — The beneficiary account holder address 1.

SD_BEN_WIR_ACCT_ADDR2 — The beneficiary account holder address 2.

SD_BEN_WIR_ACCT_IDENT — Beneficiary identifying information, which can include name and address.

SD_BEN_WIR_ACCT_NAM — The beneficiary account holder name.

SD_BEN_WIR_CNTRY_CDE — The country code of the bank where the beneficiary account resides.

SD_BEN_WIR_CRNCY_CDE — The ISO code which reflects the currency code of the bank where the beneficiary account resides.

SD_BEN_WIR_INST_ADDR1 — The beneficiary bank address 1.

SD_BEN_WIR_INST_ADDR2 — The beneficiary bank address 2.

SD_BEN_WIR_INST_ID_NUM — The identifying number of the bank where the beneficiary account resides.

SD_BEN_WIR_INST_NAM — The name of the beneficiary bank.

SD_BIN — Prefix or IIN (previously called the "Bank Identification Number" - BIN) for the PAN or card number used for portfolio and filter identification in the Analysis and Review system.

IIN (or BIN) is the combination of the first six digits of a card number, or PAN, (including the initial MII digit). These identify the institution that issued the card to the cardholder. Many card issuers print the first four digits of the IIN on their card, just beneath where the number is embossed, as an added security measure.

SD_BRCH_ID_NUM — The originating branch ID.

SD_BRCH_REGN — The originating branch region.

SD_BRCH_RSK_IND — Indicates whether branch is near the border and therefore high risk.

SD_BTCH_ID — An identifier indicating the batch in which the transaction is contained.

SD_CASE_CREATOR — Party that created the investigation case.
This indicates the Financial Institution (BICFI).

SD_CASH_IND — The cash or noncash indicator.

SD_CHK_ACCT_NUM — The account number the check is drawn against.

SD_CHK_SERIAL_NUM — The serial number of the check, if used for this transaction.

SD_CHK_SERIAL_NUM_NEW — This column is used starting with upgrade PRM 8.6

SD_CHK_SERIAL_NUM_OLD — This column is used until upgrade PRM 8.6 . After that column will be cleanup.

SD_CLIENT_IP — The client's IP, which can be parsed from the X-Forwarded-For string.

SD_CLIENT_LANGUAGE — The language for which the user's client has been localized, which can be parsed from the User-Agent string.

SD_COMPLETE_TRACK2_DATA — A flag indicating whether the terminal or transaction acquirer has the ability to capture and transmit complete Track 2 data on card swipe transactions.

SD_CRD_ACCPT_ID_NUM — An alphanumeric or numeric code identifying the card acceptor for this transaction if it originated at an acquirer host. Card Acceptor is the owner of the terminal. It may be a financial, or retail, institution that owns its card-accepting terminal, or it may be a broker company that rents the card-accepting terminal to the financial, or retail, institution.

SD_CRD_BLK_CDE — A code that indicates that a card has been blocked and the reason why. These values are user defined.

SD_CRD_PLASTIC_TYP — The type of plastic card associated with the transaction (for example, Visa or MasterCard). Any values can be accommodated with a customer-specific data dictionary.

SD_CRD_PROD_TYP — A code for the product or member type associated with this card (for example, gold or classic). Any values can be accommodated with a customer-specific data dictionary.

SD_CRD_SEQ_NUM — A card's order in the sequence of multiple cards that were issued against a single PAN. The first card issued against the PAN would have a Card Sequence Number of 1; the following card, for example one issued upon expiration of the first, would have a Card Sequence Number of 2; and so on.

SD_CRD_STAT — A code that indicates the status of the card (for example lost or stolen).

SD_CRD_VRFY_DIGITS — The manually entered values such as the American Express Card Identification Code (CID), MasterCard Card Validation Codes (CVC2), and Visa Card Verification Value 2 (CVV2). Only the leftmost three bytes are used in CVC2 and CVV2 verification processing. This field is only used in POS transactions.

SD_CRD_VRFY_FLG — This field indicates the result of verifying the CVV, CVV2, or CVC value for the card involved in this transaction.

SD_CREDITOR_ALIAS — NPP: If Addressing Service is used, must be populated with the Alias value that was used to look up the Creditor's bank and account information. The possible aliases will include the creditor's mobile number, email address, Australian business number, or organization ID.

SD_CREDITOR_ALIAS_ACCT_ID_TYPE — NPP:

If Addressing Service is used and an AUBN is used to look up the Creditor's bank and account information, this field is populated with the account identification type, i.e.:

ABSB - Australian Bank-State-Branch Code (BSB) identification, or

AIIN - For cards, the Issuer Identification Number

SD_CREDITOR_ALIAS_ACCT_ISSUER — NPP:

If Addressing Service is used and an AUBN is used to look up the Creditor's bank and account information, this field is populated with the BSB or BIN of the issuer of the Creditor's account, i.e.:
a 6 digit BSB number, or a 6 digit BIN (Bank Identification Number)

SD_CREDITOR_ALIAS_SHORT_NAME — NPP:

If Addressing Service is used, must be populated with the Creditor's Alias Short Name.

SD_CREDITOR_ALIAS_TYPE — NPP: If Addressing Service is used, must be populated with the code for the type of alias that was used to look up the Creditor's bank and account information: TELI, EMAL, AUBN, or ORGN.

TELI = mobile number

EMAL = email address

AUBN = Australian business number

ORGN = organization ID

SD_CR_DB_IND — The credit or debit indicator.

SD_CUST_HEADER — A customer-use field that can be used to carry additional HTTP request header information.

SD_CUST_TRAN_FLD — An alphanumeric value used to hold user defined customized data.

SD_CVD_PRESENT_FLG — A code indicating whether the manual Card Verification Value is printed on the card. This field is used in POS transactions only.

Note: The first code, called CVC1 or CVV1, is encoded on track-2 of the magnetic stripe of the card and used for card present transactions. The purpose of the code is to verify that a payment card is actually in the hand of the merchant. This code is automatically retrieved when the magnetic stripe of a card is swiped on a point-of-sale (card present) device and is verified by the issuer. A limitation is that if the entire card has been duplicated and the magnetic stripe copied, then the code is still valid. The second code, and the most cited, is CVV2 or CVC2. This code is often sought by merchants for card not present transactions occurring by mail, fax, over the telephone, or Internet. In some countries in Western Europe, card issuers require a merchant to obtain the code when the cardholder is not present in person.

SD_DATEKEY — The transaction date and time.

SD_DEVICE_BRWS_PLGIN — Details about the plug-ins installed on the device browser to help identify potential anomalies or possible presence of malware.

Note: This field will not be present in the real-time message due to its size.

SD_DEVICE_COOKIE — A unique value provided by the cookie deployed on the device.

Note: This field will not be present in the real-time message due to its size.

SD_DEVICE_COOKIE_ENBL — An indicator for whether cookies are enabled on the device, which is an indicator of risk for the device.

SD_DEVICE_CPU_TYPE — The type of processor used by the device. This data can be used within profiling to help determine whether the device is genuine.

SD_DEVICE_DISPL — The resolution/screen size for the device. It is used to determine whether the device is genuine (certain values may indicate that an emulator is being used).

SD_DEVICE_DOTNET — The version of Dot Net supported by the device, if applicable. This data may be used in profiling to help determine whether the device is genuine. It may also be used to determine the riskiness of a device if bugs have been found in a particular version of Dot Net.

SD_DEVICE_FLASH — The version of Adobe Flash supported by the device, if applicable. This data may be used in profiling to help determine whether the device is genuine. It may also be used to determine the riskiness of a device if bugs have been found in a particular version of Adobe Flash.

SD_DEVICE_FONT — The fonts supported by the user device. This data may be used within profiling to help determine whether the device is genuine.

Note: This field will not be present in the real-time message due to its size.

SD_DEVICE_HTTP — The result of the HTTP request. It is used to compare to the expect result to determine the presence of malware.

SD_DEVICE_ID — A unique identifier for the device.

SD_DEVICE_IMEI — The International Mobile Equipment Identity (IMEI), a unique number given to every mobile phone, typically found behind the battery. IMEI number of cellular phones connected to a GSM network are stored in a database (EIR - Equipment Identity Register) containing all valid mobile phone Equipment. When a phone is reported stolen or is not type approved, the number is marked invalid. This data can be used within profiling to compare the current transaction with the customer's typical IMEI.

SD_DEVICE_IMSI — The International Mobile Subscriber Identity (IMSI), a unique number that is associated with all GSM and UMTS network mobile phone users. An IMSI is up to 15 digits long. The first three digits represent the country code, followed by the network code. The remaining digits represent the unique subscriber number from within the network's customer base. This data can be used within profiling to compare the current transaction with the customer's typical IMSI.

SD_DEVICE_JAVA — The version of Java supported by the device, if applicable. This data may be used in profiling to help determine whether the device is genuine. It may also be used to determine the riskiness of a device if bugs have been found in a particular version of Java.

SD_DEVICE_MEM — The total memory allotted to the device. This data is used to help determine whether the device is genuine. This data may be used in profiling or in comparison with other device data (for example, whether memory is consistent with the device type or OS).

SD_DEVICE_MSISDN — The Mobile Station International Subscriber Directory Number (MSISDN), which is used to identify a mobile phone number internationally. MSISDN is defined by the E.164 numbering plan. This number includes a country code and a National Destination Code, which identifies the subscriber's operator. This data can be used within profiling to compare the current transaction with the customer's typical MSISDN.

SD_DEVICE_NAME — The name of the device the request was sent from, which can be parsed or derived from the User-Agent string.

SD_DEVICE_PDF — The PDF version supported by the device, if applicable. This data may be used to determine whether the device has been "jail broken" which is an indicator of the device being more susceptible to malware and other attacks.

SD_DEVICE_RISK_SCORE — A value indicating the risk score or rating for the device. It may be a numeric value such as 999, or it may be a word such as "HIGH".

SD_DEVICE_SILVERLIGHT — The version of Microsoft Silverlight supported by the device, if applicable. This data may be used in profiling to help determine whether the device is genuine. It may also be used to determine the riskiness of a device if bugs have been found in a particular version of Microsoft Silverlight.

SD_DEVICE_STOR — The total storage allotted to the device. This data is used to help determine whether the device is genuine. This data may be used in profiling or in comparison with other device data (for example, whether memory is consistent with the device type or OS).

SD_DEVICE_SUPERCOOKIE — The information returned from a test to determine whether super cookie files are present on the device.

SD_DEVICE_VERSION — The version of the device the request was sent from, which can be parsed or derived from the User-Agent string.

SD_EMPLOYEE_ID — The unique identifier of the employee, Depending on the type and location of the transaction, this may be an employee at a branch or at a merchant who processed or authorized the transaction.

SD_EMV_CRD_VRFY_RSLTS — The card verification result for EMV transactions.

SD_EMV_TERM_TYPE — The EMV terminal type indicating the environment of the terminal, its communications capability, and its operational control, as shown in the tables below.

The following apply to attended terminals for merchants.

Environment	Financial Institution	Merchant	Cardholder
Online only	11	21	N/A
Offline with online capability	12	22	N/A
Offline only	13	23	N/A

The following apply to unattended terminals for merchants.

Environment	Financial Institution	Merchant	Cardholder
Online only	14	24	34
Offline with online capability	15	25	35
Offline only	16	26	36

SD_EMV_TVR — The terminal verification result for EMV transactions.

SD_EMV_USER_FILLER — Used as a filler field for additional customer-defined EMV usage.

SD_END_TO_END_IDENT — Unique identification, as assigned by the initiating party, to unambiguously identify the transaction. This identification is passed on, unchanged, throughout the entire end-to-end chain.

SD_EVENT_DETAIL1 — Details about the event.

SD_EVENT_DETAIL2 — Details about the event.

SD_EVENT_TYP — Identifies the type of event that occurred in the online banking application. Valid values provided by customer.

SD_EXT_AUTH_RESULT — "ExtAuthenticationResult" of type NVARCHAR (20) representing the result of the SCA ("Strong Customer Authentication (SCA) Result") performed by the Payment Service User (e.g. successful, failed, failed with 3 retries)

SD_EXT_AUTH_TYPE — "ExtAuthenticationType" of type NVARCHAR (20) representing the type of the SCA ("Strong Customer Authentication (SCA) Type") requested from the Payment Service User (e.g. 3D secure, 2nd factor auth, etc.)

SD_E_COM_FLG — The electronic commerce flag.

SD_FIID — Financial institution servicing an account for the debtor.
This indicates the Financial Institution (BICFI).

SD_FILLER_FIELD — Used to specify user defined information.

SD_FRGN_FLG — A flag indicating whether the card involved in the transaction was issued by domestic or foreign issuer.

SD_FRWD_INST_ID_NUM — The identification number of the institution that forwards the transaction in an interchange system to the card issuer. For example, if an acquirer routes a transaction via a third-party EFT switch to the card issuer, in the request from the acquirer to the EFT switch, this field contains the code of the acquirer. When the request is forwarded by the EFT switch to the card issuer, this field contains the code assigned to the EFT switch.

SD_HOST_DECISION — The action taken by the host system after the transaction was sent through PRM real-time processing.

SD_IBK1_ACCT_IDENT — The first intermediary bank identifying information, which can include name and address.

SD_IBK1_CNTRY_CDE — The country code for the first intermediary bank.

SD_IBK1_CRNCY_CDE — The ISO code, which reflects the currency code of the first intermediary bank.

SD_IBK1_INST_ADDR1 — The first intermediary bank address 1.

SD_IBK1_INST_ADDR2 — The first intermediary bank address 2.

SD_IBK1_INST_ID_NUM — The identifying number of the first intermediary bank.

SD_IBK1_INST_NAM — The first intermediary bank name.

SD_IBK2_ACCT_IDENT — The second intermediary bank identifying information, which can include name and address.

SD_IBK2_CNTRY_CDE — The country code for the second intermediary bank.

SD_IBK2_CRNCY_CDE — The ISO code, which reflects the currency code of the second intermediary bank.

SD_IBK2_INST_ADDR1 — The second intermediary bank address 1.

SD_IBK2_INST_ADDR2 — The second intermediary bank address 2.

SD_IBK2_INST_ID_NUM — The identifying number of the second intermediary bank.

SD_IBK2_INST_NAM — The second intermediary bank name.

SD_INSTRUCTED_AGT — Agent that is instructed by the previous party in the chain to carry out the (set of) instruction(s).

This indicates the Financial Institution (BICFI).

SD_INSTRUCTED_REIMB_AGT — Agent at which the instructed agent will be reimbursed.

This indicates the Financial Institution (BICFI).

SD_INSTRUCTING_AGT — Agent that instructs the next party in the chain to carry out the (set of) instruction(s).

This indicates the Financial Institution (BICFI).

SD_INSTRUCTING_REIMB_AGT — Agent through which the instructing agent will reimburse the instructed agent.

This indicates the Financial Institution (BICFI).

SD_INSTRUCTION_IDENT — Unique identification, as assigned by an instructing party for an instructed party, to unambiguously identify the instruction.

SD_INSTR_CREDITOR_AGT — Further information related to the processing of the payment instruction, provided by the initiating party, and intended for the creditor agent.

SD_INSTR_NEXT_AGT — Further information related to the processing of the payment instruction that may need to be acted upon by the next agent.

SD_INST_ID_NUM — The terminal owner's routing and transit number or issuer identification number.

SD_INTERNTL_IND — Indicates whether the wire has an international destination.

SD_INVESTIGATION_TEXT — Investigation free format field.

SD_INVESTIGATION_TYPE — Investigation type. For NPP eg: INV1, INV2, INV3.

SD_IP_CITY — The city of the IP address.

SD_IP_CNTRY — The country of the IP address.

SD_IP_DOM — The domain where the IP address resides.

SD_IP_FRAUD_FLG — A value indicating whether this IP has been used to commit fraud.

SD_IP_LAT — The latitude of the IP address.

SD_IP_LONG — The longitude of the IP address.

SD_IP_MAL_CAT — The category for the reason this IP has been flagged as potentially malicious, for example, Malware Infection.

SD_IP_MAL_FLG — A value that indicate whether the IP is on a network used by suspicious entities.

SD_IP_MAL_TYPE — The type of malicious risk, for example, HTTP.

SD_IP_POSTAL_CDE — The postal code of the IP address.

SD_IP_PROXY_CAT — When the SD_IP_PROXY_FLG is set to 1 (Yes), The type of proxy service that is used by the IP.

SD_IP_PROXY_FLG — A value that indicates whether the IP is used by a proxy service.

SD_IP_RISK_SCORE — A value indicating the risk score or rating for the IP address. It may be a numeric value such as 999, or it may be a word such as "HIGH".

SD_IP_STATE — The region of the IP address.

SD_IP_TYP — Indicates whether the IP is dynamic or static or whether the type is unknown/can't be determined.

SD_ISP_NAM — The name of the ISP.

SD_LOGIN_TOKEN_FLG — Indicates whether the user entered a one-time password from a token device as part of the login process.

SD_MAL_DEVICE_CAT — The category for the reason this Device ID has been flagged as potentially malicious, for example, Malware Infection.

SD_MAL_DEVICE_FLG — A value that indicates whether the device has been flagged as malicious.

SD_MAL_DEVICE_TYPE — The type of malicious risk, for example, HTTP.

SD_MBR_NUM — A value which uniquely identifies individual holders of the same card number.

SD_MODEL_CLIENT_ID — A unique identifier for each customer. It is filled in by the Scoring Engine.

SD_MODEL_STATUS — Identifies the model type. It is filled in the by the Scoring Engine.

SD_MODEL_SUBN — Identifies the environment to be a multi-model configuration. It is filled in by the Scoring Engine.

SD_MODEL_TYPE — Identifies the type of model. It is filled in by the Scoring Engine.

SD_MODEL_VERSION — Used to identify the software version. It is filled in by the Scoring Engine. The version numbers begin with zero and are incremented with every new model of the same type that is installed.

SD_MSG_ID — Point to point reference, as assigned by the instructing party, and sent to the next party in the chain to unambiguously identify the message

SD_MSG_SRC — Identifies the source of the wire message. Used to distinguish which host sent the message when multiple systems involved in the wire lifecycle are sending messages to PRM.

SD_MSG_TYP — This field indicates the type of message. Refer to the ISO 8583 Message Types for further information.

SD_NRT_MODEL_1_ID — The ID of the Near Real-Time Model 1.

SD_NRT_MODEL_2_ID — The ID of the Near Real-Time Model 2.

SD_NRT_MODEL_3_ID — The ID of the Near Real-Time Model 3.

SD_OFAC — The results of an OFAC Compliance screening.

Valid values are:

- 0 = Indicates that there is no potential blocked party, as identified by OFAC on its list of Specially Designated Nationals (SDN list)
- 1 = Indicates the potential presence of a blocked party

SD_OFFSET_LIVE_IND — Indicates whether the transaction is an offset transaction, live transaction, or unknown.

SD_ORG_CDE — The country code or organization of the prefix or BIN issuer.

SD_ORIG_CRNCY_CDE — The ISO code, which represents the currency code of the original transaction.

SD_ORIG_WIR_ACCT_ADDR1 — Originating accountholder address1.

SD_ORIG_WIR_ACCT_ADDR2 — Originating accountholder address2.

SD_ORIG_WIR_ACCT_IDENT — The originator identifying information, which can include name and address.

SD_ORIG_WIR_ACCT_NAM — The name of the accountholder of the originating account.

SD_ORIG_WIR_CNTRY_CDE — The country code of the bank where the originator account

resides.

SD_ORIG_WIR_CRNCY_CDE — The ISO code which reflects the currency code where the originator account resides.

SD_ORIG_WIR_INST_ADDR1 — Originating bank address 1.

SD_ORIG_WIR_INST_ADDR2 — Originating bank address 2.

SD_ORIG_WIR_INST_ID_NUM — The identifying number of the bank where the originator account resides.

SD_ORIG_WIR_INST_NAM — Originating bank name.

SD_OS_NAME — The user's operating system name, which can be parsed or derived from the User-Agent string.

SD_OS_VERSION — The version of the user's operating system, which can be parsed or derived from the User-Agent string.

SD_PAN — The card number (PAN) that identifies the card, which is contained in the track 2 data.

The PAN is made up of 3 components: Issuer identification number (IIN), individual account identification identifying the customer and a check digit.

SD_PAYEE_ADDR — The address for the secondary, or payee, account.

SD_PAYEE_CITY — The city for the secondary, or payee, account.

SD_PAYEE_COUNTRY — The country of the Receiver.

SD_PAYEE_POSTAL_CDE — The postal code for the secondary, or payee, account.

SD_PAYEE_ST — The state for the secondary, or payee, account.

SD_PAYMENT_INFO_IDENT — Reference assigned by a sending party to unambiguously identify the payment information block within the message.

SD_PAY_TYPE — The type of payment, such as Recurring or One-Time.

SD_PIN_IND — Indicates whether a PIN was associated with this transaction.

SD_PIN_TRIES — The number of PIN attempts made at the terminal when this transaction was being entered. This field can be left blank if the number of PIN attempts is not known.

SD_PRI_ACCT_NAM — Party that owes an amount of money to the (ultimate) creditor.

SD_PRI_ACCT_NUM — Unambiguous identification of the account of the debtor to which a debit entry will be made as a result of the transaction.

SD_PRI_ACCT_OTHR_CDE — An additional code for the primary or sub-account. A data dictionary must be supplied.

SD_PRI_ACCT_PROD_CDE — The product code for the primary or sub-account. A data dictionary must be supplied.

SD_PRI_ACCT_TYP — The type of account, or if the transaction involves two accounts, the *from* account.

SD_PRI_BRCH_ID_NUM — The branch ID of, or if the transaction involves two accounts, the *from* universal account.

SD_PRI_BRCH_RSK_IND — Indicates whether the branch is near the border and therefor at high risk.

SD_PRI_INST_ID_NUM — The financial institution identifier (FIID) where the primary (from) account is held.

SD_PRM_MESSAGE_TYP — Identifies the PRM Message Type.

SD_PROC_CDE — Identifies the *from* and *to* account types associated with the transaction.

SD_PROD_IND — The type of transaction or originating terminal. This information is received from each customer.

SD_PROXY_1_IP — The first proxy's IP, which can be parsed from the X-Forwarded-For string.

SD_PROXY_2_IP — The second proxy's IP, which can be parsed from the X-Forwarded-For string.

SD_PT_SRV_COND_CDE — Indicates a special condition that exists at the time a transaction is initiated.

SD_PT_SRV_ENTRY_MDE — The transaction entry mode. The first two bytes of this column indicate how the transaction

SD_PYMNT_INFO — Used to include other details related to the payment. For NACHA, this column comes in on some addenda records.

SD_REAL_TIME_DISPOSITION — Identifies the outcome of the original real-time transaction.

SD_REAL_TIME_RULE_DISPOSITION — The recommended disposition of the transaction.

SD_REAL_TIME_STATUS — Filled in by the Scoring Engine and or the real-time rules Analytic Gateway process to control and identify the status of the real-time transaction.

Valid values are:

- 0 = Initial state. Transaction has not yet been processed in real-time
- 1 = Transaction has been processed by the Scoring Engine in real-time
- 2 = Transaction has been processed by the real-time rules Analytic Gateway process in real-time
- 3 = Transaction has been processed by both the Scoring Engine and real-time rules Analytic

Gateway process in real-time

Note: This field is deprecated.

SD_REF_NUM — A transaction reference number. This identifier is a transaction reference number in a secondary system that assisted with the processing of the transaction. For example, if a payment system referenced the processing system of a network, such as Visa, this value will represent the transaction number in Visa's system.

SD_REGULATORY_REPORTING — Information needed due to regulatory and statutory requirements.

SD_RELEASE_TOKEN_IND — Indicates whether the user entered a one-time password from a token device when releasing the wire.

SD_REMITTANCE_INFO_1 — Information supplied to enable the matching/reconciliation of an entry with the items that the payment is intended to settle.

SD_REMITTANCE_INFO_2 — Information supplied to enable the matching/reconciliation of an entry with the items that the payment is intended to settle.

SD_REMOTE_IP — The remote IP address of the machine the client is running on from the HTTP header.

SD_REOPEN_CASE_IND — Indicates whether or not the case was previously closed and is now re-opened.

SD_RESP_CDE — The response as determined by the authorizer. It specifies whether the transaction was approved, referred, or denied and the reason why it was denied. For valid response code values, refer to the ISO8583:1993 standard, **Financial Transaction Card Originated Messages —Interchange Message Specifications**, field P-39, Action Code assignments.

SD_RETL_ID — The alphanumeric or numeric code that identifies the retailer or merchant that owns or operates the terminal at which this transaction originated. It equates to a single physical location or Internet storefront. For merchants with multiple store locations, the merchant ID must be unique per store. This field is populated with the terminal ID for ATM transactions and can be used to monitor ATM transactions.

SD_RETL_SIC_CDE — The Standard Industrial Classification (SIC) code indicating the retailer's

line of business. Valid values are per industry standards. In the payments world, the MCC is used, which is based on the ISO 18254 definition.

SD_RSN_DESCR_CDE — The chargeback or retrieval or copy reason description code.

SD_RT_MODEL_1_ID — The ID of Real-Time Model 1.

SD_RT_MODEL_2_ID — The ID of Real-Time Model 2.

SD_RT_MODEL_3_ID — The ID of Real-Time Model 3.

SD_SALES_RJCT_CDE — The sales reject code. This field is used mainly for acquirer transactions to provide additional merchant-side information about a rejected sale. For example, if a card was used to attempt a purchase but the sale was rejected, this field would contain information (codes) about the rejection. The rejection codes could be: insufficient funds, wrong signature, expired card, un-activated card, blocked card, etc. These codes are defined and passed to PRM by customers.

SD_SCORE_EVENT_TYPE — The transaction's event type, which is used by the optional Universal Scoring Engine to determine which models to process.

SD_SECURITY_LEVEL — The security level indicator of the user's agent/client, which can be parsed from the User-Agent string.

SD_SEC_ACCT_ACCT_TYP — The secondary account type.

SD_SEC_ACCT_BANK_NAM — The name of the recipient bank.

SD_SEC_ACCT_CNTRY_CDE — The country code for the secondary *to* account.

SD_SEC_ACCT_ID — The identification number for the recipient account. It differs from the account number, as it may be another unique number such as SSN, Customer ID, etc. used by the receiving bank to identify the account.

SD_SEC_ACCT_NAM — Party to which an amount of money is due.

SD_SEC_ACCT_NUM — Unambiguous identification of the account of the creditor to which a credit entry will be posted as a result of the payment transaction.

SD_SEC_ACCT_OTHR_CDE — An additional code for the secondary or secondary sub-account. A data dictionary must be supplied.

SD_SEC_ACCT_PROD_CDE — The product code for the secondary or secondary sub-account. A data dictionary must be supplied.

SD_SEC_BRCH_ID_NUM — The branch ID of the *to* universal account.

SD_SEC_BRCH_RSK_IND — Indicates whether the branch is near the border and therefore high risk.

SD_SEC_CDE — Identifies the Standard Entry Class (SEC) code.

SD_SEC_CRNCY_CDE — The secondary currency code.

SD_SEC_INST_ID_NUM — Financial institution servicing an account for the creditor.

This indicates the Financial Institution (BICFI).

SD_SEC_OFAC — The results of a secondary OFAC Compliance or other type of compliance screening (PEP, etc.).

Valid values are:

0 = Indicates that a blocked party has not been identified

1 = Indicates the potential presence of a blocked party

SD_SEC_PIN_IND — Indicates whether a secondary PIN was associated with this transaction.

SD_SEC_PIN_TRIES — The number of secondary PIN attempts made at the terminal when this transaction was being entered. This field can be left blank if the number of PIN attempts is unknown.

SD_SEQ_NUM — Unique identification, as assigned by the first instructing agent, to unambiguously identify the transaction that is passed on, unchanged, throughout the entire interbank chain.

SD_SEQ_NUM_NEW — This column is used starting with upgrade PRM 8.6

SD_SEQ_NUM_OLD — This column is used until upgrade PRM 8.6 . After that column will be cleanup.

SD_SESSION_ID — The session ID associated with the user's online banking session.

SD_SETL_CRNCY_CDE — The ISO currency code that identifies the currency of settlement for a transaction. If this field is not present for a transaction, it is assumed that this field is the same as the transaction's originating, or local, currency code.

For Issuer and On-Us transactions, Settlement is usually between the Network (for example, Visa) that processed the transaction and the account-holder's card-issuing financial institution. For Issuer transactions, Settlement Currency will most often be the currency of the cardholder's account.

For Acquirer transactions, Settlement is usually between the transaction Acquirer the Network (for example, Visa) of the card involved in the transaction. For Acquirer transactions, Settlement Currency will most often be the currency of the account of the merchant that was involved in the transaction (as Acquirers tend to operate in the same geographic areas as the Merchants whose transactions they acquire).

SD_SIM — The Subscriber Identification Module (SIM) card number for the mobile device.

SD_SPRVSR_OVRD_ID — The supervisor ID. It is used when authorization denial override is necessary.

SD_STATUS — The status of wire. This field can be used to send an updated status based on the decision taken by the online banking application, wire settlement system, or authorities such as the Federal Reserve Bank and SWIFT.

SD_TAX_ID_IND — The tax ID indicator or the user's government ID.

SD_TERM_CITY — The city in which the terminal is located.

SD_TERM_CITY_NEW — This column is used starting with upgrade PRM 8.6

SD_TERM_CITY_OLD — This column is used until upgrade PRM 8.6 . After that column will be cleanup.

SD_TERM_CNTRY — The ISO code for the country in which the terminal is located.

Note: This value can also represent the two-character alpha representation of the country (for example, JP = Japan, MX = Mexico).

SD_TERM_ID — Identifies the terminal where the transaction originated.

SD_TERM_NAME_LOC — The name and location of the terminal from which this transaction originated.

SD_TERM_POSTAL_CDE — This field contains the postal or ZIP code of the originating terminal.

SD_TERM_ST — The state or province in which the terminal is located.

SD_TIEBREAKER — A value that makes a transaction unique. It is used to distinguish transactions that may have occurred at the same date and time or that may have the same reference identifier in host system(s). In PRM, this identifier can be based on a combination of values from different fields that taken as a group identify the transaction as unique. The structure of this field is defined at installation.

SD_TRACK1_2_IND — Indicates which track was sent in the message to the authorization system.

SD_TRAN_CDE — The type of transaction.

SD_TRAN_CDE_CAT — A transaction code category that is supplied by the customer.

SD_TRAN_RSN_CDE — Additional information about the transaction code (for example, cash loan, CD purchase, etc.). It represents the reason for the transaction type and can help to distinguish between transactions with the same transaction code.

SD_TRAN_TYP — This field contains the type of transaction from the merchant's point of view.

SD_UAN — The unique identifier of the universal account number or Customer.

SD_ULTIMATE_CREDITOR — Ultimate party to which an amount of money is due.

SD_ULTIMATE_DEBTOR — Name by which a party is known and which is usually used to identify that party.

SD_USER_ACCT_ID — The user's account ID for the online banking application.

SD_USER_AGENT — The User-Agent string from the HTTP request header, which contains information about the device and browser that the user is logged in on. Example: http://en.wikipedia.org/wiki/User_agent.

SD_USER_AGENT_TOKEN — Additional User-Agent string values that are application specific.

SD_USER_TIMEZONE — The user's time zone.

SD_USER_TYP — Identifies whether the user is a financial institution/bank (wholesale) or a customer (retail).

SD_VISA_ADV_COND_CDE_1 — A compromised account risk condition code related to a high-risk in the Compromised Account Management System (CAMS).

SD_VISA_ADV_COND_CDE_2 — A Compromised Event Reference (CER) ID related to a high-risk CAMS event.

SD_VISA_ADV_COND_CDE_3 — Online risk assessment condition code, reserved for future use.

SD_VISA_ADV_RSN_CDE_1 — Online risk assessment Reason Code1, reserved for future use.

SD_VISA_ADV_RSN_CDE_2 — Online risk assessment Reason Code 2, reserved for future use.

SD_WIR_ID — A unique identifier for the wire. This ID is used to link multiple messages sent to PRM for the same wire.

SD_WIR_PYMT_METHOD — The method of payment.

SD_WIR_TYPE — The type of wire.

SD_X_FWDED_FOR — The X-Forwarded-For string from the HTTP request header, which contains the originating IP address of a client connecting to a webserver through an HTTP proxy or load balancer.

SM_ACCT_MRKT_SEG — The VIP indicator for the key account.

SM_ACCT_STAT — This field contains a flag that indicates the account's activity status.

SM_ACTVTY_STAT — The merchant activity status.

SM_EXP_DAT — The expiration date of the card. It is also referred to as the ending date.

SM_RETL_CNTRY — The country in which the retailer is located.

SM_RETL_POSTAL_CDE — The postal or ZIP code where the retailer is located.

SM_STAT — The merchant status. This value is independent of merchant activity status in that merchant can be open but inactive, merchant can be open and active, merchant can be closed and inactive, etc.

SM_USER_POSTAL_CDE — The postal or ZIP code for the primary cardholder's country of residence.

SM_USER_TYP — Identifies whether the user is a financial institution/bank (wholesale) or a customer (retail).

Employee_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor (Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the Employee_Master table (EMPLOYEE_MASTER).

Index Name: EMPLOYEE_MASTER__IX1

Fields: SM_PRI_LAST_NAM
 SM_PRI_FIRST_NAM

Index Name: EMPLOYEE_MASTER__IX2

Fields: SM_EMP_PHN_NUM

Index Name: EMPLOYEE_MASTER_IX3

Fields: DM_EMPMF_DAT_TIM

Index Name: EMPLOYEE_MASTER_PK

Fields: SM_EMPLOYEE_ID

FraudDetail Table

The FraudDetail table is used by the ACI Proactive Risk Manager Analysis and Review system. It contains fraudulent transaction history. This table also has columns representing clients' authorization data that is defined in the appropriate Input File (IF) document. The FraudDetail table holds an exact replica of all transactions in the Detail table for accounts that have been marked suspicious.

Proactive Risk Manager configures a variable for every input field. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing.

When a user wants to use an input variable in aggregate, rule, or queue creation, they can type the variable name or select a variable from the Variables dropdown list on any Aggregate, Rule, or Queue Editor (Add) screen. The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle. See the **ACI Proactive Risk Manager Team Administrator User Guide** for details.

Refer to the "Detail Table" topic for a list of the columns in the FraudDetail table and for descriptions of those columns.

Refer to the Detail table for columns definitions for the FraudDetail table (FRAUDDetail).

Index Name: IDX_FD_SM_PRI_ACCT_NUM

Fields: SD_PRI_ACCT_NUM
 DD_PARTITION_DATE
 DD_DATE

Index Name: IDX_FRAUDDetail_CLUSTER

Fields: DD_PARTITION_DATE
 ND_KEY_HASH
 RECORD_SOURCE_ID
 SD_TIEBREAKER

Index Name: IDX_FRAUDDetail_SM_EMPLOYEE_ID

Fields: SD_EMPLOYEE_ID
 DD_PARTITION_DATE
 DD_DATE

Index Name: IDX_FRAUDDetail_SM_PAN

Fields: SD_PAN
 DD_PARTITION_DATE
 DD_DATE

Index Name: IDX_FRAUDDetail_SM_RETL_ID

Fields: SD_RETL_ID
 DD_PARTITION_DATE
 DD_DATE

Index Name: **IDX_FRAUDDetail_SM_TERM_ID**

Fields: SD_TERM_ID
 DD_PARTITION_DATE
 DD_DATE

Index Name: **IDX_FRAUDDetail_SM_UAN**

Fields: SD_UAN
 DD_PARTITION_DATE
 DD_DATE

Index Name: **IDX_FRAUDDetail_SM_USER_ACCT_ID**

Fields: SD_USER_ACCT_ID
 DD_PARTITION_DATE
 DD_DATE

Index Name: **IDX_FRAUDPOCDetail_DATE**

Fields: DD_PARTITION_DATE

Merchant_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor (Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the Merchant_Master table (MERCHANT_MASTER).

Index Name: **MERCHANT_MASTER_IX1**

Fields: SM_RETL_BUS_NAM

Index Name: **MERCHANT_MASTER_IX2**

Fields: SM_RETL_DBA_NAM

Index Name: **MERCHANT_MASTER_IX3**

Fields: DM_MMF_DAT_TIM

Index Name: **MERCHANT_MASTER_PK**

Fields: SM_RETL_ID

PRM_Heritage_Pass Table

Keeps encrypted password

The columns in the PRM_Heritage_Pass table (PRM_HERITAGE_PASS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ENC_KEY	varchar(512)
ENC_PASS	varchar(512)

Column Descriptions

The following are the descriptions of the PRM_Heritage_Pass table columns.

ENC_KEY — Encryption key

ENC_PASS — Encrypted password

PRM_Ref_Data Table

The PRM_Ref_Data table is used to store institution-managed reference data that can be checked within aggregates, rules and queues. Examples of the types of data that can be stored in the table and referenced within aggregates, rules, and queues include potentially compromised accounts, risky IP addresses, VIP accounts, or other hotlist information. Data can be loaded to this table or deleted from the table on the Reference Data Manager UI screen.

The columns in the PRM_Ref_Data table (PRM_REF_DATA) are listed below with the data type.

Column Name	Data Type
DDATE	datetime
ID	bigint
PRM_REF_DATA_ID	nvarchar(50)
PRM_REF_DATA_VALUE	nvarchar(50)

Index Name: **PRM_REF_DATA_IX1**

Fields: PRM_REF_DATA_VALUE

Index Name: **PRM_REF_DATA_IX2**

Fields: PRM_REF_DATA_ID
 PRM_REF_DATA_VALUE

Column Descriptions

The following are the descriptions of the PRM_Ref_Data table columns.

DDATE — The date the information was loaded.

ID — The unique identifier for PRM_REF_DATA and RT_PRM_REF_DATA tables. It's populated from PRM_REF_DATA_ID_SEQ sequence. It's used to synchronize data between PRM_REF_DATA and RT_PRM_REF_DATA tables.

PRM_REF_DATA_ID — The reference data identifier assigned to a row in this table.

PRM_REF_DATA_VALUE — Reference values.

RT_Account_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to

the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor (Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the RT_Account_Master table (RT_ACCOUNT_MASTER).

Index Name: **PK_RT_ACCOUNT_MASTER**

Fields: SM_PRI_ACCT_NUM

RT_Card_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor(Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the RT_Card_Master table (RT_CARD_MASTER).

Index Name: **RT_CARD_MASTER_PK**

Fields: SM_PAN

RT_Employee_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor (Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the RT_Employee_Master table (RT_EMPLOYEE_MASTER).

Index Name: RT_EMPLOYEE_MASTER_PK

Fields: SM_EMPLOYEE_ID

RT_Merchant_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor(Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the RT_Merchant_Master table (RT_MERCHANT_MASTER).

Index Name: **RT_MERCHANT_MASTER_PK**

Fields: SM_RETL_ID

RT_PRM_Install Table

The PRM_Install table stores information regarding the RT PRM installation.

The columns in the RT_PRM_Install table (RT_PRM_INSTALL) are listed below with the data type.

Column Name	Data Type
INSTALL_END_DT	datetime27
INSTALL_START_DT	datetime27
INSTALL_STATUS	varchar(1)
PRM_INSTALL_ID	int
PRM_VERSION_FROM	varchar(200)
PRM_VERSION_TO	varchar(200)

Index Name: **PK_RT_PRM_INSTALL**

Fields: PRM_INSTALL_ID

Column Descriptions

The following are the descriptions of the RT_PRM_Install table columns.

INSTALL_END_DT — The RT PRM install end date.

INSTALL_START_DT — The RT PRM install start date.

INSTALL_STATUS — The RT PRM install status.

Valid values are:

R = Running

E = Error

T = Terminated

PRM_INSTALL_ID — The unique RT PRM install ID.

PRM_VERSION_FROM — The PRM starting version for the install. When a fresh PRM install is performed the value is NULL.

PRM_VERSION_TO — The targeted PRM version by the install.

RT_PRM_Install_Log Table

The PRM_Install_log table stores logging information regarding the RT PRM installation.

The columns in the RT_PRM_Install_Log table (RT_PRM_INSTALL_LOG) are listed below with the data type.

Column Name	Data Type
LOG_TEXT	nvarchar(2000)
LOG_TS	datetime27
LOG_TYPE	varchar(1)
PRM_INSTALL_ID	int
PRM_INSTALL_LOG_ID	int
SCRIPT_NAME	varchar(200)
STEP_DESC	varchar(200)

Index Name: **PK_RT_PRM_INSTALL_LOG**

Fields: PRM_INSTALL_LOG_ID

Column Descriptions

The following are the descriptions of the RT_PRM_Install_Log table columns.

LOG_TEXT — The text saved during the PRM install.

LOG_TS — The PRM install Log start date.

LOG_TYPE — The PRM install Log type.

Valid values are:

I = Terminated successfully

W = Skipped

PRM_INSTALL_ID — The unique PRM install ID corresponding to the RT_PRM_Install table.

PRM_INSTALL_LOG_ID — The unique RT PRM install Log ID.

SCRIPT_NAME — The script which contains the log text.

STEP_DESC — The description for each log step.

RT_PRM_Ref_Data Table

The existing NRT PRM_Ref_Data table stores institution-managed reference data that can be checked within aggregates, rules and queues in near real-time. When the RTR Reference Data Access capability is purchased, the reference data is copied from the NRT database into the RT database where it can be used in real-time aggregates and rules.

To ensure that data from the PRM_Ref_Data table in the NRT database is copied into the RT_PRM_Ref_Data table in the RT database, there are two paths for copying the data:

- 1 = Direct copy using a stored procedure named PP_RT_COPY_REF_DATA, which resides in the RT database. This procedure reads the PRM Ref Data records in the NRT database and merges them into the RT_PRM_Ref_Data table in the RT database. This procedure must be run in the RT database when this capability is purchased in order to load the existing NRT records into the RT database. A DB link between the RT and NRT databases is required and is created

during installation.

Note: To ensure the RT database is properly synchronized with the NRT database, do not load or delete any reference data via the PRM user interface while the procedure is running. The best approach is to stop the server, and then restart it only after the procedure has been run.

2 = Java code copy. The existing Reference Data Manager class that loads data from external files and the user interface into the PRM_Ref_Data table in the NRT database has been modified to also insert/update/delete the data in the RT_PRM_Ref_Data table in the RT database, using another database connection.

Note: You can modify the NRT PRM_Ref_Data table by adding new columns. If you modify the NRT PRM_Ref_Data table, you must also modify the RT_PRM_Ref_Data table. The structure of the two tables must remain aligned.

If new columns are added, then the indexes should be reviewed to ensure they support any new rules. Although it is not necessary for NRT index definitions to match RT index definitions, it is recommended that they are the same.

As this table is updated infrequently and is not part of the transaction path, many indexes can be added to support rules without negatively impacting performance.

The columns in the RT_PRM_Ref_Data table (RT_PRM_REF_DATA) are listed below with the data type.

Column Name	Data Type
DDATE	datetime
ID	bigint
PRM_REF_DATA_ID	varchar(50)
PRM_REF_DATA_VALUE	varchar(50)

Index Name: RT_PRM_REF_DATA_IX2

Fields: PRM_REF_DATA_VALUE

Index Name: RT_PRM_REF_DATA_PK

Fields: PRM_REF_DATA_ID

PRM_REF_DATA_VALUE

Column Descriptions

The following are the descriptions of the RT_PRM_Ref_Data table columns.

DDATE — The date the information was loaded into the RT database.

ID — The unique identifier for PRM_REF_DATA and RT_PRM_REF_DATA tables. It's populated from PRM_REF_DATA_ID_SEQ sequence. It's used to synchronize data between PRM_REF_DATA and RT_PRM_REF_DATA tables.

PRM_REF_DATA_ID — The reference data identifier assigned to a row in this table.

PRM_REF_DATA_VALUE — Reference values.

RT_Shortwindow Table

The RT_ShortWindow table is used by the real-time rules Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Proactive Risk Manager configures a variable for every input field for use in writing rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing.

When a user wants to use an input variable in aggregate, rule, or queue creation, they can type the variable name or select a variable from the Variables dropdown list on any Aggregate, Rule, or Queue Editor (Add) screen. The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle. See the **ACI Proactive Risk Manager Team Administrator User Manual** for details.

Refer to the "Detail Table" topic for a list of the columns in the RT_ShortWindow table and for descriptions of those columns.

Refer to the Detail table for columns definitions for the RT_Shortwindow table (RT_SHORTWINDOW).

Index Name: **IDX_RT_SHORTWINDOW_CLUSTER**

Fields: ND_KEY_HASH

RECORD_SOURCE_ID

SD_TIEBREAKER

DD_PARTITION_DATE

Index Name: IDX_RT_SHORTWINDOW_SM_EMPLOYEE_ID

Fields: SD_EMPLOYEE_ID

DD_DATE

DD_PARTITION_DATE

Index Name: IDX_RT_SHORTWINDOW_SM_PAN

Fields: SD_PAN

DD_DATE

DD_PARTITION_DATE

Index Name: IDX_RT_SHORTWINDOW_SM_RETL_ID

Fields: SD_RETL_ID

DD_DATE

DD_PARTITION_DATE

Index Name: IDX_RT_SHORTWINDOW_SM_TERM_ID

Fields: SD_TERM_ID

DD_DATE

DD_PARTITION_DATE

Index Name: IDX_RT_SHORTWINDOW_SM_UAN

Fields: SD_UAN

DD_DATE

DD_PARTITION_DATE

Index Name: IDX_RT_SHORTWINDOW_SM_USER_ACCT_ID

Fields: SD_USER_ACCT_ID

DD_DATE

DD_PARTITION_DATE

RT_Terminal_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor(Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the RT_Terminal_Master table (RT_TERMINAL_MASTER).

Index Name: RT_TERMINAL_MASTER_PK

Fields: SM_TERM_ID

RT_UAID_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor(Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the RT_UAID_Master table (RT_UAID_MASTER).

Index Name: IDX_RT_UAID_MASTER_FILTER

Fields: SM_FILTER

Index Name: RT_UAID_MASTER_PK

Fields: SM_USER_ACCT_ID

RT_UAN_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor(Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the RT_UAN_Master table (RT_UAN_MASTER).

Index Name: IDX_RT_UAN_MASTER_FILTER

Fields: SM_FILTER

Index Name: RT_UAN_MASTER_PK

Fields: SM_UAN

ShortWindow Table

The ShortWindow table is used by the Analytic Gateway process. It contains the authorization history information that stores a 2-3 day history table for the purpose of executing rules and queues.

Proactive Risk Manager configures a variable for every input field. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing.

When a user wants to use an input variable in aggregate, rule, or queue creation, they can type the variable name or select a variable from the Variables dropdown list on any Aggregate, Rule, or Queue Editor (Add) screen. The @ symbol must precede the field name for the SQL Server. A v_

designation must precede the field name for Oracle. See the **ACI Proactive Risk Manager Team Administrator User Guide** for details.

Refer to the "Detail Table" topic for a list of the columns in the ShortWindow table and for descriptions of those columns.

Refer to the Detail table for columns definitions for the ShortWindow table (SHORTWINDOW).

Index Name: IDX_SHORTWINDOW_CLUSTER

Fields: ND_KEY_HASH
 RECORD_SOURCE_ID
 SD_TIEBREAKER

Index Name: IDX_SHORTWINDOW_SM_EMPLOYEE_ID

Fields: SD_EMPLOYEE_ID
 DD_DATE

Index Name: IDX_SHORTWINDOW_SM_PAN

Fields: SD_PAN
 DD_DATE

Index Name: IDX_SHORTWINDOW_SM_RETL_ID

Fields: SD_RETL_ID
 DD_DATE

Index Name: IDX_SHORTWINDOW_SM_TERM_ID

Fields: SD_TERM_ID
 DD_DATE

Index Name: IDX_SHORTWINDOW_SM_UAN

Fields: SD_UAN
 DD_DATE

Index Name: IDX_SHORTWINDOW_SM_USER_ACCT_ID

Fields: SD_USER_ACCT_ID
 DD_DATE

Index Name: IDX_SW_SM_PRI_ACCT_NUM

Fields: SD_PRI_ACCT_NUM
 DD_DATE

Std_Profile_Status Table

Table STD_PROFILE_STATUS holds the standard profiles jobs for all the action levels. It is set to be cleaned up by default after 30 days.

The columns in the Std_Profile_Status table (STD_PROFILE_STATUS) are listed below with the data type.

Column Name	Data Type
ACTIONLEVELID	integer
ENDTIME	datetime
FAILEDKEYS	integer
ID	integer
LASTUPDATED	datetime
PRCSID	varchar(50)
PREVIOUSSTATUSES	varchar(1000)
RECOMMENDATION	varchar(254)
RQBYPRCSID	varchar(50)
RUNDATE	date
STARTTIME	datetime
STATUS	varchar(50)
SUCCESSFULKEYS	integer

Index Name: **PK_STD_PROFILE_STATUS**

Fields: ACTIONLEVELID

 RUNDATE

Index Name: **IDX_STD_PROFILE_STATUS_ID**

Fields: ID

Column Descriptions

The following are the descriptions of the Std_Profile_Status table columns.

ACTIONLEVELID — The action level id for which the job processes and generates the data and rules.

ENDTIME — The time the job was finished.

FAILEDKEYS — The number of entries from the action level's daily profile table that were processed encountering exceptions.

ID — Unique identifier of a standard profiles job, generated.

LASTUPDATED — The last time the SUCCESSFULKEYS and FAILEDKEYS columns were updated in the process of running roll-up rules. It is used only to give a periodic update on the progress.

PRCSID — The web server process ID that runs this job

PREVIOUSSTATUSES — The last steps that a job followed.

RECOMMENDATION — When a job reaches an unfortunate status, the system can make a basic recommendation to the user, so they can follow some steps to put the job back on track.

RQBYPRCSID — The web server process that requests the running process to stop the job.

RUNDATE — The day of the transactions for which the job is run.

STARTTIME — The time the job was started.

STATUS — The status in which a job is at a given time.

SUCCESSFULKEYS — The number of entries from the action level's daily profile table that were processed without encountering exceptions.

Terminal_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor (Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the Terminal_Master table (TERMINAL_MASTER).

Index Name: TERMINAL_MASTER__IX1

Fields: SM_TERM_NAME_LOC

Index Name: TERMINAL_MASTER__IX2

Fields: SM_TERM_CITY
 SM_TERM_ST
 SM_TERM_ID
 SM_TERM_NAME_LOC

Index Name: TERMINAL_MASTER__IX3

Fields: SM_TERM_POSTAL_CDE
 SM_TERM_ID
 SM_TERM_NAME_LOC

Index Name: TERMINAL_MASTER_IX4

Fields: DM_TERMMF_DAT_TIM

Index Name: TERMINAL_MASTER_PK

Fields: SM_TERM_ID

UAID_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor (Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the UAID_Master table (UAID_MASTER).

Index Name: IDX_UAID_MASTER_FILTER

Fields: SM_FILTER

Index Name: IDX_UAID_MASTER_LINK

Fields: SM_LINK

Index Name: UAID_MASTER_IDX_2

Fields: DM_UAIDMF_DAT_TIM

Index Name: UAID_MASTER_IX1

Fields: SM_PRI_LAST_NAM

 SM_PRI_FIRST_NAM

Index Name: UAID_MASTER_PK

Fields: SM_USER_ACCT_ID

UAN_Master Table

The Master table is used by the Analytic Gateway process and contains demographic information for the action level IDs being monitored in the system. This table also has columns representing clients' account data.

The RTR Master table is used by the RTR Analytic Gateway process. All transactions are delivered to

the RTR Analytic Gateway process. Those transactions that are not requiring an RTR response are loaded into this table and then delivered to the Analytic Gateway process.

Note: Proactive Risk Manager configures a variable for every input field for use in defining rules and queues. In some cases, the use of these variables in rules or queues results in performance gains. Performance gains depend on the institution environment and the efficiency of rule writing. Use of variables also simplifies rule writing. When you want to use an input variable in aggregate, rule, or queue creation, you can type the variable name or select a variable from the Variables drop-down list on any Aggregate, Rule, or Queue Editor (Add) screen.

The @ symbol must precede the field name for the SQL Server. A v_ designation must precede the field name for Oracle.

Refer to the Master and RTR Master table section for columns definitions for the UAN_Master table (UAN_MASTER).

Index Name: IDX_UAN_MASTER_DTLASTTX

Fields: DM_ERMF_DAT_TIM

Index Name: IDX_UAN_MASTER_FILTER

Fields: SM_FILTER

Index Name: IDX_UAN_MASTER_LINK

Fields: SM_LINK

Index Name: UAN_MASTER_IX1

Fields: SM_PRI_LAST_NAM
 SM_PRI_FIRST_NAM

Index Name: UAN_MASTER_IX2

Fields: SM_USER_HOME_PHN

Index Name: UAN_MASTER_IX3

Fields: SM_USER_MOB_PHN

Index Name: UAN_MASTER_IX4

Fields: SM_USER_WRK_PHN

Index Name: UAN_MASTER_IX5

Fields: SM_USER_PRI_NAM

Index Name: UAN_MASTER_PK

Fields: SM_UAN

Analysis Tables

The Analysis tables contain information used by the Analysis and Review system. These tables are used to create the screen displays and for report generation.

The below analysis tables are described on the following pages:

- Alert_Category
- APR_Mark_History
- APR_Statistic
- Category_History
- DASHB_QST_ALERT_CATEGORY
- Detail_Alerted_Rule
- Detail_Flag
- Forward
- QueueHistory
- Rules_OP_Events_KPI
- RULES_OP_EVENTS_LOG
- RvQuAISum
- TEMP_APR_APR_INCBLK
- TEMP_APR_APR_LOSS
- TEMP_APR_APR_LOSSPREV
- TEMP_APR_APR_LOSS_BLK
- TEMP_APR_APR_MISSED
- TEMP_APR_USERS_AL_AC_BK
- TEMP_APR_USERS_BLK
- TEMP_APR_USERS_INCBLK
- TEMP_APR_USERS_LOSS
- TEMP_APR_USERS_MARK

Alert_Category Table

The Alert_Category table is used by the Analysis and Review system. It contains alert category configuration information within the PRM system.

The columns in the Alert_Category table (ALERT_CATEGORY) are listed below with the data type.

Column Name	Data Type
ALERT_CATEGORY_COLOR	char(6)
ALERT_CATEGORY_ID	int
ALERT_CATEGORY_NAME	int
ALERT_PROPERTY_ID	integer
CREATED_BY	int
DATE_CREATED	datetime
DATE_MODIFIED	datetime
DESCRIPTION	int
EMAIL_AFTER_MINUTES	int
EMAIL_NOTIFICATION_IND	bit
EMAIL_TEXT	int
MODIFIED_BY	int
SOFT_DELETE_IND	bit

Index Name: ALERT_CATEGORY_IX1

Fields: ALERT_CATEGORY_NAME
EMAIL_TEXT

Index Name: ALERT_CATEGORY_PK

Fields: ALERT_CATEGORY_ID

Column Descriptions

The following are the descriptions of the Alert_Category table columns.

ALERT_CATEGORY_COLOR — The name of the color in which alerts will be processed.

ALERT_CATEGORY_ID — The name of the action level if selected during rule creation.

ALERT_CATEGORY_NAME — The name of the alert category.

ALERT_PROPERTY_ID — Stores the alert property ID when the rule was defined.

CREATED_BY — The unique identifier for who created the alert category.

DATE_CREATED — The date in which the alert category was created.

DATE_MODIFIED — The date in which the alert category was modified.

DESCRIPTION — The description of the alert category.

EMAIL_AFTER_MINUTES — The time in minutes after which an email will be sent when categories are available in Queue/Alert Category.

EMAIL_NOTIFICATION_IND — Determines whether email option is used for Rule (with matching queue or Alert Category ID), Queue, or Alert Category ID.

EMAIL_TEXT — The email text.

MODIFIED_BY — The user ID for the last person to modify this category.

SOFT_DELETE_IND — Determines whether the entry was deleted from the user interface or not.

APR_Mark_History Table

The APR_Mark_History table contains marked and unmarked transactions used to calculate the statistics for the Analyst Performance Report.

The columns in the APR_Mark_History table (APR_MARK_HISTORY) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
DD_PARTITION_DATE	date
DTACTDATEKEY	datetime
LACTIONTYPE	int
LPORTFOLIOID	int
LSTATE	int
ND_KEY_HASH	smallint
NREVID	int
RECORD_SOURCE_ID	smallint
SD_TIEBREAKER	varchar(75)

Column Descriptions

The following are the descriptions of the APR_Mark_History table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The action level key value from one of the master tables. It can contain a SM_PAN, SM_UAN, SM_EMPLOYEE_ID, SM_RETL_ID, SM_TERM_ID. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and is used to determine what type of value is stored in ACTION_LEVEL_KEY.

DD_PARTITION_DATE — Derived from DD_DATE or DD_APDATE column and contain only date information.

DTACTDATEKEY — This column contains the date the mark/unmark action was taken.

LACTIONTYPE — The action type.

LPORTFOLIOID — This represents the identifier of the portfolio from which the action was taken on this account. In the case of Cross Action Level actions, this column is set to -1.

LSTATE — The action status. It is linked to the LSTATUS column in the ActionsText table.

Valid values are as follows:

- 0 = Completed
- 1 = Requested
- 2 = Failed
- 3 = Submitted

ND_KEY_HASH — The value associated with the transaction in the Detail or FraudDetail table.

NREVID — The ID of the analyst who marked/unmarked the transaction. It links to the LID in the PRM_Users table.

RECORD_SOURCE_ID — The identifier of the record source.

SD_TIEBREAKER — A value that makes a transaction unique.

APR_Statistic Table

The APR_Statistic table is the repository for the statistics (counts and sums) collected for the Analyst Performance Report.

The columns in the APR_Statistic table (APR_STATISTIC) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DDATEKEY	date
LACCOUNTS	int
LALERTS	int
LINCORRECTBLOCKED	int
LOSS	numeric(32,4)
LOSSPREVENTED	numeric(32,4)
LPORTFOLIOID	int
LTOTALBLOCKED	int
MISSED	int

<i>Column Name</i>	<i>Data Type</i>
NREVID	int

Index Name: **PK_APR_STATISTIC**

Column Descriptions

The following are the descriptions of the APR_Statistic table columns.

DDATEKEY — The transaction date in YYYYMMDD HH:MM:SS.FFF format. It is displayed in the Transaction Date column on the Actions tab of the Review screen. The Transaction Date column displays n/a if the action taken was not against a specific transaction.

LACCOUNTS — Contains the count of Action Level IDs that were reviewed, but not as alerts.

LALERTS — Contains the count of Action Level IDs that were reviewed as alerts.

LINCORRECTBLOCKED — Contains the count of Action Level IDs that were blocked incorrectly and subsequently had the block cleared by a different user within the configured number of minutes of the APBlkClearedMinutes parameter.

The system uses the APBlkClearedMinutes parameter in the Config table, having 1,440 minutes as default value.

This parameter contains the number of minutes within which a block must be removed by a different user in order for the unblock to increment a user's Blocks Cleared statistic for the Analyst Performance Report.

When edited, the system begins using the modified value from the time it was edited onward. The Block Cleared statistics that were calculated using the previous value will not be recalculated.

LOSS — Contains the amount of Losses Incurred due to not correctly blocking an Action Level ID.

When a user marks one or more transactions for an Action Level ID, but does not block it, and it is later blocked by another user within the configured number of minutes for APBlkMissedMinutes parameter, the system increments Losses Incurred by the MD_TRAN_AMT1 value of each marked transaction that occurred between the Mark and the Block actions for the user that performed the mark action.

LOSSPREVENTED — Contains the amount of Losses Prevented when marking an Action Level ID.

The system increments Losses Prevented by the MD_TRAN_AMT1 value of each marked transaction when a user marks one or more transactions for an Action Level ID.

LPORTFOLIOID — This represents the identifier of the portfolio from which the action was taken on this account. In the case of Cross Action Level actions, this column is set to -1.

LTOTALBLOCKED — Contains the count of Action Level IDs that were blocked.

MISSED — Contains the the number of transactions for the grouping values that the analyst marked and for which another analyst blocked the associated action level ID(s) within a configured number of minutes of the mark action(s).

A transaction is considered to be missed if the analyst marked it, but did not block the action level ID, and another analyst blocked the action level ID within a configured number of minutes after the mark action, based on the APBlkMissedMinutes parameter.

The system uses the APBlkMissedMinutes parameter in the Config table, having 1,440 minutes as default value.

This parameter contains the number of minutes within which a block must be placed by a different user from the time the preceding mark action was performed in order for the block to increment a user's Missed statistic for the Analyst Performance Report.

When edited, the system begins using the modified value from the time it was edited onward. The Missed statistics that were calculated using the previous value will not be recalculated.

NREVID — The ID of the analyst who marked/unmarked the transaction. It links to the LID in the PRM_Users table.

Category_History Table

The Category_History table is used by the Analysis and Review system. It stores the historical record of alerts generated and worked for an alert category per date.

The columns in the Category_History table (CATEGORY_HISTORY) are listed below with the data type.

Column Name	Data Type
AG_PROCESS_ID	varchar(32)
ALERT_CATEGORY_ID	int
DDATE	char(8)

Column Name	Data Type
LHITS	int
LUSED	int

Index Name: **IDX_CATEGORYHISTORY_CLUSTER**

Fields: ALERT_CATEGORY_ID
 DDATE
 AG_PROCESS_ID

Column Descriptions

The following are the descriptions of the Category_History table columns.

AG_PROCESS_ID — The Analytic Gateway Process identifier.

ALERT_CATEGORY_ID — The name of the action level if selected during rule creation. The value is linked to the Alert_Category table.

DDATE — The date the alert was processed from the Alerts table.

LHITS — The number of alerts that met this category criteria.

LUSED — The number of times an alert was retrieved from the alerts queue.

DASHB_QST_ALERT_CATEGORY Table

The DASHB_QST_ALERT_CATEGORY table is a snapshot of ALERT_CATEGORY table and is used in dashboard Queue Status Report

The columns in the DASHB_QST_ALERT_CATEGORY table (DASHB_QST_ALERT_CATEGORY) are listed below with the data type.

Column Name	Data Type
ALERT_CATEGORY_COLOR	char(6)
ALERT_CATEGORY_ID	int
ALERT_CATEGORY_NAME	int
CREATED_BY	int
DATE_CREATED	datetime
DATE_MODIFIED	datetime
DESCRIPTION	int
EMAIL_AFTER_MINUTES	int
EMAIL_NOTIFICATION_IND	bit
EMAIL_TEXT	int
MODIFIED_BY	int
SOFT_DELETE_IND	bit

Index Name: DASHB_AP_ALERT_CATEGORY_IX1

Fields: ALERT_CATEGORY_NAME
EMAIL_TEXT

Index Name: PK_DASHB_AP_ALERT_CATEGORY

Fields: ALERT_CATEGORY_ID

Column Descriptions

The following are the descriptions of the DASHB_QST_ALERT_CATEGORY table columns.

ALERT_CATEGORY_COLOR — The name of the color in which alerts will be processed.

ALERT_CATEGORY_ID — The name of the action level if selected during rule creation.

ALERT_CATEGORY_NAME — The name of the alert category.

CREATED_BY — The unique identifier for who created the alert category.

DATE_CREATED — The date in which the alert category was created.

DATE_MODIFIED — The date in which the alert category was modified.

DESCRIPTION — The description of the alert category.

EMAIL_AFTER_MINUTES — The time in minutes after which an email will be sent when categories are available in Queue/Alert Category.

EMAIL_NOTIFICATION_IND — Determines whether email option is used for Rule (with matching queue or Alert Category ID), Queue, or Alert Category ID.

EMAIL_TEXT — The email text.

MODIFIED_BY — The user ID for the last person to modify this category.

SOFT_DELETE_IND — Determines whether the entry was deleted from the user interface or not.

Detail_Alerted_Rule Table

The Detail_Alerted_Rule table is used by the Analysis and Review system. It identifies alert-related information such as color, score alerted, iced, and rule alerted for a specific transaction within the NRT component.

The columns in the Detail_Alerted_Rule table (DETAIL_ALERTED_RULE) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
ALERT_COLOR	char(6)
ALERT_DATE	datetime
APPLICABLE_CATEGORIES	varchar(2000)
APPLICABLE_QUES	varchar(2000)
BD_ALERTEDRULE	bit
BD_ALERTEDSCORING	bit
BD_ICED	bit
DD_PARTITION_DATE	date
ND_KEY_HASH	smallint
ND_MANUAL_ACT_STAT	smallint
NS_RULEHITS	int
RECORD_SOURCE_ID	smallint
RETRIEVED_FROM_CATEGORY	varchar(2000)
RETRIEVED_FROM_QUE	varchar(2000)

Column Name	Data Type
SD_RULES	varchar(1000)
SD_TIEBREAKER	varchar(75)

Index Name: DETAIL_ALERTED_RULE_IX1

Fields: ACTION_LEVEL_KEY
 ACTION_LEVEL_ID
 ND_MANUAL_ACT_STAT

Index Name: DETAIL_ALERTED_RULE_PK

Fields: DD_PARTITION_DATE
 ND_KEY_HASH
 RECORD_SOURCE_ID
 SD_TIEBREAKER
 ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the Detail_Alerted_Rule table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the DETAIL. It may contain a SD_PAN, SD_UAN, SD_EMPLOYEE_ID, SD_RETL_ID or SD_TERM_ID. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and will be used to determine what type of

value is stored in ACTION_LEVEL_KEY.

ALERT_COLOR — The name of the color in which alerts will be processed.

ALERT_DATE — The date and time of the alert.

APPLICABLE_CATEGORIES — The names of the categories on which the alerts were placed and that are assigned to the user.

APPLICABLE_QUEUES — The names of the queues on which the alerts were placed and that are assigned to the user. It includes all queues except for the system Catch-All queue.

BD_ALERTEDRULE — A Boolean flag specifying the alert status.

Valid values are:

- 0 = Transaction was not alerted
- 1 = Transaction was alerted

BD_ALERTEDSCORING — A Boolean flag specifying the alert type.

Valid values are:

- 0 = The transaction was not alerted by any rules using a score
- 1 = The transaction was alerted by at least one rule that used a score

BD_ICED — A Boolean flag specifying the status at the time the transaction was processed through rules.

Valid values are:

- 0 = The account was not iced
- 1 = The account was iced (no alerts were displayed)

DD_PARTITION_DATE — The value associated with the transaction in the Detail or FraudDetail tables.

ND_KEY_HASH — The value associated with the transaction in the Detail or FraudDetail table.

ND_MANUAL_ACT_STAT — The state of the manual action associated with a transaction.

Valid values are:

-1 = No action (Default)

0 = Clear

1 = Confirm

2 = Manual rule alerted

NS_RULEHITS — The number of rules that matched against this transaction.

RECORD_SOURCE_ID — The value associated with the transaction in the Detail or FraudDetail table.

RETRIEVED_FROM_CATEGORY — This column is either set to NULL to indicate that the alert generated for a transaction was never retrieved from a category, or it contains the values (that is, the ALERT_CATEGORY.ALERT_CATEGORY_IDs) that specify the categories from which the alert was retrieved.

RETRIEVED_FROM_QUE — This column is either set to NULL to indicate that the alert generated for a transaction was never retrieved from a queue, or it contains the values (that is, the RQPORTASSIGN.LIDs) that specify the queues from which the alert was retrieved.

SD_RULES — The numeric value of the rules that were evaluated to true at the time the transaction was evaluated.

SD_TIEBREAKER — The value associated with the transaction in the Detail or FraudDetail table.

Detail_Flag Table

The Detail_Flag table is used by the Analysis and Review system. It identifies mark type, identified by, and tracking information with an action level.

The columns in the Detail_Flag table (DETAIL_FLAG) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
COPY_STATUS	smallint
DD_MARK_DATE	datetime
DD_PARTITION_DATE	date
LD_MARK_REVID	int
ND_IDENTIFIED_BY	int
ND_KEY_HASH	smallint
ND_MARK_REQ	smallint
ND_MARK_TYPE	int
RECORD_SOURCE_ID	smallint
SD_MARK_SOURCE	nvarchar(30)
SD_TIEBREAKER	varchar(75)
SD_TRACKING_ID	varchar(30)

Index Name: DETAIL_FLAG_IX1

Fields: ACTION_LEVEL_ID
 ACTION_LEVEL_KEY
 ND_MARK_TYPE

Index Name: DETAIL_FLAG_IX2

Fields: ACTION_LEVEL_ID
ACTION_LEVEL_KEY
DD_MARK_DATE
DD_PARTITION_DATE
ND_KEY_HASH
RECORD_SOURCE_ID
SD_TIEBREAKER

Index Name: DETAIL_FLAG_PK

Fields: DD_PARTITION_DATE
ND_KEY_HASH
RECORD_SOURCE_ID
SD_TIEBREAKER
ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the Detail_Flag table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — Contains an action level key value that links to the DETAIL table. The value in the ACTION_LEVEL_ID column of this table identifies a row in the ACTION_LEVEL table and is used to determine the type of value that is stored in this column. This column may contain an SD_PAN, SD_RET_L_ID , SD_UAN, SD_TERM_ID, SD_EMPLOYEE_ID, SD_USER_ACCT_ID or SD_PRI_ACCT_NUM.

For example, if the value in the ACTION_LEVEL_ID column is 1 (Card), this column will link to an SD_PAN in the DETAIL table.

COPY_STATUS — Indicates copy status.

DD_MARK_DATE — The date and time that the transaction was marked.

DD_PARTITION_DATE — The value associated with the transaction in the Detail or FraudDetail tables.

LD_MARK_REVID — The user identifier that performed the Mark action on the transaction.

ND_IDENTIFIED_BY — The identified by options configured for the institution at time of installation.

ND_KEY_HASH — The value associated with the transaction in the Detail or FraudDetail table.

ND_MARK_REQ — Used during MARK processing. Typically a value of 1 indicates that the row requires processing. The value is set to 0 after the row is processed.

ND_MARK_TYPE — Used to identify the type of mark applied to the transaction. This column is a foreign key and maps to the FLAGS.LID column where FLAGS.NTYPE equals 2.

RECORD_SOURCE_ID — The value associated with the transaction in the Detail or FraudDetail table.

SD_MARK_SOURCE — Identifies the system that initiated the mark request for the transaction.

SD_TIEBREAKER — The value associated with the transaction in the Detail or FraudDetail table.

SD_TRACKING_ID — The free-form text capable of accepting alphanumeric data of up to 30 characters. This allows institutions to tie suspicious transactions together, even if they occurred in different accounts.

Forward Table

The Forward table is used by the Analysis and Review system. Each time a user sets a reminder or forwards an alert or a card to another analyst, the system adds a record to the Forward table.

The columns in the Forward table (FORWARD) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
ALERT_CATEGORY_ID	int
ALERT_DATE	datetime
DD_DATE	datetime
DTPICKUP	datetime
FORWARDED_BY	int
FORWARD_DESCRIPTION	nvarchar(400)
LACTIONTYPE	int
LID	bigint
LQUEID	int
LREVID	int
MESSAGE_ID	int

Index Name: **IDX_FORWARD_CLUSTER**

Fields: LREVID

DTPICKUP

Index Name: **IDX_FORWARD_DTPICKUP**

Fields: DTPICKUP

Index Name: **IDX_FORWARD_UNQ**

Fields: ACTION_LEVEL_KEY

ACTION_LEVEL_ID

LREVID

DTPICKUP

LACTIONTYPE

FORWARD_DESCRIPTION

Column Descriptions

The following are the descriptions of the Forward table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The action level key. It is linked to the ACTION_LEVEL_KEY in the Alerts table.

ALERT_CATEGORY_ID — The name of the action level if selected during rule creation. The value is linked to the Alert_Category table.

ALERT_DATE — The date and time of the alert. It is linked to the Alerts table.

DD_DATE — The authorization date.

DTPICKUP — Used for forwards and reminders and is the date and time that must be exceeded before the forward or reminder should be retrieved by the system and presented to a user.

FORWARDED_BY — The analyst ID of the analyst who created the forward or reminder.

FORWARD_DESCRIPTION — Text providing additional information about the forward or reminder.

LACTIONTYPE — The action type.

Valid values are:

7 = Reminder

8 = Forward

LID — Internal ID of FORWARD table

LQUEID — The queue that the alert came from when it was forwarded or set to remind later. It links to the LID in the RuleQueue table.

LREVID — The analyst ID. It links the recipient of the forwarded card or reminder, to a user listed in the PRM_Users table.

MESSAGE_ID — A value from the MESSAGE_ID column in the External_Message_Data table. This allows a forward record to be associated with an external message data record.

QueueHistory Table

The QueueHistory table is used by the Analytic Gateway process. It contains a record of the daily activity of each queue in the system.

The columns in the QueueHistory table (QUEUEHISTORY) are listed below with the data type.

Column Name	Data Type
AG_PROCESS_ID	varchar(32)
DDATE	char(8)
LHITS	int
LPORTFOLIOID	int
LRQAID	int
LUSED	int

Index Name: **IDX_QUEUEHISTORY_CLUSTER**

Fields: DDATE
LRQAID
LPORTFOLIOID
AG_PROCESS_ID

Column Descriptions

The following are the descriptions of the QueueHistory table columns.

AG_PROCESS_ID — The Analytic Gateway Process identifier.

DDATE — The date of the transaction.

LHITS — The number of alerts that met this queue criteria.

LPORTFOLIOID — The portfolio ID. It is linked to the LID column in the Portfolios table.

LRQAID — The queue ID. It is linked to the LID column in the RQPortAssign table.

LUSED — The number of times an alert was retrieved from the Alerts queue.

Rules_OP_Events_KPI Table

The RULES_OP_EVENTS_KPI table is a configuration table and is used to obtain Operational Events reports.

The columns in the Rules_OP_Events_KPI table (RULES_OP_EVENTS_KPI) are listed below with the data type.

Column Name	Data Type
BDEBUG	integer
DB_LOG	integer
EMAIL_ADDRESS	nvarchar(2000)
EMAIL_LOG	integer
KPI_ID	integer
LOCALE_ID	nvarchar(10)
NSTATUS	integer
POLL_INTERVAL	integer
RULE_TYPE	varchar(20)
SSQL	nvarchar(2000)
THRESHOLD	integer

Index Name: PK_RULES_OP_EVENTS_KPI

Fields: KPI_ID

Column Descriptions

The following are the descriptions of the Rules_OP_Events_KPI table columns.

BDEBUG — Debug flag. Debug information is recorded in SYSTEMAUDIT table.

0 = False

1 = True

DB_LOG — Flag that indicates if events are logged in RULES_OP_EVENTS_LOG table.

0 = False

1 = True

EMAIL_ADDRESS — Email address.

EMAIL_LOG — Flag that indicates if event is emailed.

0 = False

1 = True

KPI_ID — Event ID.

LOCALE_ID — Locale ID for reporting data.

NSTATUS — Flag that indicates if event is monitored:

0 = False

1 = True

POLL_INTERVAL — Time interval for report's execution. Value is in seconds.

RULE_TYPE — Rules type to monitor

Possible values : NRT and RT

SSQL — Additional filter condition for triggering event. Columns referenced in this condition must be from SHORTWINDOW table.

THRESHOLD — When number of alerts for a rule exceeds THRESHOLD value, information is reported.

RULES_OP_EVENTS_LOG Table

RULES_OP_EVENTS_LOG contains recorded information related to operation events for rule's performance.

The columns in the RULES_OP_EVENTS_LOG table (RULES_OP_EVENTS_LOG) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
END_DATE	datetime
KPI_ID	integer
LOG_ID	integer
RULE_COUNT	integer
RULE_ID	integer
RULE_NAME	nvarchar(500)
START_DATE	datetime

Index Name: **IDX_RULES_OP_EVENTS_LOG**

Fields: LOG_ID

Column Descriptions

The following are the descriptions of the RULES_OP_EVENTS_LOG table columns.

END_DATE — End date of monitored event.

KPI_ID — Event ID.

LOG_ID — ID value of event execution.

RULE_COUNT — Number of alerts for monitored event in given interval that exceeds THRESHOLD value and are filtered by SSQL value.

RULE_ID — Rule's ID.

RULE_NAME — Rule's Name.

START_DATE — Start date for monitored event.

RvQuAlSum Table

The RvQuAlSum table is used by the Analysis and Review system. It contains analyst and queue information.

The columns in the RvQuAlSum table (RVQUALSUM) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DDATEKEY	char(8)
LACCOUNTS	int
LALERTS	int
LFILTERID	int
LFORWARDED	int
LINCORRECTBLOCKED	int
LMAXREVIEWTIME	int
LMINREVIEWTIME	int
LRECEIVED	int
LREVID	int
LSECACCOUNTS	int

Column Name	Data Type
LSECALERTS	int
LSECFORWARDED	int
LSECRECEIVED	int
LTOTALBLOCKED	int

Index Name: IDX_RVQUALSUM_CLUSTER

Fields: DDATEKEY

 LREVID

 LFILTERID

Index Name: IDX_RVQUALSUM_REVID

Fields: LREVID

Column Descriptions

The following are the descriptions of the RvQuAlSum table columns.

DDATEKEY — The date that the account was reviewed.

LACCOUNTS — The number of accounts opened.

LALERTS — The number of alerts processed by an analyst.

LFILTERID — The portfolio filter ID.

LFORWARDED — The number of accounts forwarded from this analyst.

LINCORRECTBLOCKED — The number of blocks the analyst removed.

LMAXREVIEWTIME — The maximum time spent reviewing accounts.

LMINREVIEWTIME — The minimum time spent reviewing accounts.

LRECEIVED — The number of accounts forwarded to this analyst.

LREVID — The analyst ID.

LSECACCOUNTS — The time spent reviewing open accounts.

LSECALERTS — The time spent reviewing alerts.

LSECFORWARDED — The time spent reviewing alerts before forwarding.

LSECRECEIVED — The time spent reviewing alerts forwarded to this analyst.

LTOTALBLOCKED — The number of blocks the analyst placed.

TEMP_APR_APR_INCBLK Table

The TEMP_APR_APR_INCBLK table is an Oracle Temporary Table created only in the Oracle PRM schema. It is used to calculate the statistics for the Analyst Performance Report.

The columns in the TEMP_APR_APR_INCBLK table (TEMP_APR_APR_INCBLK) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
---------------------------	-------------------------

Column Descriptions

The following are the descriptions of the TEMP_APR_APR_INCBLK table columns.

TEMP_APR_APR_LOSS Table

The TEMP_APR_APR_LOSS table is an Oracle Temporary Table created only in the Oracle PRM schema. It is used to calculate the statistics for the Analyst Performance Report.

The columns in the TEMP_APR_APR_LOSS table (TEMP_APR_APR_LOSS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
---------------------------	-------------------------

Column Descriptions

The following are the descriptions of the TEMP_APR_APR_LOSS table columns.

TEMP_APR_APR_LOSSPREV Table

The TEMP_APR_APR_LOSSPREV table is an Oracle Temporary Table created only in the Oracle PRM schema. It is used to calculate the statistics for the Analyst Performance Report.

The columns in the TEMP_APR_APR_LOSSPREV table (TEMP_APR_APR_LOSSPREV) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
---------------------------	-------------------------

Column Descriptions

The following are the descriptions of the TEMP_APR_APR_LOSSPREV table columns.

TEMP_APR_APR_LOSS_BLK Table

The TEMP_APR_APR_LOSS_BLK table is an Oracle Temporary Table created only in the Oracle PRM schema. It is used to calculate the statistics for the Analyst Performance Report.

The columns in the TEMP_APR_APR_LOSS_BLK table (TEMP_APR_APR_LOSS_BLK) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
---------------------------	-------------------------

Column Descriptions

The following are the descriptions of the TEMP_APR_APR_LOSS_BLK table columns.

TEMP_APR_APR_MISSED Table

The TEMP_APR_APR_MISSED table is an Oracle Temporary Table created only in the Oracle PRM schema. It is used to calculate the statistics for the Analyst Performance Report.

The columns in the TEMP_APR_APR_MISSED table (TEMP_APR_APR_MISSED) are listed below with the data type.

Column Name	Data Type
--------------------	------------------

Column Descriptions

The following are the descriptions of the TEMP_APR_APR_MISSED table columns.

TEMP_APR_USERS_AL_AC_BK Table

The TEMP_APR_USERS_AL_AC_BK table is an Oracle Temporary Table created only in the Oracle PRM schema. It is used to calculate the statistics for the Analyst Performance Report.

The columns in the TEMP_APR_USERS_AL_AC_BK table (TEMP_APR_USERS_AL_AC_BK) are listed below with the data type.

Column Name	Data Type
--------------------	------------------

Column Descriptions

The following are the descriptions of the TEMP_APR_USERS_AL_AC_BK table columns.

TEMP_APR_USERS_BLK Table

The TEMP_APR_USERS_BLK table is an Oracle Temporary Table created only in the Oracle PRM schema. It is used to calculate the statistics for the Analyst Performance Report.

The columns in the TEMP_APR_USERS_BLK table (TEMP_APR_USERS_BLK) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
---------------------------	-------------------------

Column Descriptions

The following are the descriptions of the TEMP_APR_USERS_BLK table columns.

TEMP_APR_USERS_INCBLK Table

The TEMP_APR_USERS_INCBLK table is an Oracle Temporary Table created only in the Oracle PRM schema. It is used to calculate the statistics for the Analyst Performance Report.

The columns in the TEMP_APR_USERS_INCBLK table (TEMP_APR_USERS_INCBLK) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
---------------------------	-------------------------

Column Descriptions

The following are the descriptions of the TEMP_APR_USERS_INCBLK table columns.

TEMP_APR_USERS_LOSS Table

The TEMP_APR_USERS_LOSS table is an Oracle Temporary Table created only in the Oracle PRM schema. It is used to calculate the statistics for the Analyst Performance Report.

The columns in the TEMP_APR_USERS_LOSS table (TEMP_APR_USERS_LOSS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
---------------------------	-------------------------

Column Descriptions

The following are the descriptions of the TEMP_APR_USERS_LOSS table columns.

TEMP_APR_USERS_MARK Table

The TEMP_APR_USERS_MARK table is an Oracle Temporary Table created only in the Oracle PRM schema. It is used to calculate the statistics for the Analyst Performance Report.

The columns in the TEMP_APR_USERS_MARK table (TEMP_APR_USERS_MARK) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
---------------------------	-------------------------

Column Descriptions

The following are the descriptions of the TEMP_APR_USERS_MARK table columns.

Rule/Queue System Tables

The Rule/Queue System tables contain information for Analytic Gateway process rule processing.

The below Rule/Queue System tables are described on the following pages:

- AutoActionsRule
- Pending_Aggregates
- Rqa
- RQCategories
- RQDisposition
- RQOrder
- RQPortAssign
- RQVarDefAssign
- RqVariables
- RuleDefTemplateLink
- RULEPERFMONITOR_DEF
- RULEPERFMONITOR_LOG
- RuleQue
- RuleSubTypes
- RuleSubtypeTemplate

- RuleTypes
- Rule_Tester_Alerted
- Rule_Tester_Dataset
- Templates
- Template_Types

AutoActionsRule Table

The AutoActionsRule table is used by the Analysis and Review system. It contains a row for each auto action rule defined.

Each time an auto action rule is created, the system adds a record to this table.

The columns in the AutoActionsRule table (AUTOACTIONSRULE) are listed below with the data type.

Column Name	Data Type
ACTION_DATETIME	datetime
ACTION_DESCRIPTION	nvarchar(255)
ACTION_DESCRIPTION2	nvarchar(255)
ACTION_ORDER	int
AUTO_ADDIN_TYPE	int
CONTACT_STRATEGY_ID	int
IDENTIFIEDBY	int
ISCALCULATEDFUNDSATRISK	int
LACTIONID	int

Column Name	Data Type
LAGGID	int
LID	int
LREVID	int
LRULEID	int
LTEAMID	int
MARKTYPE	int
NSTATUS	int
RESPONSECODE	nvarchar(30)
SBLOCKCODE	nvarchar(5)
SHOST_VALUE	nvarchar(1024)
SNOTIFYTYPE	nvarchar(50)
TRACKINGID	varchar(30)

Index Name: IDX_AUTOACTIONSRULE_CLUSTER

Fields: LID

Index Name: IDX_AUTOACTIONSRULE_RULEID

Fields: LRULEID

LACTIONID

Column Descriptions

The following are the descriptions of the AutoActionsRule table columns.

ACTION_DATETIME — The date and time for the action. This is not applicable for all actions.

ACTION_DESCRIPTION — The action description for the auto action.

ACTION_DESCRIPTION2 — The action description2 for the auto action.

ACTION_ORDER — Contains the auto action order if more than one action is used within a rule.

AUTO_ADDIN_TYPE — Contains the add-in type if the auto action is an add-in action.

CONTACT_STRATEGY_ID — A numeric value identifying a contact strategy which is assigned to a notification auto action when an auto actioned rule is defined. It references the table CONTACT_STRATEGY.

IDENTIFIEDBY — Contains the Identified By options configured for auto-action rule.

ISCALCULATEDFUNDSATRISK — Determines whether the funds at risk is calculated for an alerted transaction. Accepted values are:

0 = Funds at Risk are not calculated.

1 = Funds at Risk are calculated.

LACTIONID — The auto action selected on the Auto Action dialog box.

LAGGID — The aggregate selected on the Auto Action dialog box.

LID — The row ID.

LREVID — The user ID selected on the Auto Action dialog box.

LRULEID — The Rule ID. The index to the RuleQue table.

LTEAMID — The ID of the team to which the user belongs.

MARKTYPE — Identifies the type of mark that was applied to the transaction.

NSTATUS — Determines whether the auto action portion of a rule is active. The rule can be active even though the auto action portion is not. The rule is then a standard rule or a profile rule.

Valid values are:

0 = Not active/deleted

1 = Active

RESPONSECODE — This field contains the auto actions response code.

SBLOCKCODE — Contains the block code selected on the Auto Action dialog box. This column can be null or empty.

SHOST_VALUE — The host value if external message processing is enabled for the action.

SNOTIFYTYPE — Contains the notify type.

TRACKINGID — Contains the free-form text and is capable of accepting alphanumeric data of up to 30 characters. This allows institutions to tie suspicious transactions together, even if they occurred in different accounts.

Pending_Aggregates Table

The Pending_Aggregates table is used to keep the approved version of an aggregate that is set to pending status.

The columns in the Pending_Aggregates table (PENDING_AGGREGATES) are listed below with the data type.

Column Name	Data Type
PEND_DTAPPROVED	datetime
PEND_DTCREATED	datetime
PEND_ENTRANCE_CRITERION	nvarchar(Max)
PEND_LAPPROVEDBY	int
PEND_LCREATEDBY	int
PEND_LID	int
PEND_NTEAMONLY	smallint
PEND_SDESC	int
PEND_SSQL	nvarchar(Max)

Index Name: **PK_PENDING_AGGREGATES**

Fields: PEND_LID

Column Descriptions

The following are the descriptions of the Pending_Aggregates table columns.

PEND_DTAPPROVED — The date and time that the approved version of the pending aggregate was approved.

PEND_DTCREATED — The date and time that the approved version of the pending aggregate was created.

PEND_ENTRANCE_CRITERION — Contains the Entrance Criteria for the approved version of the pending aggregate.

PEND_LAPPROVEDBY — Identifies the user who approved the currently approved version of the

pending aggregate.

PEND_LCREATEDBY — Identifies the user who created the currently approved version of the pending aggregate.

PEND_LID — A unique identifier for the pending aggregate.

PEND_NTEAMONLY — The Team Only setting for the currently approved version of the pending aggregate.

PEND_SDESC — The description for the currently approved version of the pending aggregate.

PEND_SSQL — The SQL Syntax for the currently approved version of the pending aggregate.

Rqa Table

The Rqa table is used by the Analysis and Review system. It contains queue assignments.

Each time a supervisor or team administrator assigns a queue to an analyst, the system creates a record in the Reviewer Queue Assignment table.

The columns in the Rqa table (RQA) are listed below with the data type.

Column Name	Data Type
ALERT_CATEGORY_ID	int
LREVID	int
LRQAID	int
NPRIORITY	smallint
PORTFOLIO_ID	int

Index Name: **IDX_RQA_CLUSTERED**

Fields: LREVID

 NPRIORITY

Index Name: **IDX_RQA_QUEID**

Fields: LRQAID

Column Descriptions

The following are the descriptions of the Rqa table columns.

ALERT_CATEGORY_ID — The name of the action level if selected during rule creation. The value is linked to the Alert_Category table.

LREVID — The analyst ID. It links the recipient of the forwarded card or reminder to a user listed in the PRM_Users table.

LRQAID — The index to the RqPortAssign table. It links to the rule/queue ID and the portfolio ID in the RqPortAssign table.

NPRIORITY — Ranks the priority a queue has for a particular analyst. However, if a multiprocessor is using the queue override option, the NORDER field in the RuleQueue table determines the priority of a queue.

PORTFOLIO_ID — Indicates when a queue is assigned to a user.

RQCategories Table

The RQCategories table is used to identify categories of rules or queues.

The columns in the RQCategories table (RQCATEGORIES) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
LID	int

Column Name	Data Type
SCATEGORY	varchar(50)

Column Descriptions

The following are the descriptions of the RQCategories table columns.

LID — A distinct numeric value used to uniquely identify a category.

SCATEGORY — The name of the category.

RQDisposition Table

The RQDisposition table is used by the Rule Queue editor screen when editing real-time rules. It is used to populate the values in the Disposition drop-down in the editor screen.

The columns in the RQDisposition table (RQDISPOSITION) are listed below with the data type.

Column Name	Data Type
DTCREATED	datetime
LCREATEDBY	int
LID	int
LORDER	int
SMNEMONIC	nvarchar(2)
SNAME	int

Column Descriptions

The following are the descriptions of the RQDisposition table columns.

DTCREATED — The date when the Real-Time disposition was created

LCREATEDBY — The user ID for the person who created this Real-Time disposition

LID — The ID for each disposition.

LORDER — The default ordering of real-time rules to be executed in the following order:

- 1 = Authorize
- 2 = Referral
- 3 = Decline

Note: When the order of execution is changed through the portfolio deployment window, this order is no longer relevant.

SMNEMONIC — The mnemonic to be used in conjunction with the SNAME (for example, A, D, or R).

SNAME — The disposition name (for example, Authorize, Decline, or Refer).

RQOrder Table

The RQOrder table is reserved for future use for queue override processing and will contain the proper queue orders.

The columns in the RQOrder table (RQORDER) are listed below with the data type.

Column Name	Data Type
LORDER	int
LPORTFOLIOID	int
LRULEID	int
LTEAMID	int

Index Name: **IDX_RQORDER**

Fields: LPORTFOLIOID
 LRULEID
 LTEAMID

Column Descriptions

The following are the descriptions of the RQOrder table columns.

LORDER — The ordering of queues.

LPORTFOLIOID — The portfolio ID. It is linked to the LID column in the Portfolios table.

LRULEID — The Rule ID. The index to the RuleQue table.

LTEAMID — The ID of the team to which the user belongs.

RQPortAssign Table

The RqPortAssign table is used by the Analysis and Review system. It contains a unique row for each Rule/Queue to Portfolio assignment. A single rule can be assigned to multiple portfolios. This table is to facilitate that requirement.

The columns in the RQPortAssign table (RQPORTASSIGN) are listed below with the data type.

Column Name	Data Type
DTCREATED	datetime
DTMODIFIED	datetime
LCREATEDBY	int
LDEPLOYEDBY	int
LID	int
LMODIFIEDBY	int
LPORTFOLIOID	int
LRULEID	int
NDEPLOYED	smallint
NSTATUS	smallint

Index Name: IDX_PORT_STATUS

Fields: LPORTFOLIOID
 LRULEID
 NSTATUS
 NDEPLOYED
 LID

Index Name: IDX_PORTID

Fields: LID

Column Descriptions

The following are the descriptions of the RQPortAssign table columns.

DTCREATED — The date the rule/queue portfolio assignment was created.

DTMODIFIED — The date the rule/queue portfolio assignment was modified.

LCREATEDBY — The user ID for the person who created this assignment.

LDEPLOYEDBY — The user ID for the person who deployed the rule/queue portfolio assignment.

LID — The index of the rule/queue portfolio assignment. It is linked to the LRQAID column in the Alerts table.

LMODIFIEDBY — The user ID for the last person to modify this assignment.

LPORTFOLIOID — The index to the Portfolios table.

LRULEID — The Rule ID. The index to the RuleQue table.

NDEPLOYED — Indicates whether this rule assignment has been deployed.

Valid values are:

0 = Rule has not been deployed

1 = Rule has been deployed

NSTATUS — Indicates whether this assignment is active.

Valid values are:

0 = Assignment was deleted

1 = Assignment is still active

RQVarDefAssign Table

The RQVarDefAssign table is used by the Analysis and Review system. It defines the relationships between a rule type (for example, standard rule, standard queue, or profile rule) and the items that will be displayed in the pop-up lists in the Rule/Queue editor. Some examples of the pop-up lists are the SQL button and the Operator buttons.

The columns in the RQVarDefAssign table (RQVARDEFASSIGN) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
CAPTION_NAME	int
LID	int
LRULEDEFID	int
LVARIABLEID	int
NTYPE	int
NUSAGE	int

Index Name: **IDX_RQVARDEFASSIGN_CLUSTER**

Fields: LID

Column Descriptions

The following are the descriptions of the RQVarDefAssign table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

CAPTION_NAME — Stores the caption name for the rule or queue variable for the corresponding action level.

LID — The index for a row in this table.

LRULEDEFID — The index for a row in the RuleDef table. A value of -1 indicates use for all types of rules.

LVARIABLEID — The index for a row in either the RQVariables table or the RQ_Fields table.

NTYPE — Indicates which table contains the variable.

Valid values are:

0 = RQVariables table

1 = RQ_Fields table

NUSAGE — Indicates which box the variables should be contained in.

Valid values are:

1 = Field

2 = Operators

3 = SQL

4 = Aggregates

5 = Transactions

6 = Demographics

RqVariables Table

The RqVariables table is used by the Analysis and Review system. It contains a listing of fields and functions for use in rule or queue manager drop-down lists.

When a team administrator or supervisor attempts to create a rule or queue, the program lists the fields, variables, and functions that are available to write the queue definition. These available queue-building elements are listed in the RqVariables table

The columns in the RqVariables table (RQVARIABLES) are listed below with the data type.

Column Name	Data Type
LVARIABLEID	int
SNAME	varchar(255)

Column Descriptions

The following are the descriptions of the RqVariables table columns.

LVARIABLEID — A unique variable ID.

SNAME — The variable name.

RuleDefTemplateLink Table

The RuleDefTemplateLink table is used by the Analysis and Review system. It contains relationships between the rule definition and a template.

The columns in the RuleDefTemplateLink table (RULEDEFTEMPLATELINK) are listed below with the data type.

Column Name	Data Type
LID	int
LORDERID	int
LRULEDEFID	int
LTEMPLATEID	int

Column Descriptions

The following are the descriptions of the RuleDefTemplateLink table columns.

LID — The index for the table.

LORDERID — An order number that is used to build a multi-piece template.

LRULEDEFID — An index to the RuleDef table.

LTEMPLATEID — An index to the Templates table.

RULEPERFMONITOR_DEF Table

The Ruleperfmonitor_def table holds the Threshold definitions for the Rule Performance Monitor. This functionality is designed for DBA's only, as enabling/disabling will require an update into the DB. Monitor the system while the functionality is enabled.

The columns in the RULEPERFMONITOR_DEF table (RULEPERFMONITOR_DEF) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
THRESHOLDMS	int

Index Name: **IDX_RULEPERFMONITOR_DEF**

Fields: THRESHOLDMS

Column Descriptions

The following are the descriptions of the RULEPERFMONITOR_DEF table columns.

THRESHOLDMS — The Threshold definitions in milliseconds for the Rule Performance Monitor. Default value is -1 meaning that the functionality is disabled. Any value > 0 enables the functionality.

RULEPERFMONITOR_LOG Table

The Ruleperfmonitor_log table holds the rule logging information for the Rule Performance Monitor. This functionality is designed for DBA's only, as enabling/disabling will require an update into the DB. Monitor the system while the functionality is enabled.

The columns in the RULEPERFMONITOR_LOG table (RULEPERFMONITOR_LOG) are listed below with the data type.

Column Name	Data Type
LOG_DATETIME	datetime2(7)
RULEID	int
RULENAME	nvarchar(500)
RUNTIMEMS	int
SD_TIEBREAKER	varchar(75)

Index Name: **IDX_RULEPERFMONITOR_LOG_CLU**

Fields: LOG_DATETIME

Column Descriptions

The following are the descriptions of the RULEPERFMONITOR_LOG table columns.

LOG_DATETIME — The time when the log was created.

RULEID — The Rule ID. The index to the RuleQue table.

RULENAME — The Rule name.

RUNTIMEMS — The duration in milliseconds.

SD_TIEBREAKER — A transaction field that make a transaction unique when more than one transaction has the same date and time. It is defined at installation.

RuleQue Table

The RuleQue table is used by the Analysis and Review system. It identifies the deployed rules and queues (along with the queue assignments) to determine how the system distributes the alerts to analysts.

Each time a team administrator or a supervisor creates a queue definition, the system adds a record to the RuleQue table.

Records are updated if a queue is modified or its deployment status is changed.

The columns in the RuleQue table (RULEQUE) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
AGGREGATE_NAME	nvarchar(60)
ALERT_CATEGORY_ID	int
ALERT_COLOR	char(6)
ALERT_PROPERTY_ID	integer
AUTO_ACTION_ONLY	int
BISREADONLY	smallint
BUSESSCORE	smallint
DTAPPROVED	datetime

Column Name	Data Type
DTCREATED	datetime
DTMODIFIED	datetime
EMAIL_AFTER_MINUTES	int
EMAIL_NOTIFICATION_IND	bit
EMAIL_TEXT	int
ENTRANCE_CRITERION	nvarchar(4000)
LAGGTYPEID	int
LAPPROVEDBY	int
LCREATEDBY	int
LID	int
LMODIFIEDBY	int
LQUEUEID	int
LRULEDEFID	int
LTEAMID	int
NISMANUALACTION	tinyint
NSTATUS	smallint
RT_LID	int

Column Name	Data Type
RULE_SCORE	int
SAGGREGATEIDS	nvarchar(4000)
SAGGREGATETYPE	nvarchar(50)
SCORE_FIELDS_USED_BY_RULES	int
SDESC	int
SDISPOSITIONTYPE	nvarchar(50)
SKIP_BAD_SQL_COUNTER	bigint
SKIP_BAD_SQL_LAST_TIME	datetime
SNAME	int
SSQL	nvarchar(Max)

Index Name: IDX_ID_NAME

Fields: LID

SNAME

Index Name: PK_RULEQUE

Fields: LID

Column Descriptions

The following are the descriptions of the RuleQue table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level

- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

AGGREGATE_NAME — The name of the aggregate.

ALERT_CATEGORY_ID — The name of the action level if selected during rule creation. The value is linked to the Alert_Category table.

ALERT_COLOR — The name of the color in which alerts will be processed.

ALERT_PROPERTY_ID — Stores the alert property ID when the rule was defined.

AUTO_ACTION_ONLY — Determines whether the rule is an Auto Action or not.

BISREADONLY — Contains the indication of whether or not a rule can be edited.

Valid values are:

- 0 = Rule can be edited.
- 1 = Rule cannot be edited; readonly.

BUSESSCORE — The Boolean flag indicating whether the rule uses the suspicious activity score.

Valid values are:

- 0 = Does not use score
- 1 = Uses score

DTAPPROVED — The date on which the aggregate was last approved.

DTCREATED — The date the queue or rule was created.

DTMODIFIED — The date the rule or queue was last modified.

EMAIL_AFTER_MINUTES — The time in minutes after which an email will be sent when alerts are available in Queue/Alert Category.

EMAIL_NOTIFICATION_IND — Determines whether email option is used for Rule (with matching queue or Alert Category ID), Queue, or Alert Category ID.

EMAIL_TEXT — The email text.

ENTRANCE_CRITERION — The entrance criterion defined during the creation of rules, queues, or aggregates.

LAGGTYPEID — An index to the RQAggregatetype table if the rule is an aggregate. If the rule is not an aggregate, this column will contain a value of -1.

LAPPROVEDBY — Identifies the user who last approved the aggregate.

LCREATEDBY — The user ID of the user that created the rule. It is linked to the LID column in the PRM_Users table.

LID — A unique ID.

LMODIFIEDBY — The user ID of the user who modified the rule last.

LQUEUEID — The Boolean flag specifying whether the rule acts as a queue.

Valid values are:

0 = Rule does not act as a queue

1 = Rule acts as a queue

LRULEDEFID — An index to the RuleDef table. It is used to indicate if row is a Queue, Rule, Profile Queue, Profile Rule, etc.

LTEAMID — An index to the Teams table. It corresponds to the TeamID in the Teams table when a rule is defined to a specific team.

NISMANUALACTION — The Boolean flag specifying whether the rule or queue requires manual action. This column has been added to all of the product databases, but is only used in the ER Oracle product.

Valid values are:

0 = No (Default)

1 = Yes

NSTATUS — Indicates whether the rule has been marked as soft deleted.

Valid values are:

0 = Deleted

1 = Not deleted

RT_LID — The LID of the RT rule on which the matching NRT rule was based.

RULE_SCORE — The score (numeric value) to be assigned to an alert generated from this rule. It is used as an indicator of the level of risk for the transaction. The possible values are -999 to +999. The default is 0 if no rule score is specified.

SAGGREGATEIDS — A list of aggregate ID indexes that are used in the rule.

SAGGREGATETYPE — The type of aggregate.

SCORE_FIELDS_USED_BY_RULES — Contains the score of the fields used in the rule.

SDESC — A description of the rule or queue.

SDISPOSITIONTYPE — The disposition type of the rule if it is a real-time rule.

SKIP_BAD_SQL_COUNTER — The number of times the rule was skipped since the last time the skip counters were reset.

SKIP_BAD_SQL_LAST_TIME — The date and time of the last time the rule was skipped since the last time the skip counters were reset.

SNAME — The name of the rule or queue.

SSQL — The SQL for the rule that will be inserted into the stored procedure.

RuleSubTypes Table

The RuleSubTypes table is used by the Analysis and Review system and contains all rule sub-types (for example, standard, profile, real-time).

The columns in the RuleSubTypes table (RULESUBTYPES) are listed below with the data type.

Column Name	Data Type
LID	int
SDESCRIPTION	nvarchar(50)

Column Descriptions

The following are the descriptions of the RuleSubTypes table columns.

LID — The index for the table. Valid values are:

SDESCRIPTION — The description of the sub-type.

Valid values are:

- 0 = Standard rule
- 1 = Profile rule
- 2 = Real-time rule

RuleSubtypeTemplate Table

The RuleSubtypeTemplate table is used by the Analysis and Review system and contains templates and subtypes (for example, Rule, Queue, Aggregate) during the displaying of data.

The columns in the RuleSubtypeTemplate table (RULESUBTYPETEMPLATE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
SUBTYPEID	smallint
TEMPLATESUBTYPEID	smallint

Column Descriptions

The following are the descriptions of the RuleSubtypeTemplate table columns.

SUBTYPEID — The ID value from the RuleSubType table.

TEMPLATESUBTYPEID — The type of template to replace the placeholder.

Valid values are:

- 0 = For NRT
- 1 = For PROFILE
- 2 = For RT

RuleTypes Table

The RuleTypes table is used by the Analysis and Review system and contains all rule types (for example, Rule, Queue, Aggregate) during the displaying of data.

The columns in the RuleTypes table (RULETYPES) are listed below with the data type.

Column Name	Data Type
LID	int
SDESCRIPTION	nvarchar(50)

Column Descriptions

The following are the descriptions of the RuleTypes table columns.

LID — The index for the table.

Valid values are:

- 0 = Rule
- 1 = Queue
- 2 = Aggregate

SDESCRIPTION — The description of the rule types.

Valid values are:

- 0 = Rule
- 1 = Queue
- 2 = Aggregate

Rule_Tester_Alerted Table

The Rule_Tester_Alerted table contains identification information for the transactions that were alerted by the most recent test (the composite unique key only).

The columns in the Rule_Tester_Alerted table (RULE_TESTER_ALERTED) are listed below with the data type.

Column Name	Data Type
DD_DATE	datetime
DD_PARTITION_DATE	date
ND_KEY_HASH	smallint
RECORD_SOURCE_ID	smallint
SD_TIEBREAKER	varchar(75)

Index Name: RULE_TESTER_ALERTED_CLUSTER_INDEX

Fields: DD_PARTITION_DATE
 DD_DATE
 ND_KEY_HASH
 RECORD_SOURCE_ID
 SD_TIEBREAKER

Index Name: RULE_TESTER_ALERTED_IX1

Fields: DD_PARTITION_DATE
 ND_KEY_HASH
 RECORD_SOURCE_ID
 SD_TIEBREAKER

Column Descriptions

The following are the descriptions of the Rule_Tester_Alerted table columns.

DD_DATE — The transaction date and time. It is linked to DTDDATE column in the Detail table.

DD_PARTITION_DATE — Derived from DD_DATE or DD_APDATE column and contains only date information.

ND_KEY_HASH — Enables sub-partitioning on two distinct columns. If it is not used for sub-partitioning, the column is populated by a constant (for example, a hashing function). If DD_DATE is used as the base for DD_PARTITION_DATE, then SD_PAN or SD_UAN is hashed. If AP_DATE is

used as the base for DD_PARTITION_DATE, then SD_RETL_ID is hashed.

RECORD_SOURCE_ID — The identifier of the record source as defined in the Analytic Gateway.

SD_TIEBREAKER — A transaction field that makes a transaction unique when more than one transactions have the same date and time. It is defined at installation.

Rule_Tester_Dataset Table

The Rule_Tester_Dataset table holds the dataset generated by the Rule Manager. The dataset consists of a configured copy of historical transaction data against which the Rule Manager can test rules and obtain information on the effectiveness of those rules.

The columns in the Rule_Tester_Dataset table (RULE_TESTER_DATASET) are listed below with the data type.

Column Name	Data Type
BUILD_PROGRESS	varchar(4000)
BUILD_TIMEOUT	int
CREATION_END_TS	datetime
CREATION_START_TS	datetime
DATASET_CREATE_ROLE_ID	int
DATASET_CREATE_USER_ID	int
DATASET_CREATE_WORKSTATION	varchar(100)
DATASET_NAME	varchar(255)
DETAIL_NAME	varchar(255)

Column Name	Data Type
LAST_TEST_USER_ID	int
LAST_TEST_WORKSTATION	varchar(100)
MARKED_CNT	int
RANGE_OF_DAYS	int
RETENTION_INTERVAL	int
SHORTWINDOW_NAME	varchar(255)
SQL_EXPRESSION_FILTER	varchar(3000)
START_DATE	date
STATUS_DESC	varchar(50)
TEST_TIMEOUT	int
TXNS_CNT	int

Index Name: **IDX_RULE_TESTER_DATASET**

Fields: DATASET_NAME

Index Name: **IDX_RULE_TESTER_DS_UNIQUE_DETAIL**

Fields: DETAIL_NAME

Index Name: **IDX_RULE_TESTER_DS_UNIQUE_SW**

Fields: SHORTWINDOW_NAME

Column Descriptions

The following are the descriptions of the Rule_Tester_Dataset table columns.

BUILD_PROGRESS — This is a string column containing a descriptive message of the status of the build dataset process. It contains the success message, the current execution phase (if the procedure is still running), or the failure reason (if the job failed or was cancelled by a user or due

to a timeout). If the build dataset job is running, the build progress tracks its execution step. If the build dataset job has finished successfully, it contains the success message, plus additional information such as how much time it took to complete and how many records were copied. If the build dataset job ended in error, the error message is tracked into this column.

BUILD_TIMEOUT — An execution time limit in minutes for building the dataset.

CREATION_END_TS — The dataset creation end timestamp.

CREATION_START_TS — The dataset creation start timestamp.

DATASET_CREATE_ROLE_ID — Identifies the security role of the user who created the dataset.

DATASET_CREATE_USER_ID — The ID of the user who created the dataset.

DATASET_CREATE_WORKSTATION — Identifies the workstation of the user who created the dataset.

DATASET_NAME — The name of the dataset.

DETAIL_NAME — The name of the corresponding Detail table.

LAST_TEST_USER_ID — The ID of the user who ran the last test.

LAST_TEST_WORKSTATION — Identifies the workstation of the user who ran the last test.

MARKED_CNT — The number of marked transactions in the dataset.

RANGE_OF_DAYS — A range of days, identifying the time span of the transaction history subset. Mandatory and common to all datasets.

RETENTION_INTERVAL — The ShortWindow retention period. Information read from system configuration.

SHORTWINDOW_NAME — The name of the corresponding SHORTWINDOW table.

SQL_EXPRESSION_FILTER — The criteria that must be met by a transaction in order for it to be included in the dataset, in the form of an SQL expression. Optional and specific to each dataset.

START_DATE — The start date, identifying the first day of the transaction history subset. This date refers to the date when the transaction was processed by Analytic Gateway (for example, DETAIL.DD_APDATE) and not to the date when the transaction occurred.

STATUS_DESC — The state of the datasets (available, under construction, running a test, build cancelled).

TEST_TIMEOUT — The execution time limit in minutes for a rule test executed against the dataset.

TXNS_CNT — The number of transactions in the dataset.

Templates Table

The Templates table is used by the Analysis and Review system. It contains the information for deploying rules and queues.

The columns in the Templates table (TEMPLATES) are listed below with the data type.

Column Name	Data Type
LTEMPLATEID	int
NTYPE	smallint
SDATA	nvarchar(4000)
SDESCRIPTION	varchar(50)

Column Name	Data Type
SNAME	varchar(50)

Index Name: **IDX_TEMPLATES_CLUSTERED**

Fields: LTEMPLATEID

Column Descriptions

The following are the descriptions of the Templates table columns.

LTEMPLATEID — A unique template ID.

NTYPE — The Boolean flag specifying whether the template is for rule or queue.

Valid values are:

0 = Rule

1 = Queue

SDATA — The default information added to the rule procedure during the deploy process.

SDESCRIPTION — No definition available.

SNAME — No definition available.

Template_Types Table

The Templates_Types table is used by the Analysis and Review system. It contains the information defining available template types.

The columns in the Template_Types table (TEMPLATE_TYPES) are listed below with the data type.

Column Name	Data Type
NTYPE	tinyint
SDESCRIPTION	nvarchar(60)

Column Descriptions

The following are the descriptions of the Template_Types table columns.

NTYPE — The Boolean flag specifying whether the template is for rule or queue.

Valid values are:

- 0 = Rules
- 1 = Queues
- 2 = Footer
- 3 = Aggregate
- 4 = Agg declaration
- 5 = Auto action
- 6 = Manual action

SDESCRIPTION — Describes the template type.

Action/External Message Tables

The Action/External Message tables contain information for those actions that require some type of external message processing.

The below Action/External Message tables are described on the following pages:

- ActionsText
- ActionsType
- AddBlockCode_Action_Level
- Auto_Action_Pending

- CONTACT_STRATEGY
- CONTACT_STRATEGY_ACTION_LEVEL
- EMM_Status_Type
- External_Message_Data

ActionsText Table

The ActionsText table is used by the Analysis and Review system. It contains the action types and captions.

The columns in the ActionsText table (ACTIONSTEXT) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
LID	int
LSTATE	int
LSTATUS	int
LTYPE	int
REVIEW_SCREEN_TYPE	int
SIMAGENAME	nvarchar(50)
SNAME	nvarchar(50)
STEXT	int

Index Name: **IDX_ACTIONSTEXT_CLUSTER**

Fields: LID

Index Name: **IDX_ACTIONSTEXT_UNIQUE**

Fields: REVIEW_SCREEN_TYPE
 ACTION_LEVEL_ID
 LTYPE
 LSTATE
 LSTATUS

Column Descriptions

The following are the descriptions of the ActionsText table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

LID — A unique action ID.

LSTATE — The action state.

Valid values are as follows:

- 0 = Off
- 1 = On

Note: Only the actions block, watch, mark, and ice have a 0 state.

LSTATUS — The action status.

Valid values are as follows:

- 0 = Completed
- 1 = Requested

- 2 = Failed
- 3 = Submitted

LTYPE — The action type.

Valid values are as follows:

- 0 = Block
- 1 = LetterSent
- 2 = Call
- 3 = Watch
- 4 = Mark
- 5 = Ice
- 6 = Memo
- 7 = Reminder
- 8 = Forward
- 9 = Close Account
- 10 = Open Action Level ID
- 11 = Alert
- 12 = Email
- 13 = HistoryButton
- 14 = POC Block
- 15 = Export
- 16 = Alert Delete
- 17 = Response Required Clear
- 18 = Response Required Confirm
- 19 = Print
- 20 = Linked Account
- 21 = Action Level Memo
- 22 = Alert Email
- 23 = Copy
- 24 = Next
- 25 = Expand Grid
- 26 = Open Forward
- 27 = Open Reminder
- 28 = Response Required

29 = Cross Reference
30 = Open Review from Compromise
31 = Open Review from Review Screen
32 = Open Compromise Alert
33 = Close Alert
34 = Close Forward
35 = Close Reminder
36 = Close Review from Compromise
37 = Close Review from Review Screen
38 = Close Compromise Alert
39 = Alert Review Timeout
40 = Forward Timeout
41 = Review Timeout
42 = Reminder Timeout
43 = Opened Review from Compromise Block
44 = Closed Review from Compromise Block
45 = Opened Compromise Block
46 = Closed Compromise Block

REVIEW_SCREEN_TYPE — The type of review screen for which the action was logged.

Valid values are:

0 = Action level
1 = Cross action level

SIMAGENAME — The image name for the Actions table on the review form.

SNAME — The variable name.

STEXT — The numeric identifier for the localized name of the description of the action. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

ActionTypes Table

The ActionTypes table is used by the Analysis and Review system. It defines the type of actions available to the Analysts.

The columns in the ActionTypes table (ACTIONSTYPE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
AR_ACTION	int
AUTO_ACTION	int
AUTO_ACTION_PROC	varchar(30)
LTYPE	int
MULTIPLE_ACTION_LEVELS_ENABLED	smallint
NAME	nvarchar(50)
PERMISSION_ID	int
STEXT	int

Index Name: **PK_ACTIONSTYPE**

Fields: LTYPE

Column Descriptions

The following are the descriptions of the ActionTypes table columns.

AR_ACTION — Indicates if the type of action is performed from AR web UI or not.

Valid values are:

0 = Action is not AR related

1 = Action is AR related

AUTO_ACTION — Indicates whether or not auto-actions or auto add-in actions are allowed for an action in the External_Message_Data table.

Valid values are:

- 0 = NO: Not enabled for auto-actions
- 1 = YES: Enabled for auto-actions
- 2 = Auto Add-in: Enabled for auto add-in actions

AUTO_ACTION_PROC — The procedure name of the auto-action rule when the action is matched with a transaction.

LTYPE — The action type.

Valid values are as follows:

- 0 = Block
- 1 = Letter Sent
- 2 = Call
- 3 = Watch
- 4 = Mark
- 5 = Ice
- 6 = Memo
- 7 = Reminder
- 8 = Forward
- 9 = Close Account
- 10 = Open Action Level ID
- 11 = Alert
- 12 = Email
- 13 = History Button
- 14 = POC Block
- 15 = Export
- 16 = Alert Delete
- 17 = Response Required Clear

- 18 = Response Required Confirm
- 19 = Print
- 20 = Linked Account
- 21 = Action Level Memo
- 22 = Alert Email
- 23 = Copy
- 24 = Next
- 25 = Expand Grid
- 26 = Open Forward
- 27 = Open Reminder
- 28 = Response Required
- 29 = Cross Reference
- 30 = Open Review from Compromise
- 31 = Open Review from Review Screen
- 32 = Open Compromise Alert
- 33 = Close Alert
- 34 = Close Forward
- 35 = Close Reminder
- 36 = Close Review from Compromise
- 37 = Close Review from Review Screen
- 38 = Close Compromise Alert
- 39 = Alert Review Timeout
- 40 = Forward Timeout
- 41 = Review Timeout
- 42 = Reminder Timeout
- 43 = Opened Review from Compromise Block
- 44 = Closed Review from Compromise Block
- 45 = Opened Compromise Block
- 46 = Closed Compromise Block

47 = Travel Notification

48 = Open Account

MULTIPLE_ACTION_LEVELS_ENABLED — A subset of the Review screen toolbar buttons for performing actions on multiple action levels other than the one being reviewed (that is, mark, block, watch, ice, remind, and forward). The value in this column is true only for those actions; all others are false.

Valid values are:

0 = False

1 = True

NAME — The action name (for example, block).

PERMISSION_ID — The unique identifier of a permission.

STEXT — The numeric identifier for the localized name of the description of the action. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

AddBlockCode_Action_Level Table

The AddBlockCode_Action_Level table is used by the Analysis and Review system. It identifies the specific block codes that are associated with an action level.

The columns in the AddBlockCode_Action_Level table (ADDBLOCKCODE_ACTION_LEVEL) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
SBLOCKCODE	nvarchar(5)

Index Name: **ADDBLOCKCODE_ACTION_LEVEL_PK**

Fields: SBLOCKCODE
ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the AddBlockCode_Action_Level table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

SBLOCKCODE — A value from the SBLOCKCODE column in the ADDBLOCKCODES table.

Auto_Action_Pending Table

The Auto_Action_Pending table is used by the Analysis and Review system. It contains transaction data when an auto action rule is matched against a transaction. The data in this table is created and removed with the transaction life cycle.

The columns in the Auto_Action_Pending table (AUTO_ACTION_PENDING) are listed below with the data type.

Column Name	Data Type
ACTION_ID	int
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)

Column Name	Data Type
ALERT_DATE	datetime
DD_PARTITION_DATE	date
ND_KEY_HASH	smallint
RECORD_SOURCE_ID	smallint
RULE_ID	int
SD_TIEBREAKER	varchar(75)
SM_BIN	varchar(12)
SM_FIID	varchar(50)

Index Name: IDX_AUTO_ACTIONS_PENDING

Fields: ACTION_LEVEL_ID
 ACTION_LEVEL_KEY
 ACTION_ID
 RULE_ID
 DD_PARTITION_DATE
 ND_KEY_HASH
 RECORD_SOURCE_ID
 SD_TIEBREAKER

Column Descriptions

The following are the descriptions of the Auto_Action_Pending table columns.

ACTION_ID — The action identifier.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The unique key value within an Action Level.

ALERT_DATE — The date and time of an alert.

DD_PARTITION_DATE — The value that is associated with the transaction in the Detail or FraudDetail table.

ND_KEY_HASH — A value that is associated with the transaction in the Detail or FraudDetail table.

RECORD_SOURCE_ID — The identifier of the record source.

RULE_ID — Contains the unique identifier for a rule.

SD_TIEBREAKER — A transaction field that makes a transaction unique when more than one transaction has the same date and time.

SM_BIN — The bank identification number (BIN) prefix.

SM_FIID — The financial institution identifier (FIID).

CONTACT_STRATEGY Table

The Contact_Strategy table is used by the notification service and is accessed by UI and OEI. When a rule is defined with a notification auto action, a user can optionally associate a contact strategy with the notification action selected for the rule. It contains the contact strategy information which should be used to contact the cardholder.

The columns in the CONTACT_STRATEGY table (CONTACT_STRATEGY) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
CONTACT_STRATEGY_L10NTEXT	int
CONTACT_STRATEGY_ID	int
CONTACT_STRATEGY_NAME	nvarchar(50)

Column Descriptions

The following are the descriptions of the CONTACT_STRATEGY table columns.

CONTACT_STRATEGY_L10NTEXT — A numeric value corresponding to the localized text value of the contact strategy for a given locale. It references the L10N_PROPERTY_ID column of table L10N_PROPERTY.

CONTACT_STRATEGY_ID — An automatically generated numeric value uniquely identifying a contact strategy record.

CONTACT_STRATEGY_NAME — An internal name given to this contact strategy.

CONTACT_STRATEGY_ACTION_LEVEL Table

The Contact_Strategy_Action_Level table is used by the notification service. This table links a contact strategy record to an action level id.

The columns in the CONTACT_STRATEGY_ACTION_LEVEL table (CONTACT_STRATEGY_ACTION_LEVEL) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
CONTACT_STRATEGY_ID	int
PRIORITY	smallint

Column Descriptions

The following are the descriptions of the CONTACT_STRATEGY_ACTION_LEVEL table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

CONTACT_STRATEGY_ID — A numeric value uniquely identifying a contact strategy record. It references the CONTACT_STRATEGY table.

PRIORITY — A numeric value specifying the priority of a contact strategy relative to all the contact strategies assigned to the same action level id. A smaller number means a higher priority.

EMM_Status_Type Table

The EMM_Status_Type table is used by the Analysis and Review system and contains the External Message Manager status types.

The columns in the EMM_Status_Type table (EMM_STATUS_TYPE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DECORATOR	varchar(60)
LID	int
SDESCRIPTION	nvarchar(255)
SSTATUS	nvarchar(25)

Index Name: **IDX_TIESTATUSTYPES_STATUS**

Fields: LID

Column Descriptions

The following are the descriptions of the EMM_Status_Type table columns.

DECORATOR — The name of the decorator icon if one is used. It is used to indicate the status.

LID — The unique external message processing ID.

SDESCRIPTION — A detailed description of the external message process.

The descriptions are as follows:

- 0 = Request was sent to the host and a completed response was received
- 1 = Requested by user, not sent to the host yet
- 2 = Request was sent to the host and a failed response was received
- 3 = Request was sent to the host by the External Message Manager component, waiting for response

SSTATUS — A short status description.

Valid values are as follows:

- 0 = Completed
- 1 = Requested
- 2 = Failed
- 3 = Submitted

External_Message_Data Table

The External_Message_Data table is used by the Analysis and Review system. It contains an activity list of external message processing actions. The records in the External_Message_Data table hold actions that contain account, transaction, and user information.

The columns in the External_Message_Data table (EXTERNAL_MESSAGE_DATA) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
ACTION_TYPE_ID	int
DD_DATE	datetime
DD_PARTITION_DATE	date

Column Name	Data Type
DTCOMPLETED	datetime
DTENDDATE	datetime
DTMOSTRECENTTXN	datetime
DTREQUESTED	datetime
DTSTARTDATE	datetime
DTSUBMITTED	datetime
LERRID	int
LPORTFOLIOID	int
LREVID	int
LSTATE	int
LSTATUS	int
MESSAGE_ID	int
ND_KEY_HASH	smallint
ND_RECORD_SOURCE_ID	smallint
PROCSID	varchar(16)
RESPONSECODE	nvarchar(30)
RULE_ID	int

Column Name	Data Type
SD_MARK_SOURCE	nvarchar(30)
SD_MBR_NUM	char(4)
SD_SEQ_NUM	varchar(35)
SD_TIEBREAKER	varchar(75)
SEMSG	nvarchar(500)
SHOST_DATA	nvarchar(1024)
SM_BIN	varchar(12)
SM_FIID	varchar(50)
SNOTE	nvarchar(255)
SNOTE2	nvarchar(255)
SNOTIFYTYPE	nvarchar(50)
SREASON_CODE	nvarchar(5)
TDDATEKEY	varchar(21)
TRACKING_ID	bigint

Index Name: EXTERNAL_MESSAGE_DATA_IX1

Fields: LPORTFOLIOID
 ACTION_TYPE_ID

Index Name: EXTERNAL_MESSAGE_DATA_IX2

Fields: DTCOMPLETED

Index Name: EXTERNAL_MESSAGE_DATA_IX3

Fields: ACTION_LEVEL_KEY
 ACTION_LEVEL_ID
 ACTION_TYPE_ID

Index Name: IX_TXN_EXTERNAL_MESSAGE_DATA

Fields: DD_PARTITION_DATE
 ND_KEY_HASH
 ND_RECORD_SOURCE_ID
 SD_TIEBREAKER
 ACTION_TYPE_ID

Index Name: EXTERNAL_MESSAGE_DATA_PK

Fields: MESSAGE_ID

Column Descriptions

The following are the descriptions of the External_Message_Data table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the master tables. It may contain a SM_PAN, SM_UAN, SM_EMPLOYEE_ID, SM_RETL_ID, or SM_TERM_ID. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and is used to determine what type of value is stored in ACTION_LEVEL_KEY.

ACTION_TYPE_ID — The action type. It is linked to the LTYPE column in the ActionsText table.

Valid action types are as follows:

- 0 = Block
- 1 = Letter Sent
- 2 = Call
- 3 = Watch
- 4 = Mark
- 5 = Ice
- 6 = Memo
- 7 = Reminder
- 8 = Forward
- 9 = Close Account
- 10 = Open Action Level ID
- 11 = Alert
- 12 = Email
- 13 = History Button
- 14 = POC Block
- 15 = Export
- 16 = Alert Delete
- 17 = Response Required Clear
- 18 = Response Required Confirm
- 19 = Print
- 20 = Linked Account
- 21 = Action Level Memo
- 22 = Alert Email
- 23 = Copy
- 24 = Next
- 25 = Expand Grid
- 26 = Open Forward
- 27 = Open Reminder
- 28 = Response Required
- 29 = Cross Reference
- 30 = Open Review from Compromise
- 31 = Open Review from Review Screen
- 32 = Open Compromise Alert
- 33 = Close Alert
- 34 = Close Forward

- 35 = Close Reminder
- 36 = Close Review from Compromise
- 37 = Close Review from Review Screen
- 38 = Close Compromise Alert
- 39 = Alert Review Timeout
- 40 = Forward Timeout
- 41 = Review Timeout
- 42 = Reminder Timeout
- 43 = Opened Review from Compromise Block
- 44 = Closed Review from Compromise Block
- 45 = Opened Compromise Block
- 46 = Closed Compromise Block

DD_DATE — The transaction date and time. It is linked to DTDDATE column in the Detail table.

DD_PARTITION_DATE — The transaction date. It is linked to the DD_PARTITION_DATE column in Detail table.

DTCOMPLETED — The date the action was completed by the host.

DTENDDATE — The date the automatic expiration actions will end (that is, Ice).

DTMOSTRECENTTXN — The most recent transaction time the action was requested (corresponds to the Detail table).

DTREQUESTED — The date of the action request.

DTSTARTDATE — The date when automatic actions will start (that is, Ice, Suspemd).

DTSUBMITTED — The date the action was submitted to the host.

LERRID — The error ID, specified by the host.

LPORTFOLIOID — The portfolio ID.

LREVID — The analyst ID. It is linked to the LID column in the PRM_Users table.

LSTATE — The action state. It is linked to the LSTATE column in the ActionsText table.

Valid values are as follows:

- 0 = Off, the PRM UI is requesting that the action be turned off.
- 1 = On, the PRM UI is requesting that the action be turned on.

LSTATUS — The action status. It is linked to the LSTATUS column in the ActionsText table.

Valid values are as follows:

- 0 = Completed
- 1 = Requested
- 2 = Failed
- 3 = Submitted

MESSAGE_ID — A unique external message data identifier.

ND_KEY_HASH — A value that is associated with the transaction in the Detail or FraudDetail table.

ND_RECORD_SOURCE_ID — A unique record source identifier. It is linked to the ND_RECORD_SOURCE_ID column in Detail table.

PROCSID — Process id of the OEI instance processing the transaction

RESPONSECODE — Response Code

RULE_ID — Contains the rule ID.

SD_MARK_SOURCE — Identifies the system that initiated the mark request for the transaction.

SD_MBR_NUM — A value which uniquely identifies individual holders of the same card number. It is linked to the SD_MBR_NUM column in Detail table.

SD_SEQ_NUM — Contains a unique sequence number associated with this transaction. It is linked to the SD_SEQ_NUM column in the Detail table.

SD_TIEBREAKER — The unique identifier for a transaction within a record source. It links to the ND_RECORD_SOURCE_ID.

SEMSG — The error message specified by the host.

SHOST_DATA — The message that is passed to a host.

SM_BIN — The bank identification number (BIN) prefix.

SM_FIID — The financial institution identifier (FIID).

SNOTE — The memo text associated with action, part one.

SNOTE2 — The memo text associated with action, part two.

SNOTIFYTYPE — Contains the notify type.

SREASON_CODE — The reason code for an action.

TDDATEKEY — The authorization date. It is linked to the SD_DATEKEY column in the Detail table.

TRACKING_ID — Tracking id of the OEI instance processing the transaction

Security System Tables

The Security System tables contain user and security information for the Analysis and Review system.

The following Security System tables are described on the following pages:

- Action_Level_User
- FilterLayout
- Locks
- PasswordHistory
- Portfolios
- PRM_Filters
- PRM_Keys
- PRM_Tenants
- PRM_Tenants_Config
- PRM_Users
- RT_Filterlayout
- TeamPortfolioLinks
- Teams
- Trans_Category_Filter_Field
- UserConfig
- UserLockout

Action_Level_User Table

The Action_Level_User table is used to store user dual control override information for each action level.

The columns in the Action_Level_User table (ACTION_LEVEL_USER) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int

Column Name	Data Type
DTLASTATTEMPT	datetime
NFAILED_OVERRIDE_ATTEMPTS	smallint
USER_ID	int

Index Name: **AK_ACTION_LEVEL_USER__ACTION_L**

Fields: ACTION_LEVEL_ID
 USER_ID

Column Descriptions

The following are the descriptions of the Action_Level_User table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

DTLASTATTEMPT — Contains the date of the last dual control override attempt.

NFAILED_OVERRIDE_ATTEMPTS — Contains the number of failed dual control override attempts since the last successful override.

USER_ID — The ACTION_TYPE_ID column contains data from the ACTIONSTYPE.LTYPE column.

FilterLayout Table

The FilterLayout table is used by the Analysis and Review system. It defines the short reference of portfolio/filter setup information that is required by the User Interface.

The columns in the FilterLayout table (FILTERLAYOUT) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
LENDVALUE	varchar(255)
LID	int
LPORTFOLIOID	int
LSTARTVALUE	varchar(255)

Index Name: **IDX_FILTERLAYOUT_CLUSTER**

Fields: LID

Column Descriptions

The following are the descriptions of the FilterLayout table columns.

LENDVALUE — The ending value of the filter.

LID — The user's unique ID.

LPORTFOLIOID — The LID of the portfolio.

LSTARTVALUE — The starting value of the filter.

Locks Table

The Locks table is used by the Analysis and Review system. It contains user information. When a user logs on to the program, the system adds a record to the Locks table that is linked to the user's ID. When the user logs off, the system removes the record. A user cannot log on if a record linked

to his ID appears in this table.

This table is also used for locking accounts, editing locks, teams, users, or rules after they are implemented.

The columns in the Locks table (LOCKS) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
DTLOCKTIME	datetime
LINDEX	int
LOBJECT	int
LPORTFOLIOID	int
LUSERID	int
NTYPE	smallint
SINDEX	varchar(100)
SNOTE	varchar(255)
SSESSIONID	varchar(255)

Index Name: IDX_LOCKS_DATE

Fields: DTLOCKTIME

Index Name: IDX_LOCKS_KEY

Fields: LOBJECT

 LINDEX

 SINDEX

 ACTION_LEVEL_ID

LPORTFOLIOID

Index Name: IDX_LOCKS_USERID

Fields: SINDEX

ACTION_LEVEL_ID

LUSERID

Index Name: LOCKS_SESSIONID

Fields: SSESSIONID

Index Name: IDX_LOCKS_GNA

Fields: SINDEX

ACTION_LEVEL_ID

LPORTFOLIOID

Column Descriptions

The following are the descriptions of the Locks table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

DTLOCKTIME — The date and time the record was created.

LINDEX — The index.

LOBJECT — The type of object.

LPORTFOLIOID — The identifier of the portfolio.

LUSERID — A value linked to a user listed in the PRM_Users table.

NTYPE — The type of lock.

SINDEX — The account number for account locks. It also contains any lock required for character keys. It is linked to the SM_KEY column in the Master table.

SNOTE — A text description of the lock.

SSESSIONID — The user session ID.

PasswordHistory Table

The PasswordHistory table is used by the Analysis and Review system. It stores password information for the users that are specified in the PRM_Users table.

The columns in the PasswordHistory table (PASSWORDHISTORY) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DTPWDCREATED	datetime
LUSERID	int
SPASSWORD	varchar(255)

Index Name: **PASSWORDHISTORY_CLUSTER**

Fields: LUSERID

Column Descriptions

The following are the descriptions of the PasswordHistory table columns.

DTPWDCREATED — The date the password was originally created.

LUSERID — The user ID.

SPASSWORD — The associated password.

Portfolios Table

The Portfolios table is used by the Analytic Gateway process and contains portfolio information. The system assigns an authorization to a particular portfolio on the basis of the authorization's FIID or BIN code.

This table is also used by the Client to group filters to teams; it controls users' access to accounts.

The columns in the Portfolios table (PORTFOLIOS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
LID	int
LQUEDEPLOYED	int
NSTATUS	int
SDESCRIPTION	int
SNAME	int

Index Name: **IDX_PORT_NAM_ACTN_LVL**

Fields: ACTION_LEVEL_ID

 LID

Index Name: **IDX_PORTFOLIOS_CLUSTER**

Fields: LID

Index Name: **IDX_PORTFOLIOS_NAME**

Fields: SNAME

Column Descriptions

The following are the descriptions of the Portfolios table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

LID — A unique portfolio ID.

LQUEDEPLOYED — A flag that indicates that queues have been deployed for this portfolio.

NSTATUS — The delete flag.

SDESCRIPTION — A description of localized columns.

SNAME — The name of localized columns.

PRM_Filters Table

The PRM_Filters table is used by both the Client and the Analytic Gateway process. It contains filter information. A root administrator determines which authorizations go into a particular portfolio by assigning a filter or a group of filters to the portfolio. FIID codes define each filter. Each time a root administrator adds a filter to a portfolio, the system adds a record to the PRM_Filters table.

The columns in the PRM_Filters table (PRM_FILTERS) are listed below with the data type.

Column Name	Data Type
LID	int
LPORTFOLIOID	int
NSTATUS	int
SDESCRIPTION	int
SNAME	int
SVALUE	varchar(255)

Index Name: IDX_PRM_FILTERS_CLUSTERED

Fields: LID

Index Name: IDX_PRM_FILTERS_NAME

Fields: SNAME

Index Name: IDX_PRM_FILTERS_PORT

Fields: LPORTFOLIOID

LID

Column Descriptions

The following are the descriptions of the PRM_Filters table columns.

LID — The unique filter ID.

LPORTFOLIOID — A portfolio ID. It is linked to the LID column in the Portfolios table.

NSTATUS — The delete flag.

SDESCRIPTION — The description of the localized columns.

SNAME — The name of the localized columns.

SVALUE — A list of filter values.

PRM_Keys Table

The PRM_KEYS table contains the encryption keys for each tenant, used to encrypt/decrypt the DB passwords from the PRM_TENANTS table.

The columns in the PRM_Keys table (PRM_KEYS) are listed below with the data type.

Column Name	Data Type
APSF_ENTITL_KEY	nvarchar(250)
NRT_DBA_KEY	nvarchar(250)
NRT_KEY	nvarchar(250)
REPORTS_KEY	nvarchar(250)
RT_DBA_KEY	nvarchar(250)
RT_KEY	nvarchar(250)
TENANT_ID	int

Index Name: **PK_PRM_KEYS**

Fields: TENANT_ID

Column Descriptions

The following are the descriptions of the PRM_Keys table columns.

APSF_ENTITL_KEY — The encryption key for each tenant, used to encrypt/decrypt the APSF Entitlements DB password.

NRT_DBA_KEY — The encryption key for each tenant, used to encrypt/decrypt the NRT DBA DB password.

NRT_KEY — The encryption key for each tenant, used to encrypt/decrypt the NRT DB password.

REPORTS_KEY — The encryption key for each tenant, used to encrypt/decrypt the Reports DB password.

RT_DBA_KEY — The encryption key for each tenant, used to encrypt/decrypt the RT DBA DB password.

RT_KEY — The encryption key for each tenant, used to encrypt/decrypt the RT DB password.

TENANT_ID — The unique tenant ID. 0 corresponds to the ROOT.

PRM_Tenants Table

The PRM_TENANTS table contains DB related connection information (NRT, RT, Reports) for each tenant.

The columns in the PRM_Tenants table (PRM_TENANTS) are listed below with the data type.

Column Name	Data Type
AR_ENABLED	int
ID	int
NAME	int
NRT_DATABASE_NAME	varchar(100)
NRT_DBA_PASSWORD	varchar(256)
NRT_DBA_USER_NAME	varchar(100)

Column Name	Data Type
NRT_DB_MAX_CONNECTION	int
NRT_DB_MIN_CONNECTION	int
NRT_PASSWORD	varchar(256)
NRT_SERVER_NAME	varchar(100)
NRT_URL	varchar(1000)
NRT_USER_NAME	varchar(100)
PRM_ORGANIZATION	nvarchar(36)
REPORTS_DATABASE_NAME	varchar(100)
REPORTS_DB_MAX_CONNECTION	int
REPORTS_DB_MIN_CONNECTION	int
REPORTS_PASSWORD	varchar(256)
REPORTS_SERVER_NAME	varchar(100)
REPORTS_URL	varchar(1000)
REPORTS_USER_NAME	varchar(100)
RT_DATABASE_NAME	varchar(100)
RT_DBA_PASSWORD	varchar(256)
RT_DBA_USER_NAME	varchar(100)

Column Name	Data Type
RT_DB_MAX_CONNECTION	int
RT_DB_MIN_CONNECTION	int
RT_PASSWORD	varchar(256)
RT_SERVER_NAME	varchar(100)
RT_URL	varchar(1000)
RT_USER_NAME	varchar(100)
SOFT_DELETE	int

Index Name: **PK_PRM_TENANTS**

Fields: ID

Column Descriptions

The following are the descriptions of the PRM_Tenants table columns.

AR_ENABLED — Indicates if the tenant is AR enabled or not.

Valid values are:

0 = Tenant is not AR enabled

1 = Tenant is AR enabled

ID — The unique tenant ID. 0 corresponds to the ROOT.

NAME — The name of the localized columns for tenant.

NRT_DATABASE_NAME — The PRM NRT schema name for tenant.

NRT_DBA_PASSWORD — The PRM DB NRT DBA encrypted password for tenant.

NRT_DBA_USER_NAME — The PRM DB NRT DBA user name for tenant.

NRT_DB_MAX_CONNECTION — The PRM DB NRT maximum number of connections for tenant.

NRT_DB_MIN_CONNECTION — The PRM DB NRT minimum number of connections for tenant.

NRT_PASSWORD — The PRM DB NRT encrypted password for tenant.

NRT_SERVER_NAME — The PRM NRT server name for tenant.

NRT_URL — The PRM NRT URL connection for tenant.

NRT_USER_NAME — The PRM DB NRT user name for tenant.

PRM_ORGANIZATION — The PRM Organization name for tenant.

REPORTS_DATABASE_NAME — The PRM Reports schema name for tenant.

REPORTS_DB_MAX_CONNECTION — The PRM DB Reports maximum number of connections for tenant.

REPORTS_DB_MIN_CONNECTION — The PRM DB Reports minimum number of connections for tenant.

REPORTS_PASSWORD — The PRM DB Reports encrypted password for tenant.

REPORTS_SERVER_NAME — The PRM Reports server name for tenant.

REPORTS_URL — The PRM Reports URL connection for tenant.

REPORTS_USER_NAME — The PRM DB Reports user name for tenant.

RT_DATABASE_NAME — The PRM RT schema name for tenant.

RT_DBA_PASSWORD — The PRM DB RT DBA encrypted password for tenant.

RT_DBA_USER_NAME — The PRM DB RT DBA user name for tenant.

RT_DB_MAX_CONNECTION — The PRM DB RT maximum number of connections for tenant.

RT_DB_MIN_CONNECTION — The PRM DB RT minimum number of connections for tenant.

RT_PASSWORD — The PRM DB RT encrypted password for tenant.

RT_SERVER_NAME — The PRM RT server name for tenant.

RT_URL — The PRM RT URL connection for tenant.

RT_USER_NAME — The PRM DB RT user name for tenant.

SOFT_DELETE — Indicates the current delete status of the row.

PRM_Tenants_Config Table

The PRM_TENANTS_CONFIG table contains DB configuration information used at the installation of each tenant.

The columns in the PRM_Tenants_Config table (PRM_TENANTS_CONFIG) are listed below with the data type.

Column Name	Data Type
PARAM	varchar(100)
TENANT_ID	int

Column Name	Data Type
VAL	nvarchar(Max)

Index Name: **PK_PRM_TENANTS_CONFIG**

Fields: TENANT_ID
 PARAM

Column Descriptions

The following are the descriptions of the PRM_Tenants_Config table columns.

PARAM — Parameters used to configure the DB PRM install for each tenant.

TENANT_ID — The unique tenant ID. 0 corresponds to the ROOT.

VAL — Parameter values used to configure the DB PRM install for each tenant.

PRM_Users Table

The PRM_Users table is used by the Analysis and Review system. It contains a list of users in the system. Each time a root administrator or a team administrator adds a user, the system adds a record to the PRM_Users table. A record gets updated whenever user information changes or when a user attempts to log on to the system.

The columns in the PRM_Users table (PRM_USERS) are listed below with the data type.

Column Name	Data Type
BLOBACCTHIST	image
BLOBPASSWORD	image
BLOBPROFILE	image
BLOBPWDS	image

Column Name	Data Type
BMULTI_TEAM_RPT_ACS	bit
BMULTI_TEAM_USER_ACS	bit
BPWDRESET	smallint
DTLASTFAILLOGIN	datetime
DTLASTLOGIN	datetime
DTLASTPWDCHANGE	datetime
DTPREVIOUSLOGIN	datetime
LID	int
LOCALE_ID	varchar(10)
LTEAMID	int
NFAILEDATTEMPTS	smallint
NSECURITYLEVEL	smallint
NSTATUS	int
SEMAIL	nvarchar(255)
SFULLNAME	nvarchar(255)
SNAME	varchar(255)
SNOTE	nvarchar(255)

Column Name	Data Type
SPASSWORD	varchar(255)
SPHONE	varchar(255)

Index Name: IDX_PRM_USERS_CLUSTER

Fields: LID

Index Name: IDX_PRM_USERS_NAME

Fields: SNAME

Index Name: IDX_PRM_USERS_TEAMNAME

Fields: LTEAMID

SNAME

Index Name: IX_LOCALE_ID

Fields: LOCALE_ID

Column Descriptions

The following are the descriptions of the PRM_Users table columns.

BLOBACCTHIST — A list of recently opened accounts.

BLOBPASSWORD — The user password.

BLOBPROFILE — The user configuration settings.

BLOBPWDS — A list of old user passwords.

BMULTI_TEAM_RPT_ACS — Indicates whether this user may run reports containing information from multiple teams. When running a report, the available teams are retrieved from the Multi_Team_Access table.

BMULTI_TEAM_USER_ACS — Indicates whether this user has right to manipulate users in other teams.

BPWDRESET — A flag indicating the password has been reset.

DTLASTFAILLOGIN — Date and Time of the logged in user's last unsuccessful login attempt

DTLASTLOGIN — The date of the last user login.

DTLASTPWDCHANGE — The date the user password last changed.

DTPREVIOUSLOGIN — Date and Time of the logged in user's previous successful login

LID — A unique user ID.

LOCALE_ID — A unique ID associated with the user.

LTEAMID — The ID of the team to which the user belongs. It links a user to a team listed in the Teams table. If the user is a manager, this value links the user to a manager group listed in the ManagerGroup table.

NFAILEDATTEMPTS — The number of failed login attempts since the last login.

NSECURITYLEVEL — The security level configuration.

NSTATUS — The delete flag.

SEMAIL — The user's email address for the email action.

SFULLNAME — The user's full name.

SNAME — The user logon name.

SNOTE — A note field.

SPASSWORD — The user's password.

SPHONE — The user's telephone number.

RT_Filterlayout Table

The RT_FilterLayout table is used to define the short reference of portfolio/filter setup information that is required by the User Interface.

The columns in the RT_Filterlayout table (RT_FILTERLAYOUT) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
ACTION_LEVEL_LICENSE_NAME	char(50)
LENDVALUE	varchar(255)
LFILTERID	int
LPORTFOLIOID	int
LSTARTVALUE	varchar(255)
RECORD_SOURCE_ID	smallint
RT_ACTION_LEVEL_ORDER	smallint

Index Name: **IDX_RT_FILTERLAYOUT_CLUSTER**

Fields: ACTION_LEVEL_ID
 RECORD_SOURCE_ID

Column Descriptions

The following are the descriptions of the RT_Filterlayout table columns.

ACTION_LEVEL_ID — A numeric value used to identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_LICENSE_NAME — The name of the licensed action level.

LENDVALUE — The ending value of the filter.

LFILTERID — The user's unique ID.

LPORTFOLIOID — Identifies the ID of the portfolio.

LSTARTVALUE — The start value of the filter.

RECORD_SOURCE_ID — The identifier of the record source.

RT_ACTION_LEVEL_ORDER — The order in which the action levels are processed.

TeamPortfolioLinks Table

The TeamPortfolioLinks table is used by the Analysis and Review system. It contains the assignment of portfolios to the appropriate teams. A team processes the alerts and cards for the portfolio or portfolios that have been assigned to that team. Each time a root administrator assigns

a portfolio to a team, the system adds a record to the TeamPortfolioLinks table.

The columns in the TeamPortfolioLinks table (TEAMPORFOLIOLINKS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
LALERTSHIFTID	int
LPORTFOLIOID	int
LTEAMID	int
NWEIGHT	tinyint

Index Name: **IDX_TEAMPORTFOLIOLINKS_CLUSTER**

Fields: LTEAMID

 LPORTFOLIOID

Index Name: **IDX_TEAMPORTFOLIOLINKS_PORTID**

Fields: LPORTFOLIOID

Column Descriptions

The following are the descriptions of the TeamPortfolioLinks table columns.

LALERTSHIFTID — Reserved for future use.

LPORTFOLIOID — A value linked to the LID in the Portfolios table.

LTEAMID — The ID of the team to which the user belongs.

NWEIGHT — The weight of the portfolio-team association.

Teams Table

The Teams table is used by the Analysis and Review system. It contains team information. Root administrators create teams of analysts and supervisors to process alerts. Each time a root administrator adds a team, the system adds a record to this table.

The columns in the Teams table (TEAMS) are listed below with the data type.

Column Name	Data Type
BALLOWCONFIGURE	smallint
BLOGGROUPPROFILE	image
BROTATEALERTS	smallint
EMAILBCC	nvarchar(200)
EMAILCC	nvarchar(200)
EMAILFROM	nvarchar(100)
LID	int
LTYPE	int
NSTATUS	int
SDESCRIPTION	nvarchar(255)
SNAME	nvarchar(255)

Index Name: **IDX_TEAMS_CLUSTER**

Fields: LID

Index Name: **PK_TEAMS**

Fields: LID

Column Descriptions

The following are the descriptions of the Teams table columns.

BALLOWCONFIGURE — A value set through the team creation user interface screen Retain Grid Configuration.

Valid values are as follows:

- 0 = Users with "Retain Grid Configuration for Team" permission only
- 1 = Allow for all Team Members
- 2 = Disable for all Team Members

If the "Users with 'Retain Grid Configuration for Team' permission only" radio button is selected, users that are assigned to a role that has the "Retain Grid Configuration for Team" permission assigned to it will be allowed to save grid configurations for the team; all other users will not. If a user without the permission moves columns in the grid on a screen with the Change Column Order button, the columns will be reset to the default the next time the screen is accessed. The "bAllowConfigure" flag in the Teams table will be set to 0.

If the "Allow for all Team Members" radio button is selected, all users assigned to the team will be allowed to save their grid configuration. If they move columns in the grid on a screen with the Change Column Order button, those configurations will be retained every time the screen is reopened if the user elects to save the configuration. The "bAllowConfigure" flag in the Teams table will be set to 1.

If the "Disable for all Team Members" radio button is selected, no users assigned to the team will be allowed to save their grid configuration. If they move columns in the grid on any screen, the columns will be reset to the default the next time the screen is accessed. The "bAllowConfigure" flag in the Teams table will be set to 2.

BLOGROUPPROFILE — The configuration settings for the group.

BROTATEALERTS — A Boolean value, used in *get next alert* processing, to determine which queue the alert will come from.

Note: If a root administrator activates queue override processing for a team, this field will contain a value of 1.

EMAILBCC — The default email BCC address when the email option is used.

EMAILCC — The default email CC address when the email option is used.

EMAILFROM — The default email *from* address when the email option is used.

LID — A unique team ID.

LTYPE — The number for the team type.

Valid values are:

0 = System Admin

1 = Regular

2 = AutoAction

NSTATUS — The current status.

SDESCRIPTION — A description for the team.

SNAME — The name of the team.

Trans_Category_Filter_Field Table

The Trans_Category_Filter_Field table is a translation for data in a specific column for a specific filter and specific translation category. This table stores the associated values between translation category, data format, and filters.

The columns in the Trans_Category_Filter_Field table (TRANS_CATEGORY_FILTER_FIELD) are listed below with the data type.

Column Name	Data Type
COLUMN_SOURCE	smallint
FIELD_ID	int
FILTER_ID	int

<i>Column Name</i>	<i>Data Type</i>
TRANS_CATEGORY_ID	int

Index Name: TRANS_CATEGORY_FILTER_FIELD_PK

Fields: FIELD_ID
FILTER_ID

Column Descriptions

The following are the descriptions of the Trans_Category_Filter_Field table columns.

COLUMN_SOURCE — Indicates whether the field for which the translation is defined is coming from a Master table or a Detail table.

Valid values are:

- 0 = Indicates that the field for which the translation is defined is coming from a Master table.
- 1 = Indicates that the field for which the translation is defined is coming from a Detail table.

FIELD_ID — The data from the PRM_FIELD.FIELD_ID column.

FILTER_ID — The data from the FILTERLAYOUT.LID column.

TRANS_CATEGORY_ID — The data from TRANS_CATEGORY.TRANS_CATEGORY_ID column. This allows a translation category, as defined in the Trans_Category table, to be associated with one or more of the defined primary keys.

UserConfig Table

The UserConfig table is used by the Analysis and Review system. It is used to store user configuration data for the Tip of the Day functionality.

The columns in the UserConfig table (USERCONFIG) are listed below with the data type.

Column Name	Data Type
LUSERID	int
SCFGVALUE	varchar(128)
SCFGVARIABLE	varchar(32)

Index Name: **IDX_USERCONFIG_CLUSTER**

Fields: LUSERID
 SCFGVARIABLE

Column Descriptions

The following are the descriptions of the UserConfig table columns.

LUSERID — The User ID.

SCFGVALUE — Indicates whether the 'Tip of the Day' is shown at startup.

SCFGVARIABLE — The corresponding SCFGVARIABLE from the SystemConfig table.

UserLockout Table

The UserLockout table is used by the Analysis and Review system. It contains the currentuser lockout information.

The columns in the UserLockout table (USERLOCKOUT) are listed below with the data type.

Column Name	Data Type
DTF FAILEDLOGIN	datetime
LID	int

Index Name: **IDX_USERLOCKOUT_CLUSTER**

Fields: LID

Column Descriptions

The following are the descriptions of the UserLockout table columns.

DTFAILEDLOGIN — The date and time in SQL format of the lockout.

LID — The unique ID for the field entry.

Dynamic Screen Tables

The Dynamic Screen tables contain definitions for the various screen displays.

The Dynamic Screen tables below are described on the following pages:

- ActionsType_Review_Screen
- Cross_Action_Level

ActionsType_Review_Screen Table

The ActionsType_Review_Screen table stores the list of action types to be shown in each cross action level review screen.

The columns in the ActionsType_Review_Screen table (ACTIONSTYPE_REVIEW_SCREEN) are listed below with the data type.

Column Name	Data Type
ACTION_TYPE_ID	int
REVIEW_SCREEN_ID	int
TITLEBARSTRING	int

Index Name: IX_1_ACTIONSTYPE_REVIEW_SCREEN

Fields: ACTION_TYPE_ID

Index Name: IX_2_ACTIONSTYPE_REVIEW_SCREEN

Fields: REVIEW_SCREEN_ID

Column Descriptions

The following are the descriptions of the ActionType_Review_Screen table columns.

ACTION_TYPE_ID — The identifier of the action type, as it appears in the ActionType table.

REVIEW_SCREEN_ID — The identifier of the cross action level, as it appears in the Cross_Action_Level table.

TITLEBARSTRING — The localized string (referred to by the corresponding l10n_properties id) to be displayed for the corresponding action in the UI.

Cross_Action_Level Table

The Cross_Action_Level table stores the defined cross action levels.

The columns in the Cross_Action_Level table (CROSS_ACTION_LEVEL) are listed below with the data type.

Column Name	Data Type
CROSS_ACTION_LEVEL_ID	int
DETAIL_KEY_COLUMN_NAME	varchar(30)
DETAIL_TABLE_NAME	varchar(30)
DISPLAY_NAME	int
LICENSE_NAME	nvarchar(50)

Column Name	Data Type
SHORTWINDOW_TABLE_NAME	varchar(30)

Index Name: **PK_CROSS_ACTION_LEVEL**

Fields: CROSS_ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the Cross_Action_Level table columns.

CROSS_ACTION_LEVEL_ID — The identifier of the cross action level type.

DETAIL_KEY_COLUMN_NAME — The name of the Detail table column that is key for this Cross Action Level.

DETAIL_TABLE_NAME — The name of the Detail table into which this Cross Action Level has data.

DISPLAY_NAME — The UI display name of the cross action level.

LICENSE_NAME — The official code name of the cross action level.

SHORTWINDOW_TABLE_NAME — The name of the ShortWindow table into which this Cross Action Level has data.

System Tables

The System tables contain system wide parameters used for various system processing and configuration.

The System tables below are described on the following pages:

- Accnt_Routing
- ACMAAddInUsers
- ActionType_Action_Level

- ActionType_Action_Level_Emm
- ActionType_Feature
- ActionType_Permission
- Action_Level_Alert_Order_List
- Action_Level_Memo
- Action_Level_Profile_Table
- Action_Level_Record_Source
- AddBlockCodes
- AddResponseCodes
- AddResponseCodes_Action_Level
- AG_Composite_Field
- AG_Comp_Fields_Selector
- AG_Data_Sanitizer
- AG_Field
- AG_Field_Composition
- AG_Field_Selection
- AG_Field_Transformation
- AG_KPI_DEF
- AG_KPI_LOG
- AG_KPI_SLA_Report_Result
- AG_KPI_SLA_Report_Statistics
- AG_NACHA_Batch_Statistics
- AG_NACHA_File_Statistics
- AG_Services
- AG_Transformation_Param
- Application_Data_Type
- Assgnd_ActionType_ActionLevel
- AuthConfig
- AutoText
- Autotext_Action_Level
- Auto_Add_In_Config

- Auto_Add_In_Rule_Config
- Batch_Statistics
- Check_Index_Columns
- Cleanup_Tables
- Config
- DASHB_AP_SYSAUD
- DD_Routing
- Detail_MarkSelection
- DE_Filter_Fields
- External_Connection_Map
- External_Procedure
- External_Procedure_Purpose
- External_Procedure_Type
- Extrcnct_Service
- Feature
- Field_Action_Level
- Filter_Fields
- Flags
- Flags_Action_Level
- Multi_Team_Access
- Notification_Actions
- Notification_Additional_Fields
- Notification_NewTran_Filter
- NOTIFICATION_REQUEST_ADDTL
- NOTIFICATION_STATUS
- Notification_Subscriptions
- Notification_Types
- NRT_Group_Link
- PrinterAreas
- PrinterPortfolios
- Printers

- PRMJNLPCConfig
- PRM_Batch
- PRM_Batch_History
- PRM_Batch_Job
- PRM_Install
- PRM_Install_Log
- PRM_Permission
- PRM_Permission_Grp
- Profile_Alerted_Rule
- Profile_To_RT_Batch
- Queue_Link
- Record_Source
- Record_Source_Column_Mapping
- Record_Source_Field
- Record_Source_Mapping
- Record_Source_Routing
- RQAggregateTypes
- RQ_Fields
- RT_Group_Link
- RuleAggregateLink
- RuleDef
- Service_Additional_Fields
- Service_RQ_Filter
- Settings
- Shortwindow_Group
- SystemAudit
- SystemAuditSubTypes
- SystemAuditTSec
- SystemAuditTypes
- SystemConfig
- SystemFields

- SystemSql
- SystemTableMap
- Task_Semaphore
- TCR_Group
- TCR_Run_Log
- TCR_Statistic
- TFL_Report_Last_DD_Date
- Timer_Lock
- Tips
- TipTypes
- Tip_Action_Level
- Tip_PRMrroles
- Travel_Locations
- Travel_Notifications
- Travel_Notification_Countries
- Travel_Notification_Method
- Travel_Notification_Regions
- Travel_Notification_Type
- TRENDS_1_BIMONTHLY
- TRENDS_1_MONTHLY
- TRENDS_1_WEEKLY
- TRENDS_2_BIMONTHLY
- TRENDS_2_DAILY
- TRENDS_2_WEEKLY
- TRENDS_3_BIMONTHLY
- TRENDS_3_MONTHLY
- TRENDS_3_WEEKLY
- TRENDS_4_BIMONTHLY
- TRENDS_4_DAILY
- TRENDS_4_WEEKLY
- TRENDS_5_BIMONTHLY

- TRENDS_5_MONTHLY
- TRENDS_5_WEEKLY
- TRENDS_6_BIMONTHLY
- TRENDS_6_MONTHLY
- TRENDS_6_WEEKLY
- TRENDS_7_BIMONTHLY
- TRENDS_7_MONTHLY
- TRENDS_7_WEEKLY
- TRENDS_FIELDS
- TRENDS_GROUPING
- TRENDS_GROUPING_RANGE
- TRENDS_YAXIS_DISPLAY
- UserRecentHistory
- UserRecentHistory_Cross_AL
- UserSessions

Accnt_Routing Table

The Accnt_Routing table holds the account ranges and the PRM Scoring Engine connections to which the transactions belonging to the specified ranges will be routed.

The columns in the Accnt_Routing table (ACCNT_ROUTING) are listed below with the data type.

Column Name	Data Type
ACCNT_NUM_HIGH	varchar(50)
ACCNT_NUM_LOW	varchar(50)
EXTR_CNCT_ID	varchar(50)

Index Name: **ACCNT_ROUTING_IDX1**

Fields: ACCNT_NUM_LOW

Index Name: **ACCNT_ROUTING_PK**

Fields: ACCNT_NUM_LOW

 ACCNT_NUM_HIGH

Column Descriptions

The following are the descriptions of the Accnt_Routing table columns.

ACCNT_NUM_HIGH — The higher limit of the account number range.

ACCNT_NUM_LOW — The lower limit of the account number range.

EXTR_CNCT_ID — The ID of the external connection to which the Analytic Gateway routes the transactions belonging to the specified range of accounts (references a record in the AJI EXTRCNCT table).

ACMAddInUsers Table

The ACMAddInUsers table stores the mapping between the PRM user and the ACM user. This table is installed as part of PRM integration with ACI Case Manager and is needed only with PRM - ACI Case Manager integration.

The columns in the ACMAddInUsers table (ACMADDINUSERS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
CREATED_BY	int
CREATION_DATE	datetime
MODIFICATION_DATE	datetime
MODIFIED_BY	int
PASSWORD	varchar(255)
USERID	int

Column Name	Data Type
USERNAME	varchar(50)
WORKSTATION	varchar(255)

Index Name: **ACMADDINUSERS_PK**

Fields: USERID

Column Descriptions

The following are the descriptions of the ACMAAddInUsers table columns.

CREATED_BY — The PRM user ID of the user who created this entry.

CREATION_DATE — The date on which this entry was created.

MODIFICATION_DATE — The date on which this entry was last modified.

MODIFIED_BY — The PRM user ID of the user who last modified this entry.

PASSWORD — The password of the associated user in the ACI Case Manager system.

USERID — The user ID in the PRM system (from the PRM_USERS table).

USERNAME — The username of the associated user in the ACI Case Manager system.

WORKSTATION — The workstation at which this entry was created.

ActionTypes_Action_Level Table

The ActionTypes_Action_Level table is used by the Analysis and Review system. It contains action assignments for the action levels.

The columns in the ActionType_Action_Level table (ACTIONSTYPE_ACTION_LEVEL) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_TYPE_ID	int
AUTO_UPDATES_ALLOWED	smallint
HASAUTOTEXT	smallint
SHOWSTATE	smallint
SHOWSTATUS	smallint
STEXT	int
TITLEBARSTRING	int
UPDATES_ALLOWED	smallint

Index Name: ACTIONSTYPE_ACTION_LEVEL_IX2

Fields: SHOWSTATE
ACTION_LEVEL_ID

Index Name: ACTIONSTYPE_ACTION_LEVEL_PK

Fields: ACTION_TYPE_ID
ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the ActionType_Action_Level table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

1 = CARD action level

- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_TYPE_ID — The identifier of the action type.

AUTO_UPDATES_ALLOWED — Indicates whether or not records in the MasterDisp table for actions with state can be updated by Auto-Action rules performing the same action on the same account.

Valid values are:

- 0 = Records in the MasterDisp table cannot be updated by Auto-Action rules performing the same action that has state for the same state. If EMM is enabled, the record in the EMD table will only be updated if the Auto-Action state is different than the state of the record in the EMD table and the record in the EMD table has a status >0.
- 1 = Records in the MasterDisp table can be updated by Auto-Action rules performing the same action that maintains state for the same state. If EMM is enabled, a record may be inserted into the EMD table regardless of the state or status of existing EMD records.

HASAUTOTEXT — Indicates whether the action has auto text used by the action dialog.

Valid values are:

- 0 = Action does not contain autotext
- 1 = Action contain autotext

SHOWSTATE — Identifies whether the button is depressed with the state.

Valid values are:

- 0 = Button is not depressed with the state
- 1 = Button is depressed with the state

SHOWSTATUS — The action status.

Valid values are:

- 0 = Completed
- 1 = Requested
- 2 = Failed
- 3 = Submitted

STEXT — The numeric identifier for the localized description of the action. The locale specific value for STEXT is found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

TITLEBARSTRING — A string to add to the title bar when the action is an “on” state (for example, blocked, opened, or closed).

UPDATES_ALLOWED — When an action recorded in the ACTIONSTYPE_ACTION_LEVEL table has its state set to a value of 1 (ACTIONSTYPE_ACTION_LEVEL.SHOWSTATE = 1), this indicates whether or not an action may update the MASTERDISP table when the change is for the same state (for example, updating a block code on an already blocked action). If UPDATES_ALLOWED = 1 and SHOWSTATE = 1, then you are able to update the MASTERDISP table.

If UPDATES_ALLOWED = 1 and SHOWSTATE = 1 and External Message Manager is enabled, then new entries will be inserted into the EXTERNAL_MESSAGE_DATA table when taking an action on the same state.

If UPDATES_ALLOWED = 1 and SHOWSTATE = 0 and External Message Manager is enabled, then new entries will be inserted into the EXTERNAL_MESSAGE_DATA table when taking an action on the same state. But they do not update MASTERDISP as MASTERDISP tracks the current state for actions with state, so is not applicable.

If UPDATES_ALLOWED = 0 and SHOWSTATE = 1 and External Message Manager is enabled, then new entries are not allowed to be inserted into the EXTERNAL_MESSAGE_DATA table when taking an action on the same state and MASTERDISP cannot be updated.

If UPDATES_ALLOWED = 0 and SHOWSTATE = 0 and External Message Manager is enabled, then new entries are not allowed to be inserted into the EXTERNAL_MESSAGE_DATA table when taking an action on the same state and MASTERDISP is not updated/not applicable as MASTERDISP tracks the current state for actions with state.

If UPDATES_ALLOWED = 1 or 0 and External Message Manager is not enabled, then new entries are not allowed to be inserted into the EXTERNAL_MESSAGE_DATA table.

ActionTypes_Action_Level_Emm Table

The ActionTypes_Action_Level_Emm table is used by the Analysis and Review system. It contains External Message Manager settings for an action and portfolio.

The columns in the ActionTypes_Action_Level_Emm table (ACTIONSTYPE_ACTION_LEVEL_EMM) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_TYPE_ID	int
EMM_MGRSERVLET	nvarchar(25)
PORTFOLIO_ID	int

Index Name: ACTIONSTYPE_ACTION_LEVEL_EMM_X1

Fields: ACTION_TYPE_ID
ACTION_LEVEL_ID
PORTFOLIO_ID

Column Descriptions

The following are the descriptions of the ActionTypes_Action_Level_Emm table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level

- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_TYPE_ID — The identifier of the action type.

EMM_MGRSERVLET — The External Message Manager servlet name.

PORTFOLIO_ID — The portfolio ID to which External Message Manager functionality is enabled. If the assignments are set at "Action Level" level, it will contain a null value.

ActionTypes_Feature Table

The ActionTypes_Feature table is used by the Analysis and Review system. It stores the feature ID related to a specific action type.

The columns in the ActionTypes_Feature table (ACTIONSTYPE_FEATURE) are listed below with the data type.

Column Name	Data Type
ACTION_TYPE_ID	int
FEATURE_ID	int

Index Name: PK_ACTIONSTYPE_FEATURE

Fields: ACTION_TYPE_ID
FEATURE_ID

Column Descriptions

The following are the descriptions of the ActionTypes_Feature table columns.

ACTION_TYPE_ID — This column contains a distinct numeric value used to uniquely identify an action type.

FEATURE_ID — This column contains a distinct numeric value used to uniquely identify a

feature.

ActionTypes_Permission Table

The ActionTypes_Permission table is used by the Analysis and Review system. It identifies the association between permissions and actions type.

The columns in the ActionTypes_Permission table (ACTIONSTYPE_PERMISSION) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_TYPE_ID	int
PERMISSION_ID	int

Index Name: PK_ACTIONSTYPE_PERMISSION

Fields: ACTION_TYPE_ID
PERMISSION_ID

Column Descriptions

The following are the descriptions of the ActionTypes_Permission table columns.

ACTION_TYPE_ID — The unique identifier of an action type.

PERMISSION_ID — The unique identifier of a permission.

Action_Level_Alert_Order_List Table

The Action_Level_Alert_Order_List table is used by the Analysis and Review system. It defines the columns that appear for all action levels. The availability of an action level is contingent upon licensing.

This table is used by all ACI Proactive Risk Manager action levels.

The columns in the Action_Level_Alert_Order_List table (ACTION_LEVEL_ALERT_ORDER_LIST) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
SALERTSFIELD	varchar(50)
SELECT_ORDER	smallint

Index Name: **PK_ACTION_LEVEL_ALERT_ORDER_LI**

Fields: ACTION_LEVEL_ID
 SALERTSFIELD

Column Descriptions

The following are the descriptions of the Action_Level_Alert_Order_List table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

SALERTSFIELD — The value from the ALERTS table (SALERTSFIELD column) that will be used as a paging field in the Alerts Pending UI screen.

SELECT_ORDER — The sort order.

Valid values are:

- 0 = Ascending

1 = Descending

Action_Level_Memo Table

The Action_Level_Memo table is used by the Analysis and Review system. It stores memo information related to a specific action level key.

The columns in the Action_Level_Memo table (ACTION_LEVEL_MEMO) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
CREATED_BY	int
DATE_CREATED	datetime
DATE_MODIFIED	datetime
EXPIRATION_DATE	datetime
MEMO	nvarchar(255)
MODIFIED_BY	int

Index Name: **PK_ACTION_LEVEL_MEMO**

Fields: ACTION_LEVEL_ID
 ACTION_LEVEL_KEY
 DATE_CREATED
 CREATED_BY

Column Descriptions

The following are the descriptions of the Action_Level_Memo table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the master tables. It can contain an SM_PAN, SM_UAN, SM_EMPLOYEE_ID, SM_RETL_ID, SM_TERM_ID. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and is used to determine what type of value is stored in ACTION_LEVEL_KEY.

CREATED_BY — The unique identifier for the user who created the action level memo.

DATE_CREATED — The date on which the action level memo was created.

DATE_MODIFIED — The date on which the action level memo was modified.

EXPIRATION_DATE — The initial date and time the action level memo may be removed.

MEMO — The text of the action level memo.

MODIFIED_BY — The user ID for the last person to modify this action level memo.

Action_Level_Profile_Table Table

The Action_Level_Profile table is used by the Analysis and Review system. It stores profile table information available for each action level.

The columns in the Action_Level_Profile_Table table (ACTION_LEVEL_PROFILE_TABLE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
DAY_INTERVAL	int
PEER_TABLE_IND	bit
PROFILE_TABLE_NAME	varchar(30)
SOFT_DELETE_IND	bit

Index Name: **PK_ACTION_LEVEL_PROFILE_TABLE**

Fields: ACTION_LEVEL_ID
 PROFILE_TABLE_NAME
 DAY_INTERVAL
 PEER_TABLE_IND

Column Descriptions

The following are the descriptions of the Action_Level_Profile_Table table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level

- 6 = UAID action level
- 7 = ACCOUNT action level

DAY_INTERVAL — The day interval used to calculate the averages.

PEER_TABLE_IND — This flag determines whether the Peer Profile of Profile is in use.

PROFILE_TABLE_NAME — The name of the profile table.

SOFT_DELETE_IND — The current delete status of the row.

Action_Level_Record_Source Table

The Action_Level_Record_Source table is used by the Analysis and Review system. It contains record sources associated with action levels. If the Real Time component of PRM is licensed, this table will also store the action level order within the record source.

The columns in the Action_Level_Record_Source table (ACTION_LEVEL_RECORD_SOURCE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
RECORD_SOURCE_ID	smallint
RT_ACTION_LEVEL_ORDER	smallint
SOFT_DELETE_IND	bit

Index Name: ACTION_LEVEL_RECORD_SOURCE_AK1

Fields: RECORD_SOURCE_ID
RT_ACTION_LEVEL_ORDER

Index Name: PK_ACTION_LEVEL_RECORD_SOURCE

Fields: RECORD_SOURCE_ID
 ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the Action_Level_Record_Source table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

RECORD_SOURCE_ID — The identifier of the record source.

RT_ACTION_LEVEL_ORDER — The order in which the action levels are processed.

SOFT_DELETE_IND — The current delete status of the row.

AddBlockCodes Table

The AddBlockCodes table is used by the Analysis and Review system. It contains the block codes that are added by the root administrator.

The columns in the AddBlockCodes table (ADDBLOCKCODES) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
BLOCKCODE_MEMO	int

Column Name	Data Type
IS_GLOBAL	bit
SBLOCKCODE	nvarchar(5)
SDESCRIPTION	int

Index Name: **ADDBLOCKCODES_IDX**

Fields: SBLOCKCODE

Column Descriptions

The following are the descriptions of the AddBlockCodes table columns.

BLOCKCODE_MEMO — The numeric identifier for the localized additional text associated with a block code. The locale specific value for BLOCKCODE_MEMO can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTY table.

IS_GLOBAL — Indicates whether the block code is global or not. Global block codes are available to all action levels; no check for action levels is necessary.

Valid values are:

0 = Block code is not global

1 = Block code is global

SBLOCKCODE — The block code ID. With a fresh install, ACI provides the values listed below, but customers can add other values.

60 = Lost card

70 = Stolen card

9999 = Point of Compromise

SDESCRIPTION — The numeric identifier for the localized name of the block code description. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

AddResponseCodes Table

The AddResponseCodes table contains all response codes

The columns in the AddResponseCodes table (ADDRESPONSECODES) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DESCRIPTION	int
IS_GLOBAL	bit
RESPONSECODE	nvarchar(30)

Index Name: **PK_ADDRESPONSECODES**

Column Descriptions

The following are the descriptions of the AddResponseCodes table columns.

DESCRIPTION — Description not available.

IS_GLOBAL — Description not available.

RESPONSECODE — Description not available.

AddResponseCodes_Action_Level Table

The AddResponseCodes table contains response codes per action level.

The columns in the AddResponseCodes_Action_Level table (ADDRESPONSECODES_ACTION_LEVEL) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
RESPONSECODE	nvarchar(30)

Index Name: **PK_ADDRESPONSECODES_AL**

Fields: RESPONSECODE

 ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the AddResponseCodes_Action_Level table columns.

ACTION_LEVEL_ID — Contains the ID for the action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

RESPONSECODE — This field contains the response code.

AG_Composite_Field Table

The AG_Composite_Field table is used to identify which RECORD_SOURCE_FIELDS should compute their value. For example, those fields are not part of the message Analytic Gateway is processing, but they are computed to allow other features to be implemented (for instance, Tiebreaker information or the Peer Profile Groups).

The columns in the AG_Composite_Field table (AG_COMPOSITE_FIELD) are listed below with the data type.

Column Name	Data Type
COMPOSITION_ID	int
DEFINITION	nvarchar(Max)
FIELD_NAME	varchar(50)
IS_HASHED	int
RECORD_SOURCE_ID	smallint

Index Name: **AG_COMPOSITE_FIELD_PK**

Fields: RECORD_SOURCE_ID
 FIELD_NAME

Column Descriptions

The following are the descriptions of the AG_Composite_Field table columns.

COMPOSITION_ID — The unique identifier for the composition operation based on the AG_Field_Composition table.

DEFINITION — The definition of the composition. Currently, it is used by the JavaScript type of composite fields to store the JavaScript composition logic.

FIELD_NAME — The name of the field.

IS_HASHED — Indicates whether Tiebreaker hashing is enabled. The hashing functionality was tested and is supported by ACI only for PIM Card Transactions (Record Source ID = 25).

Valid values are:

0 = Disabled

1 = Enabled

RECORD_SOURCE_ID — The unique identifier for the record source.

AG_Comp_Fields_Selector Table

The AG_Comp_Fields_Selector table is used to select which fields should be used to compute the value of the composite field.

The columns in the AG_Comp_Fields_Selector table (AG_COMP_FIELDS_SELECTOR) are listed below with the data type.

Column Name	Data Type
FIELD_NAME	varchar(50)
ID	int
PRIORITY	int
RECORD_SOURCE_ID	smallint
SELECTION_ID	int
VALUE	nvarchar(500)

Index Name: AG_COMP_FIELDS_SELECTOR_PK

Fields: ID

Column Descriptions

The following are the descriptions of the AG_Comp_Fields_Selector table columns.

FIELD_NAME — The name of the field.

ID — Identifies one single selector (this is the primary key).

PRIORITY — Indicates the order in which multiple selectors should be used.

RECORD_SOURCE_ID — The unique identifier for the record source.

SELECTION_ID — The unique identifier for the selection based on the AG_Field_Selection table.

VALUE — The parameter that is going to be used to run the selection operation to identify if this selector should identify how the composite field should be computed.

AG_Data_Sanitizer Table

The AG_Data_Sanitizer is used by Analytic Gateway and it is used in order to replace incorrect characters when processing entities.

The columns in the AG_Data_Sanitizer table (AG_DATA_SANITIZER) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ORIGINAL	nvarchar(50)
REPLACEMENT	nvarchar(50)

Index Name: **PK_AG_DATA_SANITIZER**

Fields: ORIGINAL

Column Descriptions

The following are the descriptions of the AG_Data_Sanitizer table columns.

ORIGINAL — Contains the original characters of the entities.

REPLACEMENT — Contains the replacement characters of the entities.

AG_Field Table

The AG_Field table is used to identify the fields that should be used to compute the value of the composite field.

The columns in the AG_Field table (AG_FIELD) are listed below with the data type.

Column Name	Data Type
COMPOSING_ORDER	int
FIELD_NAME	varchar(50)
ID	int
RECORD_SOURCE_ID	smallint
SELECTOR_ID	int
TRANSFORMATION_ID	int

Index Name: **AG_FIELD_PK**

Fields: ID

Column Descriptions

The following are the descriptions of the AG_Field table columns.

COMPOSING_ORDER — The number which orders a list of composing fields.

FIELD_NAME — The name of the field.

ID — Identifies one single field (this is the primary key).

RECORD_SOURCE_ID — The unique identifier for the record source.

SELECTOR_ID — The unique identifier for the selector based on the AG_Comp_Selector_Field table.

TRANSFORMATION_ID — The unique identifier for the transformation based on the

AG_Field_Transformation table.

AG_Field_Composition Table

The AG_Field_Composition table is used to identify the operation that should be used to calculate the composition field.

The columns in the AG_Field_Composition table (AG_FIELD_COMPOSITION) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
CLASSNAME	nvarchar(500)
DESCRIPTION	nvarchar(500)
ID	int

Index Name: **AG_FIELD_COMPOSITION_PK**

Fields: ID

Column Descriptions

The following are the descriptions of the AG_Field_Composition table columns.

CLASSNAME — The class of the operation (it should be a fully qualified java class name).

DESCRIPTION — The description of the operation.

ID — Identifies one operation.

AG_Field_Selection Table

The AG_Field_Selection table is used to identify the operation that should be used when selecting the composing fields.

The columns in the AG_Field_Selection table (AG_FIELD_SELECTION) are listed below with the data type.

Column Name	Data Type
CLASSNAME	nvarchar(500)
DESCRIPTION	nvarchar(500)
ID	int

Index Name: **AG_FIELD_SELECTION_PK**

Fields: ID

Column Descriptions

The following are the descriptions of the AG_Field_Selection table columns.

CLASSNAME — The class of the operation (it should be a fully qualified java class name).

DESCRIPTION — The description of the operation.

ID — Identifies one selection.

AG_Field_Transformation Table

The AG_Field_Transformation table is used to identify the operation that should be used when transforming the composing fields.

The columns in the AG_Field_Transformation table (AG_FIELD_TRANSFORMATION) are listed below with the data type.

Column Name	Data Type
CLASSNAME	nvarchar(500)

Column Name	Data Type
DESCRIPTION	nvarchar(500)
ID	int

Index Name: **AG_FIELD_TRANSFORMATION_PK**

Fields: ID

Column Descriptions

The following are the descriptions of the AG_Field_Transformation table columns.

CLASSNAME — The class of the operation (it should be a fully qualified java class name).

DESCRIPTION — The description of the operation.

ID — Identifies one transformation.

AG_KPI_DEF Table

The AG_KPI_DEF table stores the definitions of the AG KPIs.

The columns in the AG_KPI_DEF table (AG_KPI_DEF) are listed below with the data type.

Column Name	Data Type
KPI_DB_LOGGING_ENABLED	bit
KPI_DESCRIPTION	varchar(50)
KPI_DISPLAY_NAME	varchar(50)
KPI_ID	int

Column Name	Data Type
KPI_NAME	varchar(50)
KPI_TYPE	smallint

Index Name: **IDX_AG_KPI_DEF_NAME**

Fields: KPI_NAME

Column Descriptions

The following are the descriptions of the AG_KPI_DEF table columns.

KPI_DB_LOGGING_ENABLED — Indicates if the DB logging is enabled for the AG KPIs.
Valid values are:

0 = DB logging is not enabled for AG KPIs

1 = DB logging is enabled for AG KPIs

KPI_DESCRIPTION — The description of the AG KPIs.

KPI_DISPLAY_NAME — The name displayed for the AG KPIs.

KPI_ID — Internal ID of the KPI.

KPI_NAME — The name of the KPI.

KPI_TYPE — The type of the KPI.

AG_KPI_LOG Table

The AG_KPI_LOG table stores the current AG KPIs which are used in calculations.

The columns in the AG_KPI_LOG table (AG_KPI_LOG) are listed below with the data type.

Column Name	Data Type
KPI_95_PERCENTILE	numeric(10, 5)
KPI_AVG	numeric(10, 5)
KPI_COUNT	int
KPI_ID	int
KPI_LOGGING_TIME	datetime
KPI_MAX	numeric(10, 5)
KPI_MIN	numeric(10, 5)
KPI_PERCENTAGE_WITIN_TARGET	numeric(10, 5)
KPI_PROCESS_ID	varchar(16)
KPI_STD_DEV	numeric(10, 5)
KPI_TPS	numeric(10, 5)

Index Name: **IDX_AG_KPI_PROCESS_ID**

Fields: KPI_PROCESS_ID

Index Name: **IDX_AG_KPI_ID_LOGGING_TIME**

Fields: KPI_ID

KPI_LOGGING_TIME

Column Descriptions

The following are the descriptions of the AG_KPI_LOG table columns.

KPI_95_PERCENTILE — Response time 95 percentiles during KPI calculation duration.

KPI_AVG — Average response time of transactions during the KPI calculation duration.

KPI_COUNT — Number of transactions processed during KPI calculation duration.

KPI_ID — Internal ID of the KPI.

KPI_LOGGING_TIME — Timestamp of the time the log was inserted into the database.

KPI_MAX — Max response time of transactions during the KPI calculation duration.

KPI_MIN — Min response time of transactions during the KPI calculation duration.

KPI_PERCENTAGE_WITIN_TARGET — Percent of transactions under target response time set in APPLCNFG table for the AG.

KPI_PROCESS_ID — ID of the AG process.

KPI_STD_DEV — Standard Deviation of transactions during KPI calculation duration.

KPI_TPS — Transaction per second during the KPI calculation duration.

AG_KPI_SLA_Report_Result Table

The AG_KPI_SLA_REPORT_RESULT table holds the results for the last report's execution.

The columns in the AG_KPI_SLA_Report_Result table (AG_KPI_SLA_REPORT_RESULT) are listed below with the data type.

Column Name	Data Type
AVG_TPS	numeric(10,5)
MAX_RESPONE_TIME	numeric(10,5)

Column Name	Data Type
MIN_RESPOSNE_TIME	numeric(10,5)
NOTES	nvarchar(255)
NUMBER_OF_TXN_NOT_WITHIN_TARGET	int
NUMBER_OF_TXN_WITHIN_TARGET	int
PERCENT_OF_TXN_WITHIN_TARGET	numeric(10,2)
PROCESS_ID	varchar(16)
TOTAL_NUMBER_OF_TXN	numeric(10,0)
UP_TIME	numeric(10,2)

Column Descriptions

The following are the descriptions of the AG_KPI_SLA_Report_Result table columns.

AVG_TPS — Average transaction per second.

MAX_RESPOSNE_TIME — Maximum response time.

MIN_RESPOSNE_TIME — Minimum response time.

NOTES — Notes for the AG KPI.

NUMBER_OF_TXN_NOT_WITHIN_TARGET — Number of transactions not processed within target response time.

NUMBER_OF_TXN_WITHIN_TARGET — Number of transactions processed within target response time.

PERCENT_OF_TXN_WITHIN_TARGET — Percent of transactions processed within target response time.

PROCESS_ID — ID of the AG process.

TOTAL_NUMBER_OF_TXN — Total number of transactions processed.

UP_TIME — AG process Up Time (NRT, RT, NRTRTU).

AG_KPI_SLA_Report_Statistics Table

The AG_KPI_SLA_REPORT_STATISTICS table holds calculated aggregates by day for each AG process.

The columns in the AG_KPI_SLA_Report_Statistics table (AG_KPI_SLA_REPORT_STATISTICS) are listed below with the data type.

Column Name	Data Type
DOWN_TIME_SECONDS	int
KPI_COUNT	int
KPI_COUNT_NOT_WITIN_TARGET	int
KPI_COUNT_WITIN_TARGET	int
KPI_MAX	numeric(10, 5)
KPI_MIN	numeric(10, 5)
KPI_PERCENTAGE_WITIN_TARGET	numeric(10, 5)
KPI_PROCESS_ID	varchar(16)

<i>Column Name</i>	<i>Data Type</i>
KPI_TPS	numeric(10, 5)
STATISTICS_DATE	date
UP_TIME_PRECENT	numeric(10,2)
VALID_KPI_LOGGING_MODE	varchar(1)
VALID_NRT	varchar(1)
VALID_RT	varchar(1)

Column Descriptions

The following are the descriptions of the AG_KPI_SLA_Report_Statistics table columns.

DOWN_TIME_SECONDS — Down time for the AG process in seconds.

KPI_COUNT — Number of transactions processed during AG KPI calculation duration.

KPI_COUNT_NOT_WITIN_TARGET — Total number of transactions not processed within target response time.

KPI_COUNT_WITIN_TARGET — Total number of transactions processed within target response time.

KPI_MAX — Maximum response time during AG KPI calculation duration.

KPI_MIN — Minimum response time during AG KPI calculation duration.

KPI_PERCENTAGE_WITIN_TARGET — Percent of transactions processed under target response time set in APPLCNFG table for the AG process.

KPI_PROCESS_ID — ID of the AG process.

KPI_TPS — Transaction per second during the KPI calculation duration.

STATISTICS_DATE — Date when the statistic was calculated.

UP_TIME_PRECENT — Up time for the AG process in percents.

VALID_KPI_LOGGING_MODE — Valid KPI logging mode.

VALID_NRT — Valid NRT.

VALID_RT — Valid RT.

AG_NACHA_Batch_Statistics Table

The AG_NACHA_Batch_Statistics table is used to keep the state of the NACHA batches within a NACHA file being processed. The batch number identifies a batch within a file. The NACHA_BATCH_FILE_NAM and the NACHA_BATCH_NUM columns make up the primary key.

The columns in the AG_NACHA_Batch_Statistics table (AG_NACHA_BATCH_STATISTICS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DETAIL_RECORDS_IN_BATCH	int
NACHA_BATCH_FILE_NAM	varchar(50)
NACHA_BATCH_NUM	int
NACHA_BATCH_SEC_CODE	varchar(3)
NACHA_BATCH_STAT	varchar(1)

Column Name	Data Type
NACHA_END_DAT	datetime
NACHA_START_DAT	datetime
PROCESS_ID	varchar(16)

Index Name: **PK_AG_NACHA_BATCH_STATISTICS**

Fields: Nacha_Batch_File_Nam
 Nacha_Batch_Num

Column Descriptions

The following are the descriptions of the AG_NACHA_Batch_Statistics table columns.

Detail_Records_In_Batch — The number of detail records the Analytic Gateway found in the batch.

Nacha_Batch_File_Nam — The value in this column will match the value in the NACHA_FILE_NAME column in the AG_NACHA_File_Statistics table. This column and the NACHA_BATCH_NUM column compose the primary key.

Nacha_Batch_Num — The number the sending entity assigned to the batch. The numbers are assigned in ascending sequence to each batch in a File of Entries. This column and the NACHA_BATCH_FILE_NAM column compose the primary key.

Nacha_Batch_Sec_Code — The Standard Entry Class (SEC) Code of the batch.

Nacha_Batch_Stat — The status of the batch within the file.

Valid values are:

- 1 = RECORD_PROCESSING
- 2 = PROCESSED
- 3 = ABORTED

Nacha_End_Dat — Identifies the date and time when the Analytic Gateway finished processing this batch.

Nacha_Start_Dat — The date and time when the Analytic Gateway started processing this batch.

Process_Id — The Process ID of the Analytic Gateway instance that updated the table.

AG_NACHA_File_Statistics Table

The AG_NACHA_File_Statistics table is used in addition to the AG_NACHA_Batch_Statistics table when NACHA files are processed. The AG_NACHA_File_Statistics table keeps the state of the NACHA files being processed. (A secondary table called the AG_NACHA_Batch_Statistics table is used to keep track of each batch processed in the NACHA file.) The column NACHA_FILE_NAM is the primary key to the AG_NACHA_File_Statistics table.

The columns in the AG_NACHA_File_Statistics table (AG_NACHA_FILE_STATISTICS) are listed below with the data type.

Column Name	Data Type
NACHA_BATCH_HEADER_COUNT	int
NACHA_END_DAT	datetime
NACHA_FILE_NAM	varchar(50)
NACHA_FILE_STAT	varchar(1)
NACHA_LAST_PROCESSED_BATCH	int
NACHA_LAST_PROCESSED_DETAIL	int
NACHA_START_DAT	datetime
PROCESS_ID	varchar(16)

Index Name: **PK_AG_NACHA_FILE_STATISTICS**

Fields: Nacha_File_Nam

Column Descriptions

The following are the descriptions of the AG_NACHA_File_Statistics table columns.

Nacha_Batch_Header_Count — The total count of Batch Header records in the file, as counted by the Analytic Gateway.

Nacha_End_Dat — The date and time when the Analytic Gateway finished processing this file.

Nacha_File_Nam — The value used to identify the NACHA file. It is the primary key.

Nacha_File_Stat — The status of the NACHA file. The file will be processed three times.

Valid status values are:

- 0 = DISCOVERY
- 1 = RECORD_PROCESSING
- 2 = PROCESSED_OK
- 3 = FILE_REJECTED
- 4 = ERR_THRESHOLD_REACHED

Nacha_Last_Processed_Batch — The last batch that the Analytic Gateway was processing.

Nacha_Last_Processed_Detail — The last detail record that the Analytic Gateway finished processing.

Nacha_Start_Dat — The date and time when the Analytic Gateway started processing this file.

Process_Id — The Process ID of the Analytic Gateway instance that updated the table.

AG_Services Table

The AG_Services table is used to load associated mappers to be used for processing the entities.

The columns in the AG_Services table (AG_SERVICES) are listed below with the data type.

Column Name	Data Type
ARGUMENTTYPE	nvarchar(256)
ISIDEMPOTENT	smallint
OPERATION	nvarchar(50)
RECORD_SOURCE_ID	int
RESPONSETYPE	nvarchar(256)
SERVICENAME	nvarchar(50)
TIMEOUTBATCH	int
TIMEOUTTXN	int
VERSION	nvarchar(10)

Column Descriptions

The following are the descriptions of the AG_Services table columns.

ArgumentType — The type of input entity. It is used to load the mapper class.

IsIdempotent — Identifies whether the service should function idempotent.

Operation — The name of the operation. At this time, it is just an identifier used for documentation purposes.

RECORD_SOURCE_ID — The identifier of the record source on which this service is mapped in PRM.

ResponseType — The type of output entity or mapper class that can be used to create the entity in case the generated mapper will not or cannot be used.

Current scenario is that the transaction entity should be populated with the reply and echoed back, without creating a different object.

ServiceName — The service name. At this time, it is used for documentation purposes.

TimeoutBatch — The timeout value, expressed in seconds, for processing the entire batch of entities.

TimeoutTxn — The timeout value, expressed in seconds, for processing one entity.

Version — The version of the service. At this time, it is used for documentation purposes.

AG_Transformation_Param Table

The AG_Transformation_Param table is used to identify the parameters that should be applied on the transformation operation on the field.

The columns in the AG_Transformation_Param table (AG_TRANSFORMATION_PARAM) are listed below with the data type.

Column Name	Data Type
FIELD_ID	int
POSITION	int
VALUE	nvarchar(500)

Index Name: **AG_TRANSFORMATION_PARAM_PK**

Fields: FIELD_ID

 POSITION

Column Descriptions

The following are the descriptions of the AG_Transformation_Param table columns.

FIELD_ID — Identifies one field.

POSITION — The parameter attribute, which, for example, could take a value 1 for position and value 2 for length. There are more possible values.

VALUE — This column stores the value assigned to position.

Application_Data_Type Table

The Application_Data_Type table holds an enumeration of all stored procedure argument data types that the Analytic Gateway understands (java.sql.Types, plus several AG-specific ones).

The columns in the Application_Data_Type table (APPLICATION_DATA_TYPE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
APPLICATION_DATA_FORMAT	nvarchar(30)
APPLICATION_DATA_TYPE	varchar(20)
APPLICATION_DATA_TYPE_ID	smallint
SQL_DATA_TYPE	varchar(30)

Index Name: **APPLICATION_DATA_TYPE_PK**

Fields: APPLICATION_DATA_TYPE_ID

Index Name: **APPLICATION_DATA_TYPE_UK**

Fields: APPLICATION_DATA_TYPE

Column Descriptions

The following are the descriptions of the Application_Data_Type table columns.

APPLICATION_DATA_FORMAT — The optional format string describing the layout of the value for the corresponding data type.

APPLICATION_DATA_TYPE — The data type description.

APPLICATION_DATA_TYPE_ID — The data type unique identifier.

SQL_DATA_TYPE — The SQL data type corresponding to the current Analytic Gateway application data type.

Assgnd_ActionsType_ActionLevel Table

The Assgnd_ActionsType_ActionLevel table is used by the Analysis and Review system. It identifies assigned action types per action level.

The columns in the Assgnd_ActionsType_ActionLevel table (ASSGND_ACTIONSTYPE_ACTIONLEVEL) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
ACTION_TYPE_ID	int

Index Name: **PK_ASSGND_ACTIONSTYPE_ACTIONLE**

Fields: ACTION_TYPE_ID
 ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the Assgnd_ActionsType_ActionLevel table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level

- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_TYPE_ID — The action type. It is linked to the LTYPE column in the ActionsText table.

Valid action types are as follows:

- 0 = Block
- 1 = Letter Sent
- 2 = Call
- 3 = Watch
- 4 = Mark
- 5 = Ice
- 6 = Memo
- 7 = Reminder
- 8 = Forward
- 9 = Close Account
- 10 = Open Action Level ID
- 11 = Alert
- 12 = Email
- 13 = History Button
- 14 = POC Block
- 15 = Export
- 16 = Alert Delete
- 17 = Response Required Clear
- 18 = Response Required Confirm
- 19 = Print
- 20 = Linked Account

- 21 = Action Level Memo
- 22 = Alert Email
- 23 = Copy
- 24 = Next
- 25 = Expand Grid
- 26 = Open Forward
- 27 = Open Reminder
- 28 = Response Required
- 29 = Cross Reference
- 30 = Open Review from Compromise
- 31 = Open Review from Review Screen
- 32 = Open Compromise Alert
- 33 = Close Alert
- 34 = Close Forward
- 35 = Close Reminder
- 36 = Close Review from Compromise
- 37 = Close Review from Review Screen
- 38 = Close Compromise Alert
- 39 = Alert Review Timeout
- 40 = Forward Timeout
- 41 = Review Timeout
- 42 = Reminder Timeout
- 43 = Opened Review from Compromise Block
- 44 = Closed Review from Compromise Block
- 45 = Opened Compromise Block
- 46 = Closed Compromise Block

AuthConfig Table

The AuthConfig table is used for the automatic login into the application, using the domain user name.

The columns in the AuthConfig table (AUTHCONFIG) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
SMODULECLASS	varchar(150)
SMODULECONTROLFLAG	varchar(15)
SNAME	varchar(50)
SOPTIONS	ntext

Index Name: **IDX_AUTHCONFIG_UNIQUE**

Fields: SNAME

Column Descriptions

The following are the descriptions of the AuthConfig table columns.

SMODULECLASS — The name of the java class used for the login. Example value: "com.aciworldwide.prm.auth.pam.PRMLLoginModule".

SMODULECONTROLFLAG — The name of the flag used to control module behavior.

SNAME — The name of the application the user is logging into.

SOPTIONS — The optional configuration values of the java class.

AutoText Table

The AutoText table is used by the Analysis and Review system. It stores text that Root Administrators have written as predefined text for action memo boxes. Root Administrators enter

the text by using the auto text component of the table editor feature. The columns in the AutoText table are listed below along with the data types.

The columns in the AutoText table (AUTOTEXT) are listed below with the data type.

Column Name	Data Type
DCREATED_TIME	datetime
DLAST_MODIFIED_TIME	datetime
IS_GLOBAL	bit
LCREATED_BY	integer
LID	int
LLAST_MODIFIED_BY	integer
LSUBTYPE	int
LTYPE	int
STEXT	int

Index Name: **IDX_MEMOS**

Fields: LID

 LTYPE

 LSUBTYPE

 STEXT

Index Name: **IDX_MEMOSUBTYPES**

Fields: LID

Column Descriptions

The following are the descriptions of the AutoText table columns.

Dcreated_time — The date and time when the auto text was added

Dlast_modified_time — - Date and time when the auto text was added or updated for the respective action.

IS_GLOBAL — The auto text as being global, that is, available to all action levels, and no check for action level is required.

Valid values are:

0 = The auto text is not global.

1 = The auto text is global.

Lcreated_by — The users's ID who added the auto text.

LID — The table-level ID for each row.

Llast_modified_by — The user's ID who last applied changes to the auto text

LSUBTYPE — The subtype. It is linked to the LID column in the ActionType table.

LTYPE — The type of text. When the value is 0, it indicates the auto text for action memo boxes.

STEXT — The numeric identifier for the localized name of the value from this column. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

Autotext_Action_Level Table

The Autotext_Action_Level table is used by the Analysis and Review system. It identifies auto text availability per action level.

The columns in the Autotext_Action_Level table (AUTOTEXT_ACTION_LEVEL) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
AUTOTEXT_ID	int

Index Name: **AUTOTEXT_ACTION_LEVEL_PK**

Fields: AUTOTEXT_ID
 ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the Autotext_Action_Level table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

AUTOTEXT_ID — A value from the LID column in the AUTOTEXT table.

Auto_Add_In_Config Table

The Auto_Add_In_Config table is used by the Analysis and Review system. It contains the auto add-in information that is added by the root administrator.

The columns in the Auto_Add_In_Config table (AUTO_ADD_IN_CONFIG) are listed below with the data type.

Column Name	Data Type
ACTION_TYPE_ID	int
AUTO_ADD_IN_CONFIG_ID	int
CONFIG_TYPE_ID	int
DESCRIPTION	nvarchar(50)
HOST_VALUE	nvarchar(256)
L10N_PROPERTY_ID	int

Index Name: **IDX_AUTO_ADD_IN_CONFIG**

Fields: AUTO_ADD_IN_CONFIG_ID

Column Descriptions

The following are the descriptions of the Auto_Add_In_Config table columns.

ACTION_TYPE_ID — The action type. It is linked to the LTYPE column in the ActionsText table.

Valid action types are as follows:

- 0 = Block
- 1 = Letter Sent
- 2 = Call
- 3 = Watch
- 4 = Mark
- 5 = Ice
- 6 = Memo
- 7 = Reminder
- 8 = Forward

- 9 = Close Account
- 10 = Open Action Level ID
- 11 = Alert
- 12 = Email
- 13 = History Button
- 14 = POC Block
- 15 = Export
- 16 = Alert Delete
- 17 = Response Required Clear
- 18 = Response Required Confirm
- 19 = Print
- 20 = Linked Account
- 21 = Action Level Memo
- 22 = Alert Email
- 23 = Copy
- 24 = Next
- 25 = Expand Grid
- 26 = Open Forward
- 27 = Open Reminder
- 28 = Response Required
- 29 = Cross Reference
- 30 = Open Review from Compromise
- 31 = Open Review from Review Screen
- 32 = Open Compromise Alert
- 33 = Close Alert
- 34 = Close Forward
- 35 = Close Reminder
- 36 = Close Review from Compromise
- 37 = Close Review from Review Screen

- 38 = Close Compromise Alert
- 39 = Alert Review Timeout
- 40 = Forward Timeout
- 41 = Review Timeout
- 42 = Reminder Timeout
- 43 = Opened Review from Compromise Block
- 44 = Closed Review from Compromise Block
- 45 = Opened Compromise Block
- 46 = Closed Compromise Block

AUTO_ADD_IN_CONFIG_ID — The auto add in configuration identifier.

CONFIG_TYPE_ID — The configuration type identifier.

DESCRIPTION — The description of the auto add-in.

HOST_VALUE — The host value if external message processing is enabled for the action

L10N_PROPERTY_ID — The L10N property identifier.

Auto_Add_In_Rule_Config Table

The Auto_Add_In_Rule_Config table is used by the Analysis and Review system. It contains the auto action rule used in the auto add-in configuration that is added by the root administrator.

The columns in the Auto_Add_In_Rule_Config table (AUTO_ADD_IN_RULE_CONFIG) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
AUTOACTIONSRULE_LID	int

Column Name	Data Type
AUTO_ADD_IN_CONFIG_ID	int

Index Name: **IDX_ADD_IN_RULE_CONFIG**

Fields: AUTOACTIONSRULE_LID

 AUTO_ADD_IN_CONFIG_ID

Column Descriptions

The following are the descriptions of the Auto_Add_In_Rule_Config table columns.

AUTOACTIONSRULE_LID — Contains the unique identifier for the auto action rule.

AUTO_ADD_IN_CONFIG_ID — The auto add-in configuration identifier.

Batch_Statistics Table

The Batch_Statistics table holds progress information for each batch file processed.

The columns in the Batch_Statistics table (BATCH_STATISTICS) are listed below with the data type.

Column Name	Data Type
BATCH_COMPLETED_DATE	datetime
BATCH_STARTED_DATE	datetime
BATCH_STATUS	smallint
FILE_NAME	varchar(50)
LAST_PROCESSED_RECORD	int
PROCESS_ID	varchar(16)

Index Name: **BATCH_STATISTICS_PK**

Fields: FILE_NAME

Column Descriptions

The following are the descriptions of the Batch_Statistics table columns.

BATCH_COMPLETED_DATE — The date on which processing of the current file ended.

BATCH_STARTED_DATE — The date on which processing of the current file started.

BATCH_STATUS — The status of the current file.

Valid values are:

- 0 = New
- 1 = Running
- 2 = Completed
- 3 = Aborted

FILE_NAME — The name of the file currently being processed.

LAST_PROCESSED_RECORD — The last processed record (1-based).

PROCESS_ID — The process ID of the Analytic Gateway instance which processes the file.

Check_Index_Columns Table

The Check_Index_Columns table is used at the PRM installation and stores the standard and nonACI existing column indexes.

The columns in the Check_Index_Columns table (CHECK_INDEX_COLUMNS) are listed below with the data type.

Column Name	Data Type
COLUMN_NAME	varchar(50)
DATASIZE	int
DATATYPE	varchar(50)
IDX_METADATA	varchar(4000)
INDEX_NAME	varchar(50)
NON_ACI	int
STD_ACI	int
TABLE_NAME	varchar(50)

Index Name: **IDX_CHECK_INDEX_COLUMNS**

Fields: TABLE_NAME
 COLUMN_NAME
 INDEX_NAME

Column Descriptions

The following are the descriptions of the Check_Index_Columns table columns.

COLUMN_NAME — Contains the name of the column.

DATASIZE — Contains the column data size.

DATATYPE — Contains the column data type.

IDX_METADATA — Contains the index metadata.

INDEX_NAME — Contains the column index.

NON_ACI — Specifies if the index is nonACI.

Valid values are:

0 = The index is PRM standard

1 = The index is nonACI

STD_ACI — Specifies if the index is PRM standard.

Valid values are:

0 = The index is not PRM standard

1 = The index is PRM standard

TABLE_NAME — Contains the name of the table.

Cleanup_Tables Table

Description not available.

The columns in the Cleanup_Tables table (CLEANUP_TABLES) are listed below with the data type.

Column Name	Data Type
ADDWHERE	varchar(200)
BATCHSIZE	int
DATECOLUMN	varchar(30)
DAYSTOKEEP	smallint
DAYS_PER_PARTITION	int
IS_PARTITIONED	char(1)

Column Name	Data Type
PARTITION_FUNCTION	varchar(40)
PARTITION_SCHEME	varchar(40)
PARTITION_START_DATE	date
REPORTSIZE	smallint
SQL_EXEC_BEFORE	varchar(4000)
TABLERNAME	varchar(30)

Index Name: **PK_CLEANUP_TABLES**

Fields: TABLERNAME

Column Descriptions

The following are the descriptions of the Cleanup_Tables table columns.

ADDWHERE — Used to prevent accounts which have transactions marked as suspicious from being deleted from the Master table.

BATCHSIZE — The number of records deleted in one transaction. Refer to Clean-Up Scripts commands in Section 7 of this manual for additional information regarding this parameter.

DATECOLUMN — The column name of the various date fields.

DAYSTOKEEP — The number of days' worth of data that remain in the table after the script is run.

DAYS_PER_PARTITION — The number of days per partition for this table.

IS_PARTITIONED — Indicates whether the table is partitioned.

Valid values are:

Y = Partitioned
N = Not partitioned

PARTITION_FUNCTION — The partition function name; it is specific for SQL Server only.

PARTITION_SCHEME — The partition schema name; it is specific for SQL Server only

PARTITION_START_DATE — The start date of the partition.

REPORTSIZE — The number of records in a report.

SQL_EXEC_BEFORE — Stores customized sql insert (into a predefined table) for saving data before cleanup execution.

TABlename — The name of the table that the cleanup will be performed on.

Config Table

The Config table is used by the Analytic Gateway process. It contains global settings that affect the operation of the ACI Proactive Risk Manager systemwide. Values that are shared with the ACI Proactive Risk Manager Client software are stored in this table. Each parameter value is stored in this table as SCFGVARIABLE, and the value is stored in the appropriate column. Strings are stored in the SCFGVALUE column, and integers in the LCFGVALUE column. Dates and times are stored in the DTCFGVALUE column. Each record has a series of storage columns, one for each supported type. Some values are stored in multiple variables.

Various features can be customized at each client site by changing a parameter value.

The Config table contains a list of parameters used for various procedures in the PRM system. Some of these parameters map generic commands to system specific settings. The parameters are only read at startup. The Config table is also read by the web application. Therefore, both the Analytic Gateway process and the web application must be stopped and restarted when changes are made to the Config table.

The Config table parameters are described in a separate section of this manual.

Note: Extreme care must be taken when changing any Config table entry as improper changes can have adverse impacts to the Analysis and Review system.

The columns in the Config table (CONFIG) are listed below with the data type.

Column Name	Data Type
BLOBEDITOR	image
BLOBVALUE	image
DTCFGVALUE	datetime
LCFGVALUE	int
LCFGVARIABLEID	int
LPORTFOLIOID	int
NTYPE	int
SCFGVALUE	varchar(150)
SCFGVARIABLE	varchar(20)
SPARAMS	varchar(255)

Index Name: **IDX_CONFIG_CLUSTER**

Fields: SCFGVARIABLE

 LPORTFOLIOID

Column Descriptions

The following are the descriptions of the Config table columns.

BLOBEDITOR — Reserved for future use.

BLOBVALUE — The binary value for the record in question.

DTCFGVALUE — The date and time value for the record in question.

LCFGVALUE — The numeric value for the record in question.

LCFGVARIABLEID — Not currently used.

LPORTFOLIOID — The portfolio ID.

NTYPE — The datatype.

SCFGVALUE — The string value for the record in question.

SCFGVARIABLE — The name of the Config table variable.

SPARAMS — Not currently used.

DASHB_AP_SYSAUD Table

The DASHB_AP_SYSAUD table is a snapshot of SystemAudit table and is used in dashboard Analyst Performance report

The columns in the DASHB_AP_SYSAUD table (DASHB_AP_SYSAUD) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DTDATE	datetime
LUSERID	int

Index Name: **IDX_SYSTEMAUDIT_CLUSTER**

Fields: LUSERID

Column Descriptions

The following are the descriptions of the DASHB_AP_SYSAUD table columns.

DTDATE — Contains the date of the audited action.

LUSERID — The user ID. It is linked to the LID column in the PRM_Users table.

DD_Routing Table

The DD_Routing table is used by the AJI DDRouting DB service.

The columns in the DD_Routing table (DD_ROUTING) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
AG_DS_ID	char(16)
HASH_KEY_HIGH	int
HASH_KEY_LOW	int
PRI_DS_ID	char(16)
SEC_DS_ID	char(16)

Index Name: **DD_ROUTING_PK**

Fields: AG_DS_ID
 HASH_KEY_LOW

Column Descriptions

The following are the descriptions of the DD_Routing table columns.

AG_DS_ID — Contains the Analytic Gateway data source ID.

HASH_KEY_HIGH — Contains the highest hash key value.

HASH_KEY_LOW — Contains the lowest hash key value.

PRI_DS_ID — Contains the primary data source ID.

SEC_DS_ID — Contains the secondary data source ID.

Detail_MarkSelection Table

The Detail_MarkSelection table is used by the Analysis and Review system. It stores transaction field value related to a specific action ID.

The columns in the Detail_MarkSelection table (DETAIL_MARKSELECTION) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
DD_MARKSELECTION_DATE	datetime
DD_PARTITION_DATE	date
GUID	varchar(36)
MD_TRAN_AMT1	money
ND_KEY_HASH	smallint
ND_MODIFIED	smallint
ND_SELECTED	smallint
PRM_USER_ID	int

Column Name	Data Type
RECORD_SOURCE_ID	smallint
SD_TIEBREAKER	varchar(75)

Index Name: **PK_DETAIL_MARKSELECTION**

Fields: GUID

 SD_TIEBREAKER

 ACTION_LEVEL_KEY

Column Descriptions

The following are the descriptions of the Detail_MarkSelection table columns.

ACTION_LEVEL_ID — The action level ID.

ACTION_LEVEL_KEY — The action level key.

DD_MARKSELECTION_DATE — The date when the transaction was updated for mark.

DD_PARTITION_DATE — The partition date.

GUID — Is used to uniquely identify a session.

MD_TRAN_AMT1 — The transaction amount 1.

ND_KEY_HASH — The transaction's key hash.

ND_MODIFIED — A flag that indicates that the transaction is modified.

ND_SELECTED — A flag that indicates that the transaction is selected.

PRM_USER_ID — The user ID of the user who updated the transaction for mark.

RECORD_SOURCE_ID — The transaction's Record Source ID.

SD_TIEBREAKER — The transaction's tiebreaker.

DE_Filter_Fields Table

The DE_Filter_Fields table is used by Data Extensivity tool and holds the names of the transaction fields (one per action level) against

which the Analytic Gateway should apply the filters in order to determine the corresponding portfolio for each transaction.

The columns in the DE_Filter_Fields table (DE_FILTER_FIELDS) are listed below with the data type.

Column Name	Data Type
ACCEPTABLE_FILTERS	varchar(4000)
ACTION_LEVEL_ID	int
CONFIGURATION_ID	integer
FIELD_NAME	varchar(50)
RECORD_SOURCE_ID	smallint

Column Descriptions

The following are the descriptions of the DE_Filter_Fields table columns.

ACCEPTABLE_FILTERS — A comma-separated list of field names. The field name stored in the FIELD_NAME field must be one of these field names.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

CONFIGURATION_ID — The configuration ID.

FIELD_NAME — The name of the field that is used to segregate the transactions into portfolios according to the filter ranges (see FilterLayout Table).

RECORD_SOURCE_ID — The unique identifier for the record source

External_Connection_Map Table

The External_Connection_Map table is used by the Analysis and Review system. It stores the external connection string. This table is populated by the PRM customer.

The columns in the External_Connection_Map table (EXTERNAL_CONNECTION_MAP) are listed below with the data type.

Column Name	Data Type
ACTION_TYPE_ID	int
LPORTFOLIOID	int
SEXTCCTN	varchar(50)

Column Name	Data Type
OPTIONS	varchar(250)
STATE	int

Index Name: **EXTERNAL_CONNECTION_MAP_PK**

Fields: LPORTFOLIOID
 ACTION_TYPE_ID
 STATE

Column Descriptions

The following are the descriptions of the External_Connection_Map table columns.

ACTION_TYPE_ID — Contains the action type. It is linked to the LTYPE column in the ActionsText table.

LPORTFOLIOID — The portfolio ID.

SEXTCTN — The external connection ID.

OPTIONS — This column is in JSON format and can hold multiple configurations. At the moment, it only can be used to specify if the rows that belong to a specific entry in EXTERNAL_CONNECTION_MAP table should send PII Data in clear instead of encrypted/hashed. This currently only applies to PAN.

STATE — Indicates the state of the action that is used to be sent to an external system. It should be used in the OEI views, where it is applicable and can be matched with the action state from the External_Message_Data table.

Default value: -1

External_Procedure Table

The External_Procedure table holds all PRM stored procedures that the Analytic Gateway needs to invoke.

The columns in the External_Procedure table (EXTERNAL_PROCEDURE) are listed below with the data type.

Column Name	Data Type
EXTERNAL_PROCEDURE_ID	smallint
EXTERNAL_PROCEDURE_TYPE_ID	smallint
PROCEDURE_DESCRIPTION	varchar(500)
PROCEDURE_NAME	varchar(30)
PURPOSE	int
RECORD_SOURCE_ID	int
SUBTYPE	int

Index Name: **EXTERNAL_PROCEDURE_IX1**

Fields: EXTERNAL_PROCEDURE_TYPE_ID

Index Name: **EXTERNAL_PROCEDURE_PK**

Fields: EXTERNAL_PROCEDURE_ID

Index Name: **UK_EXTERNAL_PROCEDURE**

Fields: PROCEDURE_NAME
 EXTERNAL_PROCEDURE_TYPE_ID
 RECORD_SOURCE_ID

Column Descriptions

The following are the descriptions of the External_Procedure table columns.

EXTERNAL_PROCEDURE_ID — The unique procedure identifier.

EXTERNAL_PROCEDURE_TYPE_ID — The procedure type ID (references a record in the EXTERNAL_PROCEDURE_TYPE table).

PROCEDURE_DESCRIPTION — The procedure description.

PROCEDURE_NAME — The procedure name.

PURPOSE — The procedure purpose ID (references a record in External_Procedure_Purpose table).

RECORD_SOURCE_ID — The identifier for the record source for which this external procedure is defined.

SUBTYPE — The procedure subtype identifier. Currently, only the feature calculation stored procedures are differentiated by this column. In this case, the scoring event identifier (see the EVENT_ID column in the Scoring_Event table) for which this procedure works.

External_Procedure_Purpose Table

The External_Procedure_Purpose table is part of the mechanism that configures the manner in which the Analytic Gateway determines the stored procedures to be called as part of a transaction flow. It holds all PRM stored procedure purposes.

The columns in the External_Procedure_Purpose table (EXTERNAL_PROCEDURE_PURPOSE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
EXT_PROC_PURPOSE	varchar(50)
EXT_PROC_PURPOSE_DESCRIPTION	nvarchar(256)
EXT_PROC_PURPOSE_ID	int

Index Name: **PK_EXT_PROC_PURPOSE**

Fields: EXT_PROC_PURPOSE_ID

Column Descriptions

The following are the descriptions of the External_Procedure_Purpose table columns.

EXT_PROC_PURPOSE — The name of the external procedure purpose.

EXT_PROC_PURPOSE_DESCRIPTION — The description of the external procedure purpose.

EXT_PROC_PURPOSE_ID — The identifier of the external procedure purpose.

External_Procedure_Type Table

The External_Procedure_Type table holds all PRM procedure types.

The columns in the External_Procedure_Type table (EXTERNAL_PROCEDURE_TYPE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
EXTERNAL_PROCEDURE_DESCRIPTION	varchar(500)
EXTERNAL_PROCEDURE_TYPE	varchar(50)
EXTERNAL_PROCEDURE_TYPE_ID	smallint

Index Name: **EXTERNAL_PROCEDURE_TYPE_PK**

Fields: EXTERNAL_PROCEDURE_TYPE_ID

Index Name: **EXTERNAL_PROCEDURE_TYPE_UK**

Fields: EXTERNAL_PROCEDURE_TYPE

Column Descriptions

The following are the descriptions of the External_Procedure_Type table columns.

EXTERNAL_PROCEDURE_DESCRIPTION — The procedure type description.

EXTERNAL_PROCEDURE_TYPE — The procedure type.

Valid values are:

NRT = Near real time

RT = Real time

RTU = Real-time update

EXTERNAL_PROCEDURE_TYPE_ID — The unique procedure type identifier.

Extrcnct_Service Table

The Extrcnct_Service table is used by the Online Extract Interface (OEI). It stores the configuration for communicating with external systems through BSI services. This table is populated by the PRM customer.

The columns in the Extrcnct_Service table (EXTRCNCT_SERVICE) are listed below with the data type.

Column Name	Data Type
ACTIONTYPE	int
ARGUMENT	varchar(256)
CALLTYPE	varchar(50)
ENDPOINT	varchar(50)
EXTRCNCTID	varchar(50)
OPERATION	varchar(256)
PORTFOLIO	int

Column Name	Data Type
RESPONSE	varchar(256)
SERVICENAME	varchar(256)

Column Descriptions

The following are the descriptions of the Extrcnct_Service table columns.

actiontype — Contains the ID of the action for which messages should be sent to the external system. The valid values are:

- 0 = Block
- 1 = LetterSent
- 2 = Call
- 3 = Watch
- 4 = Mark
- 5 = Ice
- 6 = Me
- 7 = Reminder
- 8 = Forward
- 9 = Close Account
- 10 = Open Action Level ID
- 11 = Alert
- 12 = Email
- 13 = HistoryButton
- 14 = POC Block
- 15 = Export
- 16 = Alert Delete
- 17 = Response Required Clear
- 18 = Response Required Confirm
- 19 = Print
- 20 = Linked Account
- 21 = Action Level Memo

- 22 = Alert Email
- 23 = Copy
- 24 = Next
- 25 = Expand Grid
- 26 = Open Forward
- 27 = Open Reminder
- 28 = Response Required
- 29 = Cross Reference
- 30 = Open Review from Compromise
- 31 = Open Review from Review Screen
- 32 = Open Compromise Alert
- 33 = Close Alert
- 34 = Close Forward
- 35 = Close Reminder
- 36 = Close Review from Compromise
- 37 = Close Review from Review Screen
- 38 = Close Compromise Alert
- 39 = Alert Review Timeout
- 40 = Forward Timeout
- 41 = Review Timeout
- 42 = Reminder Timeout
- 43 = Opened Review from Compromise Block
- 44 = Closed Review from Compromise Block
- 45 = Opened Compromise Block
- 46 = Closed Compromise Block

argument — Contains the operation's argument type. It is a request of the call, and it is a PIM object.

calltype — Column defines the type of the communication between OEI and the external system. The valid values are:

- Synchronous
- Asynchronous

ENDPOINT — Indicates the endpoint to which multiple external connections can be directed

(through BSI static registry config).

extrcnctid — Contains the name of the external connection defined in the EXTRCNCT table (AJI table), defined by the customer. It must match the SECTCCTN column in the External_Connection_Map table.

operation — Contains the name of the operation or method of the BSI interface that will be invoked for that action.

portfolio — Contains the portfolio ID for which messages should be sent to the external system.

response — Contains the operation's return type. It is the response of the call, and it is a PIM object.

servicename — Contains the name of the BSI Interface that will be used for that action.

Feature Table

The Feature table is used by the Analysis and Review system. It stores the feature information.

The columns in the Feature table (FEATURE) are listed below with the data type.

Column Name	Data Type
FEATURE_ID	int
FEATURE_LICENSE_NAME	nvarchar(50)
SOFT_DELETE_IND	bit

Index Name: **PK_FEATURE**

Fields: FEATURE_ID
 FEATURE_LICENSE_NAME

Column Descriptions

The following are the descriptions of the Feature table columns.

FEATURE_ID — A distinct numeric value used to uniquely

FEATURE_LICENSE_NAME — The feature's license name.

SOFT_DELETE_IND — The current delete status of the row.

Field_Action_Level Table

The Field_Action_Level table shows if the fields per action level have translations or not.

The columns in the Field_Action_Level table (FIELD_ACTION_LEVEL) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	numeric
FIELD_ID	numeric
TRANSLATABLE	numeric
TRANSLATION_AVAILABLE	numeric

Index Name: **PK_FIELD_ACTION_LEVEL**

Fields: ACTION_LEVEL_ID
 FIELD_ID

Column Descriptions

The following are the descriptions of the Field_Action_Level table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level

- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

FIELD_ID — A numeric ID for the field names.

TRANSLATABLE — Specifies if the field can be translated

TRANSLATION_AVAILABLE — Specifies if there is a translation available for the field

Filter_Fields Table

The Filter_Fields table holds the names of the transaction fields (one per action level) against which the Analytic Gateway should apply the filters in order to determine the corresponding portfolio for each transaction.

The columns in the Filter_Fields table (FILTER_FIELDS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACCEPTABLE_FILTERS	varchar(4000)
ACTION_LEVEL_ID	int
FIELD_NAME	varchar(50)
RECORD_SOURCE_ID	smallint

Index Name: **FILTER_FIELDS_PK**

Fields: ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the Filter_Fields table columns.

ACCEPTABLE_FILTERS — A comma-separated list of field names. The field name stored in the FIELD_NAME field must be one of these field names.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

FIELD_NAME — The name of the field that is used to segregate the transactions into portfolios according to the filter ranges (see FilterLayout Table).

RECORD_SOURCE_ID — The unique identifier for the record source

Flags Table

The Flags table is used by the Analysis and Review system. It contains a system mapping of IDs to assorted enumerations (that is, suspicious activity types).

The columns in the Flags table (FLAGS) are listed below with the data type.

Column Name	Data Type
EXTERNAL_MARK_REASON	nvarchar(200)
LID	int

Column Name	Data Type
NTYPE	smallint
SDESCRIPTION	int
SNAME	int

Index Name: **IDX_FLAGS_CLUSTER**

Fields: LID

Index Name: **IDX_FLAGS_TYPENAME**

Fields: NTYPE

SNAME

Column Descriptions

The following are the descriptions of the Flags table columns.

EXTERNAL_MARK_REASON — Contains the mark reason.

LID — A unique ID for each flag.

The following IDs and their descriptions are used for the UAN action level:

- 1 = Tax Evasion
- 2 = Structuring
- 3 = General ML
- 4 = BSA Violation
- 5 = Unexplainable Activity
- 6 = Terrorist Financing
- 7 = Correspondent Banking
- 8 = Prohibited Name List
- 9 = Other

NTYPE — The type of flag.

Valid values are:

- 0 = No flag
- 1 = Fraud type
- 2 = Analyst action
- 3 = Identify by

SDESCRIPTION — The numeric identifier for the localized name of the description of the flag. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

SNAME — The numeric identifier for the localized name of the flag name. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

Flags_Action_Level Table

The Flags_Action_Level table is used by the Analysis and Review system. It identifies the specific flag that is associated with an action level.

The columns in the Flags_Action_Level table (FLAGS_ACTION_LEVEL) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
FLAG_ID	int
NORDER	smallint

Index Name: **FLAGS_ACTION_LEVEL_PK**

Fields: FLAG_ID

 ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the Flags_Action_Level table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

FLAG_ID — A value from the LID column in the Flags table.

NORDER — Allows the institution to determine the ordering of values displayed in various selectable lists throughout the PRM system. This order can be configured by the institution using the Flags table editor.

Multi_Team_Access Table

The Multi_Team_Access table is used by the Analysis and Review system. It contains user information for configuring permissible team.

MultiTeam access is only allowed for users that need to change and manage other users and users that need to run reports across different teams. Users are not allowed to access alerts across teams.

The columns in the Multi_Team_Access table (MULTI_TEAM_ACCESS) are listed below with the data type.

Column Name	Data Type
TEAMID	int

Column Name	Data Type
USERID	int

Index Name: **MULTI_TEAM_ACCESS_PK**

Fields: USERID

 TEAMID

Column Descriptions

The following are the descriptions of the Multi_Team_Access table columns.

TEAMID — A unique identifier of the team.

USERID — A unique identifier of the user.

Notification_Actions Table

The Notification_Actions table is used by the Analysis and Review system. It stores the notifications related to a specific action.

The columns in the Notification_Actions table (NOTIFICATION_ACTIONS) are listed below with the data type.

Column Name	Data Type
LDELAY	int
LSTATE	int
LTYPE	int
MFUNDSATRISK	money
SDESCRIPTION	varchar(100)

Column Name	Data Type
SIDENTIFIEDBY	varchar(50)
SMARKTYPE	varchar(50)
SNAME	varchar(50)
SREASONCODE	varchar(50)
SRESPONSEREQCODE	varchar(50)
STRACKINGID	varchar(50)

Column Descriptions

The following are the descriptions of the Notification_Actions table columns.

LDELAY — Delay for the Notification.

LSTATE — The Notification state.

LTYPE — The Notification type.

MFUNDSATRISK — The funds at risk value for a mark action

SDESCRIPTION — The Notification description.

SIDENTIFIEDBY — The Identified By Code as it is defined in column EXTERNAL_MARK_REASON in table FLAGS.

SMARKTYPE — The Mark Reason Code as it is defined in column EXTERNAL_MARK_REASON in table FLAGS.

SNAME — The status provided by a 3rd party.

SREASONCODE — The notification status in PRM.

SRESPONSEREQCODE — The response required code as it is defined in column RESPONSECODE in table ADDRESPONSECODES

STRACKINGID — The tracking ID value for a mark action

Notification_Additional_Fields Table

The Notification_Additional_Fields table is used by the Analysis and Review system. It stores the column name related to a specific action level ID.

The columns in the Notification_Additional_Fields table (NOTIFICATION_ADDITIONAL_FIELDS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
COLUMN_NAME	varchar(30)

Index Name: **PK_NOTIFICATION_ADDITIONAL_FIELDS**

Fields: ACTION_LEVEL_ID
 COLUMN_NAME

Column Descriptions

The following are the descriptions of the Notification_Additional_Fields table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action.

COLUMN_NAME — A distinct value used to uniquely identify a column.

Notification_NewTran_Filter Table

The Notification_NewTran_Filter table is used by the Analysis and Review system. It stores the transaction field value related to a specific action level ID.

The columns in the Notification_NewTran_Filter table (NOTIFICATION_NEWTRAN_FILTER) are listed below with the data type.

Column Name	Data Type
TRAN_FIELD_NAME	varchar(30)
TRAN_FIELD_VALUE	varchar(50)

Column Descriptions

The following are the descriptions of the Notification_NewTran_Filter table columns.

TRAN_FIELD_NAME — The field name.

TRAN_FIELD_VALUE — The field value.

NOTIFICATION_REQUEST_ADDTL Table

The Notification_Request_Addtl table is used by the Analysis and Review system. This table can be used in the notification API where one or more custom fields can be inserted dynamically to the event notification request object (RiskPartnerEventNotifyRq_Rev1_Type) as "additional attributes". When the configuration parameter in table applcnfg "risk.oei.NotificationRequestMoreAttributes.enabled" is set to true, this table is queried and additional fields and values are added to a notification request based on event types associated with the request.

The columns in the NOTIFICATION_REQUEST_ADDTL table (NOTIFICATION_REQUEST_ADDTL) are listed below with the data type.

Column Name	Data Type
ACTION_EVENT	nvarchar(50)
ACTION_LEVEL_ID	int
ATTRIBUTE_NAME	nvarchar(50)
ATTRIBUTE_TYPE	nvarchar(10)
ATTRIBUTE_VALUE	nvarchar(50)

Column Descriptions

The following are the descriptions of the NOTIFICATION_REQUEST_ADDTL table columns.

ACTION_EVENT — The name of the event associated with the notification request.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ATTRIBUTE_NAME — The name of the field to be dynamically added to the notification service request.

ATTRIBUTE_TYPE — The name of the dynamic field which is understood by the receiver of the notification service request.

ATTRIBUTE_VALUE — The value of the dynamic field.

NOTIFICATION_STATUS Table

The Notification_Status table is used by the Analysis and Review system. It stores the mapping of a status provided by a 3rd party to the status in PRM.

The columns in the NOTIFICATION_STATUS table (NOTIFICATION_STATUS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
SCODE	varchar(50)
SNAME	varchar(50)

Column Descriptions

The following are the descriptions of the NOTIFICATION_STATUS table columns.

SCODE — The notification status in PRM. Valid values are: Success or Failure

SNAME — The notification status provided by a 3rd party.

Notification_Subscriptions Table

The Notification_Subscriptions table is used by the Analysis and Review system. It stores the relationships between action level keys and action level IDs.

The columns in the Notification_Subscriptions table (NOTIFICATION_SUBSCRIPTIONS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(70)

Index Name: **PK_NOTIFICATION_SUBSCRIPTIONS**

Fields: ACTION_LEVEL_KEY
 ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the Notification_Subscriptions table columns.

ACTION_LEVEL_ID — The action level ID.

ACTION_LEVEL_KEY — The action level key.

Notification_Types Table

The Notification_Types table is used by the Analysis and Review system. It stores information for notify type.

The columns in the Notification_Types table (NOTIFICATION_TYPES) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
NOTIFYTYPE_MEMO	int
SDESCRIPTION	int
SNOTIFYTYPE	nvarchar(50)

Index Name: **PK_NOTIFICATION_TYPES**

Fields: SNOTIFYTYPE

Column Descriptions

The following are the descriptions of the Notification_Types table columns.

NOTIFYTYPE_MEMO — The memo value for the notify type in L10N.

SDESCRIPTION — The description of the notify type in L10N.

SNOTIFYTYPE — The primary key. It identifies a unique notify type.

NRT_Group_Link Table

The NRT_Group_Link table contains information related to action levels associated with the ShortWindow_Group table.

The columns in the NRT_Group_Link table (NRT_GROUP_LINK) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
GROUP_ID	int

Index Name: **PK_NRT_GROUP_LINK**

Fields: ACTION_LEVEL_ID
 GROUP_ID

Column Descriptions

The following are the descriptions of the NRT_Group_Link table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level

- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

GROUP_ID — The unique identifier of the group.

PrinterAreas Table

The PrinterAreas table holds the printer areas defined in the system.

The columns in the PrinterAreas table (PRINTERAREAS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
L10N_AREA_ID	int
LID	int

Index Name: PRINTERAREAS_PK

Fields: LID

Column Descriptions

The following are the descriptions of the PrinterAreas table columns.

L10N_AREA_ID — The localized name of the printer area.

LID — The unique printer area ID.

PrinterPortfolios Table

The PrinterPortfolios table holds the association between printer locations and portfolios.

The columns in the PrinterPortfolios table (PRINTERPORTFOLIOS) are listed below with the data type.

Column Name	Data Type
PORTFOLIO_ID	int
PRINTER_ID	int

Index Name: **PRINTERPORTFOLIOS_PK**

Fields: PRINTER_ID
 PORTFOLIO_ID

Column Descriptions

The following are the descriptions of the PrinterPortfolios table columns.

PORTFOLIO_ID — A portfolio ID.

PRINTER_ID — The printer location ID.

Printers Table

The Printers table holds all the printer locations defined in the system.

The columns in the Printers table (PRINTERS) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
AREA_ID	int
CROSS_ACTION_LEVEL_ID	int
LID	int
LOCATION	nvarchar(400)

Index Name: **PRINTERS_PK**

Fields: LID

Index Name: **PRINTERS_UNIQUE**

Fields: LOCATION

 AREA_ID

 ACTION_LEVEL_ID

 CROSS_ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the Printers table columns.

ACTION_LEVEL_ID — The ID of the action level associated with this printer location.

AREA_ID — The ID of the printer area associated with this printer location.

CROSS_ACTION_LEVEL_ID — The identifier of the Cross Action Level for which this printer is defined (if this is the case) or null if the printer is not specific to a Cross Action Level.

LID — The unique printer location ID.

LOCATION — The printer location.

PRMJNLPCfg Table

The PRMJNLPCfg table is used to configure the JNLP information used by the user interface to connect to the database.

The columns in the PRMJNLPCfg table (PRMJNLPCONFIG) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
SJNLPCONFIGVERSIONNO	varchar(20)

Column Name	Data Type
SPROPERTY	varchar(100)
SVALUE	varchar(150)

Column Descriptions

The following are the descriptions of the PRMJNLPCfg table columns.

SJNLPCONFIGVERSIONNO — The version of the JNLP configuration.

SPROPERTY — The name of the JNLP property.

SVALUE — The value of the configured JNLP property.

PRM_Batch Table

The PRM_Batch table is used by the Analysis and Review system. It identifies mark type, identified by, and tracking information with an action level.

The columns in the PRM_Batch table (PRM_BATCH) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
BATCH_JOB_ID	smallint
BATCH_POC_UNIQUE_ID	varchar(36)
BATCH_STATE	smallint

Column Name	Data Type
DD_PARTITION_DATE	date
LAST_UPDATE_DATETIME	datetime
ND_KEY_HASH	smallint
RECORD_SOURCE_ID	smallint
SD_TIEBREAKER	varchar(75)

Index Name: PK_PRM_BATCH

Fields: DD_PARTITION_DATE
ND_KEY_HASH
RECORD_SOURCE_ID
SD_TIEBREAKER
ACTION_LEVEL_ID
BATCH_STATE

Column Descriptions

The following are the descriptions of the PRM_Batch table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — An action level key value that links to the Detail table. The value in the ACTION_LEVEL_ID column of this table identifies a row in the Action_Level table and is used to determine the type of value that is stored in this column. This column may contain an SD_PAN, SD_RET_L_ID, SD_UAN, SD_TERM_ID, SD_EMPLOYEE_ID, SD_USER_ACCT_ID, or SD_PRI_ACCT_NUM. For example, if the value in the ACTION_LEVEL_ID column is 1 (Card), this column will link to an SD_PAN in the Detail table.

BATCH_JOB_ID — The identifier to locate the record in the PRM_Batch_Job table.

BATCH_POC_UNIQUE_ID — The unique identifier required by the Point of Compromise Alert Generation process.

BATCH_STATE — The state of the record.

Valid values are:

- 0 = Not processed
- 1 = Currently processing
- 2 = Processing completed

DD_PARTITION_DATE — The value that is associated with the transaction in the Detail or FraudDetail table.

LAST_UPDATE_DATETIME — The date and time for each change made. The default on insert is the current date and time.

ND_KEY_HASH — The value that is associated with the transaction in the Detail or FraudDetail table.

RECORD_SOURCE_ID — The value that is associated with the transaction in the Detail or FraudDetail table.

SD_TIEBREAKER — The value that is associated with the transaction in the Detail or FraudDetail table.

PRM_Batch_History Table

The PRM_Batch_History table is used by the Analysis and Review system. It stores data relevant to batch jobs that have been completed successfully. Upon successful completion, records are copied to this table from the PRM_Batch table.

The columns in the PRM_Batch_History table (PRM_BATCH_HISTORY) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
BATCH_JOB_ID	smallint
BATCH_POC_UNIQUE_ID	varchar(36)
BATCH_STATE	smallint
DD_PARTITION_DATE	date
LAST_UPDATE_DATETIME	datetime
ND_KEY_HASH	smallint
RECORD_SOURCE_ID	smallint
SD_TIEBREAKER	varchar(75)

Index Name: **PRM_BATCH_HISTORY_IX1**

Fields: LAST_UPDATE_DATETIME

Index Name: **PK_PRM_BATCH_HISTORY**

Fields: DD_PARTITION_DATE

 ND_KEY_HASH

 RECORD_SOURCE_ID

SD_TIEBREAKER
ACTION_LEVEL_ID
BATCH_STATE
LAST_UPDATE_DATETIME

Column Descriptions

The following are the descriptions of the PRM_Batch_History table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — An action level key value that links to the Detail table. The value in the ACTION_LEVEL_ID column of this table identifies a row in the Action_Level table and is used to determine the type of value that is stored in this column. This column may contain an SD_PAN, SD_RETL_ID, SD_UAN, SD_TERM_ID, SD_EMPLOYEE_ID, SD_USER_ACCT_ID, or SD_PRI_ACCT_NUM. For example, if the value in the ACTION_LEVEL_ID column is 1 (Card), this column will link to an SD_PAN in the Detail table.

BATCH_JOB_ID — The identifier to locate the record in the PRM_Batch_Job table.

BATCH_POC_UNIQUE_ID — The unique identifier required by the Point of Compromise Alert Generation process.

BATCH_STATE — The state of the record.

Valid values are:

- 0 = Not processed
- 1 = Currently processing

2 = Processing completed

DD_PARTITION_DATE — The value that is associated with the transaction in the Detail or FraudDetail tables

LAST_UPDATE_DATETIME — The date and time for each change made. The default on insert is the current date and time

ND_KEY_HASH — The value that is associated with the transaction in the Detail or FraudDetail table.

RECORD_SOURCE_ID — The value that is associated with the transaction in the Detail or FraudDetail table.

SD_TIEBREAKER — The value that is associated with the transaction in the Detail or FraudDetail table.

PRM_Batch_Job Table

The PRM_Batch_Job table is used by the Analysis and Review system. It stores data related to valid batch processes or jobs.

The columns in the PRM_Batch_Job table (PRM_BATCH_JOB) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
BATCH_JOB_DESCRIPTION	nvarchar(500)
BATCH_JOB_ID	smallint
BATCH_JOB_NAME	nvarchar(30)

Index Name: BATCH_JOB_NAME_UI

Fields: BATCH_JOB_NAME

Index Name: PK_PRM_BATCH_JOB

Fields: BATCH_JOB_ID

Column Descriptions

The following are the descriptions of the PRM_Batch_Job table columns.

BATCH_JOB_DESCRIPTION — A description of the batch job.

BATCH_JOB_ID — The identifier to locate the record in the PRM Batch table.

BATCH_JOB_NAME — The name of the batch job.

PRM_Install Table

The PRM_Install table stores information regarding the NRT PRM installation.

The columns in the PRM_Install table (PRM_INSTALL) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
INSTALL_END_DT	datetime27
INSTALL_START_DT	datetime27
INSTALL_STATUS	varchar(1)
PRM_INSTALL_ID	int
PRM_VERSION_FROM	varchar(200)
PRM_VERSION_TO	varchar(200)

Index Name: PK_PRM_INSTALL

Fields: PRM_INSTALL_ID

Column Descriptions

The following are the descriptions of the PRM_Install table columns.

INSTALL_END_DT — The PRM install end date.

INSTALL_START_DT — The PRM install start date.

INSTALL_STATUS — The PRM install status.

Valid values are:

R = Running

E = Error

T = Terminated

PRM_INSTALL_ID — The unique PRM install ID.

PRM_VERSION_FROM — The PRM starting version for the install. When a fresh PRM install is performed the value is NULL.

PRM_VERSION_TO — The targeted PRM version by the install.

PRM_Install_Log Table

The PRM_Install_log table stores logging information regarding the NRT PRM installation.

The columns in the PRM_Install_Log table (PRM_INSTALL_LOG) are listed below with the data type.

Column Name	Data Type
LOG_TEXT	nvarchar(2000)
LOG_TS	datetime27

Column Name	Data Type
LOG_TYPE	varchar(1)
PRM_INSTALL_ID	int
PRM_INSTALL_LOG_ID	int
SCRIPT_NAME	varchar(200)
STEP_DESC	varchar(200)

Index Name: **PK_PRM_INSTALL_LOG**

Fields: PRM_INSTALL_LOG_ID

Column Descriptions

The following are the descriptions of the PRM_Install_Log table columns.

LOG_TEXT — The text saved during the PRM install.

LOG_TS — The PRM install Log start date.

LOG_TYPE — The PRM install Log type.

Valid values are:

I = Terminated successfully

W = Skipped

PRM_INSTALL_ID — The unique PRM install ID corresponding to the PRM_Install table.

PRM_INSTALL_LOG_ID — The unique RT PRM install Log ID.

SCRIPT_NAME — The script which contains the log text.

STEP_DESC — The description for each log step.

PRM_Permission Table

The PRM_Permission table is used by the Analysis and Review system. It contains the PRM permission information for a group to determine if further processing should be allowed.

The columns in the PRM_Permission table (PRM_PERMISSION) are listed below with the data type.

Column Name	Data Type
ASGN_BY_DFLT	int
DESCRIPTION	int
DISPLAY_NAME	int
PERMISSION_GRP_ID	smallint
PERMISSION_ID	int

Index Name: IX_PERMISSION_GRP

Fields: PERMISSION_GRP_ID

Index Name: PRM_PERMISSION_PK

Fields: PERMISSION_ID

Index Name: PRM_PERMISSION_UK

Fields: DISPLAY_NAME

Column Descriptions

The following are the descriptions of the PRM_Permission table columns.

ASGN_BY_DFLT — Indicates whether the permission should be assigned to all roles when they are first created. This is used for items such as exit and help that should always be available.

DESCRIPTION — The resource key to a detailed description of how the permission will be used.

DISPLAY_NAME — The resource key to the localized permission name to be displayed in permission lists.

PERMISSION_GRP_ID — The unique identifier of permission group.

PERMISSION_ID — The unique identifier of a permission.

PRM_Permission_Grp Table

The PRM_Permission_Grp table is used by the Analysis and Review system. It contains the PRM permission information for a group.

The columns in the PRM_Permission_Grp table (PRM_PERMISSION_GRP) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
AR_PERMISSION_GRP	int
DESCRIPTION	int
DISPLAY_NAME	int
PERMISSION_GRP_ID	smallint

Index Name: **PRM_PERMISSION_GRP_PK**

Fields: PERMISSION_GRP_ID

Index Name: **PRM_PERMISSION_GRP_UK**

Fields: DISPLAY_NAME

Column Descriptions

The following are the descriptions of the PRM_Permission_Grp table columns.

AR_PERMISSION_GRP — Indicates if the permission group is used by AR or not.

Valid values are:

- 0 = Permission group is not AR related
- 1 = Permission group is AR related

DESCRIPTION — The resource key to a detailed description of how the permission will be used.

DISPLAY_NAME — The resource key to the localized permission name to be displayed in permission lists.

PERMISSION_GRP_ID — The unique identifier of permission group.

Profile_Alerted_Rule Table

The Profile_Alerted_Rule table is used by the Analysis and Review system. It identifies alert-related information such as color, score alerted, and iced, and rule alerted for a specific transaction per a specific date.

The columns in the Profile_Alerted_Rule table (PROFILE_ALERTED_RULE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
ALERT_COLOR	char(6)
ALERT_DATE	datetime
APPLICABLE_CATEGORIES	varchar(2000)
APPLICABLE_QUES	varchar(2000)

Column Name	Data Type
ND_MANUAL_ACT_STAT	smallint
RETRIEVED_FROM_CATEGORY	varchar(2000)
RETRIEVED_FROM_QUE	varchar(2000)
SD_RULES	varchar(1000)

Index Name: **PROFILE_ALERTED_RULE_PK**

Fields: ACTION_LEVEL_ID
 ACTION_LEVEL_KEY
 ALERT_DATE

Column Descriptions

The following are the descriptions of the Profile_Alerted_Rule table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — An action level key value that links to the Detail table. The value in the ACTION_LEVEL_ID column of this table identifies a row in the Action_Level table and is used to determine the type of value that is stored in this column. This column may contain an SD_PAN, SD_RETL_ID, SD_UAN, SD_TERM_ID, SD_EMPLOYEE_ID, SD_USER_ACCT_ID, or SD_PRI_ACCT_NUM. For example, if the value in the ACTION_LEVEL_ID column is 1 (Card), this column will link to an SD_PAN in the Detail table.

ALERT_COLOR — The name of the color in which alerts will be processed.

ALERT_DATE — The date and time of the alert.

APPLICABLE_CATEGORIES — The names of the categories on which the alerts were placed and that are assigned to the user.

APPLICABLE_QUEUES — The names of the queues on which the alerts were placed and that are assigned to the user. It includes all queues other than the system Catch-All queue.

ND_MANUAL_ACT_STAT — Contains the state of the manual action associated with a transaction.

Valid values are:

- 1 = No action (Default)
- 0 = Clear
- 1 = Confirm
- 2 = Manual rule alerted

RETRIEVED_FROM_CATEGORY — Set either to NULL to indicate that the alert generated for a given transaction was never retrieved from a category, or to the values (that is, the ALERT_CATEGORY.ALERT_CATEGORY_IDS) that specify the categories from which the alert was retrieved.

RETRIEVED_FROM_QUE — Set either to NULL to indicate that the alert generated for a given transaction was never retrieved from a queue, or to the values (that is, the RQPORTASSIGN.LIDS) that specify the queues from which the alert was retrieved.

SD_RULES — The numeric value of the rules that were evaluated to true at the time the transaction was evaluated.

Profile_To_RT_Batch Table

The Profile_To_RT_Batch table is used to coordinate the migration of batches from the NRT

database to the RT database. It permits multiple batches to insert data into temporary tables when more Profile calculation processes are run.

The columns in the Profile_To_RT_Batch table (PROFILE_TO_RT_BATCH) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
BATCH_ID	int
NUM_ROWS	bigint
PROFILE_CATEGORY	varchar(1)
PROFILE_DATE	date
STATUS	varchar(1)

Column Descriptions

The following are the descriptions of the Profile_To_RT_Batch table columns.

BATCH_ID — The table identifier. It identifies a complete set of data in the temporary tables.

NUM_ROWS — The number of rows to be moved from NRT to RT.

PROFILE_CATEGORY — Indicates whether the set of data is 31 DAYS or 31 DAYS_PEER.

PROFILE_DATE — The DT_DATE from the Profile table for this set of data.

STATUS — A value indicating the status of the migration.

Valid values are:

I = Initial status. Set by the profile job when it copies the batch of records from the NRT Profile tables.

C = To be copied. Set by the pp_profile_to_rt_init procedure, which marks batches for copy/

deletion.

- X = To be deleted. Marked by the pp_profile_to_rt_init procedure because the batch is obsolete or marked by the final RT merging procedure because the batch was successfully migrated and records can be deleted now.

Queue_Link Table

The Queue_Link table contains information for available queue types within the PRM system.

The columns in the Queue_Link table (QUEUE_LINK) are listed below with the data type.

Column Name	Data Type
QUEUE_DESCRIPTION	int
QUEUE_ID	int

Index Name: **PK_QUEUE_LINK**

Fields: QUEUE_ID

 QUEUE_DESCRIPTION

Column Descriptions

The following are the descriptions of the Queue_Link table columns.

QUEUE_DESCRIPTION — The description of the queue.

QUEUE_ID — The unique identifier for the queue.

Record_Source Table

The Record_Source table contains information related to the record sources available within the PRM system.

The columns in the Record_Source table (RECORD_SOURCE) are listed below with the data type.

Column Name	Data Type
LAST_UPDATE_DATETIME	datetime
MESSAGE_TYPE	char(1)
RECORD_SOURCE_DESCRIPTION	varchar(500)
RECORD_SOURCE_FORMAT_CODE	varchar(10)
RECORD_SOURCE_ID	smallint
RECORD_SOURCE_NAME	varchar(50)
SOFT_DELETE_IND	bit
SYSTEM_DEFINED_IND	bit

Index Name: **PK_RECORD_SOURCE**

Fields: RECORD_SOURCE_ID

Column Descriptions

The following are the descriptions of the Record_Source table columns.

LAST_UPDATE_DATETIME — The last time the record source was updated.

MESSAGE_TYPE — The message type.

Valid values are:

- 1 = demographic only
- 2 = transaction only
- 3 = both

RECORD_SOURCE_DESCRIPTION — The description of the record source.

RECORD_SOURCE_FORMAT_CODE — The format of the record source.

Valid values are:

XF = XML format

IF = Interface format

RECORD_SOURCE_ID — The identifier of the record source.

RECORD_SOURCE_NAME — The name of the record source.

SOFT_DELETE_IND — The current delete status of the row.

SYSTEM_DEFINED_IND — Indicates that the row was added as one of the default PRM Action Levels.

Record_Source_Column_Mapping Table

The Record_Source_Column_Mapping table contains a mapping between, on one side, all record sources' attribute names and data types and on the other side, the table and column names and SQL data types on which the attributes are mapped. This table is used by both the PRM GUI and the Analytic Gateway. The PRM GUI uses it to determine which of the feature calculation stored procedures' parameters need to be mapped to each of the record sources. The Analytic Gateway uses it to determine how to map the record source attributes to column names within the parameter setup for the JavaScript composite field logic.

The columns in the Record_Source_Column_Mapping table (RECORD_SOURCE_COLUMN_MAPPING) are listed below with the data type.

Column Name	Data Type
APPLICATION_DATA_TYPE_ID	smallint
ATTRIBUTE_NAME	varchar(50)
COLUMN_NAME	varchar(30)

Column Name	Data Type
RECORD_SOURCE_ID	smallint
SQL_DATA_SIZE	smallint
SQL_DATA_TYPE	varchar(30)
TABLE_NAME	varchar(30)

Index Name: **PK_RECORD_SOURCE_COLUMN_MAPP**

Fields: RECORD_SOURCE_ID
 ATTRIBUTE_NAME
 TABLE_NAME
 COLUMN_NAME

Column Descriptions

The following are the descriptions of the Record_Source_Column_Mapping table columns.

APPLICATION_DATA_TYPE_ID — The Analytic Gateway’s application data type ID of the record source attribute. Foreign key in Application_Data_Type (APPLICATION_DATA_TYPE_ID).

ATTRIBUTE_NAME — The name of an attribute from the record source. Foreign key in Record_Source_Field (FIELD_NAME).

COLUMN_NAME — The name of the table column to which the record source attribute is mapped within an entry procedure.

RECORD_SOURCE_ID — The identifier of the record source. Foreign key in Record_Source_Field (RECORD_SOURCE_ID).

SQL_DATA_SIZE — The SQL data size of the table column to which the record source attribute is mapped within an entry procedure. It is only used for variable length SQL data types, such as the character types.

SQL_DATA_TYPE — The SQL data type of the table column to which the record source attribute is mapped within an entry procedure.

TABLE_NAME — The name of the table to which the record source attribute is mapped within an entry procedure.

Record_Source_Field Table

The Record_Source_Field table holds the names of the transaction fields for each record source.

Note: The following FIELD_NAME values can be configured manually in the Record_Source_Field table: LoadAnyway, LoadDuplicate, MFUpdate, SelectiveUpdate, and WindowPeriod. These FIELD_NAME values are described below.

- When the FIELD_NAME field is set to 'LoadAnyway', the value in the DEFAULT_VALUE field determines whether an error will be generated if the transaction being processed does not fall within at least one portfolio of the record source's assigned action levels. If the DEFAULT_VALUE field is set to 0, an error is generated. If the DEFAULT_VALUE field is set to 1, no error is generated.
- When the FIELD_NAME field is set to 'LoadDuplicate', the value in the DEFAULT_VALUE field determines how Analytic Gateway will handle duplicate transactions. If the DEFAULT_VALUE field is set to 0, Analytic Gateway will not load the duplicate transactions, and it will generate an error when a duplicate transaction is encountered. If the DEFAULT_VALUE field is set to 1, duplicate transactions are processed successfully.
- When the FIELD_NAME field is set to 'MFUpdate', the value in the DEFAULT_VALUE field determines whether the demographic data will be updated only if the value of the DMFDateTime field in the current transaction is newer than the value stored in the corresponding Master table. If the DEFAULT_VALUE field is set to 0, the demographic data will be updated only if the value of the DMFDateTime field in the current transaction is newer than the value stored in the corresponding Master table. If the DEFAULT_VALUE field is set to 1, the demographic data will always be updated, regardless of the value in the DMFDateTime field in the current transaction. MFUpdate is used only for IF record sources.
- When the FIELD_NAME field is set to 'SelectiveUpdate', the value in the DEFAULT_VALUE field determines whether a demographic field value will be updated when its value in the current transaction is NULL. If the DEFAULT_VALUE field is set to 0, a demographic field value will be not updated if its value in the current transaction is NULL. If the DEFAULT_VALUE field is set to 1, a demographic field value will be always be updated, regardless of whether its new value will be NULL. SelectiveUpdate is used only for IF record sources
- When the FIELD_NAME field is set to 'WindowPeriod', the value in the DEFAULT_VALUE field determines whether the current time is compared to the transaction date and an error is generated if the difference exceeds the number of days specified in the DEFAULT_VALUE field. If the DEFAULT_VALUE field is set to 0, Analytic Gateway does not compare the current time to the transaction date. If the DEFAULT_VALUE field contains a positive integer, Analytic Gateway compares the current time to the transaction date, and if the difference is greater than the value in the DEFAULT_VALUE field, an error is generated.

To manually configure the FIELD_NAME values described above, you must execute a statement similar to this one:

```
update RECORD_SOURCE_FIELD set DEFAULT_VALUE=1 where RECORD_SOURCE_ID=2 and  
FIELD_NAME='LoadDuplicate'
```

In the example statement, LoadDuplicate is set to 1 (duplicate transactions are processed successfully) for record source ERIF (the record source ID for ERIF is 2).

The columns in the Record_Source_Field table (RECORD_SOURCE_FIELD) are listed below with the data type.

Column Name	Data Type
ACCEPTABLE_VALUES_TEXT	varchar(4000)
DEFAULT_VALUE	varchar(50)
ENABLE_FAILSAFE_VALUE	smallint
FAILSAFE_VALUE	varchar(255)
FIELD_DESCRIPTION	varchar(500)
FIELD_NAME	varchar(50)
RECORD_SOURCE_ID	smallint

Index Name: **RECORD_SOURCE_FIELD_PK**

Fields: RECORD_SOURCE_ID
 FIELD_NAME

Column Descriptions

The following are the descriptions of the Record_Source_Field table columns.

ACCEPTABLE_VALUES_TEXT — The acceptable values for this field. It is used to validate the transaction data.

Possible values are:

- A single value, for example: '0220'

- A range, for example: '0-27'
- Any comma-separated combination of the above, for example: '0-27,51'

DEFAULT_VALUE — The default value to be used in case the field is not present in the transaction.

ENABLE_FAILSAFE_VALUE — Indicates whether or not Analytic Gateway should try to use a default in case the transaction field contains a value which cannot be converted to the data type required by the entry procedure for this particular field.

Valid values are:

- 0 = Analytic Gateway will not try to use the default. Instead, it will treat the transaction as erroneous and follow its usual error handling flow.
- 1 = Analytic Gateway will attempt to use the value stored in the FAILSAFE_VALUE field instead of the value stored in the transaction field and processing will continue.

FAILSAFE_VALUE — The value to be used by Analytic Gateway instead of the value present in the transaction field in case it cannot be converted to the datatype required by the entry procedure for this particular field. The value in this column will be ignored if ENABLE_FAILSAFE_VALUE is set to 0.

FIELD_DESCRIPTION — The field description.

FIELD_NAME — The name of the transaction field.

RECORD_SOURCE_ID — The record source unique identifier (references a record in the RECORD_SOURCE table).

Record_Source_Mapping Table

The Record_Source_Mapping table holds a mapping between the fields of the transaction and the parameters of the stored procedures for each record source.

The columns in the Record_Source_Mapping table (RECORD_SOURCE_MAPPING) are listed below with the data type.

Column Name	Data Type
APPLICATION_DATA_TYPE_ID	smallint
EXTERNAL_PROCEDURE_ID	smallint
FIELD_NAME	varchar(50)
PARAMETER_MODE	char(1)
PARAMETER_POSITION	smallint
RECORD_SOURCE_ID	smallint

Index Name: **RECORD_SOURCE_MAPPING_IX1**

Fields: APPLICATION_DATA_TYPE_ID

Index Name: **RECORD_SOURCE_MAPPING_IX2**

Fields: RECORD_SOURCE_ID

FIELD_NAME

Index Name: **RECORD_SOURCE_MAPPING_PK**

Fields: EXTERNAL_PROCEDURE_ID

PARAMETER_POSITION

Column Descriptions

The following are the descriptions of the Record_Source_Mapping table columns.

APPLICATION_DATA_TYPE_ID — The stored procedure parameter data type (references a record in the APPLICATION_DATA_TYPE table).

EXTERNAL_PROCEDURE_ID — The external procedure unique identifier (references a record in the EXTERNAL_PROCEDURE table).

FIELD_NAME — The name of the transaction field (references a record in the RECORD_SOURCE_FIELD table).

PARAMETER_MODE — Designates an in/out parameter.

Valid values are:

I = In

O = Out

PARAMETER_POSITION — The 1-based position in the stored procedure's list of formal parameters. Input and output parameters are numbered separately, that is, there will be an input parameter with a PARAMETER_POSITION of 1 and also an output parameter with a PARAMETER_POSITION of 1.

RECORD_SOURCE_ID — The record source unique identifier (references a record in the RECORD_SOURCE table).

Record_Source_Routing Table

The Record_Source_Routing table identifies which transactions are to be sent to the PRM Scoring Engine (PSE) or to the Universal Scoring Engine (USE) when the Analytic Gateway runs in certain analysis modes, based on their record source ID's.

The columns in the Record_Source_Routing table (RECORD_SOURCE_ROUTING) are listed below with the data type.

Column Name	Data Type
ANALYSIS_MODE	varchar(50)
RECORD_SOURCE_ID	smallint
ROUTING_ENABLED	smallint

Index Name: **RECORD_SOURCE_ROUTING_PK**

Fields: RECORD_SOURCE_ID
ANALYSIS_MODE

Column Descriptions

The following are the descriptions of the Record_Source_Routing table columns.

ANALYSIS_MODE — The Analytic Gateway's current analysis mode as configured in the AJI table APPLCNFG under the 'risk.gateway.analysis.mode' key.

RECORD_SOURCE_ID — The record source unique identifier (references a record in the RECORD_SOURCE table).

ROUTING_ENABLED — Indicates whether transactions from this record source will be sent to a scoring engine.

Valid values are:

0 = Transactions from this record source will not be sent to PSE or USE.

1 = Transactions from this record source will be sent to PSE or USE.

RQAggregateTypes Table

The RQAggregateTypes table defines the datatypes that are available in the drop-down combination box when defining and aggregate rule.

Note: This table should only be modified by ACI Worldwide, Inc. personnel.

The columns in the RQAggregateTypes table (RQAGGREGATETYPES) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
BSIZE	smallint
LID	int
SNAME	varchar(255)
SSUBSTITUTION	varchar(255)

Column Descriptions

The following are the descriptions of the RQAggregateTypes table columns.

BSIZE — The size of the defined aggregate.

LID — A unique ID.

SNAME — Aggregate variable.

SSUBSTITUTION — The substitution for the syntax checking.

RQ_Fields Table

The RQ_Fields table is used to populate the transaction and demographic lists. It defines available columns for the ShortWindow, RT_ShortWindow, Master tables, Profile and Peer Profile tables.

The columns in the RQ_Fields table (RQ_FIELDS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
FIELD_ID	int
FIELD_NAME	nvarchar(30)
TABLE_NAME	nvarchar(30)

Index Name: **PK_RQ_FIELDS**

Fields: FIELD_ID

Column Descriptions

The following are the descriptions of the RQ_Fields table columns.

FIELD_ID — The unique identifier for the field.

FIELD_NAME — The name of the field.

TABLE_NAME — The name of the table.

RT_Group_Link Table

The RT_Group_Link table contains information related to action levels associated with the ShortWindow_Group table.

The columns in the RT_Group_Link table (RT_GROUP_LINK) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
GROUP_ID	int

Index Name: **PK_RT_GROUP_LINK**

Fields: ACTION_LEVEL_ID
 GROUP_ID

Column Descriptions

The following are the descriptions of the RT_Group_Link table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

GROUP_ID — The unique identifier of the group.

RuleAggregateLink Table

The RuleAggregateLink table is used by the Analysis and Review System. It is used by the GUI when deploying rules and queues. It tracks the IDs of the rules and the IDs of the aggregates that they use.

The columns in the RuleAggregateLink table (RULEAGGREGATELINK) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
AGG_MOD_IND	int
LAGGREGATEID	int
LRULEID	int

Index Name: **IDX_RULEAGGREGATELINK_UNIQUE**

Fields: LRULEID

 LAGGREGATEID

Column Descriptions

The following are the descriptions of the RuleAggregateLink table columns.

AGG_MOD_IND — Description currently unavailable.

LAGGREGATEID — The aggregate ID.

LRULEID — The Rule ID. The index to the RuleQue table.

RuleDef Table

The RuleDef table defines the variety of rules and queues that are available within the PRM system.

Note: This table should only be modified by ACI Worldwide, Inc. personnel.

The columns in the RuleDef table (RULEDEF) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
BEDITORENABLED	smallint
BMATCHINGQUE	int
BUSEORDER	smallint
DTCREATED	datetime
LID	int
LMATCHINGQUE	int
LSUBTYPE	int
LTYPE	int
NSTATUS	int
SDESCRIPTION	nvarchar(255)
SPROCEDURENAME	varchar(255)

Column Descriptions

The following are the descriptions of the RuleDef table columns.

BEDITORENABLED — Indicates whether the Rule/Queue editor is enabled for this rule type.

BMATCHINGQUE — Indicates whether matching queues can be created with rules of this type.

BUSEORDER — The order.

DTCREATED — The date the rule was created.

LID — A unique ID.

LMATCHINGQUE — The LID of the matching queue in the RuleDef table.

LSUBTYPE — The sub-type.

LTYPE — The type.

NSTATUS — Indicates whether or not the rule type is enabled for users.

SDESCRIPTION — A description.

SPROCEDURENAME — The prefix used when creating a rule or queue procedure.

Service_Additional_Fields Table

The Service_Additional_Fields table contains additional configuration for the service.

The columns in the Service_Additional_Fields table (SERVICE_ADDITIONAL_FIELDS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
COLUMN_NAME	varchar(30)
EXTERNAL_SYSTEM	varchar(32)

Column Name	Data Type
FIELD_NAME	varchar(50)
FIELD_TYPE	smallint
FIELD_USAGE	smallint
SERVICE_NAME	varchar(100)

Column Descriptions

The following are the descriptions of the Service_Additional_Fields table columns.

COLUMN_NAME — is optional for incoming messages and required for outgoing messages. For incoming messages, this column contains the name of the Detail table column to which the corresponding field_name should be matched. For outgoing messages, this column indicates that the corresponding Detail table column needs to be included in the outgoing message.

EXTERNAL_SYSTEM — column is required. It indicates the system for which this configuration is defined.

FIELD_NAME — is optional for incoming messages. It identifies the name of the field used in the incoming mark or unmark message that should be mapped to the corresponding Detail table column_name. If missing, the corresponding column_name is used. This column is not needed for outgoing mark messages because they always contain Detail table column_names.

FIELD_TYPE — is required. It indicates the type of field. Valid values are:

0=Outgoing field

1=Incoming field

FIELD_USAGE — is required. It indicates the field usage. Valid values are:

0=Transaction identification field

1=Additional transaction field

SERVICE_NAME — is required. It indicates the service for which this configuration applies (it should match the OEI connection's EXTRCNCTID).

Service_RQ_Filter Table

The Service_RQ_Filter table contains information regarding the columns and column values from the corresponding Detail table which is used as a filter by the service.

The columns in the Service_RQ_Filter table (SERVICE_RQ_FILTER) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
FILTER_NAME	varchar(30)
FILTER_VALUE	nvarchar(2000)
SERVICE_NAME	varchar(100)

Column Descriptions

The following are the descriptions of the Service_RQ_Filter table columns.

FILTER_NAME — is required. It identifies the name of the Detail table column used for matching.

FILTER_VALUE — is required. It indicates the value that the corresponding Detail table field should match in order for the mark or unmark message to be sent.

SERVICE_NAME — is required. It indicates the service for which this filter applies (it should match the OEI connection's EXTRCNCT ID).

Settings Table

The Settings table is used by the Analysis and Review system. It is used to allow suspicious activity selection in the mark transaction screen.

Note: This table should only be modified by ACI Worldwide, Inc. personnel.

The columns in the Settings table (SETTINGS) are listed below with the data type.

Column Name	Data Type
BLOB_VALUE	ntext
DESCRIPTION	nvarchar(100)
INT_VALUE	int
LID	int
NAME	varchar(50)
STRING_VALUE	nvarchar(200)
SUBTYPE	int
TYPE	int

Column Descriptions

The following are the descriptions of the Settings table columns.

BLOB_VALUE — The blob value.

DESCRIPTION — The description of the setting.

INT_VALUE — The integer value.

LID — A unique ID.

NAME — The name of the setting.

STRING_VALUE — The string value.

SUBTYPE — The sub-type value.

TYPE — The type value.

Shortwindow_Group Table

The ShortWindow_Group table contains information related to ShortWindow table using groups. All default action levels use ShortWindow and RT_ShortWindow respectively for NRT and RT modules. All actions levels that are using same set of ShortWindow and/or RT_ ShortWindow tables form a group. If using a new table to replace the ShortWindow table functionality, it is necessary to create a group of action levels that uses these new tables. This group information is used to display the available fields during the creation of aggregates if the action level selected is ALL.

The columns in the Shortwindow_Group table (SHORTWINDOW_GROUP) are listed below with the data type.

Column Name	Data Type
DEFAULT_ACTION_LEVEL	int
DUAL_CONTROL_OVERRIDE_IND	bit
ENABLE_DUAL_CONTROL_IND	bit
GROUP_DISPLAY_NAME	int
GROUP_ID	int
GROUP_NAME	nvarchar(25)
MASTER_KEY_COLUMN_NAME	varchar(30)
MASTER_TABLE_NAME	varchar(30)
MAX_FAILED_OVERRIDE_ATTEMPTS	smallint

Column Name	Data Type
NRT_SHORTWINDOW_TAB_NAME	varchar(30)
OVERRIDE_CODE	nvarchar(255)
RT_SHORTWINDOW_TAB_NAME	varchar(30)
SOFT_DELETE_IND	bit

Index Name: **PK_SHORTWINDOW_GROUP**

Fields: GROUP_DISPLAY_NAME
 GROUP_ID
 NRT_SHORTWINDOW_TAB_NAME
 MASTER_TABLE_NAME
 MASTER_KEY_COLUMN_NAME

Column Descriptions

The following are the descriptions of the Shortwindow_Group table columns.

DEFAULT_ACTION_LEVEL — The ACTION_LEVEL_ID value.

DUAL_CONTROL_OVERRIDE_IND — Indicates whether or not dual control override is enabled.

Valid values are:

- 0 = Dual control override is not enabled. This is the default value.
- 1 = Dual control override is enabled.

ENABLE_DUAL_CONTROL_IND — Indicates whether or not dual control is enabled.

Valid values are:

- 0 = Dual control is not enabled.
- 1 = Dual control is enabled. This is the default value.

GROUP_DISPLAY_NAME — An integer that identifies the localized name of the group.

GROUP_ID — The unique identifier of the group.

GROUP_NAME — The name of the ShortWindow group as text.

MASTER_KEY_COLUMN_NAME — The column name for the master key.

MASTER_TABLE_NAME — The column name for the master table.

MAX_FAILED_OVERRIDE_ATTEMPTS — The maximum number of failed Override Code entry attempts allowed per user, if Dual Control Override is enabled. The default value for this field is 0.

NRT_SHORTWINDOW_TAB_NAME — The name of the ShortWindow database table for Near Real Time processing.

VERRIDE_CODE — The code (similar to a password) that controls the ability to use override functionality. The default value is null.

RT_SHORTWINDOW_TAB_NAME — The name of the ShortWindow database table for Real Time processing.

SOFT_DELETE_IND — Determines whether the entry was deleted from the user interface or not.

SystemAudit Table

The SystemAudit table is used by the Analysis and Review system. It tracks system actions for Java based client users and root administrators.

The columns in the SystemAudit table (SYSTEMAUDIT) are listed below with the data type.

Column Name	Data Type
BLOBDATA	image

Column Name	Data Type
DTDATE	datetime
LUSERID	int
NACTIONTYPE	int
NOBJECTID	int
NSUBTYPE	int
NTYPE	int
SMSG	varchar(2000)
SWORKSTATION	varchar(255)

Index Name: IDX_SYSTEMAUDIT_CLUSTER

Fields: LUSERID
 SWORKSTATION
 DTDATE

Index Name: IDX_SYSTEMAUDIT_DTDAT

Fields: DTDATE

Index Name: IDX_SYSTEMAUDIT_DASHB

Fields: DTDATE
 LUSERID
 NTYPE
 NSUBTYPE

Column Descriptions

The following are the descriptions of the SystemAudit table columns.

BLOBDATA — Reserved for future comprehensive XML description.

DTDATE — Contains the date of the audited action.

LUSERID — The user ID. It is linked to the LID column in the PRM_Users table.

NACTIONTYPE — The action type that was taken.

NOBJECTID — The ID of the appropriate object (for example, user ID, team ID, or portfolio ID).

NSUBTYPE — The subtype audit. It is linked to the LID column in the SystemAuditSubTypes table.

NTYPE — The type of audit. It is linked to the LID column in the SystemAuditTypes table.

SMSG — A short description of the audited action.

SWORKSTATION — The name of the workstation that was the source of the audited action.

SystemAuditSubTypes Table

The SystemAuditSubtypes table is used by the Analysis and Review system. It contains a list of audit action subtypes.

The columns in the SystemAuditSubTypes table (SYSTEMAUDITSUBTYPES) are listed below with the data type.

Column Name	Data Type
LSUBTYPEID	int
LTYPEID	int
SSUBTYPENAME	int
SYSTEMAUDITSUBTYPES_DSC	nvarchar(256)

Index Name: **IDX_SYSAUDSUBTYPE**

Fields: LSUBTYPEID

Column Descriptions

The following are the descriptions of the SystemAuditSubTypes table columns.

LSUBTYPEID — The ID of the subtype.

LTYPEID — The type ID. It is linked to the LID column in the SystemAuditTypes table.

SSUBTYPENAME — The numeric identifier for the localized name of the subtype name. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

SYSTEMAUDITSUBTYPES_DSC — Text that further describes the SYSTEMAUDITSUBTYPES record.

SystemAuditTSec Table

The SystemAuditTSec table is used by the Analysis and Review system. It specifies which users can see reports on a specific audit action type.

The columns in the SystemAuditTSec table (SYSTEMAUDITTSEC) are listed below with the data type.

Column Name	Data Type
LSECURITYLEVEL	int
LTYPEID	int

Index Name: **IDX_SYSAUDTSEC**

Fields: LTYPEID

 LSECURITYLEVEL

Column Descriptions

The following are the descriptions of the SystemAuditTSec table columns.

LSECURITYLEVEL — The binary value that indicates which users have report rights to the audit action type.

LTYPEID — The type ID. It is linked to the LID column in the SystemAuditTypes table.

SystemAuditTypes Table

The SystemAuditTypes table is used by the Analysis and Review system. It contains a list of the general types of audit actions.

The columns in the SystemAuditTypes table (SYSTEMAUDITTYPES) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
LID	int
SNAME	int
SYSTEMAUDITTYPES_DSC	nvarchar(256)

Index Name: **IDX_SYSAUDTYPE**

Fields: LID

Column Descriptions

The following are the descriptions of the SystemAuditTypes table columns.

LID — The ID of the audit type.

SNAME — The numeric identifier for the localized name of the performed action. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

SYSTEMAUDITTYPES_DSC — Text that further describes the SystemAuditTypes record.

SystemConfig Table

The SystemConfig table is used by the Analysis and Review system. It contains the system control parameters, which are described in a separate section of this manual.

The columns in the SystemConfig table (SYSTEMCONFIG) are listed below with the data type.

Column Name	Data Type
BLOBEDITOR	image
BLOBVALUE	image
DTCFGVALUE	datetime
LCFGVALUE	int
LCFGVARIABLEID	int
LPORTFOLIOID	int
NTYPE	int
PRMRESERVED	int
SCFGVALUE	varchar(255)
SCFGVARIABLE	varchar(30)
SPARAMS	varchar(255)

Index Name: **SYSTEMCONFIG_PRIMARY**

Fields: SCFGVARIABLE

Column Descriptions

The following are the descriptions of the SystemConfig table columns.

BLOBEDITOR — Reserved for future use.

BLOBVALUE — The binary value for the record in question.

DTCFGVALUE — The date and time value for the record in question.

LCFGVALUE — The numeric value for the record in question.

LCFGVARIABLEID — Not currently used.

LPORTFOLIOID — The portfolio ID. It is linked to the LID column in the Portfolios table.

NTYPE — The datatype.

PRMRESERVED — Reserved for future use.

SCFGVALUE — The string value for the record in question.

SCFGVARIABLE — The name of the SystemConfig table variable.

SPARAMS — Not currently used.

SystemFields Table

The SystemFields table is used to store all of the database fields. It lists the system required items and their associated site-specific database locations. This table is used by the pp_Calc_Fraud_Statistics stored procedure.

The columns in the SystemFields table (SYSTEMFIELDS) are listed below with the data type.

Column Name	Data Type
SFIELDNAME	varchar(255)
SSYSTEMFIELD	varchar(255)

Index Name: **IDX_SYSTEMFIELDS_CLUSTER**

Fields: SSYSTEMFIELD

Column Descriptions

The following are the descriptions of the SystemFields table columns.

SFIELDNAME — The name of the site-specific database field that satisfies the program's requirement.

SSYSTEMFIELD — The name of the item required by the program. The actual field value that is needed varies from site to site.

SystemSql Table

The SystemSql table is used by the Analysis and Review system. It holds the SQL statements that are unique to a specific database management system. The functions between Oracle and MS SQL database syntax may differ.

Note: This table should only be modified by ACI Worldwide, Inc. personnel.

The columns in the SystemSql table (SYSTEMSQL) are listed below with the data type.

Column Name	Data Type
SNAME	varchar(50)
SSQL	text

Column Descriptions

The following are the descriptions of the SystemSql table columns.

SNAME — The name of the SQL calls performed by the application.

SSQL — The text of the SQL statement to be executed.

SystemTableMap Table

The SystemTableMap table is used by the Analytic Gateway process. It contains a list of internal system tables and their database specific map values.

The columns in the SystemTableMap table (SYSTEMTABLEMAP) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
SMAPNAME	varchar(255)
STABLENAME	varchar(255)

Index Name: **SYSTEMTABLEMAP_PRIMARY**

Fields: STABLENAME

Column Descriptions

The following are the descriptions of the SystemTableMap table columns.

SMAPNAME — The name of the site.

STABLENAME — The internal name.

Task_Semaphore Table

The Task_Semaphore table is used to define tasks for jobs in PRM.

The columns in the Task_Semaphore table (TASK_SEMAPHORE) are listed below with the data type.

Column Name	Data Type
RUN_FLAG	bit
TASK_CODE	varchar(30)
TASK_DESCRIPTION	varchar(256)

Index Name: **PK_TASK_SEMAPHORE**

Fields: TASK_CODE

Column Descriptions

The following are the descriptions of the Task_Semaphore table columns.

RUN_FLAG — Indicates whether the job should be run or not for the corresponding task.

Valid values are:

0 = The job should not be run for the task

1 = The job should be run for the task

TASK_CODE — The name of the task

TASK_DESCRIPTION — The description for the task

TCR_Group Table

The TCR_Group table is used to store information about a customer's transaction groups.

The columns in the TCR_Group table (TCR_GROUP) are listed below with the data type.

Column Name	Data Type
ACTIVE	varchar(1)

Column Name	Data Type
ACTIVE_DATETIME	datetime
AMOUNT_ABSOLUT_VALUE	varchar(1)
AMOUNT_FIELD_NAME	varchar(30)
CREATE_DATETIME	datetime
DETAIL_TABLE	varchar(30)
GROUP_CKSUM	int
GROUP_ID	int
GROUP_NAME	nvarchar(100)
GROUP_ORDER	int
INCLUDED	varchar(1)
MODIFY_DATETIME	datetime
SHORTWINDOW_TABLE	varchar(30)
SQL_CRITERIA	nvarchar(Max)

Index Name: UX_01_TCR_GROUP

Fields: INCLUDED
GROUP_ORDER
DETAIL_TABLE

Index Name: PK_TCR_GROUP

Fields: GROUP_ID

Column Descriptions

The following are the descriptions of the TCR_Group table columns.

ACTIVE — A flag set to Y for an active transaction group or to N for an inactive transaction group.

ACTIVE_DATETIME — The date and time of the last time the Active flag was changed.

AMOUNT_ABSOLUT_VALUE — A flag that is set either to Y to include the absolute value of negative amount in the computations or to N to include only positive amounts in the computations.

AMOUNT_FIELD_NAME — The amount field that is used to build the SUM statistics.

CREATE_DATETIME — The date and time when the transaction group was created.

DETAIL_TABLE — The Action Level Detail table defined for the transaction group.

GROUP_CKSUM — The checksum value computed on the values defined for the transaction group.

GROUP_ID — The unique transaction group ID.

GROUP_NAME — The non-unique transaction group name.

GROUP_ORDER — The order number for processing the transaction group.

INCLUDED — A flag that is set either to Y for an included transaction group or to N for an excluded transaction group.

MODIFY_DATETIME — The date and time of the last time the transaction group attributes were modified.

SHORTWINDOW_TABLE — The Action Level ShortWindow table defined for the transaction group.

SQL_CRITERIA — The criteria used to filter the transactions tables, ShortWindow and Detail.

TCR_Run_Log Table

The TCR_Run_Log table is used to keep the log of the statistics collection process.

The columns in the TCR_Run_Log table (TCR_RUN_LOG) are listed below with the data type.

Column Name	Data Type
DETAIL_TABLE	varchar(30)
GROUP_ID	int
LOG_DATETIME	datetime
RUN_DATE	date
RUN_MESSAGE	varchar(400)
RUN_STATE	varchar(1)
TRANSACTION_TABLE	varchar(30)

Index Name: **PK_TCR_RUN_LOG**

Fields: RUN_DATE
 GROUP_ID
 DETAIL_TABLE

Column Descriptions

The following are the descriptions of the TCR_Run_Log table columns.

DETAIL_TABLE — The Action Level Detail table defined for the transaction group.

GROUP_ID — The unique transaction group ID.

LOG_DATETIME — The date and time of the current action.

RUN_DATE — The date on which the statistical data was collected. It is the same as the LAST_RUN_DATE column in the TCR_Statistic table.

RUN_MESSAGE — A message indicating a successful action, or an error message if either the procedure was run against the current day or the action failed.

RUN_STATE — A flag that is set to Y for statistics collected successfully, to N for statistics collected for the current date or a future date, or to E for other types of errors.

TRANSACTION_TABLE — The name of the table used to collect statistical data (Detail or ShortWindow).

TCR_Statistic Table

The TCR_Statistic table is the repository for the statistics (counts and sums) collected on the active transaction groups.

The columns in the TCR_Statistic table (TCR_STATISTIC) are listed below with the data type.

Column Name	Data Type
DETAIL_TABLE	varchar(30)
GROUP_ID	int
LAST_RUN_DATE	date
STATISTIC_AMOUNT	money
STATISTIC_CKSUM	int
STATISTIC_COUNT	int

Column Name	Data Type
STATISTIC_DATE	date

Index Name: **PK_TCR_STATISTIC**

Fields: STATISTIC_DATE
 GROUP_ID
 DETAIL_TABLE

Column Descriptions

The following are the descriptions of the TCR_Statistic table columns.

DETAIL_TABLE — The Action Level Table defined for the transaction group.

GROUP_ID — The unique transaction group ID.

LAST_RUN_DATE — The date when the statistical data was collected. It is used to prevent the same statistical data from being added multiple times.

STATISTIC_AMOUNT — The total cumulative amount of transactions found for the transaction group, excluding the negative values.

STATISTIC_CKSUM — The checksum value computed on the values defined for the transaction group.

STATISTIC_COUNT — The total number of transactions found for the transaction group.

STATISTIC_DATE — The date for which the statistical data was collected.

TFL_Report_Last_DD_Date Table

The TFL_REPORT_LAST_DD_DATE table is used to collect every day (by job) the number of days from the original mark date to the date of the most recent transaction that occurred after the original mark date as an integer value, and the DD_DATE of last transaction occurred. This table is

used by Total Fraud Losses report (for performance reasons) instead of scanning the entire Detail table.

The columns in the TFL_Report_Last_DD_Date table (TFL_REPORT_LAST_DD_DATE) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
DD_DATE	date
LAST_ACTIVE_DAYS	int

Index Name: **PK_TFL_REPORT_LAST_DD_DATE**

Fields: ACTION_LEVEL_KEY
 DD_DATE

Column Descriptions

The following are the descriptions of the TFL_Report_Last_DD_Date table columns.

ACTION_LEVEL_ID — This column indicates the action level ID.

ACTION_LEVEL_KEY — This column indicates the master key value from each action level.

DD_DATE — This column indicates the last transaction date.

LAST_ACTIVE_DAYS — This column contains the number of active days since the transaction was marked.

Timer_Lock Table

The Timer_Lock table stores timer information used to schedule timer tasks: sending e-mails, reading the capability configuration and copying it to RT.

The columns in the Timer_Lock table (TIMER_LOCK) are listed below with the data type.

Column Name	Data Type
TIMER_NAME	varchar(50)

Index Name: **PK_TIMER_LOCK**

Fields: TIMER_NAME

Column Descriptions

The following are the descriptions of the Timer_Lock table columns.

TIMER_NAME — This name of the timer.

Tips Table

The Tips table is used by the Analysis and Review system. It contains Tip records.

The columns in the Tips table (TIPS) are listed below with the data type.

Column Name	Data Type
CREATED_DATETIME	datetime
IS_GLOBAL	bit
LID	int
LTYPE	int
NCATEGORY	int
STIP	int

Index Name: **IDX_TIPS_PRIMARY**

Fields: LID

Index Name: **IDX_TIPS_TIPTYPE**

Fields: LTYPE

Column Descriptions

The following are the descriptions of the Tips table columns.

CREATED_DATETIME — The date and time in which the tip was created.

IS_GLOBAL — Determines whether the tip is global or not. Global tips are available to all action levels; no check for action levels is necessary.

Valid values are:

0 = Tip is not global.

1 = Tip code is global.

LID — A unique tip ID.

LTYPE — A value that links to the LID column in the TipTypes table.

NCATEGORY — The category of the tip involved.

STIP — The numeric identifier for the localized name of the tip text. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

TipTypes Table

The TipTypes table is used by the Analysis and Review system. It contains the various tip categories.

The columns in the TipTypes table (TIPTYPES) are listed below with the data type.

Column Name	Data Type
LID	int
STYPE	int

Index Name: **PK_TIPTYPES**

Fields: LID

Column Descriptions

The following are the descriptions of the TipTypes table columns.

LID — A unique ID.

STYPE — The numeric identifier for the localized name of the category text. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

Tip_Action_Level Table

The Tip_Action_Level table is used by the Analysis and Review system. It identifies the specific tips that are associated with an action level.

The columns in the Tip_Action_Level table (TIP_ACTION_LEVEL) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
TIP_ID	int

Index Name: **TIP_ACTION_LEVEL_PK**

Fields: ACTION_LEVEL_ID

TIP_ID

Column Descriptions

The following are the descriptions of the Tip_Action_Level table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

TIP_ID — A value from LID column in the Tips table.

Tip_PRMrroles Table

The Tip_PRMrroles table is used by the Analysis and Review system. It groups specific tips with PRM roles.

The columns in the Tip_PRMrroles table (TIP_PRMRoles) are listed below with the data type.

Column Name	Data Type
ROLEID	int
TIP_ID	int

Index Name: **TIP_PRMRoles_PK**

Fields: ROLEID

 TIP_ID

Column Descriptions

The following are the descriptions of the Tip_PRMRoles table columns.

ROLEID — A value from ID column in the PRMRoles table.

TIP_ID — A value from LID column in the Tips table.

Travel_Locations Table

The Travel_Locations table is linked to the Travel_Notifications table and is used to store the geographic locations for all notifications. Each travel notification may have up to 25 locations (that is, rows) in this table.

The columns in the Travel_Locations table (TRAVEL_LOCATIONS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
COUNTRY_CODE	varchar(3)
ORDER_NUM	int
OTHER_CODE	nvarchar(64)
REGION_CODE	varchar(3)
TRAVEL_ID	int

Column Descriptions

The following are the descriptions of the Travel_Locations table columns.

COUNTRY_CODE — The ISO 3-letter country code for a country to which the customer is traveling.

ORDER_NUM — Indicates the order in which the customer is traveling to the specified locations.

OTHER_CODE — Any text entered by the user in the Other field in the Locations panel of the Travel Notification Editor window.

REGION_CODE — The ISO 3-letter region code for the region to which the customer is traveling.

TRAVEL_ID — A unique number that is used to identify the travel notification record.

Travel_Notifications Table

The Travel_Notifications table is used to store travel notifications.

The columns in the Travel_Notifications table (TRAVEL_NOTIFICATIONS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
CREATED_BY	int
DATE_CREATED	datetime
DATE_MODIFIED	datetime
EXPECTED_MAX_SPEND_AMT	money
MODIFIED_BY	int
NOTES	nvarchar(256)
NOTIFICATION_METHOD	varchar(32)
NOTIFICATION_TYPE	varchar(32)

Column Name	Data Type
TRAVEL_END_DATE	datetime
TRAVEL_ID	int
TRAVEL_START_DATE	datetime

Index Name: AK_1_TRAVEL_NOTIFICATIONS

Fields: ACTION_LEVEL_ID
 ACTION_LEVEL_KEY
 TRAVEL_START_DATE
 TRAVEL_END_DATE

Index Name: PK_TRAVEL_NOTIFICATIONS

Fields: TRAVEL_ID

Column Descriptions

The following are the descriptions of the Travel_Notifications table columns.

ACTION_LEVEL_ID — References the ACTION_LEVEL_ID in the Action_Level table.

ACTION_LEVEL_KEY — References the ACTION_LEVEL_KEY field of the chosen ACTION_LEVEL_ID.

CREATED_BY — The user ID of the user who created the travel notification record.

DATE_CREATED — The date and time the travel notification record was created.

DATE_MODIFIED — The date and time at which the travel notification record was last modified.

EXPECTED_MAX_SPEND_AMT — The maximum amount the customer expects to spend on a transaction.

MODIFIED_BY — The user ID of the user who last modified the travel notification record.

NOTES — Any text the user typed in the Notes field on the Travel Notification Editor window, or any auto-text selected by the user from the Auto-Text pop-up and then placed in the Notes field on the Travel Notification Editor window.

NOTIFICATION_METHOD — Identifies how the customer notified the bank about their travel plans. When a user enters a travel notification for a customer, the user can identify the method the customer used to notify the bank by selecting Phone, Email, Online, Branch, or Other from a drop-down list.

NOTIFICATION_TYPE — The reason for the customer's travel. When a user enters a travel notification for a customer, the user can indicate the notification type by selecting Business, Leisure, Gambling, or Other from a drop-down list.

TRAVEL_END_DATE — The end date for the customer's travel.

TRAVEL_ID — The primary key. It contains a unique number that is used to identify the travel notification record.

TRAVEL_START_DATE — The start date for the customer's travel.

Travel_Notification_Countries Table

The Travel_Notification_Countries table contains the ISO 3-letter codes that correspond to the countries that a user can select from a drop-down list on the Travel Notification Editor window.

The columns in the Travel_Notification_Countries table (TRAVEL_NOTIFICATION_COUNTRIES) are listed below with the data type.

Column Name	Data Type
COUNTRY_CODE	varchar(3)
COUNTRY_NAME_L10N	int

Index Name: **PK_TRAVEL_NOTIFICATION_COUNTRIES**

Fields: COUNTRY_CODE

Column Descriptions

The following are the descriptions of the Travel_Notification_Countries table columns.

COUNTRY_CODE — The primary key. It contains the ISO 3-letter country codes.

COUNTRY_NAME_L10N — References the L10N_Property table, which contains the localized name of the country identified by the value in the COUNTRY_CODE column of the Travel_Notification_Countries table.

Travel_Notification_Method Table

The Travel_Notification_Method table contains values for the possible methods customers can use to notify the bank of their travel plans. For example, a customer may notify the bank via “Email.”

The columns in the Travel_Notification_Method table (TRAVEL_NOTIFICATION_METHOD) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
METHOD_CODE	varchar(32)
METHOD_NAME_L10N	int

Index Name: **PK_TRAVEL_NOTIFICATION_METHOD**

Fields: METHOD_CODE

Column Descriptions

The following are the descriptions of the Travel_Notification_Method table columns.

METHOD_CODE — The primary key. It contains the methods customers can use to notify the bank of their travel plans. At initial installation, the values Other, Branch, Online, Phone, and Email are provided; however, the user can supply other values after installation by adding them to the database manually.

METHOD_NAME_L10N — References the L10N_Property table, which contains the localized name for the value in the METHOD_CODE column of the Travel_Notification_Method table.

Travel_Notification_Regions Table

The Travel_Notification_Regions table contains the ISO 3-letter codes that correspond to the regions that a user can select from a drop-down list on the Travel Notification Editor window. The value selected in the Country drop-down list determines the values that are available in the Region drop-down list.

The columns in the Travel_Notification_Regions table (TRAVEL_NOTIFICATION_REGIONS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
COUNTRY_CODE	varchar(3)
REGION_CODE	varchar(3)
REGION_NAME_L10N	int

Index Name: **PK_TRAVEL_NOTIFICATION_REGIONS**

Fields: REGION_CODE
 COUNTRY_CODE

Column Descriptions

The following are the descriptions of the Travel_Notification_Regions table columns.

COUNTRY_CODE — An ISO 3-letter country code.

REGION_CODE — An ISO 3-letter region code for a region within the country identified by the value in the COUNTRY_CODE column of the Travel_Notification_Regions table.

REGION_NAME_L10N — References the L10N_Property table, which contains the localized name of the region identified by the value in the REGION_CODE column of the Travel_Notification_Regions table.

Travel_Notification_Type Table

The Travel_Notification_Type table contains values for the possible reasons for customers to travel. For example, a customer may travel for "Business."

The columns in the Travel_Notification_Type table (TRAVEL_NOTIFICATION_TYPE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
TYPE_CODE	varchar(32)
TYPE_NAME_L10N	int

Index Name: PK_TRAVEL_NOTIFICATION_TYPE

Fields: TYPE_CODE

Column Descriptions

The following are the descriptions of the Travel_Notification_Type table columns.

TYPE_CODE — The primary key. It contains the reasons customers travel. At initial installation, the values Other, Business, Leisure, and Gambling are provided; however, the user can supply other values after installation by adding them to the database manually.

TYPE_NAME_L10N — References the L10N_Property table, which contains the localized name for the value in the TYPE_CODE column of the Travel_Notification_Type table.

TRENDS_1_BIMONTHLY Table

Description not available.

The columns in the TRENDS_1_BIMONTHLY table (TRENDS_1_BIMONTHLY) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DD_PARTITION_DATE	date

Column Name	Data Type
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)
ND_UAN_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
SD_PAN	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: IDX_TRENDS_1_BIMONTHLY_CLUSTER

Fields: SD_PAN

DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_1_BIMONTHLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_PAN — The card number (PAN) that identifies the card, which is contained in the track 2 data.

The PAN is made up of 3 components: Issuer identification number (IIN), individual account identification identifying the customer and a check digit.

TXNS_COUNT — Description not available.

TRENDS_1_MONTHLY Table

Description not available.

The columns in the TRENDS_1_MONTHLY table (TRENDS_1_MONTHLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_PAN	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: **IDX_TRENDS_1_MONTHLY_CLUSTER**

Fields: SD_PAN

DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_1_MONTHLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_PAN — The card number (PAN) that identifies the card, which is contained in the track 2 data.

The PAN is made up of 3 components: Issuer identification number (IIN), individual account identification identifying the customer and a check digit.

TXNS_COUNT — Description not available.

TRENDS_1_WEEKLY Table

Description not available.

The columns in the TRENDS_1_WEEKLY table (TRENDS_1_WEEKLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAID_NRT_RULE_SCR	numeric(18,0)
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_PAN	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: **IDX_TRENDS_1_WEEKLY_CLUSTER**

Fields: SD_PAN

DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_1_WEEKLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Description not available.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_PAN — The card number (PAN) that identifies the card, which is contained in the track 2 data.

The PAN is made up of 3 components: Issuer identification number (IIN), individual account identification identifying the customer and a check digit.

TXNS_COUNT — Description not available.

TRENDS_2_BIMONTHLY Table

Description not available.

The columns in the TRENDS_2_BIMONTHLY table (TRENDS_2_BIMONTHLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAID_NRT_RULE_SCR	numeric(18,0)
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_RETL_ID	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: **IDX_TRENDS_2_BIMONTHLY_CLUSTER**

Fields: SD_RETL_ID
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_2_BIMONTHLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_RETL_ID — The alphanumeric or numeric code that identifies the retailer or merchant that owns or operates the terminal at which this transaction originated. It equates to a single physical location or Internet storefront. For merchants with multiple store locations, the merchant ID must be unique per store. This field is populated with the terminal ID for ATM transactions and can be used to monitor ATM transactions.

TXNS_COUNT — Description not available.

TRENDS_2_DAILY Table

Description not available.

The columns in the TRENDS_2_DAILY table (TRENDS_2_DAILY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)

Column Name	Data Type
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_RETL_ID	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: **IDX_TRENDS_2_DAILY_CLUSTER**

Fields: SD_RETL_ID
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_2_DAILY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_RETL_ID — The alphanumeric or numeric code that identifies the retailer or merchant that owns or operates the terminal at which this transaction originated. It equates to a single physical location or Internet storefront. For merchants with multiple store locations, the merchant ID must be unique per store. This field is populated with the terminal ID for ATM transactions and can be used to monitor ATM transactions.

TXNS_COUNT — Description not available.

TRENDS_2_WEEKLY Table

Description not available.

The columns in the TRENDS_2_WEEKLY table (TRENDS_2_WEEKLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)

Column Name	Data Type
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_RETL_ID	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: IDX_TRENDS_2_WEEKLY_CLUSTER

Fields: SD_RETL_ID
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_2_WEEKLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_RETL_ID — The alphanumeric or numeric code that identifies the retailer or merchant that owns or operates the terminal at which this transaction originated. It equates to a single physical location or Internet storefront. For merchants with multiple store locations, the merchant ID must be unique per store. This field is populated with the terminal ID for ATM transactions and can be used to monitor ATM transactions.

TXNS_COUNT — Description not available.

TRENDS_3_BIMONTHLY Table

Description not available.

The columns in the TRENDS_3_BIMONTHLY table (TRENDS_3_BIMONTHLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)

Column Name	Data Type
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_UAN	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: **IDX_TRENDS_3_BIMONTHLY_CLUSTER**

Fields: SD_UAN

DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_3_BIMONTHLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_UAN — The unique identifier of the universal account number or Customer.

TXNS_COUNT — Description not available.

TRENDS_3_MONTHLY Table

Description not available.

The columns in the TRENDS_3_MONTHLY table (TRENDS_3_MONTHLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)

Column Name	Data Type
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_UAN	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: **IDX_TRENDS_3_MONTHLY_CLUSTER**

Fields: SD_UAN

DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_3_MONTHLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_UAN — The unique identifier of the universal account number or Customer.

TXNS_COUNT — Description not available.

TRENDS_3_WEEKLY Table

Description not available.

The columns in the TRENDS_3_WEEKLY table (TRENDS_3_WEEKLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAID_NRT_RULE_SCR	numeric(18,0)
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_UAN	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: **IDX_TRENDS_3_WEEKLY_CLUSTER**

Fields: SD_UAN

DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_3_WEEKLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_UAN — The unique identifier of the universal account number or Customer.

TXNS_COUNT — Description not available.

TRENDS_4_BIMONTHLY Table

Description not available.

The columns in the TRENDS_4_BIMONTHLY table (TRENDS_4_BIMONTHLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_TERM_ID	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: **IDX_TRENDS_4_BIMONTHLY_CLUSTER**

Fields: SD_TERM_ID
DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_4_BIMONTHLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_TERM_ID — Identifies the terminal where the transaction originated.

TXNS_COUNT — Description not available.

TRENDS_4_DAILY Table

Description not available.

The columns in the TRENDS_4_DAILY table (TRENDS_4_DAILY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_TERM_ID	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: IDX_TRENDS_4_DAILY_CLUSTER

Fields: SD_TERM_ID
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_4_DAILY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_TERM_ID — Identifies the terminal where the transaction originated.

TXNS_COUNT — Description not available.

TRENDS_4_WEEKLY Table

Description not available.

The columns in the TRENDS_4_WEEKLY table (TRENDS_4_WEEKLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_TERM_ID	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: IDX_TRENDS_4_WEEKLY_CLUSTER

Fields: SD_TERM_ID

DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_4_WEEKLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_TERM_ID — Identifies the terminal where the transaction originated.

TXNS_COUNT — Description not available.

TRENDS_5_BIMONTHLY Table

Description not available.

The columns in the TRENDS_5_BIMONTHLY table (TRENDS_5_BIMONTHLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_EMPLOYEE_ID	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: **IDX_TRENDS_5_BIMONTHLY_CLUSTER**

Fields: SD_EMPLOYEE_ID
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_5_BIMONTHLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_EMPLOYEE_ID — The unique identifier of the employee, Depending on the type and location of the transaction, this may be an employee at a branch or at a merchant who processed or authorized the transaction.

TXNS_COUNT — Description not available.

TRENDS_5_MONTHLY Table

Description not available.

The columns in the TRENDS_5_MONTHLY table (TRENDS_5_MONTHLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_EMPLOYEE_ID	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: **IDX_TRENDS_5_MONTHLY_CLUSTER**

Fields: SD_EMPLOYEE_ID
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_5_MONTHLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_EMPLOYEE_ID — The unique identifier of the employee, Depending on the type and location of the transaction, this may be an employee at a branch or at a merchant who processed or authorized the transaction.

TXNS_COUNT — Description not available.

TRENDS_5_WEEKLY Table

Description not available.

The columns in the TRENDS_5_WEEKLY table (TRENDS_5_WEEKLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_EMPLOYEE_ID	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: IDX_TRENDS_5_WEEKLY_CLUSTER

Fields: SD_EMPLOYEE_ID
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_5_WEEKLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_EMPLOYEE_ID — The unique identifier of the employee, Depending on the type and location of the transaction, this may be an employee at a branch or at a merchant who processed or authorized the transaction.

TXNS_COUNT — Description not available.

TRENDS_6_BIMONTHLY Table

Description not available.

The columns in the TRENDS_6_BIMONTHLY table (TRENDS_6_BIMONTHLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_USER_ACCT_ID	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: IDX_TRENDS_6_BIMONTHLY_CLUSTER

Fields: SD_USER_ACCT_ID
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_6_BIMONTHLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — Description not available.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_USER_ACCT_ID — Description not available.

TXNS_COUNT — Description not available.

TRENDS_6_MONTHLY Table

Description not available.

The columns in the TRENDS_6_MONTHLY table (TRENDS_6_MONTHLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_USER_ACCT_ID	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: **IDX_TRENDS_6_MONTHLY_CLUSTER**

Fields: SD_USER_ACCT_ID
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_6_MONTHLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_USER_ACCT_ID — Description not available.

TXNS_COUNT — Description not available.

TRENDS_6_WEEKLY Table

Description not available.

The columns in the TRENDS_6_WEEKLY table (TRENDS_6_WEEKLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_USER_ACCT_ID	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: **IDX_TRENDS_6_WEEKLY_CLUSTER**

Fields: SD_USER_ACCT_ID
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_6_WEEKLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_USER_ACCT_ID — Description not available.

TXNS_COUNT — Description not available.

TRENDS_7_BIMONTHLY Table

Description not available.

The columns in the TRENDS_7_BIMONTHLY table (TRENDS_7_BIMONTHLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_PRI_ACCT_NUM	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: IDX_TRENDS_7_BIMONTHLY_CLUSTER

Fields: SD_PRI_ACCT_NUM
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_7_BIMONTHLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_PRI_ACCT_NUM — Unambiguous identification of the account of the debtor to which a debit entry will be made as a result of the transaction.

TXNS_COUNT — Description not available.

TRENDS_7_MONTHLY Table

Description not available.

The columns in the TRENDS_7_MONTHLY table (TRENDS_7_MONTHLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_PRI_ACCT_NUM	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: IDX_TRENDS_7_MONTHLY_CLUSTER

Fields: SD_PRI_ACCT_NUM
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_7_MONTHLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_PRI_ACCT_NUM — Unambiguous identification of the account of the debtor to which a debit entry will be made as a result of the transaction.

TXNS_COUNT — Description not available.

TRENDS_7_WEEKLY Table

Description not available.

The columns in the TRENDS_7_WEEKLY table (TRENDS_7_WEEKLY) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
MD_TRAN_AMT2	money
MD_TRAN_AMT3	money
ND_ACCOUNT_NRT_RULE_SCR	numeric(18,0)
ND_CARD_NRT_RULE_SCR	numeric(18,0)
ND_CUST_SCORE	numeric(18,0)
ND_EMPLOYEE_NRT_RULE_SCR	numeric(18,0)
ND_MERCHANT_NRT_RULE_SCR	numeric(18,0)
ND_NEAR_TIME_SCORE	numeric(18,0)
ND_NEAR_TIME_SCORE_2	numeric(18,0)
ND_NEAR_TIME_SCORE_3	numeric(18,0)
ND_REAL_TIME_SCORE	numeric(18,0)
ND_REAL_TIME_SCORE_2	numeric(18,0)
ND_REAL_TIME_SCORE_3	numeric(18,0)
ND_TERMINAL_NRT_RULE_SCR	numeric(18,0)
ND_UAID_NRT_RULE_SCR	numeric(18,0)

Column Name	Data Type
ND_UAN_NRT_RULE_SCR	numeric(18,0)
SD_PRI_ACCT_NUM	varchar(50)
TXNS_COUNT	numeric(18,0)

Index Name: IDX_TRENDS_7_WEEKLY_CLUSTER

Fields: SD_PRI_ACCT_NUM
 DD_PARTITION_DATE

Column Descriptions

The following are the descriptions of the TRENDS_7_WEEKLY table columns.

DD_PARTITION_DATE — Description not available.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

MD_TRAN_AMT2 — Amount of money moved between the instructing agent and the instructed agent.

MD_TRAN_AMT3 — The account balance (either ledger or available) amount as a result of the transaction. In a reversal of a deposit with cash back, the net amount of the reversal.

ND_ACCOUNT_NRT_RULE_SCR — Description not available.

ND_CARD_NRT_RULE_SCR — Description not available.

ND_CUST_SCORE — Description not available.

ND_EMPLOYEE_NRT_RULE_SCR — Description not available.

ND_MERCHANT_NRT_RULE_SCR — Description not available.

ND_NEAR_TIME_SCORE — Description not available.

ND_NEAR_TIME_SCORE_2 — Description not available.

ND_NEAR_TIME_SCORE_3 — Description not available.

ND_REAL_TIME_SCORE — Description not available.

ND_REAL_TIME_SCORE_2 — Description not available.

ND_REAL_TIME_SCORE_3 — Description not available.

ND_TERMINAL_NRT_RULE_SCR — Description not available.

ND_UAID_NRT_RULE_SCR — Description not available.

ND_UAN_NRT_RULE_SCR — Description not available.

SD_PRI_ACCT_NUM — Unambiguous identification of the account of the debtor to which a debit entry will be made as a result of the transaction.

TXNS_COUNT — Description not available.

TRENDS_FIELDS Table

TRENDS_FIELDS table contains the Trends fields used to build the statistics, with internationalized field description for each action level.

The columns in the TRENDS_FIELDS table (TRENDS_FIELDS) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
FIELD_DESCRIPTION	numeric
FIELD_NAME	varchar(30)
IS_DEFAULT	int
IS_ENABLED	int

Index Name: **PK_TRENDS_FIELDS**

Fields: ACTION_LEVEL_ID
 FIELD_NAME

Column Descriptions

The following are the descriptions of the TRENDS_FIELDS table columns.

ACTION_LEVEL_ID — ACTION_LEVEL_ID column contains value

FIELD_DESCRIPTION — FIELD_DESCRIPTION column contains id value defined in L10N_PROPERTY table to store the field name internationalized.

FIELD_NAME — FIELD_NAME column contains the field column name as is defined in the database

IS_DEFAULT — IS_DEFAULT column contains value 1, if the that field is displayed by default in the UI drop down, and 0 for not.

IS_ENABLED — IS_ENABLED column contains value 1 (default seed), if that filed is enabled for calculation and display in UI, and 0 if not.

TRENDS_GROUPING Table

TRENDS_GROUPING table contains the Trends grouping configuration

The columns in the TRENDS_GROUPING table (TRENDS_GROUPING) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
CALCULATION_DATE	date
GROUPING_ID	int
IS_DEFAULT	int

Index Name: **PK_TRENDS_GROUPING**

Fields: ACTION_LEVEL_ID
 GROUPING_ID

Column Descriptions

The following are the descriptions of the TRENDS_GROUPING table columns.

ACTION_LEVEL_ID — Description not available.

CALCULATION_DATE — CALCULATION_DATE column is updated with the last day of calculation done for each Trends table.

GROUPING_ID — GROUPING_ID column contains the CYCLE_TYPE_ID possible values from ENH_PROFILE_CYCLE_TYPE table (already predefined cycle intervals for Enhance Profiles feature).

IS_DEFAULT — IS_DEFAULT column contains value 1, if the that group is displayed by default in the UI drop down, and 0 for not.

TRENDS_GROUPING_RANGE Table

TRENDS_GROUPING_RANGE table contains the internationalized Trends range intervals predefined for each group.

The columns in the TRENDS_GROUPING_RANGE table (TRENDS_GROUPING_RANGE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
GROUPING_ID	int
IS_DEFAULT	int
RANGE_ID	int
RANGE_NAME	numeric
RANGE_NO	int

Index Name: **PK_TRENDS_GROUPING_RANGE**

Fields: RANGE_ID

Column Descriptions

The following are the descriptions of the TRENDS_GROUPING_RANGE table columns.

GROUPING_ID — Description not available.

IS_DEFAULT — IS_DEFAULT column contains value 1, if the that range group is displayed by default in the UI drop down, and 0 for not.

RANGE_ID — RANGE_ID column contains an incremented value for the internationalized Trends range names (RANGE_NAME) for each group.

Example of range names: Past 1 Week, Past 2 Weeks, Past 3 Weeks.

RANGE_NAME — Description not available.

RANGE_NO — RANGE_NO column contains the number of range intervals.

TRENDS_YAXIS_DISPLAY Table

TRENDS_YAXIS_DISPLAY table contains the internationalized Trends statistical grouping column displayed on Y axis, like: Average Sum, Total Sum, Count.

The columns in the TRENDS_YAXIS_DISPLAY table (TRENDS_YAXIS_DISPLAY) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
IS_DEFAULT	int
YAXIS_ID	int
YAXIS_NAME	numeric

Index Name: **PK_TRENDS_YAXIS_DISPLAY**

Fields: YAXIS_ID

Column Descriptions

The following are the descriptions of the TRENDS_YAXIS_DISPLAY table columns.

IS_DEFAULT — IS_DEFAULT column contains value 1 (Average Sum), if the that range group is displayed by default in the UI drop down, and 0 for not.

YAXIS_ID — YAXIS_ID column contains an incremented id.

YAXIS_NAME — YAXIS_NAME column contains an incremented value for the internationalized

Trends statistical grouping column.

UserRecentHistory Table

The UserRecentHistory table contains the list of accounts that were recently opened by PRM users.

Note: This table should only be modified by ACI Worldwide, Inc. personnel.

The columns in the UserRecentHistory table (USERRECENTHISTORY) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
ALERT_CATEGORY_ID	int
BALERTED	int
DTCLOSEDATE	datetime
DTOPENDATE	datetime
LID	int
LQUEID	int
NAME	varchar(50)
NSTATUS	int
SACCOUNTTOKEN	varchar(100)
TDTRECENTTXN	varchar(21)

Index Name: **USERRECENTHISTORY_CLUSTER**

Fields: LID

DTOPENDATE

Index Name: **USERRECENTHISTORY_IX1**

Fields: LID

NSTATUS

Index Name: **USERRECENTHISTORY_IX2**

Fields: LID

ACTION_LEVEL_ID

ACTION_LEVEL_KEY

Column Descriptions

The following are the descriptions of the UserRecentHistory table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the master tables. It can contain an SM_PAN, SM_UAN, SM_EMPLOYEE_ID, SM_RETL_ID, or SM_TERM_ID. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and will be used to determine what type of value is stored in ACTION_LEVEL_KEY.

ALERT_CATEGORY_ID — The name of the action level if selected during rule creation. The value is linked to the Alert_Category table.

BALERTED — Indicates whether the most recent transaction accessed by the user was alerted.

DTCLOSEDATE — The date the Analyst closed the Account Review screen.

DTOPENDATE — The date the Analyst opened the Account Review screen.

LID — Contains a unique ID from the PRM_Users table of the user who opened the account.

LQUEID — The queue ID from which the account came.

NAME — Contains the account name or cardholder name, merchant business name, name and location of the terminal, or the first name of the primary account owner. The value depends on the action level.

NSTATUS — Corresponds to the recent disposition of the account.

SACCOUNTTOKEN — The account token.

TDTRECENTTXN — Contains the most recent transaction when the account was accessed.

UserRecentHistory_Cross_AL Table

The UserRecentHistory_Cross_AL table is used by the UI component to store the history of the last accessed cross action levels.

The columns in the UserRecentHistory_Cross_AL table (USERRECENTHISTORY_CROSS_AL) are listed below with the data type.

Column Name	Data Type
CROSS_AL_ID	int
CROSS_AL_KEY	varchar(50)

Column Name	Data Type
DTCLOSEDATE	datetime
DTOPENDATE	datetime
NSTATUS	int
TDTRECENTTXN	varchar(21)
USER_ID	int

Column Descriptions

The following are the descriptions of the UserRecentHistory_Cross_AL table columns.

CROSS_AL_ID — The identifier of the cross action level type.

Valid values are:

- 1 = Device ID
- 2 = IP Address
- 3 = Payee

CROSS_AL_KEY — The key of the accessed cross action level.

DTCLOSEDATE — Contains the timestamp when the cross action level was closed.

DTOPENDATE — The timestamp when the cross action level was opened.

NSTATUS — The most recent disposition of the cross action level.

TDTRECENTTXN — The most recent transaction when the cross action level was accessed.

USER_ID — The identifier of the PRM user that accessed the cross action level.

UserSessions Table

The UserSessions table is used by the Analysis and Review system. It holds a list of user session IDs and the date that the sessions are due to expire.

Note: This table should only be modified by ACI Worldwide, Inc. personnel.

The columns in the UserSessions table (USERSESSIONS) are listed below with the data type.

Column Name	Data Type
DTEXPIREDATE	datetime
LUSERID	int
SSESSIONID	varchar(255)
SWORKSTATION	varchar(255)

Index Name: **USERSESSIONS_UNIQUE**

Fields: LUSERID

 SSESSIONID

Column Descriptions

The following are the descriptions of the UserSessions table columns.

DTEXPIREDATE — The expiration date.

LUSERID — The user ID.

SSESSIONID — The session ID number.

SWORKSTATION — The workstation number.

Letter Generator Tables

The Letter Generator tables contain information pertaining to the Letter Generator functionality.

The following Letter Generator tables are described in this subsection:

- LetterColumns
- LetterPostClass
- LetterPrintLocation
- LetterSelect
- LetterSignatures
- LetterTags
- LetterTemplates
- Letter_Config

LetterColumns Table

The LetterColumns table is used by the Analysis and Review system. It contains the configurable column headings for the letter generator report.

The columns in the LetterColumns table (LETTERCOLUMNS) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
CAPTION	int
FIELDNAME	varchar(50)
FORMATSTRING	varchar(50)
FORMATTYPE	int
ID	int

Index Name: **IDX_LETTERCOLUMNS**

Fields: ID

Index Name: **IDX_LETTERCOLUMNS_IX1**

Fields: ACTION_LEVEL_ID
 CAPTION

Column Descriptions

The following are the descriptions of the LetterColumns table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

CAPTION — The numeric identifier for the localized text of the caption. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

FIELDNAME — The field name from the Detail table.

FORMATSTRING — The format string for date fields and number fields.

FORMATTYPE — The format type for the field data.

Valid values are as follows:

- 0 = String field
- 1 = Date field

- 2 = Number field
- 3 = Currency field with currency symbol
- 6 = Currency field with no currency symbol

ID — The unique letter columns ID number.

LetterPostClass Table

The LetterPostClass table is used by the Analysis and Review system. It contains the letter post class and a description.

The columns in the LetterPostClass table (LETTERPOSTCLASS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
SDESCRIPTION	int
SPOSTCLASSID	varchar(10)

Index Name: IDX_LETTERPOSTCLASS

Fields: SPOSTCLASSID

Index Name: PK_LETTERPOSTCLASS

Fields: SPOSTCLASSID

 ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the LetterPostClass table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level

- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

SDESCRIPTION — The numeric identifier for the localized text of the description. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

SPOSTCLASSID — The letter post class ID name.

LetterPrintLocation Table

The LetterPrintLocation table is used by the Analysis and Review system. It contains the letter print location code and a description.

The columns in the LetterPrintLocation table (LETTERPRINTLOCATION) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
SDESCRIPTION	int
SPRINTLOCATIONID	varchar(10)

Index Name: **IDX_LETTERPRINTLOCATION**

Fields: SPRINTLOCATIONID

Index Name: **PK_LETTERPRINTLOCATION**

Fields: SPRINTLOCATIONID
 ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the LetterPrintLocation table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

SDESCRIPTION — The localized version of the description.

SPRINTLOCATIONID — The location ID of the printer.

LetterSelect Table

The LetterSelect table is used by the Analysis and Review system. It is used to track the transaction selections.

The columns in the LetterSelect table (LETTERSELECT) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
DD_DATE	datetime
MASTER_KEY	varchar(20)
ND_KEY_HASH	smallint

Column Name	Data Type
ND_LTR_REQ	tinyint
RECORD_SOURCE_ID	smallint
SD_TIEBREAKER	varchar(75)
USERID	int

Index Name: LETTERSELECT_PK

Fields: DD_DATE
ND_KEY_HASH
RECORD_SOURCE_ID
SD_TIEBREAKER
USERID
ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the LetterSelect table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

DD_DATE — The transaction date from the Detail table.

MASTER_KEY — The action level key.

ND_KEY_HASH — The value that is associated with the transaction in the Detail or FraudDetail table.

ND_LTR_REQ — Indicates whether this particular letter was selected.

Valid values are as follows:

0 = Letter was not selected

1 = Letter was selected

RECORD_SOURCE_ID — The value that is associated with the transaction in the Detail or FraudDetail table.

SD_TIEBREAKER — A value used to uniquely identify transactions. It is associated with the value from DETAIL table.

USERID — The user ID from the PRM_USERS table.

LetterSignatures Table

The LetterSignatures table is used by the Analysis and Review system. It contains the letter signature User ID and location.

The columns in the LetterSignatures table (LETTERSIGNATURES) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
BLOBSIGNATURE	image
LUSERID	int

Index Name: **IDX_LETTERSIGNATURES**

Fields: LUSERID

Column Descriptions

The following are the descriptions of the LetterSignatures table columns.

BLOBSIGNATURE — The signature image of the person initiating the letter.

LUSERID — The user ID of the person initiating the letter.

LetterTags Table

The LetterTags table is used by the Analysis and Review system. It contains the user defined letter tags.

The columns in the LetterTags table (LETTERTAGS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
DATEFIELD	int
DESCRIPTION	int
FIELD	varchar(50)
FIELDFORMAT	varchar(40)
FIELDTYPE	tinyint
TABLEID	int
TAGNAME	nvarchar(255)
TAG_TYPE	smallint

Index Name: **IDX_LETTERTAGS**

Fields: TAGNAME

 ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the LetterTags table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

DATEFIELD — Indicates whether the field is a date that needs to be formatted.

Valid values are:

- 1 = The date will be formatted.
- 0 = The date will not be formatted.

DESCRIPTION — The localized description.

FIELD — The field name.

FIELDFORMAT — The format of field.

FIELDTYPE — The type of field.

TABLEID — The unique table identifier.

TAGNAME — The name of the tag as it will be used. For example, the TagName field for the <AccountName> tag will be set to "AccountName".

TAG_TYPE — The type of tag.

Valid values are as follows:

0 = System tag

1 = Letter tag

LetterTemplates Table

The LetterTemplates table is used by the Analysis and Review system. It contains the letter templates, their assigned portfolio ID, the post class, and the printer code.

The columns in the LetterTemplates table (LETTERTEMPLATES) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
CODE	varchar(10)
DESCRIPTION	int
LOCALE_ID	varchar(10)
LOGOURL	varchar(512)
NAME	int
PORTFOLIOID	int
POSTCLASSID	varchar(10)
PRINTLOCATIONID	varchar(10)

<i>Column Name</i>	<i>Data Type</i>
TEXT	ntext

Index Name: **IDX_LETTERTEMPLATES**

Fields: CODE

 LOCALE_ID

 PORTFOLIOID

Column Descriptions

The following are the descriptions of the LetterTemplates table columns.

CODE — The code assigned to this letter (for example, Code ABC or Code 123).

DESCRIPTION — The localized description.

LOCALE_ID — The Foreign Key to the column LOCALE_ID in the AVAILABLE_LOCALE table.

LOGOURL — The letter template logo URL.

NAME — The localized name.

PORTFOLIOID — The ID of the portfolio to which this letter is assigned.

POSTCLASSID — The ID of the post class code assigned to this letter.

PRINTLOCATIONID — The ID of the printer code assigned to this letter.

TEXT — The text of the letter.

Letter_Config Table

The Letter_Config table is used by the Analysis and Review system. It contains the letter configuration variable and settings information.

The columns in the Letter_Config table (LETTER_CONFIG) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
LCFGVALUE	int
SCFGVALUE	varchar(255)
SCFGVARIABLE	varchar(20)

Index Name: **LETTER_CONFIG_PK**

Fields: ACTION_LEVEL_ID
 SCFGVARIABLE

Column Descriptions

The following are the descriptions of the Letter_Config table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

LCFGVALUE — The numeric value for the record in question.

SCFGVALUE — The string value for the record in question.

SCFGVARIABLE — The name of the Config table variable.

User Interface Tables

The User Interface tables contain information pertaining to the PRM User Interface (i.e., menu, toolbar, etc.).

The following User Interface tables are described in this subsection:

- Active_AL_Report
- AL_Last_AP_Date
- Available_Locale
- ConfigSortOptions
- FieldConfig
- L10N_Property
- L10N_Property_Additional_Info
- L10N_Property_Range
- MasterDisp
- MasterDisp_Temp
- PrmMenu
- PRM_Dictionary
- PRM_Field
- PRM_UI_Component
- PRM_UI_Component_Type
- PRM_UI_Datasource
- PRM_UI_Field
- PRM_UI_Field_Format
- PRM_UI_Field_Search
- PRM_UI_Gridbag_Config

- PRM_UI_Grid_Config
- PRM_UI_Masking
- PRM_UI_Panel
- ReportCategory
- ReportCategoryLink
- ReportFonts
- Reports
- ReportWizardPanelLink
- RT_Masterdisp
- RT_Masterdisp_Temp
- SelectListValues
- Titanium_Port_Total
- Titanium_Reports_Categories
- Titanium_RT_Rule_Perf
- Titanium_Rule_Perf
- ToolbarButtons
- Txns_Processed_Rpt
- UI_External_View_Config
- UI_KPI
- UserTableParams
- User_Date_Patterns
- WizardPanels

Active_AL_Report Table

The Active_AL_Report table contains calculated data for the Active Action Level report. It is populated by the PP_ACTIVE_AL_REPORT procedure, which runs nightly, as follows:

- On the 1st of each month, the procedure will store data for four reports: one report for the previous twelve months, one report for the previous six months, one report for the previous three months, and one report for the previous month.
- On the first day of each week, the procedure will store data for the previous week's report.

Note: The first day of each week will be Sunday or Monday depending on the locale setting of the

database server.

- Everyday, the procedure will store data for the previous day's report.

The columns in the Active_AL_Report table (ACTIVE_AL_REPORT) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
COUNT	int
END_DATE	date
PORTFOLIO_ID	int
START_DATE	date
TYPE	int

Index Name: **IDX_ACTIVE_AL_REPORT_1**

Fields: TYPE

START_DATE

END_DATE

ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the Active_AL_Report table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level

- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

COUNT — The number of action levels that transacted through the system during the reporting interval and belong to the specified portfolio.

END_DATE — The end date of the reporting interval.

PORTFOLIO_ID — The ID of the portfolio for which the action levels are counted.

START_DATE — The start date of the reporting interval.

TYPE — A distinct numeric value that indicates the time span of the report.

Valid values are:

- 0 = Yearly
- 1 = Semiannually
- 2 = Quarterly
- 3 = Monthly
- 4 = Weekly
- 5 = Daily

AL_Last_AP_Date Table

The AL_Last_AP_Date table holds a list with the most recent transaction date (DETAIL.DD_APDATE) for each action level (card, merchant, terminal, and so on) that exists in the system. It is kept current (up to yesterday) by the PP_ACTIVE_AL_REPORT procedure, which runs nightly.

The columns in the AL_Last_AP_Date table (AL_LAST_AP_DATE) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
DD_AUPDATE	datetime

Index Name: **IDX_AL_LAST_AP_DATE_1**

Fields: ACTION_LEVEL_ID
 DD_AUPDATE
 ACTION_LEVEL_KEY

Index Name: **PK_AL_LAST_AP_DATE**

Fields: ACTION_LEVEL_ID
 ACTION_LEVEL_KEY

Column Descriptions

The following are the descriptions of the AL_Last_AP_Date table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level. This column and the ACTION_LEVEL_KEY column constitute the composite primary key of this table.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the DETAIL. It can contain an SD_PAN, SD_UAN, SD_EMPLOYEE_ID, SD_RETL_ID or SD_TERM_ID.

The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and will be used to determine what type of value is stored in ACTION_LEVEL_KEY. This column and the ACTION_LEVEL_ID column constitute the composite primary key of this table.

DD_UPDATE — The most recent date and time when Analytic Gateway processed a transaction for this action level.

Available_Locale Table

The Available_Locale table is used by the Analysis and Review system. It contains localization information.

The columns in the Available_Locale table (AVAILABLE_LOCALE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
L10N_PROPERTY_ID	int
LOCALE_ID	varchar(10)

Index Name: **AVAILABLE_LOCALE_PK**

Fields: LOCALE_ID

 L10N_PROPERTY_ID

Column Descriptions

The following are the descriptions of the Available_Locale table columns.

L10N_PROPERTY_ID — The localized text stored in the L10N Properties table. The localized text is the name displayed in the drop-down field shown on the user's tab of the security screen.

LOCALE_ID — The locale identifier.

ConfigSortOptions Table

The ConfigSortOptions table stores the sort options that have been selected by the user through

the Screen Configuration Manager window. The user can select a primary and secondary sort field for each tab in a transaction grid and can specify whether the values are sorted in ascending or descending order.

The columns in the ConfigSortOptions table (CONFIGSORTOPTIONS) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
FIELD_ID	int
FIELD_NAME	varchar(30)
FIELD_NUMBER	int
SORT_ORDER	varchar(3)
TRANSACTION_TAB_ID	int

Column Descriptions

The following are the descriptions of the ConfigSortOptions table columns.

ACTION_LEVEL_ID — A number that corresponds to the action level of the transaction grid to which these sort options apply (for example: 1 for Card, 2 for Merchant, and so on).

FIELD_ID — The ID of the field used to sort the transaction grid. The value is a COMPONENT_ID from the PRM_UI_Component table.

FIELD_NAME — The field name of the sorting field, in the format "Database column".

FIELD_NUMBER — Indicates whether the field is the primary or secondary sorting field.

The valid values are as follows:

1 = Primary sorting field

2 = Secondary sorting field

SORT_ORDER — The order in which this field is sorted.

The valid values are as follows:

ASC = The field is sorted in ascending order.

DSC = The field is sorted in descending order.

TRANSACTION_TAB_ID — The ID of the transaction grid to which the sort options apply. The value is a COMPONENT_ID from the PRM_UI_Component table.

FieldConfig Table

The FieldConfig table is used by the Analysis and Review system. It defines the minimum and maximum lengths for values in specific fields and information used to validate the values in those fields. Each of those fields corresponds to a parameter. The name of each parameter is stored in the SFIELDNAME column. The minimum and maximum lengths for the values in the corresponding fields are stored in LMINLENGTH and LMAXLENGTH columns, respectively. The strings that define regular expressions used to validate the values in the fields are stored in the SREGEX column. The parameters are described in a separate section of this manual.

The columns in the FieldConfig table (FIELDCONFIG) are listed below with the data type.

Column Name	Data Type
LMAXLENGTH	int
LMINLENGTH	int
SFIELDNAME	varchar(50)
SREGEX	varchar(100)

Column Descriptions

The following are the descriptions of the FieldConfig table columns.

LMAXLENGTH — The maximum length of the column allowed for the field validation.

LMINLENGTH — The minimum length of the column allowed for the field validation.

SFIELDNAME — The field name within the column.

SREGEX — A string that defines a regular expression that is used to validate the field.

L10N_Property Table

The L10N_Property table is used by the Analysis and Review system. It contains localization information.

The columns in the L10N_Property table (L10N_PROPERTY) are listed below with the data type.

Column Name	Data Type
L10N_PROPERTY_ID	int
L10N_VALUE	nvarchar(500)
LOCALE_ID	varchar(10)
RANGE_LID	int

Index Name: **L10N_PROPERTY_PK**

Fields: LOCALE_ID

 L10N_PROPERTY_ID

Column Descriptions

The following are the descriptions of the L10N_Property table columns.

L10N_PROPERTY_ID — The numeric value used as the identifier for the localized value. ID 0 is reserved for "Resource Not Found" for each locale. The first 1,000,000 IDs are reserved for PRM seed data. This group of IDs is further sub-divided into specific ranges (having 5,000 values in each) for each column requiring localization; this maintains a level of clean separation of seed data for different tables. Together, this column and the LOCALE_ID column compose the composite primary key.

L10N_VALUE — Contains the localized content (that is, value) for the fields which need to be localized.

LOCALE_ID — The value in this column is present in the AVAILABLE_LOCALE. Together, this column and the L10N_PROPERTY_ID column compose the composite primary key.

RANGE_LID — Contains enhancements to the L10N_Property tables in order to eliminate the possible limitation of the ranges.

L10N_Property_Additional_Info Table

The L10N_Property_Additional_Info table is used by the Analysis and Review system. It has a one-to-one relationship to the L10N_PROPERTY table. The columns in this table enable the L10N_PROPERTY table to store more rows per block and therefore more rows in cache.

Because the L10N_PROPERTY table is heavily accessed, this table helps performance.

The columns in the L10N_Property_Additional_Info table (L10N_PROPERTY_ADDITIONAL_INFO) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
CACHE_ON_INITIALIZATION	bit
L10N_PROPERTY_ID	int
L10N_PROPERTY_NOTE	varchar(500)
LOCALE_ID	varchar(10)

Index Name: **L10N_PROPERTY_ADDL_INFO_PK**

Fields: LOCALE_ID
 L10N_PROPERTY_ID

Column Descriptions

The following are the descriptions of the L10N_Property_Additional_Info table columns.

CACHE_ON_INITIALIZATION — A Boolean value that designates whether this value should be cached on system initialization. This value is used to determine whether a field is cached or not when the server is started. This value is TRUE for all the properties having L10N_PROPERTY_ID = 0 ('resource not found').

L10N_PROPERTY_ID — The numeric value used as the identifier for the localized value. ID 0 is reserved for "Resource Not Found" for each locale. The first 1,000,000 IDs are reserved for PRM seed data. This is further sub-divided into specific ranges (having 5,000 values in each) for each column requiring localization; this maintains a level of clean separation of seed data for different tables. Together with LOCALE_ID, this column composes the composite primary key.

L10N_PROPERTY_NOTE — The text that describes the origin or use of the L10N_VALUE, to aid a translator in understanding its context.

LOCALE_ID — The value in this column is present in the AVAILABLE_LOCALE. Together with L10N_PROPERTY_ID, this column composes the composite primary key.

L10N_Property_Range Table

The L10N_Property_Range table is used by the Analysis and Review system. It contains the ranges for the Translations.

The columns in the L10N_Property_Range table (L10N_PROPERTY_RANGE) are listed below with the data type.

Column Name	Data Type
COLUMN_NAME	varchar(30)
CURRENT_VALUE	int
DB_MAPPING	varchar(2000)
IS_ACTIVE	varchar(1)

Column Name	Data Type
LID	int
RANGE_DESC	varchar(2000)
RANGE_END	int
RANGE_START	int
TABLE_NAME	varchar(30)
VALUE_LENGTH	int

Index Name: **PK_L10N_PROPERTY_RANGE**

Fields: LID

Column Descriptions

The following are the descriptions of the L10N_Property_Range table columns.

COLUMN_NAME — Contain the name of the column to use for a range of values.

CURRENT_VALUE — The current highest L10N_PROPERTY_ID for the table_name.column_name.

DB_MAPPING — The mapping information.

IS_ACTIVE — Identifies whether the range is active.

Valid values are:

Y = Yes

N = No

LID — The unique ID for the range of values.

RANGE_DESC — A description for the range.

RANGE_END — The ending value for the range.

RANGE_START — The starting value for the range.

TABLE_NAME — The name of the table to use for a range of values.

VALUE_LENGTH — The length of the value.

MasterDisp Table

The MasterDisp table is used by the Analysis and Review system. It stores Master table information for those accounts with a disposition change (for example watch, ice, block, and so on).

The columns in the MasterDisp table (MASTERDISP) are listed below with the data type.

Column Name	Data Type
ACTIONDATE	datetime
ACTIONID	int
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
ENDDATE	datetime
MOSTRECENTTXNDATE	datetime
SREASON_CODE	nvarchar(5)
STARTDATE	datetime

Column Name	Data Type
STATE	int
STATUS	int
USERID	int

Index Name: **IDX_MASTERDISP_CLUSTER**

Fields: ACTION_LEVEL_KEY
 ACTION_LEVEL_ID
 ACTIONID

Column Descriptions

The following are the descriptions of the MasterDisp table columns.

ACTIONDATE — The date of the disposition change.

ACTIONID — The action ID from the ActionsType table.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the master tables. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and is used to determine what type of value is stored in ACTION_LEVEL_KEY.

ENDDATE — The date when automatic actions will end (Ice, Suspend).

MOSTRECENTTXNDATE — The most recent transaction for the SM_KEY when an action is taken.

SREASON_CODE — The reason code for an action.

STARTDATE — The date when automatic actions will start (Ice, Suspend).

STATE — The state of the action.

Valid values are as follows:

0 = Do not activate button

1 = Activate button on PRM GUI screen

STATUS — The status of a transaction when external message processing is invoked.

USERID — The user ID of the Analyst who performed the action taken from the PRM_Users table. It is the ID of the analyst who initiated the action.

MasterDisp_Temp Table

A trigger on the MasterDisp table continuously captures new and modified records from the MasterDisp table and inserts them into the MasterDisp_Temp table. The MasterDisp_Temp table is similar to the MasterDisp table, but it has two additional columns, RECORD_ID and DML_OPER. The RECORD_ID column is auto-incremented and used to determine the last inserted record corresponding to every key. The DML_OPER column identifies the type of operation that was performed on the source table (that is, Insert, Update, or Delete).

The columns in the MasterDisp_Temp table (MASTERDISP_TEMP) are listed below with the data type.

Column Name	Data Type
ACTIONDATE	datetime
ACTIONID	int
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
DML_OPER	varchar(1)
ENDDATE	datetime
MOSTRECENTTXNDATE	datetime
RECORD_ID	int
SREASON_CODE	nvarchar(5)
STARTDATE	datetime
STATE	int
STATUS	int
USERID	int

Index Name: IX_MASTERDISP_TEMP

Fields: RECORD_ID
ACTION_LEVEL_KEY
ACTION_LEVEL_ID
ACTIONID

Index Name: MASTERDISP_TEMP_PK

Fields: RECORD_ID

Column Descriptions

The following are the descriptions of the MasterDisp_Temp table columns.

ACTIONDATE — The date of the disposition change.

ACTIONID — The action ID from the ActionType table.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

1 = CARD action level

2 = MERCHANT action level

3 = UAN action level

4 = TERMINAL action level

5 = EMPLOYEE action level

6 = UAID action level

7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the Master tables. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and is used to determine what type of value is stored in ACTION_LEVEL_KEY.

DML_OPER — Identifies the type of operation performed on the source table (that is, Insert, Update, or Delete).

ENDDATE — The date when automatic actions will end (Ice, Suspend).

MOSTRECENTTXNDATE — The most recent transaction for the SM_KEY when an action is taken.

RECORD_ID — A value used to determine the last inserted record corresponding to every key. The value in this column is incremented automatically.

SREASON_CODE — The reason code for an action.

STARTDATE — The date when automatic actions will start (Ice, Suspend).

STATE — The state of the action.

Valid values are as follows:

0 = Do not activate button

1 = Activate button on PRM GUI screen

STATUS — The status of a transaction when external message processing is invoked.

USERID — The user ID of the analyst who performed the action taken from the PRM_Users table. It is the ID of the analyst who initiated the action.

PrmMenu Table

The PrmMenu table is used by the Analysis and Review system. It defines the buttons on the User Interface screen.

The columns in the PrmMenu table (PRMMENU) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACCELERATOR	int
CAPTION	nvarchar(255)
CLASSNAME	varchar(255)
DEFORDER	int
HOTKEY	int
ID	int

Column Name	Data Type
INITCLASS	varchar(255)
ISCENTERED	smallint
ISINITONLY	smallint
ISPARENT	smallint
ISSEPARATOR	smallint
ISSINGLE	smallint
ISVISIBLE	int
LISTENER	varchar(255)
NAME	varchar(255)
PARENTID	int
PERMISSION_ID	int
TOOLTIP	nvarchar(255)

Index Name: **IDX_PRMMENU_CLUSTER**

Fields: ID

Index Name: **IX_PERMISSIONS**

Fields: PERMISSION_ID

Column Descriptions

The following are the descriptions of the PrmMenu table columns.

ACCELERATOR — The ASCII value of the shortcut assign to the PrmMenu item.

CAPTION — The caption shown on the GUI screen when the cursor is placed over the item (that is, file).

CLASSNAME — The associated Java class file called when the key is pressed.

DEFORDER — The order of display within each parent caption.

HOTKEY — The hot key for the menu item.

ID — The menu identifier.

INITCLASS — The class called to initialize the menu item.

ISCENTERED — Indicates whether the item is centered.

ISINITONLY — Indicates whether the item is to be initialized only.

ISPARENT — Indicates whether a row is the main selection or a sub-selection.

ISSEPARATOR — Indicates whether the item is a separator.

ISSINGLE — Indicates a single instance of the item.

ISVISIBLE — A value that determines whether a menu item is displayed or not.

Valid values are:

0 = Do not display menu item.

1 = Display menu item.

LISTENER — The listener assigned to the menu item.

NAME — The name of the menu item.

PARENTID — The parent ID of the menu item.

PERMISSION_ID — The unique identifier of a permission.

TOOLTIP — A description display when you hover over an option.

PRM_Dictionary Table

PRM_DICTIONARY is used by Proactive Manager and Analysis and Review systems. It is used to display/translate words used in static queries

The columns in the PRM_Dictionary table (PRM_DICTIONARY) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
L10N_ID	int
WORD	varchar(100)

Column Descriptions

The following are the descriptions of the PRM_Dictionary table columns.

L10N_ID — ID linked to L10N_PROPERTY table used to obtain value to displayed for WORD string

WORD — Word used to display/translate

PRM_Field Table

The PRM_Field table contains a list of all the fields that can be used in the ACI Proactive Risk Manager user interface.

The table contains three types of fields:

- Fields from the Detail table
- Fields from the Master tables
- Fields from other tables that are returned by the database views and are used to display in the user interface screens

The columns in the PRM_Field table (PRM_FIELD) are listed below with the data type.

Column Name	Data Type
DEFAULT_FORMAT_ID	numeric
DEFAULT_MASKING_ID	numeric
FIELD_ID	numeric
FIELD_NAME	varchar(50)
FIELD_TYPE	numeric
INTERNAL_PRM_COLUMN	int
ORIGINAL_NAME_L10N	int
VISIBLE_SCREEN_CONFIG	int

Index Name: IX_1_PRM_FIELD

Fields: DEFAULT_FORMAT_ID

Index Name: IX_2_PRM_FIELD

Fields: DEFAULT_MASKING_ID

Index Name: UX_3_PRM_FIELD

Fields: FIELD_NAME

Index Name: PK_PRM_FIELD

Fields: FIELD_ID

Column Descriptions

The following are the descriptions of the PRM_Field table columns.

DEFAULT_FORMAT_ID — The format identifiers that indicate the default format to be used on the field if no other formats are configured.

DEFAULT_MASKING_ID — The masking identifiers that indicate the default masking to be used on the field if no other mask is configured.

FIELD_ID — A numeric ID for the field names.

FIELD_NAME — A unique list of field names that can be used to display in the Proactive Risk Manager user interface.

FIELD_TYPE — A numeric value to indicate the type of field to display in the Proactive Risk Manager user interface.

Valid values are as follows:

- 0 = Column coming from Master tables
- 1 = Column coming from Detail table
- 2 = Column coming from database views

INTERNAL_PRM_COLUMN — Indicates whether a field is needed by the UI client to function properly and is needed even if the field is disabled by using the Screen Configuration functionality.

Valid values are:

- 0 = Is not internal PRM column
- 1 = Is internal PRM column

ORIGINAL_NAME_L10N — The original name of a field. The value is used in the Screen Configuration functionality, demographic fields tab, when the field is selected in the "Database column" drop-down field and populates the "Original Field Name" and "Displayed field name" cells.

VISIBLE_SCREEN_CONFIG — Indicates whether a field will be displayed by the Screen Configuration functionality. Some fields which are internal to PRM (so they have INTERNAL_PRM_COLUMN = 1) also need to be displayed by the Screen Configuration functionality (for example, SD_TIEBREAKER), and other fields do not need to be displayed (for example,

ND_PAN_IS_KEY).

Valid values are:

- 0 = Field will not be displayed by Screen Configuration
- 1 = Field will be displayed by Screen Configuration

PRM_UI_Component Table

The PRM_UI_Component table is used by the ACI Proactive Risk Manager application to configure the user interface screens for the Analysis and Review system.

The types of components stored in this table are:

- Screen
- Grid
- TabPanel
- Field
- Form
- Container
- Label

A component can be the parent of other component(s).

The columns in the PRM_UI_Component table (PRM_UI_COMPONENT) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	numeric
ACTION_LEVEL_TYPE	numeric
COMPONENT_ID	numeric
COMPONENT_NAME	varchar(100)

Column Name	Data Type
COMPONENT_TYPE	varchar(30)
DESCRIPTION	nvarchar(255)
ORDER_NUM	numeric
ORIGINAL_NAME_L10N	numeric
PARENT_ID	numeric
TEXT_L10N	numeric
TOOLTIP	nvarchar(100)
VISIBLE	numeric

Index Name: IX_1_PRMUI_COMP

Fields: PARENT_ID

Index Name: IX_2_PRMUI_COMP

Fields: COMPONENT_TYPE

Index Name: IX_3_PRMUI_COMP

Fields: ACTION_LEVEL_ID

Index Name: PK_PRMUI_COMPONENT

Fields: COMPONENT_ID

Column Descriptions

The following are the descriptions of the PRM_UI_Component table columns.

ACTION_LEVEL_ID — A numeric value used to optionally identify the action level that the component is assigned to.

ACTION_LEVEL_TYPE — Indicates whether a component is related to a cross action level review screen or an action level review screen. The cross action level review screens are the Device, IP, and Payee review screens.

Valid values are:

- 0 = Component is displayed in an action level review screen
- 1 = Component is displayed in a cross action level review screen

COMPONENT_ID — The unique numeric values used to identify a component.

COMPONENT_NAME — The name of the component used in the user interface.

COMPONENT_TYPE — The text name of the component type.

Valid values are as follows:

- Screen
- Grid
- TabPanel
- Field
- Form
- Container
- Label

DESCRIPTION — The description of the component.

ORDER_NUM — The numeric value to be used to assign the order in which components appear on the screen.

ORIGINAL_NAME_L10N — The numeric ID of the original L10N property.

PARENT_ID — A numeric value of the parent component used in the user interface.

TEXT_L10N — The numeric ID of the L10N property.

TOOLTIP — The text of the tool tip to be displayed in the user interface when the user hovers the

mouse over a user interface component.

VISIBLE — The indicator to determine if the component is visible on the user interface or not.

Valid values are as follows:

0 = Not visible

1 = Visible

PRM_UI_Component_Type Table

The PRM_UI_Component_Type table is used by the ACI Proactive Risk Manager application to configure the type of components that are used in the user interface screens for the Analysis and Review system.

The types of components stored in this table are:

- Screen
- Grid
- TabPanel
- Field
- Form
- Container
- Label

The columns in the PRM_UI_Component_Type table (PRM_UI_COMPONENT_TYPE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
COMPONENT_TYPE	varchar(30)
DESCRIPTION	nvarchar(255)

Index Name: **PK_PRM_UI_COMP_TP**

Fields: COMPONENT_TYPE

Column Descriptions

The following are the descriptions of the PRM_UI_Component_Type table columns.

COMPONENT_TYPE — A unique name value used to identify a component type.

Valid values are as follows:

- Screen
- Grid
- TabPanel
- Field
- Form
- Container
- Label

DESCRIPTION — The description of the component type used in the user interface.

PRM_UI_Datasource Table

The PRM_UI_Datasource table is used by the ACI Proactive Risk Manager application to configure SQL queries as data sources to different grids in the user interface screens for the Analysis and Review system.

Note: This table is reserved for future use.

The columns in the PRM_UI_Datasource table (PRM_UI_DATASOURCE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DATASOURCE_ID	numeric
SQL_TEXT	nvarchar(2000)

Index Name: **PK_PRM_UI_DS**

Fields: DATASOURCE_ID

Column Descriptions

The following are the descriptions of the PRM_UI_Datasource table columns.

DATASOURCE_ID — A unique numeric value used to identify an SQL query text used as a data source for a user interface panel.

SQL_TEXT — The text of an SQL query used in the user interface to populate a panel.

PRM_UI_Field Table

The PRM_UI_Field table is used by the ACI Proactive Risk Manager application to configure the fields that appear on user interface screens for the Analysis and Review system.

The columns in the PRM_UI_Field table (PRM_UI_FIELD) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ALIGNMENT	numeric
COMPONENT_ID	numeric
EDITABLE	numeric
FIELD_ID	numeric
FILTER	numeric
FORMAT_ID	numeric
HYPERLINK	varchar(50)
HYPERLINK_TYPE	numeric
L10N_ENABLED	numeric
LABELID	numeric

Column Name	Data Type
MASKING_ID	numeric
NULLDISPLAY	varchar(15)
WIDTH	numeric
ZERODISPLAY	varchar(15)

Index Name: **IX_1_PRMUI_FLD**

Fields: FIELD_ID

Index Name: **IX_2_PRMUI_FLD**

Fields: FORMAT_ID

Index Name: **IX_3_PRMUI_FLD**

Fields: MASKING_ID

Index Name: **PK_PRMUI_FIELD**

Fields: COMPONENT_ID

Column Descriptions

The following are the descriptions of the PRM_UI_Field table columns.

ALIGNMENT — A numeric value to indicate the field alignment.

Valid values are as follows:

- 0 = Left justified
- 1 = Right justified
- 2 = Centered

COMPONENT_ID — A unique numeric value used to identify a component.

EDITABLE — The indicator to determine if the component is editable on the user interface or not.

Valid values are as follows:

- 0 = False

1 = True

FIELD_ID — The name ID of the PRM_Field table that identifies a field used in the user interface.

FILTER — A numeric value to indicate whether the field can be used to filter the data shown in the user interface.

Valid values are as follows:

0 = False

1 = True

FORMAT_ID — A numeric value of the parent format in the PRM_UI_Field_Format table.

HYPERLINK — The field name to be used to display as a hyperlink. When you click this hyperlink, the review screen associated with the action level key in the hyperlink is displayed.

HYPERLINK_TYPE — A numeric value used to optionally identify a hyperlink is available for the field described in the HYPERLINK field.

L10N_ENABLED — A numeric value to indicate whether the value returned by a query is internationalized.

LABELID — The numeric value for the component type of label which will be assigned to the component ID of the corresponding field.

MASKING_ID — The numeric value of the parent masking ID in the PRM_UI_Masking table.

NULLDISPLAY — The string that will be displayed when the field returns a NULL value.

WIDTH — The numeric value to be used to assign the column width on the user interface.

ZERODISPLAY — The string that will be displayed when the field returns a zero value.

PRM_UI_Field_Format Table

The PRM_UI_Field_Format table is used by the ACI Proactive Risk Manager application to configure how data will appear on user interface screens for the Analysis and Review system.

The columns in the PRM_UI_Field_Format table (PRM_UI_FIELD_FORMAT) are listed below with the data type.

Column Name	Data Type
FORMATSTRING	varchar(255)
FORMATTYPE	int
FORMAT_ID	numeric

Index Name: **PK_PRMUI_FIELD_FMT**

Fields: FORMAT_ID

Column Descriptions

The following are the descriptions of the PRM_UI_Field_Format table columns.

FORMATSTRING — A string that describes the format used on the field values. Note that not all FORMATTYPE values can have a FORMATSTRING value.

If the FORMATTYPE value is 1, this column will contain one of the following values:

- DATE.MEDIUM -The name of the month will be shortened, for example, June 30, 2015 will be displayed as Jun 30, 2015.
- DATETIME.MEDIUM.MEDIUM - The data will be formatted as a medium date and medium time (includes seconds), for example, June 30, 2015 7h 3m 47s AM for "en_US" locale will be formatted as Jun 30, 2015 7:03:47 AM.
- DATETIME.SHORT.SHORT - The data will be formatted as a short date and short time (excludes seconds), for example, June 30, 2015 7h 3m 47s AM for "en_US" locale will be formatted as 6/30/15 7:03 AM.
- DATETIME.SHORT.MEDIUM - The data will be formatted as a short date and medium time (includes seconds), for example, June 30, 2015 7h 3m 47s AM for "en_US" locale will be formatted as 6/30/15 7:03:47 AM.
- MMM yyyy
- yyyy-MM-dd hh:mm:ss a

- NULL - The data will be formatted as a short date and medium time (includes seconds), for example, June 30, 2015 7h 3m 47s AM for "en_US" locale will be formatted as 6/30/15 7:03:47 AM.

To see how the date and datetime values are displayed for the other FORMATSTRING values, and also for formats that are not present but can be used in PRM, you can consult <https://docs.oracle.com/javase/tutorial/i18n/format/dateintro.html>.

If the FORMATTYPE value is 3 or 6, this column will contain one of the following values:

- NULL - If FORMATSTRING is NULL, then the currency is displayed using the user's LOCALE set in the PRM_USERS.LOCAL_ID column. No currency symbol will be displayed for either FORMATTYPE 3 or 6.

Example:

1,131.75 in en_US locale 1.131,75 in ro_RO locale

- A locale string, such as "en_US" or "ro_RO"

Example for FORMATTYPE of 3:

\$1,131.75 (en_US)

1.131,75 LEI (ro_RO)

Example for FORMATTYPE of 6:

1,131.75 (en_US)

1.131,75 LEI (ro_RO)

- A currency code, such as "USD" or "RON"

Example for FORMATTYPE of 3:

USD : \$1,131.75

RON : RON1.131,75

Example for FORMATTYPE of 6:

USD : 1,131.75

RON : 1.131,75

FORMATTYPE — A numeric value to indicate the format type.

Valid values are as follows:

- 0 = String field
- 1 = Date field
- 2 = Number field
- 3 = Currency field
- 4 = Boolean field
- 5 = Image field
- 6 = Currency field without symbol
- 7 = Checkbox field
- 8 = Hyperlink field
- 9 = Truncated field

FORMAT_ID — A unique numeric value to identify a specific format type and description.

PRM_UI_Field_Search Table

The PRM_UI_Field_Search table is used by the ACI Proactive Risk Manager application to configure the search validation configurations that are used in the search screen.

The columns in the PRM_UI_Field_Search table (PRM_UI_FIELD_SEARCH) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
COMPONENT_ID	numeric
MAXCHAR	numeric
SEARCH_ASSOCIATION	varchar(250)
VALIDATION_DEPENDENCY	varchar(100)
VALIDATION_WILDCARD	smallint

Index Name: PK_PRM_UI_SRCH

Fields: COMPONENT_ID

Column Descriptions

The following are the descriptions of the PRM_UI_Field_Search table columns.

COMPONENT_ID — The unique numeric values used to identify a component's field search validations.

MAXCHAR — The maximum number of characters that the user can enter in the input fields from the Search screens.

SEARCH_ASSOCIATION — Indicates whether a field that can be used in the Search screen (to search for action level keys) has an associated field. If a field has an associated field and the user searches for all action level keys with a given value for the original field, then the UI will also display all action level keys which have the same searched value for the associated field. For example, the SM_PRI_FIRST_NAM field has SM_SEC_FIRST_NAM as an associated field, and when the user searches for all accounts for which "First name" is 'John'(that is, SM_PRI_FIRST_NAM = 'John'), the UI will also return all accounts for which "Secondary First Name" is 'John' (that is, SM_SEC_FIRST_NAM = 'John').

VALIDATION_DEPENDENCY — The name of the database field which will also be required to be provided so the search can be executed.

VALIDATION_WILDCARD — A numeric value which will be the minimum number of characters needed to perform the search.

PRM_UI_Gridbag_Config Table

The PRM_UI_Gridbag_Config table is used by the ACI Proactive Risk Manager application. It contains a list of the field components in the Master table displayed on the upper portion of the Analysis and Review system.

Note: These columns are standard Java Swing Gridbag parameters.

The columns in the PRM_UI_Gridbag_Config table (PRM_UI_GRIDBAG_CONFIG) are listed below with the data type.

Column Name	Data Type
ANCHOR	varchar(25)
COMPONENT_ID	numeric
FILL	varchar(25)
GRIDHEIGHT	numeric
GRIDWIDTH	numeric
GRIDX	numeric
GRIDY	numeric
IPADX	numeric
IPADY	numeric
WEIGHTX	numeric
WEIGHTY	numeric

Index Name: **PK_PRM_UI_GRIDBAG_CONFIG**

Fields: COMPONENT_ID

Column Descriptions

The following are the descriptions of the PRM_UI_Gridbag_Config table columns.

ANCHOR — The anchor value of the gridbag layout. Examples of valid values are: NORTH, SOUTH, EAST, WEST, and NORTHWEST.

COMPONENT_ID — The numeric value of the component ID.

FILL — The fill value.

Valid values are as follows: NONE, HORIZONTAL, and RELATIVE.

GRIDHEIGHT — A numeric value to define the height of the grid component. Any numeric value that is equal to or greater than 1 is valid.

GRIDWIDTH — A numeric value to define the width of the grid component. Any numeric value that is equal to or greater than 1 is valid.

GRIDX — The Grid x value of the gridbag configuration. Any numeric value that is equal to or greater than 1 is valid.

GRIDY — The Grid y value of the gridbag configuration. Any numeric value that is equal to or greater than 1 is valid.

IPADX — The Ipad x value

IPADY — The Ipad y value.

WEIGHTX — The Weight x value of the gridbag configuration. The valid values are any positive numeric values (in pixels).

WEIGHTY — The Weight y value of the gridbag configuration. The valid values are any positive numeric values (in pixels).

PRM_UI_Grid_Config Table

The PRM_UI_Grid_Config table is used by the ACI Proactive Risk Manager application to configure the tabs that appear in the transaction grid components. The tabs appear on user interface screens for the Analysis and Review system.

The columns in the PRM_UI_Grid_Config table (PRM_UI_GRID_CONFIG) are listed below with the data type.

Column Name	Data Type
ACCOUNTSOURCEKEY	numeric
ADD_PORTFOLIO_ID_PARAM	numeric
ADD_USER_PARAM	numeric
COMPONENT_ID	numeric
FILTERING	numeric
LOGACTION	numeric
MAXROWS	varchar(255)
ORDERBYPF	numeric
ORDERBYPFDIRECTION	numeric
PAGEFIELD	varchar(30)
PARAMNAME	varchar(50)
PARAMTYPE	numeric
PARTITION_PAGING	numeric
PARTITION_TABLE_NAME	varchar(30)
PF_FORMATTYPE	numeric
RCNT_TXN_DATE_IND	varchar(1)
SELECT_COLUMNS	varchar(4000)

Column Name	Data Type
SHOW_TOTAL_PAGES	numeric
SHOW_USER_DEF_INPUT	numeric
SOURCE	nvarchar(255)
SOURCEKEY	varchar(255)
SOURCE_ALIAS	varchar(10)
SQLOPERATOR	varchar(50)
SUBTYPE	numeric
SUMFIELD	varchar(255)
SYSTEMFIELDLINK	varchar(255)
UNIQUEFIELDS	varchar(255)
UNIQUEINDEX	varchar(255)

Index Name: **PK_PRMUI_GRID_CONFIG**

Fields: COMPONENT_ID

Column Descriptions

The following are the descriptions of the PRM_UI_Grid_Config table columns.

ACCOUNTSOURCEKEY — A numeric value that indicates whether the account number is used to build the SQL statement. If this column is not set, the SQL statement is built using an input parameter from the user interface.

Valid values are as follows:

NULL = Value not needed by UI

0 = User input

- 1 = Action Level ID and Action Level Key
- 2 = Action Level ID and Action Level Key and User ID
- 4 = No WHERE clause

ADD_PORTFOLIO_ID_PARAM — A numeric value used to add portfolio identifier to the where clause of an SQL statement.

Valid values are as follows:

- 0 = Parameter will not be added
- 1 = Parameter will be added

ADD_USER_PARAM — A numeric value to separate passing the Account Source Key and User. This string is used to pass the column to be checked for the user ID.

Valid values are as follows:

- 0 = Parameter will not be added
- 1 = Parameter will be added

COMPONENT_ID — The unique numeric values used to identify a component's gridbag configuration.

FILTERING — A numeric value to indicate whether filtering is enabled for this tab.

Valid values are as follows:

NULL = Unassigned

- 0 = False
- 1 = True

LOGACTION — A numeric value to indicate whether the log export action is enabled or not.

Valid values are as follows:

- 0 = False
- 1 = True

MAXROWS — The number of rows to be displayed on the transaction grid. This value can be

increased so that all of the transactions are returned. If this column is set to 0, the default of 100 rows is used. If this column is set to -1, all rows are returned.

ORDERBYPF — A numeric value used to build the SQL statement for retrieving a page of data.

ORDERBYPFDIRECTION — A numeric value to indicate the order in which the alerts are displayed.

Valid values are as follows:

- 0 = Ascending order
- 1 = Descending order

PAGEFIELD — The name of the transaction field by which the tab sorts the pages.

PARAMNAME — A comma-delimited list of field names that are used as parameters in the query.

PARAMTYPE — A numeric indicator to determine the data type of the parameter.

Valid values are as follows:

NULL = Value not needed by UI

- 0 = String field
- 1 = Date field
- 2 = Number field
- 3 = Currency field
- 4 = Boolean field
- 5 = Image field
- 6 = Currency no symbol field
- 9 = BigInt field
- 10 = Only date field (no time)

PARTITION_PAGING — A numeric value to indicate whether partition paging is allowed.

Valid values are as follows:

NULL = False (Partition paging is not used)

0 = False (Partition paging is not used)

1 = True (Partition paging is used)

PARTITION_TABLE_NAME — The name of the table stored in the CLEANUP_TABLES.TABLENAME column.

PF_FORMATTYPE — A numeric value to indicate the page field format type for the transaction grid.

Valid values are as follows:

0 = String

1 = Date

2 = Number

6 = Currency, NULL

RCNT_TXN_DATE_IND — A flag indicating which components (tabs) are taken into consideration to populate MOST_RCNT_TRAN_DATE field. It should be populated with 1 for the both components (that is, Txn-All and Txn-Summary tabs) for all action levels and 0 for the other components.

SELECT_COLUMNS — The comma-delimited list of columns that will be selected from the DB view (used to populate the grid).

SHOW_TOTAL_PAGES — A numeric value that controls whether the total number of pages will be displayed on the user interface.

Valid values are as follows:

0 = False

1 = True

SHOW_USER_DEF_INPUT — A numeric value to indicate whether user input fields are hidden on the filter panel.

Valid values are as follows:

0 = False

1 = True

SOURCE — The view from which the tab data is derived.

SOURCEKEY — The description of the SystemField link.

SOURCE_ALIAS — The name of the alias used in the SQL statement.

SQLOPERATOR — The text that is used to form the SQL statement used to retrieve a page of data.

SUBTYPE — A numeric value that indicates the name of the subtype. Valid values are as follows: NULL; all values different from NULL are controlled by the JAVA UI code.

SUMFIELD — The name of the transaction field used to sum and display at the top of each transaction page.

SYSTEMFIELDLINK — The field in the SystemFields table which indicates the account key type.

UNIQUEFIELDS — The name of the view which returns the unique fields of the tabs.

UNIQUEINDEX — The fields that uniquely identify a record into the corresponding view. This field is used when navigating through pages, so it should contain all the needed fields to uniquely identify the record. Each table/view may have its own field combination to identify a certain record, and thus the corresponding UNIQUEINDEX may be different.

- The pattern is FIELD_NAME;FIELD_TYPE;ORDER BY CLAUSE.
- When no view is needed (PRM_UI_GRID_CONFIG.SOURCE=NO_VIEW_NEEDED), the UNIQUEINDEX field is null.
- DD_TXN_ID is an auto incremental field, but for detail views add the DD_PARTITION_DATE and DD_DATE for better table index usage.

PRM_UI_Masking Table

The PRM_UI_Masking table is used by the ACI Proactive Risk Manager application to configure the

masks that can be assigned to user interface components.

The columns in the PRM_UI_Masking table (PRM_UI_MASKING) are listed below with the data type.

Column Name	Data Type
MASKING_ID	numeric
MASK_CHAR	nvarchar(1)
UNMASK_LEFT	int
UNMASK_RIGHT	int

Index Name: **PK_PRM_UI_MASK**

Fields: MASKING_ID

Column Descriptions

The following are the descriptions of the PRM_UI_Masking table columns.

MASKING_ID — A unique numeric value used to identify a masking configuration.

MASK_CHAR — The character used to mask the column data values.

UNMASK_LEFT — A numeric value to define the leftmost x characters as unmasked.

UNMASK_RIGHT — A numeric value to define the rightmost x characters as unmasked.

PRM_UI_Panel Table

The PRM_UI_Panel table is used by the ACI Proactive Risk Manager application to configure the fields that appear on user interface screens for the Analysis and Review system.

The columns in the PRM_UI_Panel table (PRM_UI_PANEL) are listed below with the data type.

Column Name	Data Type
COMPONENT_ID	numeric
DATASOURCE_ID	numeric
PANEL_TYPE	varchar(30)

Index Name: **IX_1_PRMUI_PANEL**

Fields: DATASOURCE_ID

Index Name: **PK_PRM_UI_PANEL**

Fields: COMPONENT_ID

Column Descriptions

The following are the descriptions of the PRM_UI_Panel table columns.

COMPONENT_ID — Contains a numeric value of the component ID for the panel used in the user interface.

DATASOURCE_ID — Contains a numeric value of the datasource identifier for the panel component.

PANEL_TYPE — Contains a description of the panel type. The valid value is GRID.

ReportCategory Table

The ReportCategory table is used by the Analysis and Review system and stores report categories. A category is a “parent” in the reports menu.

Note: If a report category contains only one item, it will be listed as a menu item in the reports menu. It will not be listed as a parent menu.

The columns in the ReportCategory table (REPORTCATEGORY) are listed below with the data type.

Column Name	Data Type
LID	int
SDESCRIPTION	int

Index Name: **IDX_REPORTCATEGORY**

Fields: LID

Column Descriptions

The following are the descriptions of the ReportCategory table columns.

LID — The report category ID.

SDESCRIPTION — The numeric identifier for the localized name of description of the report category. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

ReportCategoryLink Table

The ReportCategoryLink table is used by the Analysis and Review system. This table is used to define a link between a report and a report category.

Note: A report must belong to a category. If a report is not required to belong to a category, it may be listed as a single item in the report menu by adding it to a category with the same name.

The columns in the ReportCategoryLink table (REPORTCATEGORYLINK) are listed below with the data type.

Column Name	Data Type
LCATEGORYID	int
LID	int
LREPORTID	int

Index Name: **IDX_REPORTCATEGORYLINK**

Fields: LID

Column Descriptions

The following are the descriptions of the ReportCategoryLink table columns.

LCATEGORYID — The LID column from the ReportCategory table.

LID — The report category link ID.

LREPORTID — The LID column from the Reports table.

ReportFonts Table

The ReportFonts table is used for overriding the hard-coded fonts from the Jasper reports when the reports are opened. For every font from every report, a replacing font can be set for report output and another one for the PDF report.

The columns in the ReportFonts table (REPORTFONTS) are listed below with the data type.

Column Name	Data Type
BISBOLD	int
BISDEFAULT	int
BISITALIC	int
BISPDFEMBEDDED	int
BISSTRIKETHROUGH	int
BISUNDERLINE	int
LREPORTID	int

Column Name	Data Type
LSIZE	int
SFONTNAME	nvarchar(50)
SNAME	nvarchar(50)
SPDFENCODING	nvarchar(50)
SPDFFONTNAME	nvarchar(50)

Index Name: **IDX_REPORTFONTS_UNIQUE**

Fields: SNAME

 LREPORTID

Column Descriptions

The following are the descriptions of the ReportFonts table columns.

BISBOLD — A flag for marking whether the font is to be replaced with a bold font (for example, **bold**).

Valid values are:

0 = No

1 = Yes

BISDEFAULT — A flag for marking whether the font is the default value to display in reports.

Valid values are:

0 = No

1 = Yes

BISITALIC — A flag for marking whether the font is to be replaced with an italicized font (for example, *italicized*).

Valid values are:

0 = No

1 = Yes

BISPDFEMBEDDED — A flag for marking whether the new font is to be embedded in the PDF.

Valid values are:

0 = No

1 = Yes

BISSTRIKETHROUGH — A flag for marking whether the font is to be replaced with a strikethrough font (for example, ~~strikethrough~~).

Valid values are:

0 = No

1 = Yes

BISUNDERLINE — A flag for marking whether the font is to be replaced with an underlined font (for example, underlined).

0 = No

1 = Yes

LREPORTID — The report ID for the report where the override is made. It is the ID of the report from Reports table.

LSIZE — The size in pixels for the new font.

SFONTNAME — The replacing font name.

SNAME — The name of the original font from the report that must be overridden.

SPDFENCODING — The encoding for the font if the report is output as PDF.

SPDFFONTNAME — The font name for the report if the report is output as PDF.

Reports Table

The Reports table is used by the Analysis and Review system. It contains the report configuration information.

The columns in the Reports table (REPORTS) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
BISDISPLAYED	smallint
LID	int
LMAXROWS	int
PERMISSION_ID	int
SNAME	nvarchar(255)
SORIENTATION	nvarchar(255)
SPACKAGENAME	varchar(255)
STITLE	int

Index Name: **IDX_REPORTS_CLUSTER**

Fields: LID

Index Name: **IDX_REPORTS_LID**

Fields: LID

SNAME

Index Name: **IX_PERMISSION**

Fields: PERMISSION_ID

Column Descriptions

The following are the descriptions of the Reports table columns.

BISDISPLAYED — A value that determines whether the report is displayed in the Reports menu

list.

Valid values are as follows:

0 = Report will not be displayed in the reports menu.

1 = Report will be displayed in the reports menu.

LID — The unique ID of the report.

LMAXROWS — The maximum number of rows that will be displayed in a report. A value of 0 or less will have no restriction on the number of rows displayed. Any value greater than zero will display the set number of rows regardless of the actual size of the data set. When data is truncated, the message "The maximum number of rows was exceeded in the query used for this report. The data represented in this report uses a truncated data set" will be displayed at the top of the report.

PERMISSION_ID — The unique identifier of a permission.

SNAME — The name of the report. This name must match the java class name for the report as well as the Jasper report template name.

SORIENTATION — The page orientation of the report.

Valid values are as follows:

0 = Landscape

1 = Portrait

SPACKAGENAME — The package to which the report java class belongs. This value may be used for writing a custom report that is not part of the ACI reports package.

STITLE — The numeric identifier for the localized name of the title of the report. The locale specific value for this column can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

ReportWizardPanelLink Table

The ReportWizardPanelLink table links what wizard panels are displayed when a report is run (for

example, date range or account number).

The columns in the ReportWizardPanelLink table (REPORTWIZARDPANELLINK) are listed below with the data type.

Column Name	Data Type
LORDER	int
LREPORTID	int
LWIZARDID	int

Index Name: **IX_REPORTWIZARDPANELLINK**

Fields: LREPORTID

 LWIZARDID

Column Descriptions

The following are the descriptions of the ReportWizardPanelLink table columns.

LORDER — The order that the wizard panel ID appears when running the report.

LREPORTID — The LID column from the Reports table.

LWIZARDID — The Wizard Panel ID from the WizardPanels table.

RT_Masterdisp Table

The data in the RT_MasterDisp_Temp table is copied into the RT_MasterDisp table. The structure of the two tables is identical. After the data has been copied to the RT_MasterDisptable, customers can use it in real-time aggregates and rules.

The columns in the RT_Masterdisp table (RT_MASTERDISP) are listed below with the data type.

Column Name	Data Type
ACTIONDATE	datetime
ACTIONID	int
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
ENDDATE	datetime
MOSTRECENTTXNDATE	datetime
SREASON_CODE	nvarchar(5)
STARTDATE	datetime
STATE	int
STATUS	int
USERID	int

Index Name: **IX_RT_MASTERDISP**

Fields: ACTION_LEVEL_KEY
 ACTION_LEVEL_ID
 ACTIONID

Column Descriptions

The following are the descriptions of the RT_Masterdisp table columns.

ACTIONDATE — The date of the disposition change.

ACTIONID — The action ID from the ActionType table.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the Master tables. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and is used to determine what type of value is stored in ACTION_LEVEL_KEY.

ENDDATE — The date when automatic actions will end (Ice, Suspend).

MOSTRECENTTXNDATE — The most recent transaction for the SM_KEY when an action is taken.

SREASON_CODE — The reason code for an action.

STARTDATE — The date when automatic actions will start (Ice, Suspend).

STATE — The state of the action.

Valid values are as follows:

- 0 = Do not activate button
- 1 = Activate button on PRM GUI screen

STATUS — The status of a transaction when external message processing is invoked.

USERID — The user ID of the analyst who performed the action taken from the PRM_Users table. It is the ID of the analyst who initiated the action.

RT_Masterdisp_Temp Table

The data on the MasterDisp_Temp table is copied to the RT_MasterDisp_Temp table. The structure of the two tables is similar, except that the RT_MasterDisp_Temp table does not include the RECORD_ID column because the RT table contains only the last modification for every key.

The columns in the RT_Masterdisp_Temp table (RT_MASTERDISP_TEMP) are listed below with the data type.

Column Name	Data Type
ACTIONDATE	datetime
ACTIONID	int
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
DML_OPER	varchar(1)
ENDDATE	datetime
MOSTRECENTTXNDATE	datetime
SREASON_CODE	nvarchar(5)
STARTDATE	datetime
STATE	int
STATUS	int
USERID	int

Index Name: IX_RT_MASTERDISP_TEMP

Fields: ACTION_LEVEL_KEY
 ACTION_LEVEL_ID
 ACTIONID

Column Descriptions

The following are the descriptions of the RT_Masterdisp_Temp table columns.

ACTIONDATE — The date of the disposition change.

ACTIONID — The action ID from the ActionType table.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the Master tables. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and is used to determine what type of value is stored in ACTION_LEVEL_KEY.

dml_oper — Identifies the type of operation performed on the source table (that is, Insert, Update, or Delete).

ENDDATE — The date when automatic actions will end (Ice, Suspend).

MOSTRECENTTXNDATE — The most recent transaction for the SM_KEY when an action is taken.

SREASON_CODE — The reason code for an action.

STARTDATE — The date when automatic actions will start (Ice, Suspend).

STATE — The state of the action.

Valid values are as follows:

0 = Do not activate button

1 = Activate button on PRM GUI screen

STATUS — The status of a transaction when external message processing is invoked.

USERID — The user ID of the analyst who performed the action taken from the PRM_Users table. It is the ID of the analyst who initiated the action.

SelectListValues Table

The SelectListValues table is used by the Analysis and Review system. It defines the selections on the User Interface screen for selecting alert order.

The columns in the SelectListValues table (SELECTLISTVALUES) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
LOPTIONDATATYPE	int
LORDER	int
LSELECTID	int
MASTER_DETAIL_FLAG	int
SALERTSFIELD	varchar(50)

Column Name	Data Type
SID	varchar(50)
SOPTIONNAME	int
SOPTIONVARIABLEVALUE	varchar(50)
SPAGEFIELD	varchar(50)
STABLEFIELD	varchar(50)

Index Name:

idx_Nonclustered_SELECTLISTVALUES_SOPTIONVALUE_ACTION_LEVEL_ID

Fields: SALERTSFIELD

ACTION_LEVEL_ID

Column Descriptions

The following are the descriptions of the SelectListValues table columns.

ACTION_LEVEL_ID — Contains a distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

LOPTIONDATATYPE — Contains the data type of the column pointed to by SOPTIONVALUE.

LORDER — The order in which the field should be displayed.

LSELECTID — The unique ID for the select list.

MASTER_DETAIL_FLAG — Indicates whether the column belongs to the Master or Detail table.

Valid values are:

0 = Detail table column

1 = Action level Master table column

SALERTSFIELD — Contains the name of the column from the ALERTS table in which the STABLEFIELD will be stored. For example, ND_UAID_NRT_RULE_SCR is stored in the RULE_SCORE column of the ALERTS table.

SID — Holds the internal ID used for PRMClient-PRMServer communication when changing alert priorities.

SOPTIONNAME — The name of the option to be displayed in the select list on the User Interface screen for alert order selection, for example, TranAmount1.

SOPTIONVARIABLEVALUE — The value for the option's variable.

SPAGEFIELD — Contains the field used for pagination in the Alerts Pending screen in the UI. This must be non-null. For example, in the PV_ALERTSPENDING view, the rule score cannot be used for pagination directly because it can contain null values. Therefore, RULE_SCORE_PAGING is used instead (coalesce(A.RULE_SCORE,0) as RULE_SCORE_PAGING).

STABLEFIELD — Contains the name of the Master or Detail column name that will be used in the ALERTS table as an ordering field for the alert priority.

Titanium_Port_Total Table

Table is used by the Web Ui Analysis and review module. It contains all transactions aggregated by date and portfolio and is used by NRT Rule Performance report. Data is aggregated by PP_TITANIUM_RULE_PERF_CALC procedure in an ETL process

The columns in the Titanium_Port_Total table (TITANIUM_PORT_TOTAL) are listed below with the data type.

Column Name	Data Type
DD_DATE	date
PORTFOLIO_ID	int
TOTAL_COUNT	bigint

Column Descriptions

The following are the descriptions of the Titanium_Port_Total table columns.

DD_DATE — Date

PORTFOLIO_ID — Portfolio ID

TOTAL_COUNT — Number of transaction

Titanium_Reports_Categories Table

The TITANIUM_REPORTS_CATEGORIES table is used by the Web Ui Analysis and review module. It contains the categories of the dashboard reports, the dashboard reports being splitted now into several categories, along with information relating to the categories permissions.

The columns in the Titanium_Reports_Categories table (TITANIUM_REPORTS_CATEGORIES) are listed below with the data type.

Column Name	Data Type
MANAGE_PERMISSION_KEY	varchar(50)
NAME	varchar(50)
TITLE_L10N	int

Column Name	Data Type
VIEW_PERMISSION_KEY	varchar(50)

Column Descriptions

The following are the descriptions of the Titanium_Reports_Categories table columns.

MANAGE_PERMISSION_KEY — Represents the permission key for managing the category of reports. Users with this permission will be able to add, edit or delete their own dashboards reports which are part of the category

NAME — A distinct text value used to uniquely identify a category of reports

TITLE_L10N — The title with which the category is displayed. It point to the L10N_PROPERTY table.

VIEW_PERMISSION_KEY — Represents the permission key for viewing the category reports. Users should have this permission to be able to view reports of the category type.

Titanium_RT_Rule_Perf Table

Table is used by the Web Ui Analysis and review module. It contains RT alerted transactions aggregated by date, portfolio and rule and is used by RT Rule Performance report. Data is aggregated by PP_TITANIUM_RULE_PERF_CALC procedure in an ETL process

The columns in the Titanium_RT_Rule_Perf table (TITANIUM_RT_RULE_PERF) are listed below with the data type.

Column Name	Data Type
DD_DATE	date
ND_REAL_TIME_RULE_FIRED	
NO_ALERTS	bigint

Column Name	Data Type
PORTFOLIO_ID	
SD_REAL_TIME_RULE_DISPOSITION	varchar(1)
TOTAL_ALERTED_AMT1	float

Index Name: **TOTAL_ALERTED_AMT1**

Fields: DD_DATE
 PORTFOLIO_ID
 ND_REAL_TIME_RULE_FIRED
 SD_REAL_TIME_RULE_DISPOSITION

Column Descriptions

The following are the descriptions of the Titanium_RT_Rule_Perf table columns.

DD_DATE — Date

ND_REAL_TIME_RULE_FIRED — RT rule fired ID

NO_ALERTS — Number of alerted rules

PORTFOLIO_ID — Portfolio ID

SD_REAL_TIME_RULE_DISPOSITION — The recommended disposition of the transaction.

TOTAL_ALERTED_AMT1 — Total amount of RT alerted rules

Titanium_Rule_Perf Table

Table used by Analysis and Review system. It contains NRT alerted transactions aggregated by date, portfolio and rule and is used by NRT Rule Performance report. Data is aggregated by PP_TITANIUM_RULE_PERF_CALC procedure in an ETL process

The columns in the Titanium_Rule_Perf table (TITANIUM_RULE_PERF) are listed below with the data type.

Column Name	Data Type
DD_DATE	date
NO_ALERTS	bigint
PORTFOLIO_ID	int
RULE_ID	
TOTAL_ALERTED_AMT1	float

Column Descriptions

The following are the descriptions of the Titanium_Rule_Perf table columns.

DD_DATE — Date

NO_ALERTS — Number of alerts

PORTFOLIO_ID — Description not available.

RULE_ID — Rule ID

TOTAL_ALERTED_AMT1 — Total alerted amoount

ToolbarButtons Table

The ToolbarButtons table is used by the Analysis and Review system. It defines the buttons on the User Interface screens (for example, edit, remind, forward, and so on).

The columns in the ToolbarButtons table (TOOLBARBUTTONS) are listed below with the data type.

Column Name	Data Type
ACTIONTYPE	int
ALTTOOLTIP	varchar(200)
CAPTION	nvarchar(40)
CLASSNAME	varchar(255)
DEFAULTORDER	int
DISPLAYMNEMONIC	int
ENABLED	smallint
FORMTYPE	int
HOTKEY	int
ICON	varchar(50)
ID	int
LISTENER	varchar(200)
NAME	varchar(20)
PERMISSION_ID	int
READONLYENABLED	smallint
SELECTABLE	smallint
SERVLETNAME	varchar(50)

Column Name	Data Type
TOOLTIP	nvarchar(200)
TYPE	int
VISIBLE	smallint

Index Name: IDX_TOOLBARBUTTONS_ACTIONTYPE

Fields: ACTIONTYPE

Index Name: IDX_TOOLBARBUTTONS_TYPE

Fields: TYPE

DEFAULTORDER

Index Name: IX_PERMISSIONS3

Fields: PERMISSION_ID

Index Name: PK_TOOLBARBUTTONS

Fields: ID

Column Descriptions

The following are the descriptions of the ToolbarButtons table columns.

ACTIONTYPE — The action type of the button.

ALTTOOLTIP — The alternate tool tip.

CAPTION — The caption of the button.

CLASSNAME — The name of the class when the button is clicked.

DEFAULTORDER — The default order of this button.

DISPLAYMNEMONIC — The display mnemonic for the button.

ENABLED — This column indicates if the button is enabled.

FORMTYPE — The form type of the button.

HOTKEY — The hot key for the button.

ICON — The name of the icon.

ID — Contains the unique ID.

LISTENER — The listener for the button.

NAME — The name of the button.

PERMISSION_ID — The unique identifier of a permission.

READONLYENABLED — Indicates whether read only is an option.

SELECTABLE — Indicates whether the button is selectable.

SERVLETNAME — The servlet called when the button is clicked.

TOOLTIP — The tooltip for the button.

TYPE — The type of the button.

VISIBLE — Indicates whether the button is visible.

Txns_Processed_Rpt Table

The Txns_Processed_Rpt table is used to populate the Transactions Processed Report. This is done by a scheduled job which calls the PP_TXNS_PROCESSED_RPT procedure using the following arguments: SOURCE_TABLE, START_DATE, and END_DATE. The report can be run only by using the Detail table as the SOURCE_TABLE parameter. When the Transaction Processed Report is run, it uses the counted number of transactions from the TRAN_COUNT column of the Txns_Processed_Rpt table without scanning the Detail table. The PP_TXNS_PROCESSED_RPT procedure which is called by the Transactions Processed Report calculates offline the transactions processed for a given period of time.

The columns in the Txns_Processed_Rpt table (TXNS_PROCESSED_RPT) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
DD_AUPDATE	datetime
PORTFOLIO	nvarchar(400)
RECORD_SOURCE_ID	smallint
TRAN_COUNT	numeric

Index Name: **IDX_TXNS_PROCESSED_RPT**

Fields: DD_AUPDATE
 RECORD_SOURCE_ID
 ACTION_LEVEL_ID
 PORTFOLIO

Column Descriptions

The following are the descriptions of the Txns_Processed_Rpt table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

1 = CARD action level

- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level
- 1 = used only to keep unique values

DD_UPDATE — The date and time that the transaction processing started in the database.

PORTFOLIO — The portfolio ID if the ACTION_LEVEL_ID is one of the values from the ACTION_LEVEL table. In case the ACTION_LEVEL_ID is -1, the PORTFOLIO field contains a list of portfolios, used to calculate only the unique transactions.

RECORD_SOURCE_ID — The identifier of the record source as defined in Analytic Gateway.

TRAN_COUNT — The number of processed transactions.

UI_External_View_Config Table

The UI_EXTERNAL_VIEW_CONFIG holds the external configuration for AR for cross action levels.

The columns in the UI_External_View_Config table (UI_EXTERNAL_VIEW_CONFIG) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
BCHECKDIRTYDATA	bit
BISACTIONABLE	bit
LACTIONLEVELID	int

Column Name	Data Type
SCOLUMNS	varchar(255)
SEXTERNALSYSTEM	varchar(50)
SFORMULAS	varchar(255)
SLOCALIZEDCOLUMNS	varchar(255)
SNAME	varchar(50)
SSEARCHKEY	nvarchar(50)
STYPE	varchar(50)

Column Descriptions

The following are the descriptions of the UI_External_View_Config table columns.

BCHECKDIRTYDATA — Specifies if the dirty data checks are enabled or disabled. Default value is 0 - disabled.

BISACTIONABLE — Specifies if the external configuration is set. The default value is 1.

LACTIONLEVELID — The ID of the action level.

SCOLUMNS — The columns from the database view used for sorting.

SEXTERNALSYSTEM — Specifies the external system. Default value is AR.

SFORMULAS — The formulas used to calculate the configured value.

SLOCALIZEDCOLUMNS — Specifies the localized columns for the AR views.

SNAME — The name of the database view containing external configuration data for AR used for cross action levels.

SSEARCHKEY — Filter expresion used in view recorded on SNAME column

STYPE — The type of configuration used for cross action levels (ALL_TRANSACTIONS, ALERTED_TRANSACTIONS, MARKED_TRANSACTIONS, ENHANCED_PROFILES, SEARCH_SCREEN, pending-alerts, action-history).

UI_KPI Table

Table UI_KPI is used to store information about the duration of preconfigured actions performed on the UI server – queries and servlets.

The columns in the UI_KPI table (UI_KPI) are listed below with the data type.

Column Name	Data Type
DURATION	bigint
END_TIME	datetime
PARAMS	varchar(Max)
SESSIONID	varchar(100)
SOURCE_ID	varchar(Max)
START_TIME	datetime
TYPE	varchar(50)

Index Name: **IDX_UI_KPI_END_TIME**

Column Descriptions

The following are the descriptions of the UI_KPI table columns.

DURATION — the duration of the query/servlet

END_TIME — the date and time when the query/servlet ended

PARAMS — the parameters that were passed to the query/nothing for the servlets at the moment

SESSIONID — The session under which a certain servlet was called. Available for calls from the swing application and from AR. For BSI, it writes the consumer ID, since we use no sessions for BSI calls.

SOURCE_ID — the string of the query that ran/the path of the servlet

START_TIME — the date and time when the query/servlet started to run

TYPE — the type of the action. Possible values: "Query"/"Servlet"

UserTableParams Table

The UserTableParams table is used by the Analysis and Review system. It contains the custom column arrangement for the transaction grid. It is used to allow users to arrange the column layout individually by logon.

Note: This table should only be modified by ACI Worldwide Inc. personnel.

The columns in the UserTableParams table (USERTABLEPARAMS) are listed below with the data type.

Column Name	Data Type
CHANGETYPE	tinyint
COLSETTINGS	varchar(Max)
FORMID	int

<i>Column Name</i>	<i>Data Type</i>
TABLEID	int
TEAMID	int
USERID	int

Index Name: **IDX_USERTABLEPARAMS_CLUSTER**

Fields: FORMID

TABLEID

TEAMID

USERID

CHANGETYPE

Column Descriptions

The following are the descriptions of the UserTableParams table columns.

CHANGETYPE — Indicates whether changes were made by the team administrator or analyst.

Valid values are as follows:

0 = Team administrator made changes

1 = Analyst made changes

COLSETTINGS — The user interface tab field order.

FORMID — The form ID.

TABLEID — The table ID.

TEAMID — The Team ID.

USERID — The User ID.

User_Date_Patterns Table

The User_Date_Patterns table is used by the Analysis and Review system. It contains various date and time formats that are available for the user and locale.

The columns in the User_Date_Patterns table (USER_DATE_PATTERNS) are listed below with the data type.

Column Name	Data Type
DATE_PATTERN	nvarchar(60)
LOCALE_ID	varchar(10)
VALIDATION_ORDER	smallint

Index Name: **PK_USER_DATE_PATTERNS**

Fields: LOCALE_ID
 DATE_PATTERN

Column Descriptions

The following are the descriptions of the User_Date_Patterns table columns.

DATE_PATTERN — The Java date pattern.

LOCALE_ID — The LOCALE_ID associated with the DATE_PATTERN. This value in this column is present in the AVAILABLE_LOCALE.

VALIDATION_ORDER — Used to determine the order that date patterns are validated.

WizardPanels Table

The WizardPanels table contains a list of wizard panels used for the report wizard.

The columns in the WizardPanels table (WIZARDPANELS) are listed below with the data type.

Column Name	Data Type
LID	int
SNAME	varchar(255)
SPACKAGENAME	varchar(255)

Index Name: **IX_WIZARDPANELS**

Fields: LID

Column Descriptions

The following are the descriptions of the WizardPanels table columns.

LID — A unique ID.

SNAME — The name of the Wizard Panel.

SPACKAGENAME — The wizard panel Java class belongs to. This value may be used for writing a custom wizard panel that is not part of the ACI package.

Profile Tables

The Profile tables contain information for reporting and analysis purposes.

The Profile tables below are described on the following pages:

- Enh_Profile_Cycle_Type
- ENH_Profile_Frequency
- ENH_Profile_Mark_Types
- ENH_Profile_New_Txns
- ENH_Profile_Setup
- ENH_Profile_Type

- ENH_Temp
- EP_Dummy
- Profile_Lookup

Enh_Profile_Cycle_Type Table

The Enh_Profile_Cycle_Type table contains the possible values for the cycle types an enhanced profile can have. The possible values are: Daily, Weekly, Semi-Monthly, Monthly, Yearly, and Perpetual. Together with cycle ID and description, this table also contains formulas to calculate the start and end dates for a cycle.

The columns in the Enh_Profile_Cycle_Type table (ENH_PROFILE_CYCLE_TYPE) are listed below with the data type.

Column Name	Data Type
CYCLE_END_DATE_EXPR	varchar(2000)
CYCLE_START_DATE_EXPR	varchar(2000)
CYCLE_TYPE_CODE	varchar(20)
CYCLE_TYPE_DESC	int
CYCLE_TYPE_ID	int

Index Name: **PK_ENH_PROFILE_CYCLE_TYPE**

Fields: CYCLE_TYPE_ID

Column Descriptions

The following are the descriptions of the Enh_Profile_Cycle_Type table columns.

CYCLE_END_DATE_EXPR — The SQL expression that returns the end date of the cycle type. The expression contains placeholders for the reference date.

CYCLE_START_DATE_EXPR — The SQL expression that returns the start date of the cycle type. The expression contains placeholders for the reference date.

CYCLE_TYPE_CODE — A descriptive string that describes the purpose of the record. It is not displayed; it is used for future development or for debug activities.

CYCLE_TYPE_DESC — An ID from the L10N_Property table containing the translated description of the cycle type. The translation associated with this ID is displayed in the user interface.

CYCLE_TYPE_ID — The primary key of the table. Its value is used as a logical foreign key by the Enh_Profile_Setup table.

Enh_Profile_Frequency Table

The Enh_Profile_Frequency table stores the frequency for enhanced profiles.

The columns in the Enh_Profile_Frequency table (ENH_PROFILE_FREQUENCY) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
CHANGED	int
LAST_FILL_ENH_TEMP_DATE	datetime
PARALLEL_ENABLED	int
PROFILE_FREQUENCY_ID	smallint
PROFILE_FREQUENCY_MINUTES	int
PROFILE_FREQUENCY_NAME	VARCHAR(50)

Column Descriptions

The following are the descriptions of the Enh_Profile_Frequency table columns.

CHANGED — Specifies if the frequency has been modified.

LAST_FILL_ENH_TEMP_DATE — Specifies the last time the data from ENH_PROFILE_NEW_TXNS table has been replicated into the ENH_TEMP table.

PARALLEL_ENABLED — Specifies if the parallel calculation is enabled at the frequency level for the enhanced profile.

PROFILE_FREQUENCY_ID — Contains the internal frequency ID for the enhanced profile.

PROFILE_FREQUENCY_MINUTES — Contains the frequency duration in minutes for the enhanced profile.

PROFILE_FREQUENCY_NAME — Contains the frequency name for the enhanced profile.

Enh_Profile_Mark_Types Table

The Enh_Profile_Mark_Types table contains the transaction mark types for each enhanced profile.

The columns in the ENH_Profile_Mark_Types table (ENH_PROFILE_MARK_TYPES) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ENH_PROFILE_ID	numeric
MARK_TYPES	varchar(4000)

Index Name: **PK_ENH_PROFILE_MARK_TYPES**

Fields: ENH_PROFILE_ID

Column Descriptions

The following are the descriptions of the ENH_Profile_Mark_Types table columns.

ENH_PROFILE_ID — The id of the enhanced profile related to the Enh_Profile_Setup table.

MARK_TYPES — The ids of the transaction mark types.

ENH_Profile_New_Txns Table

The Enh_Profile_New_Txn table contains the transactions which will be used for the enhanced profile calculation.

The columns in the ENH_Profile_New_Txns table (ENH_PROFILE_NEW_TXNS) are listed below with the data type.

Column Name	Data Type
DD_PARTITION_DATE	date
DD_SYSDATE	datetime
MARK_TYPE	int
ND_KEY_HASH	smallint
RECORD_SOURCE_ID	smallint
SD_TIEBREAKER	VARCHAR(75)
SRC_TXN_TABLE	VARCHAR(30)

Index Name: ENH_PROFILE_NEW_TXNS_CLUS_NUQ

Fields: SD_TIEBREAKER
DD_SYSDATE

Column Descriptions

The following are the descriptions of the ENH_Profile_New_Txns table columns.

DD_PARTITION_DATE — Derived from the DD_DATE or DD_APDATE column and contains only date information.

DD_SYSDATE — This is the partitioning column used for enhanced profiles.

MARK_TYPE — The type of mark used by the enhanced profile.

ND_KEY_HASH — Enables sub-partitioning on two distinct columns. If it is not used for subpartitioning, the column is populated by a constant (for example, a hashing function). If DD_DATE is used as the base for DD_PARTITION_DATE, then SD_PAN or SD_UAN is hashed. If AP_DATE is used as the base for DD_PARTITION_DATE, then SD_RETL_ID is hashed.

RECORD_SOURCE_ID — The identifier of the record source as defined in the Analytic Gateway.

SD_TIEBREAKER — A transaction field that make a transaction unique when two or more transactions have the same date and time. It is defined at installation.

SRC_TXN_TABLE — The context from which the record was inserted: a new transaction, a mark action, or an unmark action.

The valid values are: SHORTWINDOW, MARK, and UNMARK.

Enh_Profile_Setup Table

The Enh_Profile_Setup table stores the setup information for all of the enhanced profiles. The user interface inserts/updates the values in this table, and the PP_ENH_PROFILE_SETUP procedure generates or alters all the database objects needed for the enhanced profile to work.

The columns in the Enh_Profile_Setup table (ENH_PROFILE_SETUP) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTIVATE_DT	datetime
AMOUNT_FIELD	varchar(512)
CLEANUP_DT	date
CREATED_BY	int
CREATED_DT	datetime
CYCLES_RETAINED	int

Column Name	Data Type
CYCLE_FIELD	varchar(512)
CYCLE_TYPE_ID	int
ENH_PROFILE_ID	int
ENTRY_SQL	varchar(2000)
ESTIM_CYCLE_ROWS	decimal
ESTIM_ROW_SIZE	int
FREQUENCY_MOVE_DELAY_DATE	datetime
LAST_CALCULATION_DATE	datetime
MODIFIED_BY	int
MODIFIED_DT	datetime
PRIMARY_FIELD	varchar(512)
PROFILE_DESC	int
PROFILE_FREQUENCY_ID	int
PROFILE_NAME	varchar(24)
PROFILE_STATUS	varchar(1)
PROFILE_TABLE	varchar(27)
PROFILE_TYPE_ID	integer

Column Name	Data Type
REAL_CYCLE_ROWS	decimal
REAL_ROW_SIZE	int
SECONDARY_FIELD	varchar(2000)
TXN_TABLE	varchar(30)
USE_NEG_AMT	int

Index Name: **UX_ENH_PROFILE_SETUP**

Fields: PROFILE_NAME

Index Name: **PK_ENH_PROFILE_SETUP**

Fields: ENH_PROFILE_ID

Column Descriptions

The following are the descriptions of the ENH_Profile_Setup table columns.

ACTIVATE_DT — The date and time for the last time the enhanced profile was initiated. When a profile is created, it becomes immediately active and the ACTIVATE_DT field is set to the creation date and time. If the profile is modified and its data deleted, then the ACTIVATE_DT field becomes the date and time of the modification. If the profile is modified, but all of its data is kept, the ACTIVATE_DT field is kept as before (not updated). This has an impact on how the marked/unmarked transactions are treated; only the transactions that occurred in the system after the ACTIVATE_DT of a profile are considered for the profile.

AMOUNT_FIELD — The name of the field from the transactions table or Master tables used as an amount field. This is the field from which the value for SUM and STDEV (Standard Deviation) will be taken.

CLEANUP_DT — Indicates the date for cleanup.

CREATED_BY — The ID from PRM_USERS of the user who created the profile.

CREATED_DT — The date and time that the profile was created in the system.

CYCLES_RETAINED — An integer value that is used by the cleanup procedure for deleting the oldest cycles.

CYCLE_FIELD — A column of data type DATE from the transactions table or Master tables. It is used when the pp_enh_profile_calculate procedure determines the cycle to which each new transaction belongs. The length of this column is 61 because the format is: <table name>.<column name> (up to 30 characters for table name, up to 30 for column name, and 1 character for ".")

CYCLE_TYPE_ID — Identifies the type of cycle (aggregation period) used by the profile. Valid values are the IDs from the table ENH_PROFILE_CYCLE_TYPE.

ENH_PROFILE_ID — The id of the enhanced profile.

ENTRY_SQL — An SQL expression with a Boolean value to be used for filtering the transactions when calculating the enhanced profiles. Each profile can have its own entry SQL in order to qualify or not the new transactions for it.

ESTIM_CYCLE_ROWS — The estimated number of rows per cycle. It is set by the user who creates the profile.

ESTIM_ROW_SIZE — Based on the columns used in the profile and their average lengths in the data, an estimation of the storage needed for one row of information can be determined. The estimate should also include the storage needs for indexes. After some data has been generated for the profile, more accurate storage information per row can be calculated and the values for this column modified.

FREQUENCY_MOVE_DELAY_DATE — Contains the date and time when the calculation will run after changing the frequency for the enhanced profile.

LAST_CALCULATION_DATE — The last date when the calculation was run for the enhanced profile.

MODIFIED_BY — The ID from PRM_USERS of the user who last modified the profile.

MODIFIED_DT — The date and time the profile was last modified.

PRIMARY_FIELD — A name of a field from the transactions table or Master tables used as a primary aggregation field.

PROFILE_DESC — The profile description. Since this column is translated in the L10N tables, only the ID from L10N_PROPERTY is stored in the PROFILE_DESC column.

PROFILE_FREQUENCY_ID — Indicates the ID of the frequency for the profile.

PROFILE_NAME — The name of the profile. It also contains the name of the table that will be dynamically created when the profile is saved. There is a unique constraint on this column. The length restriction at 24 characters for the profile name is determined by the fact that length of the names of database objects cannot exceed 30 characters, that some derived objects will be generated for the new table (indexes, constraints), and that the name of these objects is the profile name suffixed with some strings.

PROFILE_STATUS — The status of the profile.

Valid values are:

A = Active

X = Disabled

PROFILE_TABLE — Identifies the physical table built by the system to store the data belonging to the profile. At the moment the profile is created, the profile table name is the profile name with the prefix "EP_", but this name could change over time. That is the reason for the existence of this column.

PROFILE_TYPE_ID — The id of the profile type defined in the Enh_Profile_Type table.

REAL_CYCLE_ROWS — The calculated number of rows per cycle, based on the existing data for the profile.

REAL_ROW_SIZE — The calculated row length, based on the existing data for the profile.

SECONDARY_FIELD — A name of a field from the transactions table or Master tables used as a secondary aggregation field. Instead of a simple field, a more complex expression can be set, for example, function applied on a field, field concatenation, etc., which is why the length of the field is

so large.

TXN_TABLE — The name of the transactions table used by the current enhanced profile. This value determines the table from which transactions will be selected for aggregating on profile values.

USE_NEG_AMT — Indicates whether the profile SUM will be calculated using the value or absolute value of the amount field. If this column contains 0, the profile SUM will be calculated using the absolute value of the amount field. If this column contains 1, the SUM will be calculated using the value of the amount field with sign.

ENH_Profile_Type Table

The Enh_Profile_Type table contains types of profiles used by the enhanced profile.

The columns in the ENH_Profile_Type table (ENH_PROFILE_TYPE) are listed below with the data type.

Column Name	Data Type
PROFILE_TYPE_CODE	varchar(50)
PROFILE_TYPE_DESC	numeric
PROFILE_TYPE_ID	int

Index Name: **PK_ENH_PROFILE_TYPE**

Fields: PROFILE_TYPE_ID

Column Descriptions

The following are the descriptions of the ENH_Profile_Type table columns.

PROFILE_TYPE_CODE — The value corresponding to the profile type id.

PROFILE_TYPE_DESC — The name of the localized columns for the profile type.

PROFILE_TYPE_ID — A distinct numeric value used to uniquely identify a profile type.

Valid values are:

0 = Negative profile

1 = Positive profile

ENH_Temp Table

The ENH_TEMP table contains transactions replicated from the ENH_PROFILE_NEW_TXNS table.

The columns in the ENH_Temp table (ENH_TEMP) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DD_PARTITION_DATE	date
DD_SYSDATE	datetime
MARK_TYPE	int
ND_KEY_HASH	smallint
RECORD_SOURCE_ID	smallint
SD_TIEBREAKER	VARCHAR(75)
SRC_TXN_TABLE	VARCHAR(30)

Index Name: **ENH_TEMP_CLUS_NUQ**

Fields: DD_SYSDATE

Column Descriptions

The following are the descriptions of the ENH_Temp table columns.

DD_PARTITION_DATE — Derived from the DD_DATE or DD_APDATE column and contains only date information.

DD_SYSDATE — This is the partitioning column used for enhanced profiles.

MARK_TYPE — The type of mark used by the enhanced profile.

ND_KEY_HASH — Enables sub-partitioning on two distinct columns. If it is not used for subpartitioning, the column is populated by a constant (for example, a hashing function). If DD_DATE is used as the base for DD_PARTITION_DATE, then SD_PAN or SD_UAN is hashed. If AP_DATE is used as the base for DD_PARTITION_DATE, then SD_RETL_ID is hashed.

RECORD_SOURCE_ID — The identifier of the record source as defined in the Analytic Gateway.

SD_TIEBREAKER — A transaction field that make a transaction unique when two or more transactions have the same date and time. It is defined at installation.

SRC_TXN_TABLE — The context from which the record was inserted: a new transaction, a mark action, or an unmark action.

The valid values are: SHORTWINDOW, MARK, and UNMARK.

EP_Dummy Table

The EP_Dummy table is used by the Enhanced Profiles and it stores a dummy enhanced profile.

The columns in the EP_Dummy table (EP_DUMMY) are listed below with the data type.

Column Name	Data Type
CYCLE_END_DATE	datetime
CYCLE_START_DATE	datetime
MARK_TYPE	integer

Column Name	Data Type
PRIMARY_FIELD	varchar(50)
SECONDARY_FIELD	varchar(5)
TXNS_AMOUNT	money
TXNS_COUNT	int
TXNS_MAX_AMOUNT	money
TXNS_MAX_DATE	datetime
TXNS_MIN_AMOUNT	money
TXNS_MIN_DATE	datetime
TXNS_STD_DEV	float

Column Descriptions

The following are the descriptions of the EP_Dummy table columns.

CYCLE_END_DATE — The end date of the enhanced profile calculation.

CYCLE_START_DATE — The start date of the enhanced profile calculation.

MARK_TYPE — The transaction mark types.

PRIMARY_FIELD — The primary field for the enhanced profile.

SECONDARY_FIELD — The secondary field for the enhanced profile.

TXNS_AMOUNT — The transaction amount for the enhanced profile calculation.

TXNS_COUNT — The number of transactions for the enhanced profile calculation.

TXNS_MAX_AMOUNT — The maximum amount.

TXNS_MAX_DATE — The maximum date of the transactions for the enhanced profile calculation.

TXNS_MIN_AMOUNT — The minimim amount.

TXNS_MIN_DATE — The minimim date of the transactions for the enhanced profile calculation.

TXNS_STD_DEV — The standard deviation.

Profile_Lookup Table

The Profile_Lookup table is used by the Analysis and Review system. Institutions may assign customers to different categories or groups for a variety of business requirements, for example, marketing strategies, geographical location, socioeconomic levels or risk factors. These “profiling groups” can be useful for risk analysis within the PRM product. Comparisons can be made between an individual accountholder’s transaction activity and the daily or average activity of the peer profiling group to which the accountholder belongs.

PRM allows for a large dynamic institution-defined list of peer profile groups that are derived from a variable set of fields sent to PRM in the transaction input format file. The peer profile groups are calculated by a combination of the fields from the transaction and institution-defined risk factors defined in a lookup table. PRM can then store daily statistics for a defined profile group on each day. These statistics can then be used to compare individual customer activity to typical activity for that customer’s profiling group.

Peer group profiling statistics can be used in profile rule writing to compare accountholder activity to the relevant profile group activity. Peer group profile statistics are displayed on the account review screen.

The data in the Profile_Lookup table is defined by the institution.

The columns in the Profile_Lookup table (PROFILE_LOOKUP) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
SLOOKUP	varchar(30)
SRISK	varchar(3)

Index Name: **IDX_PROFILE_LOOKUP**

Fields: SLOOKUP

Column Descriptions

The following are the descriptions of the Profile_Lookup table columns.

DTDATE — The date the risk value was changed.

SLOOKUP — The look up value. The values in this column correspond to the values in the input layout specified by the ProfileGroupLookUpArg value in the Analytic Gateway DEF file.

SRISK — The risk value.

Role Configuration Tables

The Role Configuration tables contain values for roles displayed on the Analysis and Review screen.

The following Role Configuration tables are described on the following pages:

- PrmRolePerms
- PrmRoles
- Role_Template
- Role_Template_Permission
- Role_Tran_Type
- Tran_Type

PrmRolePerms Table

The PrmRolePerms table is used by the Analysis and Review system. This table sets all menu permissions. It is used to link a report to a user role allowing a particular function to view the reports.

The columns in the PrmRolePerms table (PRMROLEPERMS) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
PERMISSION_ID	int
REVIEW_SCREEN_TYPE	int
ROLEID	int

Index Name: **IX_ACTION_LEVEL**

Fields: ACTION_LEVEL_ID

Index Name: **IX_PERMISSIONS2**

Fields: PERMISSION_ID

Index Name: **IX_ROLEID**

Fields: ROLEID

Column Descriptions

The following are the descriptions of the PrmRolePerms table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level

- 6 = UAID action level
- 7 = ACCOUNT action level

PERMISSION_ID — The ID taken from the PrmMenu table.

REVIEW_SCREEN_TYPE — Specifies whether a (role, permission) pair is related to a cross-action level or an action level.

ROLEID — Corresponds to the LID from the PRMRules table.

PrmRoles Table

The PrmRoles table is used by the Analysis and Review system. It defines the available user roles, administrator, analyst, supervisor, etc.

The columns in the PrmRoles table (PRMROLES) are listed below with the data type.

Column Name	Data Type
ID	int
IS_ADMIN_ROLE	bit
IS_DEFAULT	bit
NAME	int
ORDER_NUM	int
SDESC	int
VISIBLE	int

Index Name: **UX_PRMROLES_ID**

Fields: ID

Index Name: **PK_PRMROLES**

Fields: ID

Column Descriptions

The following are the descriptions of the PrmRoles table columns.

ID — The system-defined ID for available user roles (for example, Analyst or Supervisor).

IS_ADMIN_ROLE — Indicates whether role is an admin role.

Valid values are:

0 = Not an admin role

1 = Admin role

IS_DEFAULT — Indicates whether role is a default role.

Valid values are:

0 = Custom role

1 = Default role

NAME — The numeric identifier for the localized text of the label. The locale specific value can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

ORDER_NUM — Indicates the role order in the Roles Hierarchy; it must be a positive number. It starts with 1, which is the highest role in the hierarchy (the most permissive) and goes up. The higher the ORDER_NUM, the less permissive is the role. By default, Root Administrator has ORDER_NUM = 1.

ORDER_NUM of -1 is reserved for Model Admin, which is not part of the roles hierarchy.

SDESC — The numeric identifier for the localized text of the label. The locale specific value can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

VISIBLE — Indicates whether the current role is visible in the UI. This is to hide from the users the factory-defined roles that should not be changed.

Valid values are:

0 = Not visible

1 = Visible

Role_Template Table

The Role_Template table contains information related to the customized role template within the PRM system.

The columns in the Role_Template table (ROLE_TEMPLATE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
CREATED_DATETIME	datetime
LAST_UPDATED_DATETIME	datetime
NAME	nvarchar(50)
TEMPLATE_ID	smallint

Index Name: **ROLE_TEMPLATE_UK**

Fields: NAME

Index Name: **ROLE_TEMPLATE_PK**

Fields: TEMPLATE_ID

Column Descriptions

The following are the descriptions of the Role_Template table columns.

CREATED_DATETIME — The date and time of role template was created.

LAST_UPDATED_DATETIME — The latest date and time in which the role template was modified.

NAME — The name of role template.

TEMPLATE_ID — The unique identifier of the role template.

Role_Template_Permission Table

The Role_Template_Permission table contains information related to the assigned permissions for customized roles within each action level.

The columns in the Role_Template_Permission table (ROLE_TEMPLATE_PERMISSION) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
PERMISSION_ID	int
TEMPLATE_ID	smallint

Column Descriptions

The following are the descriptions of the Role_Template_Permission table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

PERMISSION_ID — The unique identifier of a permission.

TEMPLATE_ID — The unique identifier of the role template.

Role_Trان_Type Table

The Role_Trان_Type table contains the transaction types associated to specific roles within the PRM system.

The columns in the Role_Trان_Type table (ROLE_TRAN_TYPE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ROLE_ID	int
TRAN_TYPE_ID	char(4)

Index Name: **ROLE_TRAN_TYPE_PK**

Fields: ROLE_ID
 TRAN_TYPE_ID

Column Descriptions

The following are the descriptions of the Role_Trان_Type table columns.

ROLE_ID — The unique identifier of a role in PrmRoles table.

TRAN_TYPE_ID — The unique identifier of an ISO transaction type.

Trان_Type Table

The Tran_Type table contains the ISO transaction type information within the PRM system.

The columns in the Tran_Type table (TRAN_TYPE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
CREATED_DATETIME	datetime

Column Name	Data Type
DESCRIPTION	nvarchar(500)
LAST_UPDATED_DATETIME	datetime
NAME	nvarchar(100)
TRAN_TYPE_ID	char(4)

Index Name: **TRAN_TYPE_PK**

Fields: TRAN_TYPE_ID

Column Descriptions

The following are the descriptions of the Tran_Type table columns.

CREATED_DATETIME — The date and time when the transaction type created.

DESCRIPTION — The description of the transaction type.

LAST_UPDATED_DATETIME — The latest date and time in which the transaction type was modified.

NAME — The name of the transaction type.

TRAN_TYPE_ID — The unique identifier of the transaction type.

Translation Tables

The Translation tables contain translations for values displayed on the Analysis and Review screen.

The following Translation tables are described on the following pages:

- TransLookup

- Trans_Category

TransLookup Table

The TransLookup table is used by the Analysis and Review system. It contains a list of field value translations.

The columns in the TransLookup table (TRANSLOOKUP) are listed below with the data type.

Column Name	Data Type
STRANSLATION	int
SVALUE	nvarchar(255)
TRANS_CATEGORY_ID	int

Index Name: **IDX_TRANSLOOKUP_CLUSTER**

Fields: TRANS_CATEGORY_ID
 SVALUE

Index Name: **TRANSLOOKUP_PK**

Fields: TRANS_CATEGORY_ID
 SVALUE

Column Descriptions

The following are the descriptions of the TransLookup table columns.

STRANSLATION — The numeric identifier for the localized text of the label. The locale specific value can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

SVALUE — The value that is to be translated.

TRANS_CATEGORY_ID — The unique field ID. It is linked to the LFIELDID column in the Trans_Category table.

Trans_Category Table

The Trans_Category table is used by the Analysis and Review system. It contains a list of data types for which translations are available.

The columns in the Trans_Category table (TRANS_CATEGORY) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
TRANS_CATEGORY_ID	int
TRANS_CATEGORY_NAME	int

Index Name: **TRANS_CATEGORY_IX1**

Fields: TRANS_CATEGORY_NAME

Index Name: **TRANS_CATEGORY_PK**

Fields: TRANS_CATEGORY_ID

Column Descriptions

The following are the descriptions of the Trans_Category table columns.

TRANS_CATEGORY_ID — The ID for the translation topic. Each translation topic has a unique ID. This ID column is used to allow the Trans_Category_Filter_Field table to communicate with the TransLookup table.

TRANS_CATEGORY_NAME — The numeric identifier for the localized text of the label. The locale specific value can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTIES table.

Point of Compromise Tables

The Point of Compromise tables contain parameters and configuration information for the Point of Compromise feature.

The tables below are described on the following pages:

- PocAlerts
- PocSelect

PocAlerts Table

The PocAlerts table stores the point of compromise alerts that are generated when a user marks suspicious activity. A point of compromise alert can be a date and or terminal ID combination.

The columns in the PocAlerts table (POCALERTS) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
ALERT_DATE	datetime
DD_DATE	datetime
DD_PARTITION_DATE	date
LPORTFOLIOID	int
ND_KEY_HASH	smallint
POC_ALERT_KEY	varchar(50)
POC_END_DATE	datetime
POC_START_DATE	datetime
RECORD_SOURCE_ID	smallint
REV_ID	int

Column Name	Data Type
SD_RETL_ID	varchar(50)
SD_TERM_ID	varchar(50)
SD_TIEBREAKER	varchar(75)

Index Name: IDX_POCALERTS_ALERT_DATE

Fields: ALERT_DATE

Index Name: PK_POCALERTS

Fields: POC_ALERT_KEY

 LPORTFOLIOID

 ACTION_LEVEL_KEY

Column Descriptions

The following are the descriptions of the PocAlerts table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the Detail table. It can contain a SD_PAN, SD_UAN, SD_EMPLOYEE_ID, SD_RETL_ID or SD_TERM_ID. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and is used to determine what type of value is stored in ACTION_LEVEL_KEY.

ALERT_DATE — The date and time a record is inserted in the POCALERTS table.

DD_DATE — The point of compromise date.

DD_PARTITION_DATE — The value associated with the transaction in the FraudDetail table that matched the criteria to identify non-fraudulent transactions that might be compromised.

LPORTFOLIOID — The portfolio ID. It is linked to the LID column in the Portfolios table.

ND_KEY_HASH — The value that is associated with the transaction in the FraudDetail table that matched the criteria to identify non-fraudulent transactions that might be compromised.

POC_ALERT_KEY — The surrogate key used to group one or more ACTION_LEVEL_KEY values in the PocAlerts table. It is made up of a UUID that is passed to the PP_GENPOCALERTS procedures and a counter that is appended. The counter is incremented each time a group a records is inserted in the PocAlerts table. It is carried forward in the POCSELECT table to associate additional ACTION_LEVEL_KEY values with the POC_ALERT_KEY.

POC_END_DATE — A calculated date. The PP_GENPOCALERTS procedure reads the value of the CONFIG.LCFGVALUE where CONFIG.SCFGVARIABLE equals 'POCTerminalUsage'. This column values are hour units and it defaults to 24. The PP_GENPOCALERTS procedure determines a set of candidate records from the FraudDetail table. One of the columns in the candidate set is DD_DATE. It stored this value in variable named TXNDATE. The value of POC_END_DATE the date calculated by adding the value stored in CONFIG.LCFGVALUE from the date stored in TXNDATE.
$$\text{POC_END_DATE} = \text{TXNDATE} + \text{CONFIG.LCFGVALUE hours.}$$

POC_START_DATE — A calculated date. The PP_GENPOCALERTS procedure reads the value of the CONFIG.LCFGVALUE where CONFIG.SCFGVARIABLE equals 'POCTerminalUsage'. This column values are hour units and it defaults to 24. The PP_GENPOCALERTS procedure determines a set of candidate records from the FraudDetail table. One of the columns in the candidate set is DD_DATE. It stored this value in variable named TXNDATE. The value of POC_START_DATE the date calculated by subtracting the value stored in CONFIG.LCFGVALUE from the date stored in TXNDATE.
$$\text{POC_START_DATE} = \text{TXNDATE} - \text{CONFIG.LCFGVALUE hours.}$$

RECORD_SOURCE_ID — The value that is associated with the transaction in the FraudDetail table that matched the criteria to identify non-fraudulent transactions that might be compromised.

REV_ID — The analyst ID. It is inserted when the POC review form is closed to indicate the alert has been processed.

SD_RETL_ID — Contains the retailer ID.

SD_TERM_ID — The Terminal ID.

SD_TIEBREAKER — A transaction field that makes a transaction unique when more than one transactions has the same date and time.

PocSelect Table

The PocSelect table stores the items that are available for Point of Compromise block selection. It tracks those that are blocked Point of Compromise. These items are displayed on the Point of Compromise Block screen. The Point of Compromise Block screen lists non-suspicious activity accounts that were transacted on the same day at the same terminal and/or retailer ID.

The columns in the PocSelect table (POCSELECT) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_KEY	varchar(50)
AMT	money
BLOCKED	smallint
DD_DATE	datetime
LPORTFOLIOID	int
POC_ALERT_KEY	varchar(50)
POC_END_DATE	datetime
POC_START_DATE	datetime

Column Name	Data Type
REV_ID	int
SD_RETL_ID	varchar(50)
SD_TERM_ID	varchar(50)
SELECTED	smallint
TXNS	int

Index Name: **IDX_POCSELECT_ALERTKEYS**

Fields: POC_ALERT_KEY
 ACTION_LEVEL_KEY
 ACTION_LEVEL_ID
 REV_ID

Index Name: **IDX_POCSELECT_CLUSTER**

Fields: ACTION_LEVEL_KEY
 SD_TERM_ID

Column Descriptions

The following are the descriptions of the PocSelect table columns.

ACTION_LEVEL_ID — A distinct numeric value used to uniquely identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the columns SM_PAN, SM_UAN, SM_RETL_ID, SM_TERM_ID or SM_EMPLOYEE_ID. The value in the ACTION_LEVEL_ID column determines the specific key. It is obtained from the Detail table for records that match the POC select criteria.

AMT — Represents the sum of all PANs at risk.

BLOCKED — A value of 1 after an account has been blocked.

DD_DATE — The most recent transaction date.

LPORTFOLIOID — The portfolio ID. It links each alert to a portfolio listed in the Portfolios table.

POC_ALERT_KEY — The surrogate key used to group one or more ACTION_LEVEL_KEY values in the PocAlerts table. It is carried forward in the PocSelect table to associate additional ACTION_LEVEL_KEY values with the POC_ALERT_KEY.

POC_END_DATE — The ending date and time when searching for records that meet the POC Select criteria.

POC_START_DATE — The starting date and time when searching for records that meet the POC Select criteria.

REV_ID — The analyst ID. It is inserted when the PocSelects are generated.

SD_RETL_ID — Contains the retailer ID.

SD_TERM_ID — The Terminal ID.

SELECTED — Set to a value of 1 when a POC Account is selected for block.

TXNS — The number of transactions in the Detail table for this location and date.

Universal Scoring Engine Tables

The Universal Scoring Engine tables contain information used by PRM in order to be able to interoperate with the Universal Scoring Engine.

The following tables are described below:

- Scoring_Event
- Scoring_Feature
- Scoring_Model
- Scoring_Models_Mapping

Scoring_Event Table

The Scoring_Event table is used by the Analytic Gateway to configure the interaction with Universal Scoring Engine. Based on the contents of this table, the Analytic Gateway determines the name of the feature calculation stored procedure to be called for a certain event type. The table is managed by the PRM GUI and is truncated and repopulated on every import of a scoring model XML, based on the contents in this file.

The columns in the Scoring_Event table (SCORING_EVENT) are listed below with the data type.

Column Name	Data Type
DESCRIPTION	nvarchar(1024)
EVENT_ID	int
NAME	varchar(50)

Index Name: **PK_SCORING_EVENT**

Fields: EVENT_ID

Column Descriptions

The following are the descriptions of the Scoring_Event table columns.

DESCRIPTION — The description of the scoring event, as it appears in the imported scoring XML file.

EVENT_ID — The generated ID of the scoring event represented by this row. This is the ordinal of this scoring event, as it appears in the imported scoring model XML file.

NAME — The name of the scoring event, as it appears in the imported scoring XML file.

Scoring_Feature Table

The Scoring_Feature table is used by the Analytic Gateway to configure the interaction with Universal Scoring Engine. Based on the contents of this table, the Analytic Gateway determines the features associated to an event type that need to be sent to the Universal Scoring Engine. The table is managed by the PRM GUI and is truncated and repopulated on every import of a scoring model XML, based on the contents in this file.

The columns in the Scoring_Feature table (SCORING_FEATURE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
APPLICATION_DATA_TYPE_ID	int
DATA_SIZE	int
DESCRIPTION	nvarchar(1024)
EVENT_ID	int
FEATURE_ID	int
NAME	varchar(50)
SENSITIVE	int

Index Name: **PK_SCORING_FEATURE**

Fields: FEATURE_ID

Column Descriptions

The following are the descriptions of the Scoring_Feature table columns.

APPLICATION_DATA_TYPE_ID — The identifier of the Analytic Gateway's application data type, as it appears in the Application_Data_Type table.

DATA_SIZE — The maximum data size of the scoring feature.

DESCRIPTION — The description of the scoring feature, as it appears in the imported scoring XML file.

EVENT_ID — The identifier of the scoring event to which this scoring feature is associated. Foreign key in Scoring_Event (EVENT_ID).

FEATURE_ID — The identifier of the scoring feature represented by this row.

NAME — The name of the scoring feature, as it appears in the imported scoring XML file.

SENSITIVE — Set to either 0 or 1. If set to 1, it indicates that the current feature is sensitive.

Scoring_Model Table

The Scoring_Model table is used by the PRM GUI to maintain the current copy of the scoring model XML file, in order to display it to the Model Admin user.

The columns in the Scoring_Model table (SCORING_MODEL) are listed below with the data type.

Column Name	Data Type
CONFIG_XML	nvarchar(Max)
IMPORT_DATE	datetime27

Column Descriptions

The following are the descriptions of the Scoring_Model table columns.

CONFIG_XML — The latest successfully imported scoring model XML file.

IMPORT_DATE — The timestamp when the latest scoring model XML file was imported.

Scoring_Models_Mapping Table

The Scoring_Models_Mapping table is used by the Analytic Gateway to configure how each of the received models' scores are mapped to each of the three available score column sets.

The columns in the Scoring_Models_Mapping table (SCORING_MODELS_MAPPING) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
MODEL_ID	nvarchar(64)
POSITION	int

Index Name: **PK_SCORING_MODELS_MAPPING**

Fields: MODEL_ID

Column Descriptions

The following are the descriptions of the Scoring_Models_Mapping table columns.

MODEL_ID — The identifier of a Universal Scoring Engine's scoring model. The identifier is built based on the PRM scoring event type, USE model name, and USE model version tokens.

POSITION — The position of the PRM score field set to which the mapped model_id should be saved.

Temporary Tables

The temporary database tables are created for ease of processing; they are physical temporary tables created at installation and populated during processing. The user interface cleans the table entries after processing.

The following tables are described below:

- TT_Add_Dflt_NRT_Queue_Procs
- TT_Add_Dflt_Profile_Queue_Procs
- TT_AlertTimeout
- TT_Auto_Actions
- TT_Detail_Cleanup_Job
- TT_GenPOCAAlerts
- TT_OpenAcctTimeout
- TT_SessionLockExpired

TT_Add_Dflt_NRT_Queue_Procs Table

The TT_ADD_Dflt_NRT_Queue_Procs table is a temporary table created at installation and populated during processing. The user interface cleans the table entries after processing.

The columns in the TT_Add_Dflt_NRT_Queue_Procs table (TT_ADD_DFLT_NRT_QUEUE_PROCS) are listed below with the data type.

Column Name	Data Type
SESSIONID	smallint
TBCOLUMN_NAME	varchar(100)
TBLID	int
TBPARAMS_VALUE	varchar(300)
TBTABLE_IND	int

Index Name: TT_ADD_DFLT_NRT_QUEUE_INDX

Fields: SESSIONID

Column Descriptions

The following are the descriptions of the TT_Add_Dflt_NRT_Queue_Procs table columns.

SESSIONID — The user session ID.

TBCOLUMN_NAME — The column name.

TBLID — The unique ID.

TBPARAMS_VALUE — The parameter values.

TBTABLE_IND — The table indicator.

TT_Add_Dflt_Profile_Queue_Procs Table

The TT_ADD_Dflt_Profile_Queue_Procs table is a temporary table created at installation and populated during processing. The user interface cleans the table entries after processing.

The columns in the TT_Add_Dflt_Profile_Queue_Procs table (TT_ADD_DFLT_PROFILE_QUEUE_PROCS) are listed below with the data type.

Column Name	Data Type
SESSIONID	smallint
TBCOLUMN_NAME	varchar(100)
TBLID	int
TBPARAMS_VALUE	varchar(300)

<i>Column Name</i>	<i>Data Type</i>
TBTABLE_IND	int

Index Name: TT_ADD_DFLT_PROFILE_QUEUE_PROCS_INDEX

Fields: SESSIONID

Column Descriptions

The following are the descriptions of the TT_Add_Dflt_Profile_Queue_Procs table columns.

SESSIONID — The user session ID.

TBCOLUMN_NAME — The column name.

TBLID — The unique ID.

TBPARAMS_VALUE — The parameter values.

TBTABLE_IND — The Table indicator.

TT_AlertTimeout Table

The TT_AlertTimeout table is a temporary table created at installation and populated during processing. The user interface cleans the table entries after processing.

The columns in the TT_AlertTimeout table (TT_ALERTTIMEOUT) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ACTION_LEVEL_ID	int
DTLOCKTIME	datetime

Column Name	Data Type
LOBJECT	int
LPORTFOLIOID	int
LRQAID	int
LUSERID	int
SESSIONID	int
SINDEX	varchar(100)

Index Name: **TT_ALERTTIMEOUT_INDX**

Fields: SESSIONID
 LOBJECT
 SINDEX
 ACTION_LEVEL_ID
 LPORTFOLIOID

Column Descriptions

The following are the descriptions of the TT_AlertTimeout table columns.

ACTION_LEVEL_ID — A numeric value used to identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

DTLOCKTIME — The date and time the record was created.

LOBJECT — The type of object.

LPORTFOLIOID — The identifier of the portfolio.

LRQAID — The queue ID. It is linked to the LID column in the RqPortAssign table.

LUSERID — Linked to a user listed in the PRM_Users table.

SESSIONID — The user session ID.

SINDEX — The account number for account locks. It also contains any lock required for character keys. It is linked to the SM_KEY column in the Master table.

TT_Auto_Actions Table

The TT_Auto_Actions table is a temporary table created at installation and populated during processing. The user interface cleans the table entries after processing.

The columns in the TT_Auto_Actions table (TT_AUTO_ACTIONS) are listed below with the data type.

Column Name	Data Type
ACTION_DATETIME	datetime
ACTION_DESCRIPTION	nvarchar(255)
ACTION_ORDER	int
ACTION_TYPE_ID	int

Column Name	Data Type
ALERT_DATE	datetime
AUTO_ACTION	int
AUTO_ACTION_PROC	varchar(30)
AUTO_ADDIN_TYPE	int
AUTO_UPDATES_ALLOWED	smallint
BLOCKCODE_MEMO	sysname
EMM_ENABLED	smallint
IDENTIFIEDBY	int
ISCALCULATEDFUNDSATRISK	int
LOCALE_ID	varchar(10)
LREVID	int
LTEAMID	int
MARKTYPE	int
NOTIFYTYPE_MEMO	sysname
RULE_ID	int
SBLOCKCODE	nvarchar(5)
SESSIONID	int

Column Name	Data Type
SHOST_VALUE	nvarchar(1024)
SHOWSTATE	smallint
SM_BIN	varchar(12)
SM_FIID	varchar(50)
SNOTIFYTYPE	nvarchar(50)
TRACKINGID	varchar(30)

Index Name: **TT_AUTO_ACTIONS_INDX**

Fields: SESSIONID
 ACTION_TYPE_ID
 RULE_ID

Column Descriptions

The following are the descriptions of the TT_Auto_Actions table columns.

ACTION_DATETIME — The date time for the action. This is not applicable for all actions.

ACTION_DESCRIPTION — The action description for the auto action.

ACTION_ORDER — The auto action order if more than one action used within a rule.

ACTION_TYPE_ID — The identifier of the action type.

ALERT_DATE — The date and time of an alert.

AUTO_ACTION — The next ID number for a new auto action (AutoActionsRule table).

AUTO_ACTION_PROC — The procedure name of the auto action rule when the action is matched with a transaction.

AUTO_ADDIN_TYPE — The add-in type if the auto action is an add-in action.

AUTO_UPDATES_ALLOWED — Indicates whether records in the MasterDisp table for actions with state can be updated by Auto-Action rules performing the same action on the same account.

Valid values are:

- 0 = Records in the MasterDisp table cannot be updated by Auto-Action rules performing the same action that has state for the same state. If EMM is enabled, the record in the EMD table will only be updated if the Auto-Action state is different than the state of the record in the EMD table and the record in the EMD table has a status >0.
- 1 = Records in the MasterDisp table can be updated by Auto-Action rules performing the same action that maintains state for the same state. If EMM is enabled, a record may be inserted into the EMD table regardless of the state or status of existing EMD records.

BLOCKCODE_MEMO — The numeric identifier for the localized additional text associated with a block code. The locale specific value for BLOCKCODE_MEMO can be found using this value and a specific value for LOCALE_ID in the L10N_PROPERTY table.

EMM_ENABLED — Specifies if the External Message Manager is enabled or not.

IDENTIFIEDBY — Contains the Identified By options configured for auto-action rule.

ISCALCULATEDFUNDSATRISK — Determines whether the funds at risk are calculated for an alerted transaction. Accepted values are:

- 0 = Funds at Risk are not calculated.
- 1 = Funds at Risk are calculated.

LOCALE_ID — The Foreign Key to the column LOCALE_ID in table AVAILABLE_LOCALE.

LREVID — The analyst ID. It links the recipient of the forwarded card or reminder, to a user listed in the PRM_Users table.

LTEAMID — The ID of the team to which the user belongs.

MARKTYPE — Identifies the type of mark that was applied to the transaction.

NOTIFYTYPE_MEMO — Identifies the memo for the notify type.

RULE_ID — Contains the rule Id.

SBLOCKCODE — Identifies a value from the SBLOCKCODE column in the
ADDBLOCKCODES table.

SESSIONID — The user session ID.

SHOST_VALUE — The host value if external message processing is enabled for the action.

SHOWSTATE — Identifies if the button is depressed with the state. Valid values are:

0 = Button is not depressed with the state

1 = Button is depressed with the state

SM_BIN — The bank identification number.

SM_FIID — The financial institution identifier (FIID) of the bank associated with the cardholder or
accountholder. This field differs from SM_BIN in that while the BIN may store the prefix for the
identifier, the FIID may store the full institution identifier number. Alternatively, the BIN and FIID
may be used to store different types of identifiers for the same financial institution.

SNOTIFYTYPE — Identifies how the auto-action rule notify alerted transaction.

TRACKINGID — Contains the free-form text and is capable of accepting alphanumeric data of up
to 30 characters. This allows institutions to tie suspicious transactions together, even if they
occurred in different accounts.

TT_Detail_Cleanup_Job Table

The TT_Detail_Cleanup_Job table is a temporary table created at installation and populated during processing. The user interface cleans the table entries after processing.

The columns in the TT_Detail_Cleanup_Job table (TT_DETAIL_CLEANUP_JOB) are listed below with the data type.

Column Name	Data Type
HOURL_PROC	int
SESSIONID	int

Index Name: TT_DETAIL_CLEANUP_JOB_INDX

Fields: SESSIONID

Column Descriptions

The following are the descriptions of the TT_Detail_Cleanup_Job table columns.

HOURL_PROC — Contains the procedure

SESSIONID — The user session ID.

TT_GenPOCAAlerts Table

The TT_GenPOCAAlerts table is a temporary table created at installation and populated during processing. The user interface cleans the table entries after processing.

The columns in the TT_GenPOCAAlerts table (TT_GENPOCALERTS) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int

Column Name	Data Type
ACTION_LEVEL_KEY	varchar(50)
ALERT_DATE	datetime
DD_DATE	datetime
DD_PARTITION_DATE	date
LPORTFOLIOID	int
ND_KEY_HASH	smallint
POC_ALERT_KEY	varchar(50)
POC_END_DATE	datetime
POC_START_DATE	datetime
RECORD_SOURCE_ID	smallint
REV_ID	int
SD_RETL_ID	varchar(50)
SD_TERM_ID	varchar(50)
SD_TIEBREAKER	varchar(75)
SESSIONID	int

Index Name: **TT_GENPOCALERTS_INDX**

Fields: POC_ALERT_KEY

 ACTION_LEVEL_KEY

 LPORTFOLIOID

SESSIONID

Column Descriptions

The following are the descriptions of the TT_GenPOCAAlerts table columns.

ACTION_LEVEL_ID — A numeric value used to identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_KEY — The key value from one of the DETAIL. It may contain a SD_PAN, SD_UAN, SD_EMPLOYEE_ID, SD_RETL_ID or SD_TERM_ID. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and will be used to determine what type of value is stored in ACTION_LEVEL_KEY.

ALERT_DATE — The date and time of an alert.

DD_DATE — The transaction date and time.

DD_PARTITION_DATE — The value that is associated with the transaction in the Detail and FraudDetail tables.

LPORTFOLIOID — The identifier of the portfolio.

ND_KEY_HASH — The value that is associated with the transaction in the FraudDetail table that matched the criteria to identify non-fraudulent transactions that might be compromised.

POC_ALERT_KEY — The surrogate key used to group one or more ACTION_LEVEL_KEY values in the PocAlerts table. It is made up of a UUID that is passed to the PP_GENPOCALERTS procedures

and a counter that is appended. The counter is incremented each time a group a records is inserted in the PocAlerts table. It is carried forward in the POCSELECT table to associate additional ACTION_LEVEL_KEY values with the POC_ALERT_KEY.

POC_END_DATE — A calculated date. The PP_GENPOCALERTS procedure reads the value of the CONFIG.LCFGVALUE where CONFIG.SCFGVARIABLE equals 'POCTerminalUsage'. This column values are hour units and it defaults to 24. The PP_GENPOCALERTS procedure determines a set of candidate records from the FraudDetail table. One of the columns in the candidate set is DD_DATE. It stored this value in variable named TXNDATE. The value of POC_END_DATE the date calculated by adding the value stored in CONFIG.LCFGVALUE from the date stored in TXNDATE.
$$\text{POC_END_DATE} = \text{TXNDATE} + \text{CONFIG.LCFGVALUE hours.}$$

POC_START_DATE — A calculated date. The PP_GENPOCALERTS procedure reads the value of the CONFIG.LCFGVALUE where CONFIG.SCFGVARIABLE equals 'POCTerminalUsage'. This column values are hour units and it defaults to 24. The PP_GENPOCALERTS procedure determines a set of candidate records from the FraudDetail table. One of the columns in the candidate set is DD_DATE. It stored this value in variable named TXNDATE. The value of POC_START_DATE the date calculated by subtracting the value stored in CONFIG.LCFGVALUE from the date stored in TXNDATE.
$$\text{POC_START_DATE} = \text{TXNDATE} - \text{CONFIG.LCFGVALUE hours.}$$

RECORD_SOURCE_ID — The value that is associated with the transaction in the FraudDetail table that matched the criteria to identify non-fraudulent transactions that might be compromised.

REV_ID — The analyst ID. It is inserted when the POC review form is closed to indicate the alert has been processed.

SD_RETL_ID — The retailer ID.

SD_TERM_ID — The terminal ID.

SD_TIEBREAKER — A transaction field that makes a transaction unique when more than one transactions has the same date and time.

SESSIONID — The user session ID.

TT_OpenAcctTimeout Table

The TT_OpenAcctTimeout table is a temporary table created at installation and populated during

processing. The user interface cleans the table entries after processing.

The columns in the TT_OpenAcctTimeout table (TT_OPENACCTTIMEOUT) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
DTLOCKTIME	datetime
LOBJECT	int
LPORTFOLIOID	int
LRQAID	int
LUSERID	int
SESSIONID	int
SINDEX	varchar(100)

Index Name: **TT_OPENACCTTIMEOUT_INDX**

Fields: SESSIONID
 LOBJECT
 SINDEX
 ACTION_LEVEL_ID
 LPORTFOLIOID

Column Descriptions

The following are the descriptions of the TT_OpenAcctTimeout table columns.

ACTION_LEVEL_ID — A numeric value used to identify an action level.

Valid values are:

1 = CARD action level

- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

DTLOCKTIME — The date and time the record was created.

LOBJECT — The type of object.

LPORTFOLIOID — The identifier of the portfolio.

LRQAID — The queue ID. It is linked to the LID column in the RqPortAssign table.

LUSERID — Linked to a user listed in the PRM_Users table.

SESSIONID — The user session ID.

SINDEX — The account number for account locks. It also contains any lock required for character keys. It is linked to the SM_KEY column in the Master table.

TT_SessionLockExpired Table

The TT_SessionLockExpired table is a temporary table created at installation and populated during processing. The user interface cleans the table entries after processing.

The columns in the TT_SessionLockExpired table (TT_SESSIONLOCKEXPIRED) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
DTLOCKTIME	datetime
LOBJECT	int
LPORTFOLIOID	int
LRQAID	int
LUSERID	int
SESSIONID	int
SINDEX	varchar(100)
SSESSIONID	varchar(255)

Column Descriptions

The following are the descriptions of the TT_SessionLockExpired table columns.

ACTION_LEVEL_ID — A numeric value used to identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

DTLOCKTIME — The date and time the record was created.

LOBJECT — The type of object.

LPORTFOLIOID — The identifier of the portfolio.

LRQAID — The queue ID. It is linked to the LID column in the RqPortAssign table.

LUSERID — Linked to a user listed in the PRM_Users table.

SESSIONID — The user session ID.

SINDEX — The account number for account locks. It also contains any lock required for character keys. It is linked to the SM_KEY column in the Master table.

SSESSIONID — The user session ID.

Data Extensibility Tables

Note: The Data Extensibility tables are used by ACI personnel to expedite development of new record sources and should not be modified or deleted from the database.

The Data Extensibility tables are used by the Data Extensibility tool accompanying the PRM product.

This tool helps making customizations based on the current PRM product, such as:

- Adding new record sources and record source fields
- Adding new action levels and corresponding demographic and transaction tables and columns
- Mapping record sources on action levels and record source fields on action levels' table columns
- Exposing the new table columns into the analysis and review UI
- All Data Extensibility tables contain the metadata reflecting several configurations of the customizable components in the PRM system, including the Running configuration that reflects the current system's configuration and the Provisioning configuration that is used to generate the desired customizations.

All Data Extensibility table names start with a "DE_" prefix.

The following Data Extensibility tables are described on the following pages:

- DE_Action_Level
- DE_Action_Level_Record_Source
- DE_AG_Class_Field
- DE_AG_Composite_Field
- DE_AG_Services
- DE_Application_Data_Type
- DE_Column
- DE_Compatible_SQL_Data_Type
- DE_Configuration
- DE_Configuration_Type
- DE_Demo_Caption
- DE_PIM_Mappings
- DE_Record_Source
- DE_Record_Source_Attr
- DE_Record_Source_Format
- DE_Record_Source_Mapping
- DE_Record_Source_Type
- DE_SQL_Data_Type
- DE_SQL_Data_Type_MSQ
- DE_SQL_Data_Type_ORA
- DE_Table
- DE_UI_Component
- DE_UI_Field
- DE_UI_Field_Format
- DE_UI_Field_Search
- DE_UI_GridBag_Config

DE_Action_Level Table

The DE_Action_Level table stores the action level metadata.

The columns in the DE_Action_Level table (DE_ACTION_LEVEL) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_LICENSE_NAME	varchar(30)
CONFIGURATION_ID	int
DETAIL_KEY_COLUMN_NAME	varchar(30)
DETAIL_PORTFOLIO_COLUMN_NAME	varchar(30)
DETAIL_TABLE_NAME	varchar(30)
DISPLAY_NAME	varchar(30)
FILTER_COLUMN_LENGTH	int
MASTER_KEY_COLUMN_NAME	varchar(30)
MASTER_MFDATE_COLUMN_NAME	varchar(30)
MASTER_TABLE_NAME	varchar(30)
RT_MASTER_TABLE_NAME	varchar(30)
RT_SHORTWINDOW_TAB_NAME	varchar(30)
SEARCH_PAGING_COLUMN_NAME	varchar(30)
SHORTWINDOW_TAB_NAME	varchar(30)

Index Name: DE_ACTION_LEVEL_UN3

Fields: CONFIGURATION_ID
DETAIL_PORTFOLIO_COLUMN_NAME

Index Name: DE_ACTION_LEVEL_UN4

Fields: CONFIGURATION_ID
RT_MASTER_TABLE_NAME

Index Name: DE_ACTION_LEVEL_UN5

Fields: CONFIGURATION_ID
DISPLAY_NAME

Index Name: DE_ACTION_LEVEL_PK

Fields: CONFIGURATION_ID
ACTION_LEVEL_ID

Index Name: DE_ACTION_LEVEL_UN1

Fields: CONFIGURATION_ID
MASTER_TABLE_NAME

Index Name: DE_ACTION_LEVEL_UN2

Fields: CONFIGURATION_ID
ACTION_LEVEL_LICENSE_NAME

Column Descriptions

The following are the descriptions of the DE_Action_Level table columns.

ACTION_LEVEL_ID — A numeric value used to identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level
- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

ACTION_LEVEL_LICENSE_NAME — The value of the License Name.

CONFIGURATION_ID — The configuration id from the DE_Configuration table.

DETAIL_KEY_COLUMN_NAME — The name of the column to use as the key to the Detail table.

DETAIL_PORTFOLIO_COLUMN_NAME — The name of this action level's detail table column that contains the ID of the portfolio associated with the action level to which the transaction belongs.

DETAIL_TABLE_NAME — The name of the Detail database table.

DISPLAY_NAME — The UI display name of the cross action level.

FILTER_COLUMN_LENGTH — The number of characters considered significant for filtering.

MASTER_KEY_COLUMN_NAME — The name of the column to use as the key to the Master table.

MASTER_MFDATE_COLUMN_NAME — The name of the modified date column for the Master table.

MASTER_TABLE_NAME — The name of the Master (demographic data) database table.

RT_MASTER_TABLE_NAME — The name of the RT Master (demographic data) database table.

RT_SHORTWINDOW_TAB_NAME — The name of the ShortWindow database table for real-time processing.

SEARCH_PAGING_COLUMN_NAME — The column name used by the tab to sort the pages.

SHORTWINDOW_TAB_NAME — The name of the ShortWindow database table for near-real-time processing.

DE_Action_Level_Record_Source Table

The DE_Action_Level_Record_Source table stores the record source to action level mapping metadata.

The columns in the DE_Action_Level_Record_Source table (DE_ACTION_LEVEL_RECORD_SOURCE) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
CONFIGURATION_ID	int
HAS_PEER_PROFILE	int
INSERT_DEMO_DATA	int
RECORD_SOURCE_ID	int

Index Name: DE_ALRS_PK

Fields: CONFIGURATION_ID
ACTION_LEVEL_ID
RECORD_SOURCE_ID

Column Descriptions

The following are the descriptions of the DE_Action_Level_Record_Source table columns.

ACTION_LEVEL_ID — A numeric value used to identify an action level.

Valid values are:

- 1 = CARD action level
- 2 = MERCHANT action level
- 3 = UAN action level
- 4 = TERMINAL action level

- 5 = EMPLOYEE action level
- 6 = UAID action level
- 7 = ACCOUNT action level

CONFIGURATION_ID — The unique ID for the configuration.

HAS_PEER_PROFILE — Specifies whether or not uses Peer Profiles.

Valid values are:

- 0 = Uses Peer Profiles
- 1 = Does not use Peer Profiles

INSERT_DEMO_DATA — Specifies whether to insert or not the demo data.

Valid values are:

- 0 = Inserts demo data
- 1 = Does not insert the demo data

RECORD_SOURCE_ID — The identifier of the record source as defined in the Analytic Gateway.

DE_AG_Class_Field Table

The DE_AG_Class_Field table stores the record source to action level mapping metadata.

The columns in the DE_AG_Class_Field table (DE_AG_CLASS_FIELD) are listed below with the data type.

Column Name	Data Type
CLASSNAME	varchar(500)
CLASS_ID	int

Column Name	Data Type
CLASS_TYPE	varchar(50)
CONFIGURATION_ID	int

Index Name: PK_DE_AG_CLASS_FIELD

Fields: CONFIGURATION_ID
CLASSNAME

Index Name: AK_1_DE_AG_CLASS_FIELD

Fields: CONFIGURATION_ID
CLASS_TYPE
CLASS_ID

Column Descriptions

The following are the descriptions of the DE_AG_Class_Field table columns.

CLASSNAME — The class of the operation (it should be a fully qualified Java class name).

CLASS_ID — The ID of the class.

CLASS_TYPE — The type of the class.

CONFIGURATION_ID — The unique ID for the configuration.

DE_AG_Composite_Field Table

The DE_AG_Composite_Field table stores the information about all defined AG composite fields, including the selection, transformation and composition type that is used to compute them.

The columns in the DE_AG_Composite_Field table (DE_AG_COMPOSITE_FIELD) are listed below with the data type.

Column Name	Data Type
COMPOSITE_FIELD	varchar(30)
COMPOSITION_CLASSNAME	varchar(500)
COMPOSITION_ORDER	int
CONFIGURATION_ID	int
DEFINITION	nvarchar(4000)
IS_HASHED	int
RECORD_SOURCE_ID	int
SELECTOR_CLASSNAME	varchar(500)
SELECTOR_CONDITION	varchar(500)
SELECTOR_PRIORITY	int
SOURCE_FIELD	varchar(30)
TRANSFORMATION_CLASSNAME	varchar(500)
TRANSFORMATION_PARAM	varchar(500)

Index Name: PK_DE_AG_COMPOSITE_FIELD

Fields:

- CONFIGURATION_ID
- RECORD_SOURCE_ID
- COMPOSITE_FIELD
- SELECTOR_CLASSNAME
- SOURCE_FIELD

Column Descriptions

The following are the descriptions of the DE_AG_Composite_Field table columns.

COMPOSITE_FIELD — The name of the field.

COMPOSITION_CLASSNAME — The class of the composition (it should be a fully qualified java class name).

COMPOSITION_ORDER — The order.

CONFIGURATION_ID — The unique ID of the configuration.

DEFINITION — The definition of the composition. Currently, it is used by the JavaScript type of composite fields to store the JavaScript composition logic.

IS_HASHED — Indicates whether Tiebreaker hashing is enabled. The hashing functionality was tested and is supported by ACI only for PIM Card Transactions (Record Source ID = 25).

Valid values are:

0 = Disabled

1 = Enabled

RECORD_SOURCE_ID — The identifier of the record source as defined in the Analytic Gateway.

SELECTOR_CLASSNAME — The class of the operation (it should be a fully qualified java class name).

SELECTOR_CONDITION — The selector condition.

SELECTOR_PRIORITY — The selector condition.

SOURCE_FIELD — The source field.

TRANSFORMATION_CLASSNAME — The class of the transformation (it should be a fully qualified java class name).

TRANSFORMATION_PARAM — The parameters for the transformation.

DE_AG_Services Table

Description not available.

The columns in the DE_AG_Services table (DE_AG_SERVICES) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ARGUMENTTYPE	nvarchar(256)
CONFIGURATION_ID	int
ISIDEMPOTENT	smallint
OPERATION	nvarchar(50)
RECORD_SOURCE_ID	int
RESPONSETYPE	nvarchar(256)
SERVICENAME	nvarchar(50)
TIMEOUTBATCH	int
TIMEOUTTXN	int
VERSION	nvarchar(10)

Index Name: **DE_AG_SERVICES_PK**

Fields: CONFIGURATION_ID

ServiceName
Version
Operation

Column Descriptions

The following are the descriptions of the DE_AG_Services table columns.

ArgumentType — The type of argument used.

CONFIGURATION_ID — The configuration ID.

IsIdempotent — Description not available.

Operation — The operation to be executed.

RECORD_SOURCE_ID — The record source ID.

ResponseType — The response type.

ServiceName — The name of the service.

TimeoutBatch — The timeout for batch.

TimeoutTxn — The timeout for the transaction.

Version — The version

DE_Application_Data_Type Table

The DE_Application_Data_Type table stores the application data types that are defined for the Analytic Gateway's record source attributes and the associated columns' SQL types, for both MSSQL and Oracle databases.

The columns in the DE_Application_Data_Type table (DE_APPLICATION_DATA_TYPE) are listed below with the data type.

Column Name	Data Type
APPLICATION_DATA_TYPE	varchar(30)
APPLICATION_DATA_TYPE_ID	int
SQL_DATA_TYPE	varchar(30)
SQL_DATA_TYPE_MSQ	varchar(30)
SQL_DATA_TYPE_ORA	varchar(30)

Index Name: DE_APP_DT_TYP_PK

Fields: APPLICATION_DATA_TYPE_ID

Column Descriptions

The following are the descriptions of the DE_Application_Data_Type table columns.

APPLICATION_DATA_TYPE — The Analytic Gateway’s application data type of the record source attribute.

APPLICATION_DATA_TYPE_ID — The Analytic Gateway’s application data type ID of the record source attribute. Foreign key in Application_Data_Type (APPLICATION_DATA_TYPE_ID).

SQL_DATA_TYPE — The SQL data type corresponding to the current Analytic Gateway application data type.

SQL_DATA_TYPE_MSQ — The SQL data type corresponding to the current Analytic Gateway application data type for MSSQL.

SQL_DATA_TYPE_ORA — The SQL data type corresponding to the current Analytic Gateway application data type for Oracle.

DE_Column Table

The DE_Column table stores the column information for all defined action level related tables, such as column type and size and the table to which they belong.

The columns in the DE_Column table (DE_COLUMN) are listed below with the data type.

Column Name	Data Type
COLUMN_NAME	varchar(30)
COLUMN_ORDER	int
CONFIGURATION_ID	int
DATASIZE	int
DATATYPE	varchar(30)
DATATYPE_MSQ	varchar(30)
DATATYPE_ORA	varchar(30)
JSON	integer
TABLE_NAME	varchar(30)

Index Name: **DE_COLUMN_PK**

Fields: CONFIGURATION_ID
 TABLE_NAME
 COLUMN_NAME

Column Descriptions

The following are the descriptions of the DE_Column table columns.

COLUMN_NAME — The name of the table column to which the record source attribute is mapped within an entry procedure.

COLUMN_ORDER — The column order.

CONFIGURATION_ID — The configuration ID.

DATASIZE — The column data size.

DATATYPE — The column data type.

DATATYPE_MSQ — The datatype used on MSSQL.

DATATYPE_ORA — The datatype used on Oracle.

JSON — Flag that indicates whether this column is a JSON formatted string.

TABLE_NAME — The name of the table to which the record source attribute is mapped within an entry procedure.

DE_Compatible_SQL_Data_Type Table

The DE_Compatible_SQL_Data_Type table stores the known compatible associations between application data type of a record source attribute and the SQL data type of an action level table column, in order to validate such mappings.

The columns in the DE_Compatible_SQL_Data_Type table (DE_COMPATIBLE_SQL_DATA_TYPE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
COLUMN_DATA_TYPE	varchar(30)
RECORD_SOURCE_ATTR_DATA_TYPE	varchar(30)

Index Name: **DE_COMPATIBLE_SQL_DATA_TYPE_PK**

Fields: RECORD_SOURCE_ATTR_DATA_TYPE
 COLUMN_DATA_TYPE

Column Descriptions

The following are the descriptions of the DE_Compatible_SQL_Data_Type table columns.

COLUMN_DATA_TYPE — The data type column.

RECORD_SOURCE_ATTR_DATA_TYPE — The record source data type attribute.

DE_Configuration Table

The DE_Configuration table stores the currently defined configurations (that is, Running, Provisioning, and so on).

The columns in the DE_Configuration table (DE_CONFIGURATION) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
CONFIGURATION_ID	int
CONFIGURATION_TYPE	varchar(50)
DEPLOY_DATE	datetime
LOCALE_ID	varchar(30)

Index Name: **DE_CONFIGURATION_PK**

Fields: CONFIGURATION_ID

Column Descriptions

The following are the descriptions of the DE_Configuration table columns.

CONFIGURATION_ID — The configuration ID.

CONFIGURATION_TYPE — The configuration type.

DEPLOY_DATE — The date of the deploy.

LOCALE_ID — The Foreign Key to the column LOCALE_ID in table AVAILABLE_LOCALE.

DE_Configuration_Type Table

The DE_Configuration_Type table stores the types of configurations that may be defined (currently: Running, Provisioning, Canceled, Old).

The columns in the DE_Configuration_Type table (DE_CONFIGURATION_TYPE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
CONFIGURATION_TYPE	varchar(50)
DESCRIPTION	varchar(200)

Index Name: DE_CONFIGURATION_TYPE_PK

Fields: CONFIGURATION_TYPE

Column Descriptions

The following are the descriptions of the DE_Configuration_Type table columns.

CONFIGURATION_TYPE — The configuration type.

DESCRIPTION — The description of the configuration.

DE_Demo_Caption Table

The DE_Demo_Caption table stores the captions for all action level columns that are exposed in the UI.

The columns in the DE_Demo_Caption table (DE_DEMO_CAPTION) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
ACTION_LEVEL_TYPE	int
CAPTION	varchar(254)
COMPONENT_NAME	varchar(254)

Index Name: **PK_DE_DEMO_CAPTION**

Fields: ACTION_LEVEL_ID
 ACTION_LEVEL_TYPE
 COMPONENT_NAME

Column Descriptions

The following are the descriptions of the DE_Demo_Caption table columns.

ACTION_LEVEL_ID — The action level ID.

ACTION_LEVEL_TYPE — The action level type.

CAPTION — The caption.

COMPONENT_NAME — The component name.

DE_PIM_Mappings Table

The DE_PIM_Mappings table stores the mappings between record source attributes and corresponding PIM paths, for PIM record sources.

The columns in the DE_PIM_Mappings table (DE_PIM_MAPPINGS) are listed below with the data type.

Column Name	Data Type
ATTRIBUTENAME	varchar(255)
CLASSNAME	varchar(255)
CONFIGURATION_ID	int
CONVERSION	smallint
ERROR	smallint
MAP_ORDER	int
PIMPATH	varchar(4000)
VALIDATION	varchar(255)

Index Name: **DE_PIM_MAPPINGS_PK**

Fields: CONFIGURATION_ID
 CLASSNAME
 ATTRIBUTENAME

Column Descriptions

The following are the descriptions of the DE_PIM_Mappings table columns.

ATTRIBUTENAME — The name of the attribute

CLASSNAME — The name of the JAVA class.

CONFIGURATION_ID — The configuration ID.

CONVERSION — Contains conversion of the PIM mapping.

ERROR — Contains the errors.

MAP_ORDER — Contains the order of the mapping.

PIMPATH — The path for the PIM.

VALIDATION — Contains validation of the PIM mapping.

DE_Record_Source Table

The DE_Record_Source table stores the defined Analytic Gateway record sources.

The columns in the DE_Record_Source table (DE_RECORD_SOURCE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
CONFIGURATION_ID	int
DBTYPE	int
DBTYPE_MSQ	int
DBTYPE_ORA	int
IF_RECORD_LENGTH	int
IF_RECORD_START_BYTES	varchar(50)
MESSAGE_TYPE	varchar(10)
PIM_CLASS_NAME	varchar(255)
RECORD_SOURCE_DESCRIPTION	varchar(500)
RECORD_SOURCE_FORMAT_CODE	varchar(10)

Column Name	Data Type
RECORD_SOURCE_ID	int
RECORD_SOURCE_NAME	varchar(50)
SOFT_DELETE_IND	int
SYSTEM_DEFINED_IND	int

Index Name: DE_RECORD_SOURCE_UN1

Fields: CONFIGURATION_ID
RECORD_SOURCE_NAME

Index Name: DE_RECORD_SOURCE_PK

Fields: CONFIGURATION_ID
RECORD_SOURCE_ID

Column Descriptions

The following are the descriptions of the DE_Record_Source table columns.

CONFIGURATION_ID — Description not available.

DBTYPE — Description not available.

DBTYPE_MSQ — Description not available.

DBTYPE_ORA — Description not available.

IF_RECORD_LENGTH — Description not available.

IF_RECORD_START_BYTES — Description not available.

MESSAGE_TYPE — Description not available.

PIM_CLASS_NAME — Description not available.

RECORD_SOURCE_DESCRIPTION — Description not available.

RECORD_SOURCE_FORMAT_CODE — Description not available.

RECORD_SOURCE_ID — Description not available.

RECORD_SOURCE_NAME — Description not available.

SOFT_DELETE_IND — Description not available.

SYSTEM_DEFINED_IND — Description not available.

DE_Record_Source_Attr Table

The DE_Record_Source_Attr table stores the information about all defined AG record source attributes.

The columns in the DE_Record_Source_Attr table (DE_RECORD_SOURCE_ATTR) are listed below with the data type.

Column Name	Data Type
ACCEPTABLE_VALUES	varchar(4000)
APPLICATION_DATA_TYPE_ID	int
ATTRIBUTE_NAME	varchar(30)
CONFIGURATION_ID	int
DEFAULT_VALUE	varchar(50)

Column Name	Data Type
ENABLE_FAILSAFE_VALUE	int
FAILSAFE_VALUE	varchar(255)
GEN_PATTERN	nvarchar(512)
IF_FIELD_LENGTH	int
IF_FIELD_OFFSET	int
IF_TRIM_FLAG	numeric
PIM_PATH	varchar(Max)
PIM_VALIDATION	varchar(256)
RECORD_SOURCE_ID	int

Index Name: **DE_RECORD_SOURCE_ATTR_PK**

Fields: CONFIGURATION_ID
 RECORD_SOURCE_ID
 ATTRIBUTE_NAME

Column Descriptions

The following are the descriptions of the DE_Record_Source_Attr table columns.

ACCEPTABLE_VALUES — Description not available.

APPLICATION_DATA_TYPE_ID — Description not available.

ATTRIBUTE_NAME — Description not available.

CONFIGURATION_ID — Description not available.

DEFAULT_VALUE — Description not available.

ENABLE_FAILSAFE_VALUE — Description not available.

FAILSAFE_VALUE — Description not available.

GEN_PATTERN — Description not available.

IF_FIELD_LENGTH — Description not available.

IF_FIELD_OFFSET — Description not available.

IF_TRIM_FLAG — Description not available.

PIM_PATH — Description not available.

PIM_VALIDATION — Description not available.

RECORD_SOURCE_ID — Description not available.

DE_Record_Source_Format Table

The DE_Record_Source_Format table stores all known Analytic Gateway record source formats (for example, IF, XF, PIM, and so on).

The columns in the DE_Record_Source_Format table (DE_RECORD_SOURCE_FORMAT) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
FORMAT_CODE	varchar(10)

Index Name: DE_RS_FORMAT_PK

Fields: FORMAT_CODE

Column Descriptions

The following are the descriptions of the DE_Record_Source_Format table columns.

FORMAT_CODE — Description not available.

DE_Record_Source_Mapping Table

The DE_Record_Source_Mapping table stores the record source attribute to action level table column mapping metadata.

The columns in the DE_Record_Source_Mapping table (DE_RECORD_SOURCE_MAPPING) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
ATTRIBUTE_NAME	varchar(30)
COLUMN_NAME	varchar(30)
CONFIGURATION_ID	int
RECORD_SOURCE_ID	int
TABLE_NAME	varchar(30)

Index Name: DE_RECORD_SOURCE_MAPPING_PK

Fields: CONFIGURATION_ID
RECORD_SOURCE_ID
ATTRIBUTE_NAME
TABLE_NAME
COLUMN_NAME

Index Name: DE_RECORD_SOURCE_MAP_UN1

Fields: CONFIGURATION_ID
 RECORD_SOURCE_ID
 TABLE_NAME
 COLUMN_NAME

Column Descriptions

The following are the descriptions of the DE_Record_Source_Mapping table columns.

ATTRIBUTE_NAME — Description not available.

COLUMN_NAME — Description not available.

CONFIGURATION_ID — Description not available.

RECORD_SOURCE_ID — Description not available.

TABLE_NAME — Description not available.

DE_Record_Source_Type Table

The DE_Record_Source_Type table stores the existing record source types.

The columns in the DE_Record_Source_Type table (DE_RECORD_SOURCE_TYPE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
MESSAGE_TYPE	varchar(10)

Index Name: DE_RS_SRC_TYPE_PK

Fields: MESSAGE_TYPE

Column Descriptions

The following are the descriptions of the DE_Record_Source_Type table columns.

MESSAGE_TYPE — Description not available.

DE_SQL_Data_Type Table

The DE_SQL_Data_Type table stores the available data types for the current database type.

The columns in the DE_SQL_Data_Type table (DE_SQL_DATA_TYPE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
SQL_DATA_TYPE	varchar(30)

Index Name: DE_SQL_DT_TYPE_PK

Fields: SQL_DATA_TYPE

Column Descriptions

The following are the descriptions of the DE_SQL_Data_Type table columns.

SQL_DATA_TYPE — Description not available.

DE_SQL_Data_Type_MSQ Table

The DE_SQL_Data_Type_MSQ table stores the available data types for the MSSQL database.

The columns in the DE_SQL_Data_Type_MSQ table (DE_SQL_DATA_TYPE_MSQ) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
SQL_DATA_TYPE	varchar(30)

Index Name: PK_DE_SQL_DATA_TYPE_MSQ

Fields: SQL_DATA_TYPE

Column Descriptions

The following are the descriptions of the DE_SQL_Data_Type_MSQ table columns.

SQL_DATA_TYPE — Description not available.

DE_SQL_Data_Type_ORA Table

The DE_SQL_Data_Type_ORA table stores the available data types for the Oracle database.

The columns in the DE_SQL_Data_Type_ORA table (DE_SQL_DATA_TYPE_ORA) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
SQL_DATA_TYPE	varchar(30)

Index Name: **PK_DE_SQL_DATA_TYPE_ORA**

Fields: SQL_DATA_TYPE

Column Descriptions

The following are the descriptions of the DE_SQL_Data_Type_ORA table columns.

SQL_DATA_TYPE — Description not available.

DE_Table Table

The DE_Table table stores the defined table names and whether they are part of the NRT or RT database.

The columns in the DE_Table table (DE_TABLE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
CONFIGURATION_ID	int
NRT_RT	varchar(3)

Column Name	Data Type
TABLE_NAME	varchar(30)

Index Name: DE_TABLE_PK

Fields: CONFIGURATION_ID
TABLE_NAME

Column Descriptions

The following are the descriptions of the DE_Table table columns.

CONFIGURATION_ID — Description not available.

NRT_RT — Description not available.

TABLE_NAME — Description not available.

DE_UI_Component Table

The DE_UI_Component table stores the defined UI components (for example, screens, fields, labels, grids, and panels) and their basic properties such as name, type, parent, and action level.

The columns in the DE_UI_Component table (DE_UI_COMPONENT) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_ID	int
COMPONENT_ID	int
COMPONENT_NAME	varchar(100)
COMPONENT_TYPE	varchar(30)

Column Name	Data Type
CONFIGURATION_ID	int
DESCRIPTION	nvarchar(255)
DISPLAY_NAME	varchar(100)
ORDER_NUM	int
PARENT_ID	int
TOOLTIP	nvarchar(100)
VISIBLE	int

Index Name: IX1_DE_UI_COMPONENT

Fields: PARENT_ID

Index Name: IX2_DE_UI_COMPONENT

Fields: COMPONENT_TYPE

Index Name: IX3_DE_UI_COMPONENT

Fields: ACTION_LEVEL_ID

Index Name: PK_DE_UI_COMPONENT

Fields: CONFIGURATION_ID
COMPONENT_ID

Column Descriptions

The following are the descriptions of the DE_UI_Component table columns.

ACTION_LEVEL_ID — Description not available.

COMPONENT_ID — Description not available.

COMPONENT_NAME — The name of the component used in the user interface.

COMPONENT_TYPE — Description not available.

CONFIGURATION_ID — Description not available.

DESCRIPTION — Description not available.

DISPLAY_NAME — Description not available.

ORDER_NUM — Description not available.

PARENT_ID — Description not available.

TOOLTIP — Description not available.

VISIBLE — Description not available.

DE_UI_Field Table

The DE_UI_Field table stores the defined action level columns that may be exposed in the UI, along with formatting options.

The columns in the DE_UI_Field table (DE_UI_FIELD) are listed below with the data type.

Column Name	Data Type
ALIGNMENT	int
COMPONENT_ID	int
CONFIGURATION_ID	int
EDITABLE	int
FILTER	int

Column Name	Data Type
FORMAT_ID	int
HYPERLINK	varchar(50)
HYPERLINK_TYPE	int
L10N_ENABLED	int
LABELID	int
MASKING_ID	int
NULLDISPLAY	varchar(15)
WIDTH	int
ZERODISPLAY	varchar(15)

Index Name: **PK_DE_UI_FIELD**

Fields: CONFIGURATION_ID
 COMPONENT_ID

Column Descriptions

The following are the descriptions of the DE_UI_Field table columns.

ALIGNMENT — Description not available.

COMPONENT_ID — Description not available.

CONFIGURATION_ID — Description not available.

EDITABLE — Description not available.

FILTER — Description not available.

FORMAT_ID — Description not available.

HYPERLINK — Description not available.

HYPERLINK_TYPE — Description not available.

L10N_ENABLED — Description not available.

LABELID — Description not available.

MASKING_ID — Description not available.

NULLDISPLAY — Description not available.

WIDTH — Description not available.

ZERODISPLAY — Description not available.

DE_UI_Field_Format Table

The DE_UI_Field_Format table stores the possible UI field formatting options.

The columns in the DE_UI_Field_Format table (DE_UI_FIELD_FORMAT) are listed below with the data type.

Column Name	Data Type
CONFIGURATION_ID	int
FORMATSTRING	varchar(255)

Column Name	Data Type
FORMATTYPE	int
FORMAT_ID	int

Index Name: **PK_DE_UI_FIELD_FORMAT**

Fields: CONFIGURATION_ID
 FORMAT_ID

Column Descriptions

The following are the descriptions of the DE_UI_Field_Format table columns.

CONFIGURATION_ID — Description not available.

FORMATSTRING — Description not available.

FORMATTYPE — Description not available.

FORMAT_ID — Description not available.

DE_UI_Field_Search Table

The DE_UI_Field_Search table stores the search options for the UI fields that are also search fields for certain action levels.

The columns in the DE_UI_Field_Search table (DE_UI_FIELD_SEARCH) are listed below with the data type.

Column Name	Data Type
COMPONENT_ID	int
CONFIGURATION_ID	int

Column Name	Data Type
MAXCHAR	numeric
SEARCH_ASSOCIATION	varchar(250)
VALIDATION_DEPENDENCY	varchar(100)
VALIDATION_WILDCARD	smallint

Index Name: **PK_DE_UI_FIELD_SEARCH**

Fields: CONFIGURATION_ID
 COMPONENT_ID

Column Descriptions

The following are the descriptions of the DE_UI_Field_Search table columns.

COMPONENT_ID — Description not available.

CONFIGURATION_ID — Description not available.

MAXCHAR — Description not available.

SEARCH_ASSOCIATION — Description not available.

VALIDATION_DEPENDENCY — Description not available.

VALIDATION_WILDCARD — Description not available.

DE_UI_GridBag_Config Table

The DE_UI_GridBag_Config table stores the grid bag placement options for the demographic action level fields that are exposed in UI.

The columns in the DE_UI_GridBag_Config table (DE_UI_GRIDBAG_CONFIG) are listed below with the data type.

Column Name	Data Type
ANCHOR	varchar(25)
COMPONENT_ID	int
CONFIGURATION_ID	int
FILL	varchar(25)
GRIDHEIGHT	int
GRIDWIDTH	int
GRIDX	int
GRIDY	int
IPADX	int
IPADY	int
WEIGHTX	int
WEIGHTY	int

Index Name: **PK_DE_UI_GRIDBAG_CONFIG**

Fields: CONFIGURATION_ID
 COMPONENT_ID

Column Descriptions

The following are the descriptions of the DE_UI_GridBag_Config table columns.

ANCHOR — Description not available.

COMPONENT_ID — Description not available.

CONFIGURATION_ID — Description not available.

FILL — Description not available.

GRIDHEIGHT — Description not available.

GRIDWIDTH — Description not available.

GRIDX — Description not available.

GRIDY — Description not available.

IPADX — Description not available.

IPADY — Description not available.

WEIGHTX — Description not available.

WEIGHTY — Description not available.

Section 5: **Profile and Peer Profile tables**

This section provides descriptions of the profile and peer profile tables for the following action levels:

- Account action level
- Card action level
- Employee action level
- Merchant action level
- Terminal action level
- UAID action level
- UAN action level

Following the tables for the actions levels, this section also provides descriptions of the profile tables for the following views:

- Device ID view
- IP Address view
- Payee view

Account action level

The following tables are specific to the Account action level:

- Acct_31_Days_Profile
- Acct_3_Days_Profile
- Acct_Daily_Profile

Acct_31_Days_Profile Table

Description not available.

The columns in the Acct_31_Days_Profile table (ACCT_31_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FMAX_DEPOSIT	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CASHINS	money
AVG_FSUM_CASHOUTS	money
AVG_FSUM_CCPAYMENT	money
AVG_FSUM_CHECKS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_NONCASHCREDIT	money
AVG_FSUM_NONCASHDEBIT	float
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WIREDOMESTICFROM	money
AVG_FSUM_WIREDOMESTICTO	money
AVG_FSUM_WIREFOREIGNFROM	money

Column Name	Data Type
AVG_FSUM_WIREFOREIGNTO	money
AVG_FSUM_WITHDRAWS	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CHECKS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_NONCASHCREDIT	float
AVG_NCNT_NONCASHDEBIT	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WIREDOMESTICFROM	float
AVG_NCNT_WIREDOMESTICTO	float
AVG_NCNT_WIREFOREIGNFROM	float
AVG_NCNT_WIREFOREIGNTO	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float

Column Name	Data Type
AVG_NCNT_XFERTO	float
DTDATE	datetime
SM_PRI_ACCT_NUM	varchar(50)

Index Name: PK_ACCT_31_DAYS_PROFILE

Fields: SM_PRI_ACCT_NUM
DTDATE

Column Descriptions

The following are the descriptions of the Acct_31_Days_Profile table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FMAX_DEPOSIT — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CASHINS — Description not available.

AVG_FSUM_CASHOUTS — Description not available.

AVG_FSUM_CCPAYMENT — Description not available.

AVG_FSUM_CHECKS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_NONCASHCREDIT — Description not available.

AVG_FSUM_NONCASHDEBIT — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WIREDOMESTICFROM — Description not available.

AVG_FSUM_WIREDOMESTICTO — Description not available.

AVG_FSUM_WIREFOREIGNFROM — Description not available.

AVG_FSUM_WIREFOREIGNTO — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CHECKS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_NONCASHCREDIT — Description not available.

AVG_NCNT_NONCASHDEBIT — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WIREDOMESTICFROM — Description not available.

AVG_NCNT_WIREDOMESTICTO — Description not available.

AVG_NCNT_WIREFOREIGNFROM — Description not available.

AVG_NCNT_WIREFOREIGNTO — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PRI_ACCT_NUM — Description not available.

Acct_3_Days_Profile Table

Description not available.

The columns in the Acct_3_Days_Profile table (ACCT_3_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money

Column Name	Data Type
AVG_FAMT_POS_TXNS	money
AVG_FMAX_DEPOSIT	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CASHINS	money
AVG_FSUM_CASHOUTS	money
AVG_FSUM_CCPAYMENT	money
AVG_FSUM_CHECKS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_NONCASHCREDIT	money
AVG_FSUM_NONCASHDEBIT	float
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WIREDOMESTICFROM	money
AVG_FSUM_WIREDOMESTICTO	money
AVG_FSUM_WIREFOREIGNFROM	money
AVG_FSUM_WIREFOREIGNTO	money
AVG_FSUM_WITHDRAWS	money

Column Name	Data Type
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CHECKS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_NONCASHCREDIT	float
AVG_NCNT_NONCASHDEBIT	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WIREDOMESTICFROM	float
AVG_NCNT_WIREDOMESTICTO	float
AVG_NCNT_WIREFOREIGNFROM	float
AVG_NCNT_WIREFOREIGNTO	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime

<i>Column Name</i>	<i>Data Type</i>
SM_PRI_ACCT_NUM	varchar(50)

Index Name: **PK_ACCT_3_DAYS_PROFILE**

Fields: SM_PRI_ACCT_NUM

DTDATE

Column Descriptions

The following are the descriptions of the Acct_3_Days_Profile table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FMAX_DEPOSIT — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CASHINS — Description not available.

AVG_FSUM_CASHOUTS — Description not available.

AVG_FSUM_CCPAYMENT — Description not available.

AVG_FSUM_CHECKS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_NONCASHCREDIT — Description not available.

AVG_FSUM_NONCASHDEBIT — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WIREDOMESTICFROM — Description not available.

AVG_FSUM_WIREDOMESTICTO — Description not available.

AVG_FSUM_WIREFOREIGNFROM — Description not available.

AVG_FSUM_WIREFOREIGNTO — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CHECKS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_NONCASHCREDIT — Description not available.

AVG_NCNT_NONCASHDEBIT — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WIREDOMESTICFROM — Description not available.

AVG_NCNT_WIREDOMESTICTO — Description not available.

AVG_NCNT_WIREFOREIGNFROM — Description not available.

AVG_NCNT_WIREFOREIGNTO — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PRI_ACCT_NUM — Description not available.

Acct_Daily_Profile Table

The Acct_Daily_Profile Table is used by the Analysis and Review system. It contains the daily totals of transaction types for an account. This table is only used by the ACI Proactive Risk Manager Account action level.

The columns in the Acct_Daily_Profile table (ACCT_DAILY_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FAMT_ATM_TXNS	money
FAMT_POS_TXNS	money

Column Name	Data Type
FMAX_DEPOSIT	money
FSUM_ATMDEPOSITS	money
FSUM_CASHINS	money
FSUM_CASHOUTS	money
FSUM_CCPAYMENT	money
FSUM_CHECKS	money
FSUM_DEPOSITS	money
FSUM_NONCASHCREDIT	money
FSUM_NONCASHDEBIT	money
FSUM_TXNSCREDIT	money
FSUM_TXNSDEBIT	money
FSUM_WIREDOMESTICFROM	money
FSUM_WIREDOMESTICTO	money
FSUM_WIREFOREIGNFROM	money
FSUM_WIREFOREIGNTO	money
FSUM_WITHDRAWS	money
LSTATUS	integer

Column Name	Data Type
NCNT_ATM_TXNS	int
NCNT_CHECKS	int
NCNT_DEPOSITS	int
NCNT_NONCASHCREDIT	int
NCNT_NONCASHDEBIT	int
NCNT_POS_TXNS	int
NCNT_TXNS	int
NCNT_TXNSCREDIT	int
NCNT_TXNSDEBIT	int
NCNT_WIREDOMESTICFROM	int
NCNT_WIREDOMESTICTO	int
NCNT_WIREFOREIGNFROM	int
NCNT_WIREFOREIGNTO	int
NCNT_WITHDRAWS	int
NCNT_XFERFROM	int
NCNT_XFERTO	int
PRCSID	varchar(50)

<i>Column Name</i>	<i>Data Type</i>
SM_PRI_ACCT_NUM	varchar(50)

Index Name: **PK_ACCT_DAILY_PRFL**

Fields: SM_PRI_ACCT_NUM

DTDATE

Column Descriptions

The following are the descriptions of the Acct_Daily_Profile table columns.

DTDATE — The transaction date.

FAMT_ATM_TXNS — The amount of ATM transactions.

FAMT_POS_TXNS — The amount of POS transactions.

FMAX_DEPOSIT — The maximum deposit amount.

FSUM_ATMDEPOSITS — The sum of the ATM deposits.

FSUM_CASHINS — The sum of the cash ins.

FSUM_CASHOUTS — The sum of the cash outs.

FSUM_CCPAYMENT — The sum of the credit card payments.

FSUM_CHECKS — The sum of the checks.

FSUM_DEPOSITS — The sum of deposits.

FSUM_NONCASHCREDIT — The sum of the non-cash credit.

FSUM_NONCASHDEBIT — The sum of the non-cash debits.

FSUM_TXNSCREDIT — The sum of the credit transactions.

FSUM_TXNSDEBIT — The sum of the debit transactions.

FSUM_WIREDOMESTICFROM — The number of wire transfers from domestic accounts.

FSUM_WIREDOMESTICTO — The number of wire transfers to domestic accounts.

FSUM_WIREFOREIGNFROM — The number of wire transfers from foreign accounts.

FSUM_WIREFOREIGNTO — The number of wire transfers to domestic accounts.

FSUM_WITHDRAWS — The sum of withdrawals.

LSTATUS — Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

0 - unassigned

1 - assigned

3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

NCNT_ATM_TXNS — The number of ATM transactions.

NCNT_CHECKS — The number of checks.

NCNT_DEPOSITS — The number of deposits.

NCNT_NONCASHCREDIT — The number of non-cash credits.

NCNT_NONCASHDEBIT — The number of non-cash debits.

NCNT_POS_TXNS — The count of POS transactions.

NCNT_TXNS — The number of transactions.

NCNT_TXNSCREDIT — The number of credit transactions.

NCNT_TXNSDEBIT — The number of debit transactions.

NCNT_WIREDOMESTICFROM — The number of wire transfer transactions from domestic accounts.

NCNT_WIREDOMESTICTO — The number of wire transfer transactions to domestic accounts.

NCNT_WIREFOREIGNFROM — The number of wire transfer transactions from foreign accounts.

NCNT_WIREFOREIGNTO — The number of wire transfer transactions to foreign accounts.

NCNT_WITHDRAWS — The number of withdrawals.

NCNT_XFERFROM — The number of transfers from an account.

NCNT_XFERTO — The number of transfers to an account.

PRCSID — Web server process that the row is assigned to for roll-up rules processing.

SM_PRI_ACCT_NUM — The account number.

Card action level

The following tables are specific to the Card action level:

- Card_31_Days_Peer_Profile
- Card_31_Days_Profile
- Card_3_Days_Peer_Profile
- Card_3_Days_Profile
- Card_Daily_Peer_Profile
- Card_Daily_Profile
- RT_Card_31_Days_Peer_Prof
- RT_Card_31_Days_Profile
- TT_Card_31_Days_Peer_Prof
- TT_RT_Card_31_Days_Peer_Prof

Card_31_Days_Peer_Profile Table

Description not available.

The columns in the Card_31_Days_Peer_Profile table (CARD_31_DAYS_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CP_TXNS	money

Column Name	Data Type
AVG_FSUM_DEPOSITS	money
AVG_FSUM_ECOM_TXNS	money
AVG_FSUM_MANUALEENTRY	money
AVG_FSUM_MOTO_TXNS	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WITHDRAWS	money
AVG_FSUM_XFERFROM	money
AVG_FSUM_XFERTO	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CP_TXNS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_ECOM_TXNS	float
AVG_NCNT_MANUALEENTRY	float
AVG_NCNT_MOTO_TXNS	float
AVG_NCNT_PANS	float
AVG_NCNT_POS_TXNS	float

Column Name	Data Type
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: IDX_CARD_31_PEER_PRFL

Fields: SM_PROFILE

Index Name: IDX_CARD_31_PEER_PRFL_CLUSTER

Fields: DTDATE
 SM_PROFILE

Column Descriptions

The following are the descriptions of the Card_31_Days_Peer_Profile table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CP_TXNS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_ECOM_TXNS — Description not available.

AVG_FSUM_MANUALEENTRY — Description not available.

AVG_FSUM_MOTO_TXNS — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_FSUM_XFERFROM — Description not available.

AVG_FSUM_XFERTO — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CP_TXNS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_ECOM_TXNS — Description not available.

AVG_NCNT_MANUALEENTRY — Description not available.

AVG_NCNT_MOTO_TXNS — Description not available.

AVG_NCNT_PANS — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

Card_31_Days_Profile Table

Description not available.

The columns in the Card_31_Days_Profile table (CARD_31_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CP_TXNS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_ECOM_TXNS	money

Column Name	Data Type
AVG_FSUM_MANUALEENTRY	money
AVG_FSUM_MOTO_TXNS	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WITHDRAWS	money
AVG_FSUM_XFERFROM	money
AVG_FSUM_XFERTO	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CP_TXNS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_ECOM_TXNS	float
AVG_NCNT_MANUALEENTRY	float
AVG_NCNT_MOTO_TXNS	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float

Column Name	Data Type
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime
SM_PAN	varchar(50)
SM_PROFILE	varchar(9)

Index Name: IDX_CARD_31_PRFL_CLUSTER

Fields: DTDATE

 SM_PAN

Index Name: IDX_CARD_31_PRFL_SM_PAN

Fields: SM_PAN

Column Descriptions

The following are the descriptions of the Card_31_Days_Profile table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CP_TXNS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_ECOM_TXNS — Description not available.

AVG_FSUM_MANUALEENTRY — Description not available.

AVG_FSUM_MOTO_TXNS — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_FSUM_XFERFROM — Description not available.

AVG_FSUM_XFERTO — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CP_TXNS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_ECOM_TXNS — Description not available.

AVG_NCNT_MANUALEENTRY — Description not available.

AVG_NCNT_MOTO_TXNS — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PAN — Description not available.

SM_PROFILE — Description not available.

Card_3_Days_Peer_Profile Table

Description not available.

The columns in the Card_3_Days_Peer_Profile table (CARD_3_DAYS_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CP_TXNS	money
AVG_FSUM_DEPOSITS	money

Column Name	Data Type
AVG_FSUM_ECOM_TXNS	money
AVG_FSUM_MANUALEENTRY	money
AVG_FSUM_MOTO_TXNS	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WITHDRAWS	money
AVG_FSUM_XFERFROM	money
AVG_FSUM_XFERTO	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CP_TXNS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_ECOM_TXNS	float
AVG_NCNT_MANUALEENTRY	float
AVG_NCNT_MOTO_TXNS	float
AVG_NCNT_PANS	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNSCREDIT	float

Column Name	Data Type
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: IDX_CARD_3_PEER_PRFL

Fields: SM_PROFILE

Index Name: IDX_CARD_3_PEER_PRFL_CLUSTER

Fields: DTDATE

SM_PROFILE

Column Descriptions

The following are the descriptions of the Card_3_Days_Peer_Profile table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CP_TXNS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_ECOM_TXNS — Description not available.

AVG_FSUM_MANUALEENTRY — Description not available.

AVG_FSUM_MOTO_TXNS — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_FSUM_XFERFROM — Description not available.

AVG_FSUM_XFERTO — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CP_TXNS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_ECOM_TXNS — Description not available.

AVG_NCNT_MANUALEENTRY — Description not available.

AVG_NCNT_MOTO_TXNS — Description not available.

AVG_NCNT_PANS — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

Card_3_Days_Profile Table

Description not available.

The columns in the Card_3_Days_Profile table (CARD_3_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CP_TXNS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_ECOM_TXNS	money

Column Name	Data Type
AVG_FSUM_MANUALEENTRY	money
AVG_FSUM_MOTO_TXNS	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WITHDRAWS	money
AVG_FSUM_XFERFROM	money
AVG_FSUM_XFERTO	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CP_TXNS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_ECOM_TXNS	float
AVG_NCNT_MANUALEENTRY	float
AVG_NCNT_MOTO_TXNS	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float

Column Name	Data Type
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime
SM_PAN	varchar(50)
SM_PROFILE	varchar(9)

Index Name: IDX_CARD_3_PRFL_CLUSTER

Fields: DTDATE

 SM_PAN

Index Name: IDX_CARD_3_PRFL_SM_PAN

Fields: SM_PAN

Column Descriptions

The following are the descriptions of the Card_3_Days_Profile table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CP_TXNS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_ECOM_TXNS — Description not available.

AVG_FSUM_MANUALEENTRY — Description not available.

AVG_FSUM_MOTO_TXNS — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_FSUM_XFERFROM — Description not available.

AVG_FSUM_XFERTO — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CP_TXNS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_ECOM_TXNS — Description not available.

AVG_NCNT_MANUALEENTRY — Description not available.

AVG_NCNT_MOTO_TXNS — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PAN — Description not available.

SM_PROFILE — Description not available.

Card_Daily_Peer_Profile Table

The Card_Daily_Peer_Profile Table is used by the Analysis and Review system. It contains the average daily totals of transaction types for a group of accounts grouped by SM_PROFILE. This table is only used by the ACI Proactive Risk Manager Card action level.

The columns in the Card_Daily_Peer_Profile table (CARD_DAILY_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CP_TXNS	money
AVG_FSUM_DEPOSITS	money

Column Name	Data Type
AVG_FSUM_ECOM_TXNS	money
AVG_FSUM_MANUALEENTRY	money
AVG_FSUM_MOTO_TXNS	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WITHDRAWS	money
AVG_FSUM_XFERFROM	money
AVG_FSUM_XFERTO	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CP_TXNS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_ECOM_TXNS	float
AVG_NCNT_MANUALEENTRY	float
AVG_NCNT_MOTO_TXNS	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float

Column Name	Data Type
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime
NCNT_PANS	int
SM_PROFILE	varchar(9)

Index Name: IDX_CARD_1_PEER_PRFL

Fields: SM_PROFILE

Index Name: IDX_CARD_1_PEER_PRFL_CLUSTER

Fields: DTDATE
 SM_PROFILE

Column Descriptions

The following are the descriptions of the Card_Daily_Peer_Profile table columns.

AVG_FAMT_ATM_TXNS — The average amount of ATM transactions.

AVG_FAMT_POS_TXNS — The average amount of POS transactions.

AVG_FSUM_ATMDEPOSITS — The average sum of the ATM deposits.

AVG_FSUM_CP_TXNS — The average value of the fSum_CP_Txns. This data is displayed in the Avg Sum CP Txns field on the Profile Avg 3 Day, Profile Avg 31 Day, Peer Daily, Peer Avg 3 Day, and Peer Avg 31 Day tabs of the Review screen for the card action level.

AVG_FSUM_DEPOSITS — The average maximum deposit amount.

AVG_FSUM_ECOM_TXNS — The average value of the fSum_ECom_ Txns. This data is displayed in the Avg Sum E-Commerce Txns field on the Profile Avg 3 Day, Profile Avg 31 Day, Peer Daily, Peer Avg 3 Day, and Peer Avg 31 Day tabs of the Review screen for the card action level.

AVG_FSUM_MANUALENTY — The average value of the fSum_ManualEntry. This data is displayed in the Avg Sum Manual Entry field on the Profile Avg 3 Day, Profile Avg 31 Day, Peer Daily, Peer Avg 3 Day, and Peer Avg 31 Day tabs of the Review screen for the card action level.

AVG_FSUM_MOTO_TXNS — The average value of the fSum_MOTO_ Txns. This data is displayed in the Avg Sum MOTO Txns field on the Profile Avg 3 Day, Profile Avg 31 Day, Peer Daily, Peer Avg 3 Day, and Peer Avg 31 Day tabs of the Review screen for the card action level.

AVG_FSUM_TXNSCREDIT — The average sum of the credit transactions.

AVG_FSUM_TXNSDEBIT — The average sum of the debit transactions.

AVG_FSUM_WITHDRAWS — The average sum of withdrawals.

AVG_FSUM_XFERFROM — The average sum of transfers from an account.

AVG_FSUM_XFERTO — The average sum of transfers to an account.

AVG_NCNT_ATM_TXNS — The average number of ATM transactions.

AVG_NCNT_CP_TXNS — The average value of the nCnt_CP_Txns. This data is displayed in the Avg CP Txns field on the Profile Avg 3 Day, Profile Avg 31 Day, Peer Daily, Peer Avg 3 Day, and Peer Avg 31 Day tabs of the Review screen for the card action level.

AVG_NCNT_DEPOSITS — The average number of deposits.

AVG_NCNT_ECOM_TXNS — The average value of the nCnt_ECom_ Txns. This data is displayed in the Avg E-Commerce Txns field on the Profile Avg 3 Day, Profile Avg 31 Day, Peer Daily, Peer Avg 3 Day, and Peer Avg 31 Day tabs of the Review screen for the card action level.

AVG_NCNT_MANUALENTRY — The average value of the nCnt_ManualEntry. This data is displayed in the Avg Manual Entry field on the Profile Avg 3 Day, Profile Avg 31 Day, Peer Daily, Peer Avg 3 Day, and Peer Avg 31 Day tabs of the Review screen for the card action level.

AVG_NCNT_MOTO_TXNS — The average value of the nCnt_MOTO_Txns. This data is displayed in the Avg MOTO Txns field on the Profile Avg 3 Day, Profile Avg 31 Day, Peer Daily, Peer Avg 3 Day, and Peer Avg 31 Day tabs of the Review screen for the card action level.

AVG_NCNT_POS_TXNS — The average number of POS transactions.

AVG_NCNT_TXNSCREDIT — The average number of credit transactions.

AVG_NCNT_TXNSDEBIT — The average number of debit transactions.

AVG_NCNT_WITHDRAWS — The average number of withdraws.

AVG_NCNT_XFERFROM — The average number of transfers from an account.

AVG_NCNT_XFERTO — The average number of transfers to an account.

DTDATE — The transaction date and time.

NCNT_PANS — Contains the number of PANs.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

Card_Daily_Profile Table

The Card_Daily_Profile Table is used by the Analysis and Review system. It contains the daily totals of transaction types for an account. This table is only used by the ACI Proactive Risk Manager Card action level.

The columns in the Card_Daily_Profile table (CARD_DAILY_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FAMT_ATM_TXNS	money
FAMT_POS_TXNS	money
FSUM_ATMDEPOSITS	money
FSUM_CP_TXNS	money
FSUM_DEPOSITS	money
FSUM_ECOM_TXNS	money
FSUM_MANUALENTRY	money
FSUM_MOTO_TXNS	money
FSUM_TXNSCREDIT	money
FSUM_TXNSDEBIT	money
FSUM_WITHDRAWS	money
FSUM_XFERFROM	money
FSUM_XFERTO	money
LSTATUS	integer
NCNT_ATM_TXNS	int

Column Name	Data Type
NCNT_CP_TXNS	int
NCNT_DEPOSITS	int
NCNT_ECOM_TXNS	int
NCNT_MANUALEENTRY	int
NCNT_MOTO_TXNS	int
NCNT_POS_TXNS	int
NCNT_TXNS	int
NCNT_TXNSCREDIT	int
NCNT_TXNSDEBIT	int
NCNT_WITHDRAWS	int
NCNT_XFERFROM	int
NCNT_XFERTO	int
PRCSID	varchar(50)
SM_PAN	varchar(50)
SM_PROFILE	varchar(9)

Index Name: **IDX_CARD_1_PRFL_CLUSTER**

Fields: DTDATE

 SM_PAN

Index Name: **IDX_CARD_1_PRFL_SM_PAN**

Fields: SM_PAN

Column Descriptions

The following are the descriptions of the Card_Daily_Profile table columns.

DTDATE — The transaction date.

FAMT_ATM_TXNS — The amount of ATM transactions.

FAMT_POS_TXNS — The amount of POS transactions.

FSUM_ATMDEPOSITS — The sum of the ATM deposits.

FSUM_CP_TXNS — The sum of MD_TRAN_AMT1 for transactions where the PT_SERV_ENTRY_MDE is equal to 02. This data is displayed in the Sum CP Txns field on the Profile Daily tab of the Review screen for the card action level.

FSUM_DEPOSITS — The sum of deposits.

FSUM_ECOM_TXNS — The sum of MD_TRAN_AMT1 for transactions where the E_COM_FLG is not equal to zero. This data is displayed in the Sum E-Commerce Txns field on the Profile Daily tab of the Review screen for the card action level.

FSUM_MANUALEENTRY — The sum MD_TRAN_AMT1 for of transactions where the PT_SERV_ENTRY_MDE is equal to 01. This data is displayed in the Sum Manual Entry field on the Profile Daily tab of the Review screen for the card action level.

FSUM_MOTO_TXNS — The sum of MD_TRAN_AMT1 for transactions where the PT_SERV_COND_CDE is equal to 08. This data is displayed in the Sum MOTO Txns field on the Profile Daily tab of the Review screen for the card action level.

FSUM_TXNSCREDIT — The sum of the credit transactions.

FSUM_TXNSDEBIT — The sum of the debit transactions.

FSUM_WITHDRAWS — The sum of withdrawals.

FSUM_XFERFROM — The sum of transfers from an account.

FSUM_XFERTO — The sum of transfers to an account.

LSTATUS — Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

0 - unassigned

1 - assigned

3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

NCNT_ATM_TXNS — The number of ATM transactions.

NCNT_CP_TXNS — The count of transactions where the PT_SERV_ENTRY_MDE is equal to 02. This data is displayed in the CP Txns field on the Profile Daily tab of the Review screen for the card action level.

NCNT_DEPOSITS — The number of deposits.

NCNT_ECOM_TXNS — The count of transactions where the E_COM_FLG is not equal to zero. This data is displayed in the E-Commerce Txns field on the Profile Daily tab of the Review screen for the card action level.

NCNT_MANUAENTRY — The count of transactions where the PT_SERV_ENTRY_MDE is equal to 01. This data is displayed in the Manual Entry field on the Profile Daily tab of the Review screen for the card action level.

NCNT_MOTO_TXNS — The count of transactions where the PT_SERV_COND_CDE is equal to 08. This data is displayed in the MOTO Txns field on the Profile Daily tab of the Review screen for the card action level.

NCNT_POS_TXNS — The count of POS transactions.

NCNT_TXNS — The number of transactions.

NCNT_TXNSCREDIT — The number of credit transactions.

NCNT_TXNSDEBIT — The number of debit transactions.

NCNT_WITHDRAWS — The number of withdrawals.

NCNT_XFERFROM — The number of transfers from an account.

NCNT_XFERTO — The number of transfers to an account.

PRCSID — Web server process that the row is assigned to for roll-up rules processing.

SM_PAN — The primary account number.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

RT_Card_31_Days_Peer_Prof Table

The RT_Card_31_Days_Peer_Prof table resides in the RT database and is identical to the Card_31_Days_Peer_Profile table. The data from the TT_RT_Card_31Days_Peer_Prof table is copied into this table. The data in this table can be used in real-time rules and aggregates.

The columns in the RT_Card_31_Days_Peer_Prof table (RT_CARD_31_DAYS_PEER_PROF) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CP_TXNS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_ECOM_TXNS	money
AVG_FSUM_MANUALENTTRY	money
AVG_FSUM_MOTO_TXNS	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WITHDRAWS	money
AVG_FSUM_XFERFROM	money
AVG_FSUM_XFERTO	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CP_TXNS	float
AVG_NCNT_DEPOSITS	float

Column Name	Data Type
AVG_NCNT_ECOM_TXNS	float
AVG_NCNT_MANUALENTTRY	float
AVG_NCNT_MOTO_TXNS	float
AVG_NCNT_PANS	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: **IX_RT_CARD_31_D_PEER_PROF**

Fields: DTDATE

 SM_PROFILE

Column Descriptions

The following are the descriptions of the RT_Card_31_Days_Peer_Prof table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CP_TXNS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_ECOM_TXNS — Description not available.

AVG_FSUM_MANUALEENTRY — Description not available.

AVG_FSUM_MOTO_TXNS — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_FSUM_XFERFROM — Description not available.

AVG_FSUM_XFERTO — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CP_TXNS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_ECOM_TXNS — Description not available.

AVG_NCNT_MANUALEENTRY — Description not available.

AVG_NCNT_MOTO_TXNS — Description not available.

AVG_NCNT_PANS — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

RT_Card_31_Days_Profile Table

The RT_Card_31_Days_Profile table resides in the RT database and is identical to the Card_31_Days_Profile table. If the relevant capability is enabled, data in RT_Card_31_Days_Profile is synchronized with data from NRT Card_31_Days_Profile table. The data in this table can be used in real-time rules and aggregates.

The columns in the RT_Card_31_Days_Profile table (RT_CARD_31_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CP_TXNS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_ECOM_TXNS	money
AVG_FSUM_MANUALEENTRY	money
AVG_FSUM_MOTO_TXNS	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WITHDRAWS	money
AVG_FSUM_XFERFROM	money
AVG_FSUM_XFERTO	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CP_TXNS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_ECOM_TXNS	float

Column Name	Data Type
AVG_NCNT_MANUAENTRY	float
AVG_NCNT_MOTO_TXNS	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime
SM_PAN	varchar(50)
SM_PROFILE	varchar(9)

Index Name: **IX_RT_CARD_31_DAYS_PROFILE**

Fields: DTDATE

 SM_PAN

Column Descriptions

The following are the descriptions of the RT_Card_31_Days_Profile table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CP_TXNS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_ECOM_TXNS — Description not available.

AVG_FSUM_MANUALEENTRY — Description not available.

AVG_FSUM_MOTO_TXNS — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_FSUM_XFERFROM — Description not available.

AVG_FSUM_XFERTO — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CP_TXNS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_ECOM_TXNS — Description not available.

AVG_NCNT_MANUALEENTRY — Description not available.

AVG_NCNT_MOTO_TXNS — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PAN — Description not available.

SM_PROFILE — Description not available.

TT_Card_31_Days_Peer_Prof Table

The TT_Card_31_Days_Peer_Prof table resides in the NRT database and is nearly identical to the Card 31 Days Peer Profile table. The data from the Card_31_Days_Peer_Profile table is copied into this table. Then, the data in this table is copied to the TT_RT_Card_31_Days_Peer_Prof table in the RT database.

Note: The TT_Card_31_Days_Peer_Prof table and the TT_RT_Card_31_Days_Peer Prof table contain a BATCH_ID column that is not included in the Card_31_Days_Peer_Prof table. The data type of the BATCH_ID column is INTEGER.

The columns in the TT_Card_31_Days_Peer_Prof table (TT_CARD_31_DAYS_PEER_PROF) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CP_TXNS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_ECOM_TXNS	money
AVG_FSUM_MANUALEENTRY	money
AVG_FSUM_MOTO_TXNS	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WITHDRAWS	money
AVG_FSUM_XFERFROM	money
AVG_FSUM_XFERTO	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CP_TXNS	float
AVG_NCNT_DEPOSITS	float

Column Name	Data Type
AVG_NCNT_ECOM_TXNS	float
AVG_NCNT_MANUALENTTRY	float
AVG_NCNT_MOTO_TXNS	float
AVG_NCNT_PANS	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
BATCH_ID	int
DTDATE	datetime
SM_PROFILE	varchar(9)

Column Descriptions

The following are the descriptions of the TT_Card_31_Days_Peer_Prof table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CP_TXNS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_ECOM_TXNS — Description not available.

AVG_FSUM_MANUALEENTRY — Description not available.

AVG_FSUM_MOTO_TXNS — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_FSUM_XFERFROM — Description not available.

AVG_FSUM_XFERTO — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CP_TXNS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_ECOM_TXNS — Description not available.

AVG_NCNT_MANUALEENTRY — Description not available.

AVG_NCNT_MOTO_TXNS — Description not available.

AVG_NCNT_PANS — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

BATCH_ID — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

TT_RT_Card_31_Days_Peer_Prof Table

The TT_RT_Card_31_Days_Peer_Prof table resides in the RT database and is nearly identical to the Card_31_Days_Peer_Profile table. The data from the TT_Card_31_Days_Peer_Prof table in the NRT database is copied into this table. Then, the data in this table is copied to the RT_Card_31_Days_Peer_Prof table.

Note: The TT_Card_31_Days_Peer_Prof table and the TT_RT_Card_31_Days_Peer Prof table contain a BATCH_ID column that is not included in the Card_31_Days_Peer_Prof table. The data type of the BATCH_ID column is INTEGER.

The columns in the TT_RT_Card_31_Days_Peer_Prof table (TT_RT_CARD_31_DAYS_PEER_PROF) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CP_TXNS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_ECOM_TXNS	money
AVG_FSUM_MANUALEENTRY	money
AVG_FSUM_MOTO_TXNS	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WITHDRAWS	money
AVG_FSUM_XFERFROM	money
AVG_FSUM_XFERTO	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CP_TXNS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_ECOM_TXNS	float

Column Name	Data Type
AVG_NCNT_MANUALENTTRY	float
AVG_NCNT_MOTO_TXNS	float
AVG_NCNT_PANS	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
BATCH_ID	int
DTDATE	date
SM_PROFILE	varchar(9)

Index Name: **IX_TT_RT_CARD_31_D_PEER_PROF**

Fields: DTDATE

 SM_PROFILE

 BATCH_ID

Column Descriptions

The following are the descriptions of the TT_RT_Card_31_Days_Peer_Prof table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CP_TXNS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_ECOM_TXNS — Description not available.

AVG_FSUM_MANUALENTRY — Description not available.

AVG_FSUM_MOTO_TXNS — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_FSUM_XFERFROM — Description not available.

AVG_FSUM_XFERTO — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CP_TXNS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_ECOM_TXNS — Description not available.

AVG_NCNT_MANUALENTRY — Description not available.

AVG_NCNT_MOTO_TXNS — Description not available.

AVG_NCNT_PANS — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

BATCH_ID — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

Employee action level

The following tables are specific to the Employee action level:

- Employee_30_Days_Peer_Profile
- Employee_30_Days_Profile
- Employee_7_Days_Peer_Profile

- Employee_7_Days_Profile
- Employee_90_Days_Peer_Profile
- Employee_90_Days_Profile
- Employee_Daily_Peer_Profile
- Employee_Daily_Profile

Employee_30_Days_Peer_Profile Table

Description not available.

The columns in the Employee_30_Days_Peer_Profile table (EMPLOYEE_30_DAYS_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM	money
AVG_NCNT	float
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: **IDX_EMP_30_PEER_PRFL**

Fields: SM_PROFILE

Index Name: **IDX_EMP_30_PEER_PRFL_CLUSTER**

Fields: DTDATE

SM_PROFILE

Column Descriptions

The following are the descriptions of the Employee_30_Days_Peer_Profile table columns.

AVG_FSUM — Description not available.

AVG_NCNT — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

Employee_30_Days_Profile Table

Description not available.

The columns in the Employee_30_Days_Profile table (EMPLOYEE_30_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM	money
AVG_NCNT	float
DTDATE	datetime
SM_EMPLOYEE_ID	varchar(50)
SM_PROFILE	varchar(9)

Index Name: **IDX_EMP_30_PRFL_CLUSTER**

Fields: DTDATE

 SM_EMPLOYEE_ID

Index Name: **IDX_EMP_30_PRFL_SM_EMP**

Fields: SM_EMPLOYEE_ID

Column Descriptions

The following are the descriptions of the Employee_30_Days_Profile table columns.

AVG_FSUM — Description not available.

AVG_NCNT — Description not available.

DTDATE — Description not available.

SM_EMPLOYEE_ID — Description not available.

SM_PROFILE — Description not available.

Employee_7_Days_Peer_Profile Table

Description not available.

The columns in the Employee_7_Days_Peer_Profile table (EMPLOYEE_7_DAYS_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM	money
AVG_NCNT	float
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: **IDX_EMP_7_PEER_PRFL**

Fields: SM_PROFILE

Index Name: **IDX_EMP_7_PEER_PRFL_CLUSTER**

Fields: DTDATE

 SM_PROFILE

Column Descriptions

The following are the descriptions of the Employee_7_Days_Peer_Profile table columns.

AVG_FSUM — Description not available.

AVG_NCNT — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

Employee_7_Days_Profile Table

Description not available.

The columns in the Employee_7_Days_Profile table (EMPLOYEE_7_DAYS_PROFILE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
AVG_FSUM	money
AVG_NCNT	float
DTDATE	datetime
SM_EMPLOYEE_ID	varchar(50)
SM_PROFILE	varchar(9)

Index Name: **IDX_EMP_7_PRFL_CLUSTER**

Fields: DTDAT

SM_EMPLOYEE_ID

Index Name: **IDX_EMP_7_PRFL_SM_EMP**

Fields: SM_EMPLOYEE_ID

Column Descriptions

The following are the descriptions of the Employee_7_Days_Profile table columns.

AVG_FSUM — Description not available.

AVG_NCNT — Description not available.

DTDATE — Description not available.

SM_EMPLOYEE_ID — Description not available.

SM_PROFILE — Description not available.

Employee_90_Days_Peer_Profile Table

Description not available.

The columns in the Employee_90_Days_Peer_Profile table (EMPLOYEE_90_DAYS_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM	money
AVG_NCNT	float
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: **IDX_EMP_90_PEER_PRFL**

Fields: SM_PROFILE

Index Name: **IDX_EMP_90_PEER_PRFL_CLUSTER**

Fields: DTDATE

 SM_PROFILE

Column Descriptions

The following are the descriptions of the Employee_90_Days_Peer_Profile table columns.

AVG_FSUM — Description not available.

AVG_NCNT — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

Employee_90_Days_Profile Table

Description not available.

The columns in the Employee_90_Days_Profile table (EMPLOYEE_90_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM	money
AVG_NCNT	float
DTDATE	datetime
SM_EMPLOYEE_ID	varchar(50)
SM_PROFILE	varchar(9)

Index Name: **IDX_EMP_90_PRFL_CLUSTER**

Fields: DTDAT

 SM_EMPLOYEE_ID

Index Name: **IDX_EMP_90_PRFL_SM_EMP**

Fields: SM_EMPLOYEE_ID

Column Descriptions

The following are the descriptions of the Employee_90_Days_Profile table columns.

AVG_FSUM — Description not available.

AVG_NCNT — Description not available.

DTDATE — The transaction date.

SM_EMPLOYEE_ID — Description not available.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

Employee_Daily_Peer_Profile Table

Description not available.

The columns in the Employee_Daily_Peer_Profile table (EMPLOYEE_DAILY_PEER_PROFILE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DTDATE	datetime
FSUM_TXNS	money
NCNT_TXNS	int
SM_PROFILE	varchar(9)

Index Name: **IDX_EMP_1_PEER_PRFL**

Fields: SM_PROFILE

Index Name: **IDX_EMP_1_PEER_PRFL_CLUSTER**

Fields: DTDATE
SM_PROFILE

Column Descriptions

The following are the descriptions of the Employee_Daily_Peer_Profile table columns.

DTDATE — The transaction date.

FSUM_TXNS — The sum of total transactions.

NCNT_TXNS — The count of all transactions.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

Employee_Daily_Profile Table

The Employee_Daily_Profile Table is used by the Analysis and Review system. It contains the daily totals of transaction types for an account. This table is only used by the ACI Proactive Risk Manager Employee action level.

The columns in the Employee_Daily_Profile table (EMPLOYEE_DAILY_PROFILE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DTDATE	datetime
FSUM_TXNS	money
LSTATUS	integer
NCNT_TXNS	int
PRCSID	varchar(50)

Column Name	Data Type
SM_EMPLOYEE_ID	varchar(50)
SM_PROFILE	varchar(9)

Index Name: **IDX_EMP_1_PRFL_CLUSTER**

Fields: DTDATE

 SM_EMPLOYEE_ID

Index Name: **IDX_EMP_1_PRFL_SM_EMP**

Fields: SM_EMPLOYEE_ID

Column Descriptions

The following are the descriptions of the Employee_Daily_Profile table columns.

DTDATE — The transaction date.

FSUM_TXNS — The sum of total transactions.

LSTATUS — Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

0 - unassigned

1 - assigned

3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

NCNT_TXNS — The count of all transactions.

PRCSID — Web server process that the row is assigned to for roll-up rules processing.

SM_EMPLOYEE_ID — The employee identifier.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

Merchant action level

The following tables are specific to the Merchant action level:

- Merchant_30_Days_Peer_Profile
- Merchant_30_Days_Profile
- Merchant_7_Days_Peer_Profile
- Merchant_7_Days_Profile
- Merchant_90_Days_Peer_Profile
- Merchant_90_Days_Profile
- Merchant_Daily_Peer_Profile
- Merchant_Daily_Profile

Merchant_30_Days_Peer_Profile Table

Description not available.

The columns in the Merchant_30_Days_Peer_Profile table (MER_30_DAYS_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_ACCOUNTS	float
AVG_ACTIVEDAY	float
AVG_AVGDEPOSITS	money
AVG_AVGTXNAMT	money

Column Name	Data Type
AVG_CNTCHARGEBACKS	float
AVG_CNTCRDIMPRINT	float
AVG_CNTCRDSWIPE	float
AVG_CNTDECLINED	float
AVG_CNTDEPOSITS	float
AVG_CNTFALLBACK	float
AVG_CNTFOREIGNCARD	float
AVG_CNTKEYENTER	float
AVG_CNTNONAUTH	float
AVG_CNTREFUNDS	float
AVG_CNTRETRIEVALREQ	float
AVG_CNTTXNS	float
AVG_SUMCHARGEBACKS	money
AVG_SUMDEPOSITS	money
AVG_SUMKEYENTER	money
AVG_SUMNONAUTH	money
AVG_SUMREFUNDS	money

Column Name	Data Type
AVG_SUMRETRIEVALREQ	money
AVG_TOTALTXNS	money
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: IDX_MER_30_PEER_PRFL

Fields: SM_PROFILE

Index Name: IDX_MER_30_PEER_PRFL_CLUSTER

Fields: DTDATE

SM_PROFILE

Column Descriptions

The following are the descriptions of the Merchant_30_Days_Peer_Profile table columns.

AVG_ACCOUNTS — the count of all transactions.

AVG_ACTIVEDAY — the average active day flag.

AVG_AVGDEPOSITS — the average of the daily average of the sum of all deposits.

AVG_AVGTXNAMT — the average of the daily average of the sum of all transaction amounts.

AVG_CNTCHARGEBACKS — the average count of charge backs.

AVG_CNTCRDIMPRINT — the average count of card imprints.

AVG_CNTCRDSWIPE — the average count of transactions when the average card was swiped.

AVG_CNTDECLINED — the average count of declined transactions.

AVG_CNTDEPOSITS — the average count of all deposits.

AVG_CNTFALLBACK — the average count of fall back transactions.

AVG_CNTFOREIGNCARD — the average count of foreign cards.

AVG_CNTKEYENTER — the average count of key entry transactions.

AVG_CNTNONAUTH — the average count of unauthorized transactions.

AVG_CNTREFUNDS — the average count of refunds.

AVG_CNTRETRIEVALREQ — the average count of retrieval requests.

AVG_CNTTXNS — the average count of all transactions.

AVG_SUMCHARGEBACKS — the average sum of charge backs.

AVG_SUMDEPOSITS — the average sum of all deposits.

AVG_SUMKEYENTER — average sum of key entry transactions.

AVG_SUMNONAUTH — the average sum of unauthorized transactions.

AVG_SUMREFUNDS — the average sum of refunds.

AVG_SUMRETRIEVALREQ — the average sum of retrieval requests.

AVG_TOTALTXNS — the average sum of total transactions.

DTDATE — the transaction date.

SM_PROFILE — profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

Merchant_30_Days_Profile Table

Description not available.

The columns in the Merchant_30_Days_Profile table (MER_30_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FAVG_AVGDEPOSITS	money
FAVG_AVGTXNAMT	money
FAVG_SUMCHARGEBACKS	money
FAVG_SUMDEPOSITS	money
FAVG_SUMKEYENTER	money
FAVG_SUMNONAUTH	money
FAVG_SUMREFUNDS	money
FAVG_SUMRETRIEVALREQ	money
FAVG_TOTALTXNS	money
NAVG_ACTIVEDAY	float
NAVG_CNTCHARGEBACKS	float

Column Name	Data Type
NAVG_CNTCRDIMPRINT	float
NAVG_CNTCRDSWIPE	float
NAVG_CNTDECLINED	float
NAVG_CNTDEPOSITS	float
NAVG_CNTFALLBACK	float
NAVG_CNTFOREIGNCARD	float
NAVG_CNTKEYENTER	float
NAVG_CNTNONAUTH	float
NAVG_CNTREFUNDS	float
NAVG_CNTRETRIEVALREQ	float
NAVG_CNTTXNS	float
SM_PROFILE	varchar(9)
SM_RETL_ID	varchar(50)

Index Name: IDX_MER_30_DAY_PRFL_CLUSTER

Fields: DTDATE

 SM_RETL_ID

Index Name: IDX_MER_30_DAY_PRFL_SM_RETL

Fields: SM_RETL_ID

Column Descriptions

The following are the descriptions of the Merchant_30_Days_Profile table columns.

DTDATE — the transaction date.

FAVG_AVGDEPOSITS — the average of the daily average of the sum of all deposits.

FAVG_AVGTXNAMT — the average of the daily average of the sum of all transaction amounts.

FAVG_SUMCHARGEBACKS — the average sum of charge backs.

FAVG_SUMDEPOSITS — the average sum of all deposits.

FAVG_SUMKEYENTER — average sum of key entry transactions.

FAVG_SUMNONAUTH — the average sum of unauthorized transactions.

FAVG_SUMREFUNDS — the average sum of refunds.

FAVG_SUMRETRIEVALREQ — the average sum of retrieval requests.

FAVG_TOTALTXNS — the average sum of total transactions.

NAVG_ACTIVEDAY — the average active day flag.

NAVG_CNTCHARGEBACKS — the average count of charge backs.

NAVG_CNTCRDIMPRINT — the average count of card imprints.

NAVG_CNTCRDSWIPE — the average count of transactions when the average card was swiped.

NAVG_CNTDECLINED — the average count of declined transactions.

NAVG_CNTDEPOSITS — the average count of all deposits.

NAVG_CNTFALLBACK — the average count of fall back transactions.

NAVG_CNTFOREIGNCARD — the average count of foreign cards.

NAVG_CNTKEYENTER — the average count of key entry transactions.

NAVG_CNTNONAUTH — the average count of unauthorized transactions.

NAVG_CNTREFUNDS — the average count of refunds.

NAVG_CNTRETRIEVALREQ — the average count of retrieval requests.

NAVG_CNTTXNS — the average count of all transactions.

SM_PROFILE — a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institutiondefined function and table.

SM_RETL_ID — the retailer identifier.

Merchant_7_Days_Peer_Profile Table

Description not available.

The columns in the Merchant_7_Days_Peer_Profile table (MER_7_DAYS_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_ACCOUNTS	float
AVG_ACTIVEDAY	float
AVG_AVGDEPOSITS	money

Column Name	Data Type
AVG_AVGTXNAMT	money
AVG_CNTCHARGEBACKS	float
AVG_CNTCRDIMPRINT	float
AVG_CNTCRDSWIPE	float
AVG_CNTDECLINED	float
AVG_CNTDEPOSITS	float
AVG_CNTFALLBACK	float
AVG_CNTFOREIGNCARD	float
AVG_CNTKEYENTER	float
AVG_CNTNONAUTH	float
AVG_CNTREFUNDS	float
AVG_CNTRETRIEVALREQ	float
AVG_CNTTXNS	float
AVG_SUMCHARGEBACKS	money
AVG_SUMDEPOSITS	money
AVG_SUMKEYENTER	money
AVG_SUMNONAUTH	money

Column Name	Data Type
AVG_SUMREFUNDS	money
AVG_SUMRETRIEVALREQ	money
AVG_TOTALTXNS	money
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: IDX_MER_7_PEER_PRFL

Fields: SM_PROFILE

Index Name: IDX_MER_7_PEER_PRFL_CLUSTER

Fields: DTDATE

SM_PROFILE

Column Descriptions

The following are the descriptions of the Merchant_7_Days_Peer_Profile table columns.

AVG_ACCOUNTS — The count of all transactions.

AVG_ACTIVEDAY — The average active day flag.

AVG_AVGDEPOSITS — The average of the daily average of the sum of all deposits.

AVG_AVGTXNAMT — The average of the daily average of the sum of all transaction amounts.

AVG_CNTCHARGEBACKS — The average count of charge backs.

AVG_CNTCRDIMPRINT — The average count of card imprints.

AVG_CNTCRDSWIPE — The average count of transactions when the average card was swiped.

AVG_CNTDECLINED — The average count of declined transactions.

AVG_CNTDEPOSITS — The average count of all deposits.

AVG_CNTFALLBACK — The average count of fall back transactions.

AVG_CNTFOREIGNCARD — The average count of foreign cards.

AVG_CNTKEYENTER — the average count of key entry transactions.

AVG_CNTNONAUTH — The average count of unauthorized transactions.

AVG_CNTREFUNDS — The average count of refunds.

AVG_CNTRETRIEVALREQ — The average count of retrieval requests.

AVG_CNTTXNS — The average count of all transactions.

AVG_SUMCHARGEBACKS — The average sum of charge backs.

AVG_SUMDEPOSITS — The average sum of all deposits.

AVG_SUMKEYENTER — Average sum of key entry transactions.

AVG_SUMNONAUTH — The average sum of unauthorized transactions.

AVG_SUMREFUNDS — The average sum of refunds.

AVG_SUMRETRIEVALREQ — The average sum of retrieval requests.

AVG_TOTALTXNS — the average sum of total transactions.

DTDATE — The transaction date.

SM_PROFILE — A profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

Merchant_7_Days_Profile Table

Description not available.

The columns in the Merchant_7_Days_Profile table (MER_7_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FAVG_AVGDEPOSITS	money
FAVG_AVGTXNAMT	money
FAVG_SUMCHARGEBACKS	money
FAVG_SUMDEPOSITS	money
FAVG_SUMKEYENTER	money
FAVG_SUMNONAUTH	money
FAVG_SUMREFUNDS	money
FAVG_SUMRETRIEVALREQ	money
FAVG_TOTALTXNS	money
NAVG_ACTIVEDAY	float
NAVG_CNTCHARGEBACKS	float

Column Name	Data Type
NAVG_CNTCRDIMPRINT	float
NAVG_CNTCRDSWIPE	float
NAVG_CNTDECLINED	float
NAVG_CNTDEPOSITS	float
NAVG_CNTFALLBACK	float
NAVG_CNTFOREIGNCARD	float
NAVG_CNTKEYENTER	float
NAVG_CNTNONAUTH	float
NAVG_CNTREFUNDS	float
NAVG_CNTRETRIEVALREQ	float
NAVG_CNTTXNS	float
SM_PROFILE	varchar(9)
SM_RETL_ID	varchar(50)

Index Name: IDX_MER_7_DAY_PRFL_CLUSTER

Fields: DTDATE

SM_RETL_ID

Index Name: IDX_MER_7_DAY_PRFL_SM_RETL

Fields: SM_RETL_ID

Column Descriptions

The following are the descriptions of the Merchant_7_Days_Profile table columns.

DTDATE — the transaction date.

FAVG_AVGDEPOSITS — the average of the daily average of the sum of all deposits.

FAVG_AVGTXNAMT — the average of the daily average of the sum of all transaction amounts.

FAVG_SUMCHARGEBACKS — the average sum of charge backs.

FAVG_SUMDEPOSITS — the average sum of all deposits.

FAVG_SUMKEYENTER — average sum of key entry transactions.

FAVG_SUMNONAUTH — the average sum of unauthorized transactions.

FAVG_SUMREFUNDS — the average sum of refunds.

FAVG_SUMRETRIEVALREQ — the average sum of retrieval requests.

FAVG_TOTALTXNS — the average sum of total transactions.

NAVG_ACTIVEDAY — the average active day flag.

NAVG_CNTCHARGEBACKS — the average count of charge backs.

NAVG_CNTCRDIMPRINT — the average count of card imprints.

NAVG_CNTCRDSWIPE — the average count of transactions when the average card was swiped.

NAVG_CNTDECLINED — the average count of declined transactions.

NAVG_CNTDEPOSITS — the average count of all deposits.

NAVG_CNTFALLBACK — the average count of fall back transactions.

NAVG_CNTFOREIGNCARD — the average count of foreign cards.

NAVG_CNTKEYENTER — the average count of key entry transactions.

NAVG_CNTNONAUTH — average count of unauthorized transactions.

NAVG_CNTREFUNDS — the average count of refunds.

NAVG_CNTRETRIEVALREQ — The average count of retrieval requests.

NAVG_CNTTXNS — the average count of all transactions.

SM_PROFILE — a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institutiondefined function and table.

SM_RETL_ID — the retailer identifier.

Merchant_90_Days_Peer_Profile Table

Description not available.

The columns in the Merchant_90_Days_Peer_Profile table (MER_90_DAYS_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_ACCOUNTS	float
AVG_ACTIVEDAY	float
AVG_AVGDEPOSITS	money

Column Name	Data Type
AVG_AVGTXNAMT	money
AVG_CNTCHARGEBACKS	float
AVG_CNTCRDIMPRINT	float
AVG_CNTCRDSWIPE	float
AVG_CNTDECLINED	float
AVG_CNTDEPOSITS	float
AVG_CNTFALLBACK	float
AVG_CNTFOREIGNCARD	float
AVG_CNTKEYENTER	float
AVG_CNTNONAUTH	float
AVG_CNTREFUNDS	float
AVG_CNTRetrievalREQ	float
AVG_CNTTXNS	float
AVG_SUMCHARGEBACKS	money
AVG_SUMDEPOSITS	money
AVG_SUMKEYENTER	money
AVG_SUMNONAUTH	money

Column Name	Data Type
AVG_SUMREFUNDS	money
AVG_SUMRETRIEVALREQ	money
AVG_TOTALTXNS	money
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: IDX_MER_90_PEER_PRFL

Fields: SM_PROFILE

Index Name: IDX_MER_90_PEER_PRFL_CLUSTER

Fields: DTDATE

SM_PROFILE

Column Descriptions

The following are the descriptions of the Merchant_90_Days_Peer_Profile table columns.

AVG_ACCOUNTS — The count of all transactions.

AVG_ACTIVEDAY — The average active day flag.

AVG_AVGDEPOSITS — The average of the daily average of the sum of all deposits.

AVG_AVGTXNAMT — The average of the daily average of the sum of all transaction amounts.

AVG_CNTCHARGEBACKS — The average count of charge backs.

AVG_CNTCRDIMPRINT — The average count of card imprints.

AVG_CNTCRDSWIPE — The average count of transactions when the average card was swiped.

AVG_CNTDECLINED — The average count of declined transactions.

AVG_CNTDEPOSITS — The average count of all deposits.

AVG_CNTFALLBACK — The average count of fall back transactions.

AVG_CNTFOREIGNCARD — The average count of foreign cards.

AVG_CNTKEYENTER — the average count of key entry transactions.

AVG_CNTNONAUTH — The average count of unauthorized transactions.

AVG_CNTREFUNDS — The average count of refunds.

AVG_CNTRETRIEVALREQ — The average count of retrieval requests.

AVG_CNTTXNS — The average count of all transactions.

AVG_SUMCHARGEBACKS — The average sum of charge backs.

AVG_SUMDEPOSITS — The average sum of all deposits.

AVG_SUMKEYENTER — Average sum of key entry transactions.

AVG_SUMNONAUTH — The average sum of unauthorized transactions.

AVG_SUMREFUNDS — The average sum of refunds.

AVG_SUMRETRIEVALREQ — The average sum of retrieval requests.

AVG_TOTALTXNS — the average sum of total transactions.

DTDATE — the transaction date.

SM_PROFILE — A profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

Merchant_90_Days_Profile Table

Description not available.

The columns in the Merchant_90_Days_Profile table (MER_90_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FAVG_AVGDEPOSITS	money
FAVG_AVGTXNAMT	money
FAVG_SUMCHARGEBACKS	money
FAVG_SUMDEPOSITS	money
FAVG_SUMKEYENTER	money
FAVG_SUMNONAUTH	money
FAVG_SUMREFUNDS	money
FAVG_SUMRETRIEVALREQ	money
FAVG_TOTALTXNS	money
NAVG_ACTIVEDAY	float

Column Name	Data Type
NAVG_CNTCHARGEBACKS	float
NAVG_CNTCRDIMPRINT	float
NAVG_CNTCRDSWIPE	float
NAVG_CNTDECLINED	float
NAVG_CNTDEPOSITS	float
NAVG_CNTFALLBACK	float
NAVG_CNTFOREIGNCARD	float
NAVG_CNTKEYENTER	float
NAVG_CNTNONAUTH	float
NAVG_CNTREFUNDS	float
NAVG_CNTRETRIEVALREQ	float
NAVG_CNTTXNS	float
SM_PROFILE	varchar(9)
SM_RETL_ID	varchar(50)

Index Name: IDX_MER_90_DAY_PRFL_CLUSTER

Fields: DTDATE

SM_RETL_ID

Index Name: IDX_MER_90_DAY_PRFL_SM_RETL

Fields: SM_RETL_ID

Column Descriptions

The following are the descriptions of the Merchant_90_Days_Profile table columns.

DTDATE — the transaction date.

FAVG_AVGDEPOSITS — the average of the daily average of the sum of all deposits.

FAVG_AVGTXNAMT — the average of the daily average of the sum of all transaction amounts.

FAVG_SUMCHARGEBACKS — the average sum of charge backs.

FAVG_SUMDEPOSITS — the average sum of all deposits.

FAVG_SUMKEYENTER — average sum of key entry transactions.

FAVG_SUMNONAUTH — the average sum of unauthorized transactions.

FAVG_SUMREFUNDS — the average sum of refunds.

FAVG_SUMRETRIEVALREQ — the average sum of retrieval requests.

FAVG_TOTALTXNS — the average sum of total transactions.

NAVG_ACTIVEDAY — the average active day flag.

NAVG_CNTCHARGEBACKS — the average count of charge backs.

NAVG_CNTCRDIMPRINT — the average count of card imprints.

NAVG_CNTCRDSWIPE — the average count of transactions when the average card was swiped.

NAVG_CNTDECLINED — the average count of declined transactions.

NAVG_CNTDEPOSITS — the average count of all deposits.

NAVG_CNTFALLBACK — the average count of fall back transactions.

NAVG_CNTFOREIGNCARD — the average count of foreign cards.

NAVG_CNTKEYENTER — the average count of key entry transactions.

NAVG_CNTNONAUTH — average count of unauthorized transactions.

NAVG_CNTREFUNDS — the average count of refunds.

NAVG_CNTRETRIEVALREQ — The average count of retrieval requests.

NAVG_CNTTXNS — the average count of all transactions.

SM_PROFILE — a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institutiondefined function and table.

SM_RETL_ID — the retailer identifier.

Merchant_Daily_Peer_Profile Table

Description not available.

The columns in the Merchant_Daily_Peer_Profile table (MER_DAILY_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FAVGDAILY_AVGDEPOSITS	money
FAVGDAILY_AVGTXNAMT	money

Column Name	Data Type
FAVGDAILY_SUMCHARGEBACKS	money
FAVGDAILY_SUMDEPOSITS	money
FAVGDAILY_SUMKEYENTER	money
FAVGDAILY_SUMNONAUTH	money
FAVGDAILY_SUMREFUNDS	money
FAVGDAILY_SUMRETRIEVALREQ	money
FAVGDAILY_TOTALTXNS	money
NAVGDAILY_ACTIVEDAY	float
NAVGDAILY_CNTCHARGEBACKS	float
NAVGDAILY_CNTCRDIMPRINT	float
NAVGDAILY_CNTCRDSWIPE	float
NAVGDAILY_CNTDECLINED	float
NAVGDAILY_CNTDEPOSITS	float
NAVGDAILY_CNTFALLBACK	float
NAVGDAILY_CNTFOREIGNCARD	float
NAVGDAILY_CNTKEYENTER	float
NAVGDAILY_CNTNONAUTH	float

Column Name	Data Type
NAVGDAILY_CNTREFUNDS	float
NAVGDAILY_CNTRETRIEVALREQ	float
NAVGDAILY_CNTTXNS	float
NCNT_ACCOUNTS	int
SM_PROFILE	varchar(9)

Index Name: **IDX_MER_1_PEER_PRFL**

Fields: SM_PROFILE

Index Name: **IDX_MER_1_PEER_PRFL_CLUSTER**

Fields: DTDAT

SM_PROFILE

Column Descriptions

The following are the descriptions of the Merchant_Daily_Peer_Profile table columns.

DTDATE — the transaction date.

FAVGDAILY_AVGDEPOSITS — the average sum of all deposits.

FAVGDAILY_AVGTXNAMT — the average sum of all transaction amounts.

FAVGDAILY_SUMCHARGEBACKS — the total sum of charge backs.

FAVGDAILY_SUMDEPOSITS — the total sum of all deposits.

FAVGDAILY_SUMKEYENTER — total sum of key entry transactions.

FAVGDAILY_SUMNONAUTH — the total sum of unauthorized transactions.

FAVGDAILY_SUMREFUNDS — the total sum of refunds.

FAVGDAILY_SUMRETRIEVALREQ — the total sum of retrieval requests.

FAVGDAILY_TOTALTXNS — the total sum of transactions.

NAVGDAILY_ACTIVEDAY — the average active day flag.

NAVGDAILY_CNTCHARGEBACKS — the total number of charge backs.

NAVGDAILY_CNTCRDIMPRINT — the total number of card imprints.

NAVGDAILY_CNTCRDSWIPE — the total number of transactions when the card was swiped.

NAVGDAILY_CNTDECLINED — the total number of declined transactions.

NAVGDAILY_CNTDEPOSITS — the total number of all deposits.

NAVGDAILY_CNTFALLBACK — the total number of fall back transactions.

NAVGDAILY_CNTFOREIGNCARD — the total number of foreign cards.

NAVGDAILY_CNTKEYENTER — the total number of key entry transactions.

NAVGDAILY_CNTNONAUTH — the total number of unauthorized transactions.

NAVGDAILY_CNTREFUNDS — the total number of refunds.

NAVGDAILY_CNTRETRIEVALREQ — the total number of retrieval requests.

NAVGDAILY_CNTTXNS — the total number of all transactions.

NCNT_ACCOUNTS — the count of all transactions.

SM_PROFILE — a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institutiondefined function and table.

Merchant_Daily_Profile Table

The Merchant_Daily_Profile Table is used by the Analysis and Review system. It contains the daily totals of transaction types for an account. This table is only used by the ACI Proactive Risk Manager Merchant action level.

The columns in the Merchant_Daily_Profile table (MER_DAILY_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FDAILY_AVGDEPOSITS	money
FDAILY_AVGTXNAMT	money
FDAILY_SUMCHARGEBACKS	money
FDAILY_SUMDEPOSITS	money
FDAILY_SUMKEYENTER	money
FDAILY_SUMNONAUTH	money
FDAILY_SUMREFUNDS	money
FDAILY_SUMRETRIEVALREQ	money
FDAILY_TOTALTXNS	money
LSTATUS	integer

Column Name	Data Type
NDAILY_ACTIVEDAY	int
NDAILY_CNTCHARGEBACKS	int
NDAILY_CNTCRDIMPRINT	int
NDAILY_CNTCRDSWIPE	int
NDAILY_CNTDECLINED	int
NDAILY_CNTDEPOSITS	int
NDAILY_CNTFALLBACK	int
NDAILY_CNTFOREIGNCARD	int
NDAILY_CNTKEYENTER	int
NDAILY_CNTNONAUTH	int
NDAILY_CNTREFUNDS	int
NDAILY_CNTRETRIEVALREQ	int
NDAILY_CNTTXNS	int
PRCSID	varchar(50)
SM_PROFILE	varchar(9)
SM_RET_L_ID	varchar(50)

Index Name: **IDX_MER_DAILY_PRFL_CLUSTER**

Fields: DTDTE

SM_RETL_ID

Index Name: **IDX_MER_DAILY_PRFL_SM_RETL**

Fields: SM_RETL_ID

Column Descriptions

The following are the descriptions of the Merchant_Daily_Profile table columns.

DTDATE — the transaction date.

FDAILY_AVGDEPOSITS — the average sum of all deposits.

FDAILY_AVGTXNAMT — the average sum of all transaction amounts.

FDAILY_SUMCHARGEBACKS — the total sum of charge backs.

FDAILY_SUMDEPOSITS — the total sum of all deposits.

FDAILY_SUMKEYENTER — total sum of key entry transactions.

FDAILY_SUMNONAUTH — the total sum of unauthorized transactions.

FDAILY_SUMREFUNDS — the total sum of refunds.

FDAILY_SUMRETRIEVALREQ — the total sum of retrieval requests.

FDAILY_TOTALTXNS — the total sum of transactions.

LSTATUS — Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

0 - unassigned

1 - assigned

3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help

managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

NDAILY_ACTIVEDAY — the average active day flag.

NDAILY_CNTCHARGEBACKS — the total number of charge backs.

NDAILY_CNTCRDIMPRINT — the total number of card imprints.

NDAILY_CNTCRDSWIPE — the total number of transactions when the card was swiped.

NDAILY_CNTDECLINED — the total number of declined transactions.

NDAILY_CNTDEPOSITS — the total number of all deposits.

NDAILY_CNTFALLBACK — the total number of fall back transactions.

NDAILY_CNTFOREIGNCARD — the total number of foreign cards.

NDAILY_CNTKEYENTER — the total number of key entry transactions.

NDAILY_CNTNONAUTH — the total number of unauthorized transactions.

NDAILY_CNTREFUNDS — the total number of refunds.

NDAILY_CNTRETRIEVALREQ — the total number of retrieval requests

NDAILY_CNTTXNS — the total number of all transactions.

PRCSID — Web server process that the row is assigned to for roll-up rules processing.

SM_PROFILE — a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institutiondefined function and table.

SM_RETL_ID — the retailer identifier.

Terminal action level

The following tables are specific to the Terminal action level:

- Term_3_Days_Peer_Profile
- Term_3_Days_Profile
- Term_7_Days_Peer_Profile
- Term_7_Days_Profile
- Term_Daily_Peer_Profile
- Term_Daily_Profile

Term_3_Days_Peer_Profile Table

Description not available.

The columns in the Term_3_Days_Peer_Profile table (TERM_3_DAYS_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CASHINS	money
AVG_FSUM_CASHOUTS	money
AVG_FSUM_CCPAYMENT	money
AVG_FSUM_CHECKS	money

Column Name	Data Type
AVG_FSUM_DEPOSITS	money
AVG_FSUM_NONCASHCREDIT	money
AVG_FSUM_NONCASHDEBIT	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WIREDOMESTICFROM	money
AVG_FSUM_WIREDOMESTICTO	money
AVG_FSUM_WIREFOREIGNFROM	money
AVG_FSUM_WIREFOREIGNTO	money
AVG_FSUM_WITHDRAWS	money
AVG_NCNTWIREFOREIGNTO	float
AVG_NCNT_CHECKS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_NONCASHCREDIT	float
AVG_NCNT_NONCASHDEBIT	float
AVG_NCNT_TXNS	float
AVG_NCNT_TXNSCREDIT	float

Column Name	Data Type
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WIREDOMESTICFROM	float
AVG_NCNT_WIREDOMESTICTO	float
AVG_NCNT_WIREFOREIGNFROM	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: IDX_TERM_3_PEER_PRFL

Fields: SM_PROFILE

Index Name: IDX_TERM_3_PEER_PRFL_CLUSTER

Fields: DTDATE

SM_PROFILE

Column Descriptions

The following are the descriptions of the Term_3_Days_Peer_Profile table columns.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CASHINS — Description not available.

AVG_FSUM_CASHOUTS — Description not available.

AVG_FSUM_CCPAYMENT — Description not available.

AVG_FSUM_CHECKS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_NONCASHCREDIT — Description not available.

AVG_FSUM_NONCASHDEBIT — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WIREDOMESTICFROM — Description not available.

AVG_FSUM_WIREDOMESTICTO — Description not available.

AVG_FSUM_WIREFOREIGNFROM — Description not available.

AVG_FSUM_WIREFOREIGNTO — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_NCNTWIREFOREIGNTO — Description not available.

AVG_NCNT_CHECKS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_NONCASHCREDIT — Description not available.

AVG_NCNT_NONCASHDEBIT — Description not available.

AVG_NCNT_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WIREDOMESTICFROM — Description not available.

AVG_NCNT_WIREDOMESTICTO — Description not available.

AVG_NCNT_WIREFOREIGNFROM — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

Term_3_Days_Profile Table

Description not available.

The columns in the Term_3_Days_Profile table (TERM_3_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CASHINS	money
AVG_FSUM_CASHOUTS	money
AVG_FSUM_CCPAYMENT	money
AVG_FSUM_CHECKS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_NONCASHCREDIT	money
AVG_FSUM_NONCASHDEBIT	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WIREDOMESTICFROM	money
AVG_FSUM_WIREDOMESTICTO	money
AVG_FSUM_WIREFOREIGNFROM	money
AVG_FSUM_WIREFOREIGNTO	money
AVG_FSUM_WITHDRAWS	money
AVG_NCNTWIREFOREIGNTO	float
AVG_NCNT_CHECKS	float

Column Name	Data Type
AVG_NCNT_DEPOSITS	float
AVG_NCNT_NONCASHCREDIT	float
AVG_NCNT_NONCASHDEBIT	float
AVG_NCNT_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WIREDOMESTICFROM	float
AVG_NCNT_WIREDOMESTICTO	float
AVG_NCNT_WIREFOREIGNFROM	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime
SM_PROFILE	varchar(9)
SM_TERM_ID	varchar(50)

Index Name: **IDX_TERM_3_PRFL_CLUSTER**

Fields: DTDAT

SM_TERM_ID

Index Name: **IDX_TERM_3_PRFL_SM_TERM**

Fields: SM_TERM_ID

Column Descriptions

The following are the descriptions of the Term_3_Days_Profile table columns.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CASHINS — Description not available.

AVG_FSUM_CASHOUTS — Description not available.

AVG_FSUM_CCPAYMENT — Description not available.

AVG_FSUM_CHECKS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_NONCASHCREDIT — Description not available.

AVG_FSUM_NONCASHDEBIT — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WIREDOMESTICFROM — Description not available.

AVG_FSUM_WIREDOMESTICTO — Description not available.

AVG_FSUM_WIREFOREIGNFROM — Description not available.

AVG_FSUM_WIREFOREIGNTO — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_NCNTWIREFOREIGNTO — Description not available.

AVG_NCNT_CHECKS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_NONCASHCREDIT — Description not available.

AVG_NCNT_NONCASHDEBIT — Description not available.

AVG_NCNT_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WIREDOMESTICFROM — Description not available.

AVG_NCNT_WIREDOMESTICTO — Description not available.

AVG_NCNT_WIREFOREIGNFROM — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

SM_TERM_ID — Description not available.

Term_7_Days_Peer_Profile Table

Description not available.

The columns in the Term_7_Days_Peer_Profile table (TERM_7_DAYS_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CASHINS	money
AVG_FSUM_CASHOUTS	money
AVG_FSUM_CCPAYMENT	money
AVG_FSUM_CHECKS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_NONCASHCREDIT	money
AVG_FSUM_NONCASHDEBIT	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WIREDOMESTICFROM	money
AVG_FSUM_WIREDOMESTICTO	money

Column Name	Data Type
AVG_FSUM_WIREFOREIGNFROM	money
AVG_FSUM_WIREFOREIGNTO	money
AVG_FSUM_WITHDRAWS	money
AVG_NCNTWIREFOREIGNTO	float
AVG_NCNT_CHECKS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_NONCASHCREDIT	float
AVG_NCNT_NONCASHDEBIT	float
AVG_NCNT_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WIREDOMESTICFROM	float
AVG_NCNT_WIREDOMESTICTO	float
AVG_NCNT_WIREFOREIGNFROM	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float

Column Name	Data Type
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: IDX_TERM_7_PEER_PRFL

Fields: SM_PROFILE

Index Name: IDX_TERM_7_PEER_PRFL_CLUSTER

Fields: DTDATE
 SM_PROFILE

Column Descriptions

The following are the descriptions of the Term_7_Days_Peer_Profile table columns.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CASHINS — Description not available.

AVG_FSUM_CASHOUTS — Description not available.

AVG_FSUM_CCPAYMENT — Description not available.

AVG_FSUM_CHECKS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_NONCASHCREDIT — Description not available.

AVG_FSUM_NONCASHDEBIT — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WIREDOMESTICFROM — Description not available.

AVG_FSUM_WIREDOMESTICTO — Description not available.

AVG_FSUM_WIREFOREIGNFROM — Description not available.

AVG_FSUM_WIREFOREIGNTO — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_NCNTWIREFOREIGNTO — Description not available.

AVG_NCNT_CHECKS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_NONCASHCREDIT — Description not available.

AVG_NCNT_NONCASHDEBIT — Description not available.

AVG_NCNT_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WIREDOMESTICFROM — Description not available.

AVG_NCNT_WIREDOMESTICTO — Description not available.

AVG_NCNT_WIREFOREIGNFROM — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

Term_7_Days_Profile Table

Description not available.

The columns in the Term_7_Days_Profile table (TERM_7_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CASHINS	money
AVG_FSUM_CASHOUTS	money
AVG_FSUM_CCPAYMENT	money
AVG_FSUM_CHECKS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_NONCASHCREDIT	money

Column Name	Data Type
AVG_FSUM_NONCASHDEBIT	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WIREDOMESTICFROM	money
AVG_FSUM_WIREDOMESTICTO	money
AVG_FSUM_WIREFOREIGNFROM	money
AVG_FSUM_WIREFOREIGNTO	money
AVG_FSUM_WITHDRAWS	money
AVG_NCNTWIREFOREIGNTO	float
AVG_NCNT_CHECKS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_NONCASHCREDIT	float
AVG_NCNT_NONCASHDEBIT	float
AVG_NCNT_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WIREDOMESTICFROM	float

Column Name	Data Type
AVG_NCNT_WIREDOMESTICTO	float
AVG_NCNT_WIREFOREIGNFROM	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime
SM_PROFILE	varchar(9)
SM_TERM_ID	varchar(50)

Index Name: IDX_TERM_7_PRFL_CLUSTER

Fields: DTDATE

 SM_TERM_ID

Index Name: IDX_TERM_7_PRFL_SM_TERM

Fields: SM_TERM_ID

Column Descriptions

The following are the descriptions of the Term_7_Days_Profile table columns.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CASHINS — Description not available.

AVG_FSUM_CASHOUTS — Description not available.

AVG_FSUM_CCPAYMENT — Description not available.

AVG_FSUM_CHECKS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_NONCASHCREDIT — Description not available.

AVG_FSUM_NONCASHDEBIT — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WIREDOMESTICFROM — Description not available.

AVG_FSUM_WIREDOMESTICTO — Description not available.

AVG_FSUM_WIREFOREIGNFROM — Description not available.

AVG_FSUM_WIREFOREIGNTO — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_NCNTWIREFOREIGNTO — Description not available.

AVG_NCNT_CHECKS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_NONCASHCREDIT — Description not available.

AVG_NCNT_NONCASHDEBIT — Description not available.

AVG_NCNT_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WIREDOMESTICFROM — Description not available.

AVG_NCNT_WIREDOMESTICTO — Description not available.

AVG_NCNT_WIREFOREIGNFROM — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

SM_TERM_ID — Description not available.

Term_Daily_Peer_Profile Table

Description not available.

The columns in the Term_Daily_Peer_Profile table (TERM_DAILY_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CASHINS	money
AVG_FSUM_CASHOUTS	money
AVG_FSUM_CCPAYMENT	money
AVG_FSUM_CHECKS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_NONCASHCREDIT	money
AVG_FSUM_NONCASHDEBIT	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WIREDOMESTICFROM	money
AVG_FSUM_WIREDOMESTICTO	money
AVG_FSUM_WIREFOREIGNFROM	money
AVG_FSUM_WIREFOREIGNTO	money
AVG_FSUM_WITHDRAWS	money
AVG_NCNTWIREFOREIGNTO	float
AVG_NCNT_CHECKS	float

Column Name	Data Type
AVG_NCNT_DEPOSITS	float
AVG_NCNT_NONCASHCREDIT	float
AVG_NCNT_NONCASHDEBIT	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WIREDOMESTICFROM	float
AVG_NCNT_WIREDOMESTICTO	float
AVG_NCNT_WIREFOREIGNFROM	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime
NCNT_TERMS	int
SM_PROFILE	varchar(9)

Index Name: IDX_TERM_1_PEER_PRFL

Fields: SM_PROFILE

Index Name: IDX_TERM_1_PEER_PRFL_CLUSTER

Fields: DTDATE

SM_PROFILE

Column Descriptions

The following are the descriptions of the Term_Daily_Peer_Profile table columns.

AVG_FSUM_ATMDEPOSITS — The average sum of ATM deposits.

AVG_FSUM_CASHINS — The average sum of the cash ins.

AVG_FSUM_CASHOUTS — The average sum of the cash outs.

AVG_FSUM_CCPAYMENT — The average sum of the credit card payments.

AVG_FSUM_CHECKS — The average sum of the checks.

AVG_FSUM_DEPOSITS — The average maximum deposit amount.

AVG_FSUM_NONCASHCREDIT — The average sum of the non-cash credit.

AVG_FSUM_NONCASHDEBIT — The average sum of the non-cash debits.

AVG_FSUM_TXNSCREDIT — Average sum of the credit transactions.

AVG_FSUM_TXNSDEBIT — The average sum of the debit transactions.

AVG_FSUM_WIREDOMESTICFROM — The average number of wire transfers from domestic accounts.

AVG_FSUM_WIREDOMESTICTO — The average number of wire transfers to domestic accounts.

AVG_FSUM_WIREFOREIGNFROM — The average number of wire transfers from foreign accounts.

AVG_FSUM_WIREFOREIGNTO — The average number of wire transfers to foreign accounts

AVG_FSUM_WITHDRAWS — The average sum of withdrawals.

AVG_NCNTWIREFOREIGNTO — The average number of withdrawals.

AVG_NCNT_CHECKS — The average number of checks.

AVG_NCNT_DEPOSITS — The average number of deposits.

AVG_NCNT_NONCASHCREDIT — The average number of non-cash credits.

AVG_NCNT_NONCASHDEBIT — The average number of non-cash debits.

AVG_NCNT_TXNSCREDIT — The average number of credit transactions.

AVG_NCNT_TXNSDEBIT — The average number of debit transactions.

AVG_NCNT_WIREDOMESTICFROM — The average number of wire transfer transactions to domestic accounts.

AVG_NCNT_WIREDOMESTICTO — The average number of wire transfer transactions from foreign accounts

AVG_NCNT_WIREFOREIGNFROM — The average number of withdrawals.

AVG_NCNT_WITHDRAWS — The average number of withdraws.

AVG_NCNT_XFERFROM — The average number of transfers from an account.

AVG_NCNT_XFERTO — The average number of transfers to an account.

DTDATE — Contains the transaction date and time.

NCNT_TERMS — The number of terminals.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

Term_Daily_Profile Table

The Term_Daily_Profile Table is used by the Analysis and Review system. It contains the daily totals of transaction types for an account. This table is only used by the ACI Proactive Risk Manager Terminal action level.

The columns in the Term_Daily_Profile table (TERM_DAILY_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FSUM_ATMDEPOSITS	money
FSUM_CASHINS	money
FSUM_CASHOUTS	money
FSUM_CCPAYMENT	money
FSUM_CHECKS	money
FSUM_DEPOSITS	money
FSUM_NONCASHCREDIT	money
FSUM_NONCASHDEBIT	money

Column Name	Data Type
FSUM_TXNSCREDIT	money
FSUM_TXNSDEBIT	money
FSUM_WIREDOMESTICFROM	money
FSUM_WIREDOMESTICTO	money
FSUM_WIREFOREIGNFROM	money
FSUM_WIREFOREIGNTO	money
FSUM_WITHDRAWS	money
LSTATUS	integer
NCNTWIREFOREIGNTO	int
NCNT_CHECKS	int
NCNT_DEPOSITS	int
NCNT_NONCASHCREDIT	int
NCNT_NONCASHDEBIT	int
NCNT_TXNS	int
NCNT_TXNSCREDIT	int
NCNT_TXNSDEBIT	int
NCNT_WIREDOMESTICFROM	int

Column Name	Data Type
NCNT_WIREDOMESTICTO	int
NCNT_WIREFOREIGNFROM	int
NCNT_WITHDRAWS	int
NCNT_XFERFROM	int
NCNT_XFERTO	int
PRCSID	varchar(50)
SM_PROFILE	varchar(9)
SM_TERM_ID	varchar(50)

Index Name: IDX_TERM_DAILY_PRFL_CLUSTER

Fields: DTDATE

 SM_TERM_ID

Index Name: IDX_TERM_DAILY_PRFL_SM_TERM

Fields: SM_TERM_ID

Column Descriptions

The following are the descriptions of the Term_Daily_Profile table columns.

DTDATE — Contains the transaction date and time.

FSUM_ATMDEPOSITS — The sum of ATM deposits.

FSUM_CASHINS — The sum of the cash ins.

FSUM_CASHOUTS — The sum of the cash outs.

FSUM_CCPAYMENT — The sum of the credit card payments.

FSUM_CHECKS — The sum of the checks.

FSUM_DEPOSITS — The sum of deposits.

FSUM_NONCASHCREDIT — The sum of the non-cash credit.

FSUM_NONCASHDEBIT — The sum of the non-cash debit.

FSUM_TXNSCREDIT — The sum of the credit transactions.

FSUM_TXNSDEBIT — The sum of the debit transactions.

FSUM_WIREDOMESTICFROM — The number of wire transfers from domestic accounts.

FSUM_WIREDOMESTICTO — The number of wire transfers to domestic accounts.

FSUM_WIREFOREIGNFROM — The number of wire transfers from foreign accounts.

FSUM_WIREFOREIGNTO — The number of wire transfers to foreign accounts.

FSUM_WITHDRAWS — The sum of withdrawals.

LSTATUS — Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

0 - unassigned

1 - assigned

3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

NCNTWIREFOREIGNTO — The number of withdrawals.

NCNT_CHECKS — The number of checks.

NCNT_DEPOSITS — The number of deposits.

NCNT_NONCASHCREDIT — The number of non-cash credits.

NCNT_NONCASHDEBIT — The number of non-cash debits.

NCNT_TXNS — The number of transactions.

NCNT_TXNSCREDIT — The number of credit transactions.

NCNT_TXNSDEBIT — The number of debit transactions.

NCNT_WIREDOMESTICFROM — The number of wire transfer transactions to domestic accounts.

NCNT_WIREDOMESTICTO — The number of wire transfer transactions from foreign accounts.

NCNT_WIREFOREIGNFROM — The number of withdrawals.

NCNT_WITHDRAWS — The number of withdraws.

NCNT_XFERFROM — The number of transfers from an account.

NCNT_XFERTO — The number of transfers to an account.

PRCSID — Web server process that the row is assigned to for roll-up rules processing.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

SM_TERM_ID — Identifies the terminal where the transaction originated.

UAID action level

The following tables are specific to the UAID action level:

- UAID_31_Days_Profile
- UAID_3_Days_Profile
- UAID_Daily_Profile

UAID_31_Days_Profile Table

The UAID_31_Days_Profile table keeps the thirty-one day average data for a User Account ID action level.

The columns in the UAID_31_Days_Profile table (UAID_31_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM_TXNS	money
AVG_NCNT_TXNS	money
DTDATE	datetime

Column Name	Data Type
SM_PROFILE	varchar(9)
SM_USER_ACCT_ID	varchar(50)

Index Name: **IDX_UAID_31_DAYS_PRFL_CLUSTER**

Fields: SM_USER_ACCT_ID
 DTDATE

Column Descriptions

The following are the descriptions of the UAID_31_Days_Profile table columns.

AVG_FSUM_TXNS — The sum of the transaction amounts for the past 31 days for the user account ID.

AVG_NCNT_TXNS — The average number of transactions for the past 31 days for the user account ID.

DTDATE — The date the profile data was calculated.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

SM_USER_ACCT_ID — The user's account ID for the online banking application.

UAID_3_Days_Profile Table

The UAID_3_Days_Profile table keeps the three day average data for a User Account ID action level.

The columns in the UAID_3_Days_Profile table (UAID_3_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM_TXNS	money
AVG_NCNT_TXNS	money
DTDATE	datetime
SM_PROFILE	varchar(9)
SM_USER_ACCT_ID	varchar(50)

Index Name: **IDX_UAID_3_DAYS_PRFL_CLUSTER**

Fields: SM_USER_ACCT_ID
 DTDAT

Column Descriptions

The following are the descriptions of the UAID_3_Days_Profile table columns.

AVG_FSUM_TXNS — The sum of the transaction amounts for the past three days for the user account ID.

AVG_NCNT_TXNS — The average number of transactions for the past three days for the user account ID.

DTDATE — The date the profile data was calculated.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

SM_USER_ACCT_ID — The user's account ID for the online banking application.

UAID_Daily_Profile Table

The UAID_Daily_Profile Table is used by the Analysis and Review system. It contains the daily totals of transaction types for an account. This table is only used by the ACI Proactive Risk Manager UAID action level.

The columns in the UAID_Daily_Profile table (UAID_DAILY_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FSUM_TXNS	money
LSTATUS	integer
NCNT_TXNS	money
PRCSID	varchar(50)
SM_PROFILE	varchar(9)
SM_USER_ACCT_ID	varchar(50)

Index Name: **IDX_UAID_DAILY_PRFL_CLUSTER**

Fields: SM_USER_ACCT_ID

DTDATE

Column Descriptions

The following are the descriptions of the UAID_Daily_Profile table columns.

DTDATE — The date the profile data was calculated.

FSUM_TXNS — The sum of the transaction amounts per day for the user account ID.

LSTATUS — Status of a daily profile table row in the process of a standard profiles job – the rules

processing phase.

Possible values

0 - unassigned

1 - assigned

3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

NCNT_TXNS — The number of transactions per day for the user account ID.

PRCSID — Web server process that the row is assigned to for roll-up rules processing.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

SM_USER_ACCT_ID — The user's account ID for the online banking application.

UAN action level

The following tables are specific to the UAN action level:

- LinkDetail
- UAN_31_Days_Peer_Profile
- UAN_31_Days_Profile
- UAN_3_Days_Peer_Profile
- UAN_3_Days_Profile
- UAN_Daily_Peer_Profile
- UAN_Daily_Profile

LinkDetail Table

The LinkDetail table is used by the ACI Proactive Risk Manager UAN action level to contain data for the Link Analysis report. The table is populated when the pp_Rollup stored procedure is run.

The columns in the LinkDetail table (LINKDETAIL) are listed below with the data type.

Column Name	Data Type
ACTION_LEVEL_KEY	varchar(50)
DD_DATE	datetime
DD_PARTITION_DATE	date
MD_TRAN_AMT1	money
ND_KEY_HASH	smallint
RECORD_SOURCE_ID	smallint
SD_SEC_ACCT_NUM	varchar(50)
SD_TIEBREAKER	varchar(75)
SD_TRAN_CDE_CAT	char(4)

Index Name: **IDX_LINK_DETAIL_CLUSTER**

Fields: DD_DATE

Index Name: **IDX_LINK_DETAIL_SEC**

Fields: SD_SEC_ACCT_NUM

Index Name: **IDX_LINK_DETAIL_UNIQUE**

Fields: DD_PARTITION_DATE

 ND_KEY_HASH

 RECORD_SOURCE_ID

 SD_TIEBREAKER

Column Descriptions

The following are the descriptions of the LinkDetail table columns.

ACTION_LEVEL_KEY — The key value from one of the DETAIL. It may contain a SD_PAN, SD_UAN, SD_EMPLOYEE_ID, SD_RETL_ID or SD_TERM_ID. The value in the ACTION_LEVEL_ID column identifies a row in the ACTION_LEVEL table and will be used to determine what type of value is stored in ACTION_LEVEL_KEY.

DD_DATE — The transaction date and time.

DD_PARTITION_DATE — The value that is associated with the transaction in the Detail and FraudDetail tables.

MD_TRAN_AMT1 — Amount of money to be moved between the debtor and creditor, before deduction of charges, expressed in the currency as ordered by the initiating party.

ND_KEY_HASH — The value that is associated with the transaction in the Detail and FraudDetail tables.

RECORD_SOURCE_ID — The value that is associated with the transaction in the Detail and FraudDetail tables.

SD_SEC_ACCT_NUM — The affected universal account number for transactions involving two accounts. This column represents the *to* account in a transaction.

SD_TIEBREAKER — A transaction field that makes a transaction unique when more than one transaction has the same date and time.

SD_TRAN_CDE_CAT — A transaction code category that is supplied by the customer.

UAN_31_Days_Peer_Profile Table

Description not available.

The columns in the UAN_31_Days_Peer_Profile table (UAN_31_DAYS_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FMAX_DEPOSIT	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CASHINS	money
AVG_FSUM_CASHOUTS	money
AVG_FSUM_CCPAYMENT	money
AVG_FSUM_CHECKS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_NONCASHCREDIT	money
AVG_FSUM_NONCASHDEBIT	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WIREDOMESTICFROM	money
AVG_FSUM_WIREDOMESTICTO	money
AVG_FSUM_WIREFOREIGNFROM	money

Column Name	Data Type
AVG_FSUM_WIREFOREIGNTO	money
AVG_FSUM_WITHDRAWS	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CHECKS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_NONCASHCREDIT	float
AVG_NCNT_NONCASHDEBIT	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_UANS	float
AVG_NCNT_WIREDOMESTICFROM	float
AVG_NCNT_WIREDOMESTICTO	float
AVG_NCNT_WIREFOREIGNFROM	float
AVG_NCNT_WIREFOREIGNTO	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float

Column Name	Data Type
AVG_NCNT_XFERTO	float
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: IDX_UAN_31_PEER_PRFL_CLUSTER

Fields: DTDATE

 SM_PROFILE

Index Name: IDX_UAN_UAN_31_PEER_PRFL

Fields: SM_PROFILE

Column Descriptions

The following are the descriptions of the UAN_31_Days_Peer_Profile table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FMAX_DEPOSIT — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CASHINS — Description not available.

AVG_FSUM_CASHOUTS — Description not available.

AVG_FSUM_CCPAYMENT — Description not available.

AVG_FSUM_CHECKS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_NONCASHCREDIT — Description not available.

AVG_FSUM_NONCASHDEBIT — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WIREDOMESTICFROM — Description not available.

AVG_FSUM_WIREDOMESTICTO — Description not available.

AVG_FSUM_WIREFOREIGNFROM — Description not available.

AVG_FSUM_WIREFOREIGNTO — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CHECKS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_NONCASHCREDIT — Description not available.

AVG_NCNT_NONCASHDEBIT — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_UANS — Description not available.

AVG_NCNT_WIREDOMESTICFROM — Description not available.

AVG_NCNT_WIREDOMESTICTO — Description not available.

AVG_NCNT_WIREFOREIGNFROM — Description not available.

AVG_NCNT_WIREFOREIGNTO — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

UAN_31_Days_Profile Table

Description not available.

The columns in the UAN_31_Days_Profile table (UAN_31_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FMAX_DEPOSIT	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CASHINS	money
AVG_FSUM_CASHOUTS	money
AVG_FSUM_CCPAYMENT	money
AVG_FSUM_CHECKS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_NONCASHCREDIT	money
AVG_FSUM_NONCASHDEBIT	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WIREDOMESTICFROM	money
AVG_FSUM_WIREDOMESTICTO	money
AVG_FSUM_WIREFOREIGNFROM	money
AVG_FSUM_WIREFOREIGNTO	money

Column Name	Data Type
AVG_FSUM_WITHDRAWS	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CHECKS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_NONCASHCREDIT	float
AVG_NCNT_NONCASHDEBIT	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WIREDOMESTICFROM	float
AVG_NCNT_WIREDOMESTICTO	float
AVG_NCNT_WIREFOREIGNFROM	float
AVG_NCNT_WIREFOREIGNTO	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float

Column Name	Data Type
DTDATE	datetime
SM_PROFILE	varchar(9)
SM_UAN	varchar(50)

Index Name: IDX_UAN_31_DAY_PRFL_CLUSTER

Fields: DTDATE

 SM_UAN

Index Name: IDX_UAN_31_DAY_PRFL_SM_UAN

Fields: SM_UAN

Column Descriptions

The following are the descriptions of the UAN_31_Days_Profile table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FMAX_DEPOSIT — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CASHINS — Description not available.

AVG_FSUM_CASHOUTS — Description not available.

AVG_FSUM_CCPAYMENT — Description not available.

AVG_FSUM_CHECKS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_NONCASHCREDIT — Description not available.

AVG_FSUM_NONCASHDEBIT — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WIREDOMESTICFROM — Description not available.

AVG_FSUM_WIREDOMESTICTO — Description not available.

AVG_FSUM_WIREFOREIGNFROM — Description not available.

AVG_FSUM_WIREFOREIGNTO — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CHECKS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_NONCASHCREDIT — Description not available.

AVG_NCNT_NONCASHDEBIT — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WIREDOMESTICFROM — Description not available.

AVG_NCNT_WIREDOMESTICTO — Description not available.

AVG_NCNT_WIREFOREIGNFROM — Description not available.

AVG_NCNT_WIREFOREIGNTO — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

SM_UAN — Description not available.

UAN_3_Days_Peer_Profile Table

Description not available.

The columns in the UAN_3_Days_Peer_Profile table (UAN_3_DAYS_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money
AVG_FAMT_POS_TXNS	money
AVG_FMAX_DEPOSIT	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CASHINS	money
AVG_FSUM_CASHOUTS	money
AVG_FSUM_CCPAYMENT	money
AVG_FSUM_CHECKS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_NONCASHCREDIT	money
AVG_FSUM_NONCASHDEBIT	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WIREDOMESTICFROM	money
AVG_FSUM_WIREDOMESTICTO	money
AVG_FSUM_WIREFOREIGNFROM	money
AVG_FSUM_WIREFOREIGNTO	money

Column Name	Data Type
AVG_FSUM_WITHDRAWS	money
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CHECKS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_NONCASHCREDIT	float
AVG_NCNT_NONCASHDEBIT	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_UANS	float
AVG_NCNT_WIREDOMESTICFROM	float
AVG_NCNT_WIREDOMESTICTO	float
AVG_NCNT_WIREFOREIGNFROM	float
AVG_NCNT_WIREFOREIGNTO	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float

Column Name	Data Type
DTDATE	datetime
SM_PROFILE	varchar(9)

Index Name: IDX_UAN_3DAY_PEER_PRFL

Fields: SM_PROFILE

Index Name: IDX_UAN_3DAY_PEER_PRFL_CLUSTER

Fields: DTDATE
 SM_PROFILE

Column Descriptions

The following are the descriptions of the UAN_3_Days_Peer_Profile table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FMAX_DEPOSIT — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CASHINS — Description not available.

AVG_FSUM_CASHOUTS — Description not available.

AVG_FSUM_CCPAYMENT — Description not available.

AVG_FSUM_CHECKS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_NONCASHCREDIT — Description not available.

AVG_FSUM_NONCASHDEBIT — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WIREDOMESTICFROM — Description not available.

AVG_FSUM_WIREDOMESTICTO — Description not available.

AVG_FSUM_WIREFOREIGNFROM — Description not available.

AVG_FSUM_WIREFOREIGNTO — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CHECKS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_NONCASHCREDIT — Description not available.

AVG_NCNT_NONCASHDEBIT — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_UANS — Description not available.

AVG_NCNT_WIREDOMESTICFROM — Description not available.

AVG_NCNT_WIREDOMESTICTO — Description not available.

AVG_NCNT_WIREFOREIGNFROM — Description not available.

AVG_NCNT_WIREFOREIGNTO — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

UAN_3_Days_Profile Table

Description not available.

The columns in the UAN_3_Days_Profile table (UAN_3_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FAMT_ATM_TXNS	money

Column Name	Data Type
AVG_FAMT_POS_TXNS	money
AVG_FMAX_DEPOSIT	money
AVG_FSUM_ATMDEPOSITS	money
AVG_FSUM_CASHINS	money
AVG_FSUM_CASHOUTS	money
AVG_FSUM_CCPAYMENT	money
AVG_FSUM_CHECKS	money
AVG_FSUM_DEPOSITS	money
AVG_FSUM_NONCASHCREDIT	money
AVG_FSUM_NONCASHDEBIT	money
AVG_FSUM_TXNSCREDIT	money
AVG_FSUM_TXNSDEBIT	money
AVG_FSUM_WIREDOMESTICFROM	money
AVG_FSUM_WIREDOMESTICTO	money
AVG_FSUM_WIREFOREIGNFROM	money
AVG_FSUM_WIREFOREIGNTO	money
AVG_FSUM_WITHDRAWS	money

Column Name	Data Type
AVG_NCNT_ATM_TXNS	float
AVG_NCNT_CHECKS	float
AVG_NCNT_DEPOSITS	float
AVG_NCNT_NONCASHCREDIT	float
AVG_NCNT_NONCASHDEBIT	float
AVG_NCNT_POS_TXNS	float
AVG_NCNT_TXNS	float
AVG_NCNT_TXNSCREDIT	float
AVG_NCNT_TXNSDEBIT	float
AVG_NCNT_WIREDOMESTICFROM	float
AVG_NCNT_WIREDOMESTICTO	float
AVG_NCNT_WIREFOREIGNFROM	float
AVG_NCNT_WIREFOREIGNTO	float
AVG_NCNT_WITHDRAWS	float
AVG_NCNT_XFERFROM	float
AVG_NCNT_XFERTO	float
DTDATE	datetime

Column Name	Data Type
SM_PROFILE	varchar(9)
SM_UAN	varchar(50)

Index Name: IDX_UAN_3_DAY_PRFL_CLUSTER

Fields: DTDATE

 SM_UAN

Index Name: IDX_UAN_3_DAY_PRFL_SM_UAN

Fields: SM_UAN

Column Descriptions

The following are the descriptions of the UAN_3_Days_Profile table columns.

AVG_FAMT_ATM_TXNS — Description not available.

AVG_FAMT_POS_TXNS — Description not available.

AVG_FMAX_DEPOSIT — Description not available.

AVG_FSUM_ATMDEPOSITS — Description not available.

AVG_FSUM_CASHINS — Description not available.

AVG_FSUM_CASHOUTS — Description not available.

AVG_FSUM_CCPAYMENT — Description not available.

AVG_FSUM_CHECKS — Description not available.

AVG_FSUM_DEPOSITS — Description not available.

AVG_FSUM_NONCASHCREDIT — Description not available.

AVG_FSUM_NONCASHDEBIT — Description not available.

AVG_FSUM_TXNSCREDIT — Description not available.

AVG_FSUM_TXNSDEBIT — Description not available.

AVG_FSUM_WIREDOMESTICFROM — Description not available.

AVG_FSUM_WIREDOMESTICTO — Description not available.

AVG_FSUM_WIREFOREIGNFROM — Description not available.

AVG_FSUM_WIREFOREIGNTO — Description not available.

AVG_FSUM_WITHDRAWS — Description not available.

AVG_NCNT_ATM_TXNS — Description not available.

AVG_NCNT_CHECKS — Description not available.

AVG_NCNT_DEPOSITS — Description not available.

AVG_NCNT_NONCASHCREDIT — Description not available.

AVG_NCNT_NONCASHDEBIT — Description not available.

AVG_NCNT_POS_TXNS — Description not available.

AVG_NCNT_TXNS — Description not available.

AVG_NCNT_TXNSCREDIT — Description not available.

AVG_NCNT_TXNSDEBIT — Description not available.

AVG_NCNT_WIREDOMESTICFROM — Description not available.

AVG_NCNT_WIREDOMESTICTO — Description not available.

AVG_NCNT_WIREFOREIGNFROM — Description not available.

AVG_NCNT_WIREFOREIGNTO — Description not available.

AVG_NCNT_WITHDRAWS — Description not available.

AVG_NCNT_XFERFROM — Description not available.

AVG_NCNT_XFERTO — Description not available.

DTDATE — Description not available.

SM_PROFILE — Description not available.

SM_UAN — Description not available.

UAN_Daily_Peer_Profile Table

The following are descriptions of the UAN_Daily_Peer_Profile Table columns.

The columns in the UAN_Daily_Peer_Profile table (UAN_DAILY_PEER_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FAVGAMT_ATM_TXNS	money
FAVGAMT_POS_TXNS	money
FAVGCNT_ATM_TXNS	float
FAVGCNT_CHECKS	float
FAVGCNT_DEPOSITS	float
FAVGCNT_NONCASHCREDIT	float
FAVGCNT_NONCASHDEBIT	float
FAVGCNT_POS_TXNS	float
FAVGCNT_TXNSCREDIT	float
FAVGCNT_TXNSDEBIT	float
FAVGCNT_WIREDOMESTICFROM	float
FAVGCNT_WIREDOMESTICTO	float
FAVGCNT_WIREFOREIGNFROM	float
FAVGCNT_WIREFOREIGNTO	float
FAVGCNT_WITHDRAWS	float
FAVGCNT_XFERFROM	float

Column Name	Data Type
FAVGCNT_XFERTO	float
FAVGSUM_ATMDEPOSITS	money
FAVGSUM_CASHINS	money
FAVGSUM_CASHOUTS	money
FAVGSUM_CCPAYMENT	money
FAVGSUM_CHECKS	money
FAVGSUM_DEPOSITS	money
FAVGSUM_NONCASHCREDIT	money
FAVGSUM_NONCASHDEBIT	money
FAVGSUM_TXNSCREDIT	money
FAVGSUM_TXNSDEBIT	money
FAVGSUM_WIREDOMESTICFROM	money
FAVGSUM_WIREDOMESTICTO	money
FAVGSUM_WIREFOREIGNFROM	money
FAVGSUM_WIREFOREIGNTO	money
FAVGSUM_WITHDRAWS	money
FMAX_DEPOSIT	money

Column Name	Data Type
LSTATUS	integer
NCNT_UANS	int
PRCSID	varchar(50)
SM_PROFILE	varchar(9)

Index Name: IDX_UAN_1_PEER_PRFL

Fields: SM_PROFILE

Index Name: IDX_UAN_1_PEER_PRFL_CLUSTER

Fields: DTDATE

 SM_PROFILE

Column Descriptions

The following are the descriptions of the UAN_Daily_Peer_Profile table columns.

DTDATE — The profiles date.

FAVGAMT_ATM_TXNS — The average amount of ATM transactions.

FAVGAMT_POS_TXNS — The average amount of POS transactions.

FAVGCNT_ATM_TXNS — The average number of ATM transactions.

FAVGCNT_CHECKS — The average number of checks.

FAVGCNT_DEPOSITS — The average number of deposits.

FAVGCNT_NONCASHCREDIT — The average number of non-cash credits.

FAVGCNT_NONCASHDEBIT — The average number of noncash debits.

FAVGCNT_POS_TXNS — The average count of POS transactions.

FAVGCNT_TXNSCREDIT — The average number of credit transactions.

FAVGCNT_TXNSDEBIT — The average number of debit transactions.

FAVGCNT_WIREDOMESTICFROM — The average number of wire transfer transactions from domestic accounts.

FAVGCNT_WIREDOMESTICTO — The average number of wire transfer transactions to domestic accounts.

FAVGCNT_WIREFOREIGNFROM — The average number of wire transfer transactions from foreign accounts.

FAVGCNT_WIREFOREIGNTO — The average number of wire transfer transactions to foreign accounts.

FAVGCNT_WITHDRAWS — The average number of withdraws.

FAVGCNT_XFERFROM — The average number of transfers from an account.

FAVGCNT_XFERTO — The average number of transfers to an account.

FAVGSUM_ATMDEPOSITS — The average sum of the ATM deposits.

FAVGSUM_CASHINS — The average sum of the cash ins.

FAVGSUM_CASHOUTS — The average sum of the cash outs.

FAVGSUM_CCPAYMENT — The average sum of the credit card payments.

FAVGSUM_CHECKS — The average sum of the checks.

FAVGSUM_DEPOSITS — The average sum of deposits.

FAVGSUM_NONCASHCREDIT — The average sum of the non-cash credit.

FAVGSUM_NONCASHDEBIT — The average sum of the non-cash debits.

FAVGSUM_TXNSCREDIT — The average sum of the credit transactions.

FAVGSUM_TXNSDEBIT — The average sum of the debit transactions.

FAVGSUM_WIREDOMESTICFROM — The average number of wire transfers from domestic accounts.

FAVGSUM_WIREDOMESTICTO — The average number of wire transfers to domestic accounts.

FAVGSUM_WIREFOREIGNFROM — The average number of wire transfers from foreign accounts.

FAVGSUM_WIREFOREIGNTO — The average number of wire transfers to domestic accounts.

FAVGSUM_WITHDRAWS — The average sum of withdrawals.

FMAX_DEPOSIT — The maximum deposit amount.

LSTATUS — Status of a daily profile table row in the process of a standard profiles job – the rules processing phase.

Possible values

0 - unassigned

- 1 - assigned
- 3 - completed

For each of the daily profiles tables, there are two columns (LSTATUS and PRCSID) that help managing the progress of a standard profiles job. The job takes batches of rows and assigns them to the current PRM Server process and change their status.

NCNT_UANS — The number of UANs.

PRCSID — Web server process that the row is assigned to for roll-up rules processing.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

UAN_Daily_Profile Table

The UAN_Daily_Profile Table is used by the Analysis and Review system. It contains the daily totals of transaction types for an account. This table is only used by the ACI Proactive Risk Manager UAN action level.

The columns in the UAN_Daily_Profile table (UAN_DAILY_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FAMT_ATM_TXNS	money
FAMT_POS_TXNS	money
FMAX_DEPOSIT	money
FSUM_ATMDEPOSITS	money

Column Name	Data Type
FSUM_CASHINS	money
FSUM_CASHOUTS	money
FSUM_CCPAYMENT	money
FSUM_CHECKS	money
FSUM_DEPOSITS	money
FSUM_NONCASHCREDIT	money
FSUM_NONCASHDEBIT	money
FSUM_TXNSCREDIT	money
FSUM_TXNSDEBIT	money
FSUM_WIREDOMESTICFROM	money
FSUM_WIREDOMESTICTO	money
FSUM_WIREFOREIGNFROM	money
FSUM_WIREFOREIGNTO	money
FSUM_WITHDRAWS	money
NCNT_ATM_TXNS	int
NCNT_CHECKS	int
NCNT_DEPOSITS	int

Column Name	Data Type
NCNT_NONCASHCREDIT	int
NCNT_NONCASHDEBIT	int
NCNT_POS_TXNS	int
NCNT_TXNS	int
NCNT_TXNSCREDIT	int
NCNT_TXNSDEBIT	int
NCNT_WIREDOMESTICFROM	int
NCNT_WIREDOMESTICTO	int
NCNT_WIREFOREIGNFROM	int
NCNT_WIREFOREIGNTO	int
NCNT_WITHDRAWS	int
NCNT_XFERFROM	int
NCNT_XFERTO	int
SM_PROFILE	varchar(9)
SM_UAN	varchar(50)

Index Name: **IDX_UAN_DAILY_PRFL_CLUSTER**

Fields: DTDATE

 SM_UAN

Index Name: **IDX_UAN_DAILY_PRFL_SM_UAN**

Fields: SM_UAN

Column Descriptions

The following are the descriptions of the UAN_Daily_Profile table columns.

DTDATE — The transaction date.

FAMT_ATM_TXNS — The amount of ATM transactions.

FAMT_POS_TXNS — The amount of POS transactions.

FMAX_DEPOSIT — The maximum deposit amount.

FSUM_ATMDEPOSITS — The sum of the ATM deposits.

FSUM_CASHINS — The sum of the cash ins.

FSUM_CASHOUTS — The sum of the cash outs.

FSUM_CCPAYMENT — The sum of the credit card payments.

FSUM_CHECKS — The sum of the checks.

FSUM_DEPOSITS — The sum of deposits.

FSUM_NONCASHCREDIT — The sum of the non-cash credit.

FSUM_NONCASHDEBIT — The sum of the non-cash debits.

FSUM_TXNSCREDIT — The sum of the credit transactions.

FSUM_TXNSDEBIT — The sum of the debit transactions.

FSUM_WIREDOMESTICFROM — The number of wire transfers from domestic accounts.

FSUM_WIREDOMESTICTO — The number of wire transfers to domestic accounts.

FSUM_WIREFOREIGNFROM — The number of wire transfers from foreign accounts.

FSUM_WIREFOREIGNTO — The number of wire transfers to domestic accounts.

FSUM_WITHDRAWS — The sum of withdrawals.

NCNT_ATM_TXNS — The number of ATM transactions.

NCNT_CHECKS — The number of checks.

NCNT_DEPOSITS — The number of deposits.

NCNT_NONCASHCREDIT — The number of non-cash credits.

NCNT_NONCASHDEBIT — The number of non-cash debits.

NCNT_POS_TXNS — The count of POS transactions.

NCNT_TXNS — The number of transactions.

NCNT_TXNSCREDIT — The number of credit transactions.

NCNT_TXNSDEBIT — The number of debit transactions.

NCNT_WIREDOMESTICFROM — The number of wire transfer transactions from domestic accounts.

NCNT_WIREDOMESTICTO — The number of wire transfer transactions to domestic accounts.

NCNT_WIREFOREIGNFROM — The number of wire transfer transactions from foreign accounts.

NCNT_WIREFOREIGNTO — The number of wire transfer transactions to foreign accounts.

NCNT_WITHDRAWS — The number of withdrawals.

NCNT_XFERFROM — The number of transfers from an account.

NCNT_XFERTO — The number of transfers to an account.

SM_PROFILE — Indicates a profile group. It can be a combination of fields from the product-specific transaction input file plus an optional lookup value from an institution-defined function and table.

SM_UAN — The account number.

Device ID view

The following tables are specific to the Device ID view:

- Device_3_Days_Profile
- Device_7_Days_Profile
- Device_Daily_Profile

Device_3_Days_Profile Table

Description not available.

The columns in the Device_3_Days_Profile table (DEVICE_3_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM_FRAUD_TXNS	money
AVG_NCNT_FRAUD_TXNS	float
DTDATE	datetime
FSUM_FRAUD_TXNS	money
NCNT_FRAUD_TXNS	int
SD_DEVICE_ID	varchar(50)

Index Name: **PK_DEVICE_3_DAYS_PROFILE**

Fields: DTDAT

 SD_DEVICE_ID

Column Descriptions

The following are the descriptions of the Device_3_Days_Profile table columns.

AVG_FSUM_FRAUD_TXNS — Description not available.

AVG_NCNT_FRAUD_TXNS — Description not available.

DTDATE — Description not available.

FSUM_FRAUD_TXNS — Description not available.

NCNT_FRAUD_TXNS — Description not available.

SD_DEVICE_ID — A unique identifier for the device.

Device_7_Days_Profile Table

Description not available.

The columns in the Device_7_Days_Profile table (DEVICE_7_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM_FRAUD_TXNS	money
AVG_NCNT_FRAUD_TXNS	float
DTDATE	datetime
FSUM_FRAUD_TXNS	money
NCNT_FRAUD_TXNS	int
SD_DEVICE_ID	varchar(50)

Index Name: **PK_DEVICE_7_DAYS_PROFILE**

Fields: DTDAT

SD_DEVICE_ID

Column Descriptions

The following are the descriptions of the Device_7_Days_Profile table columns.

AVG_FSUM_FRAUD_TXNS — Description not available.

AVG_NCNT_FRAUD_TXNS — Description not available.

DTDATE — Description not available.

FSUM_FRAUD_TXNS — Description not available.

NCNT_FRAUD_TXNS — Description not available.

SD_DEVICE_ID — A unique identifier for the device.

Device_Daily_Profile Table

The Device_Daily_Profile Table is used by the Analysis and Review system. It contains the daily totals of transaction types for an account.

The columns in the Device_Daily_Profile table (DEVICE_DAILY_PROFILE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
DTDATE	datetime
FSUM_FRAUD_TXNS	money
NCNT_FRAUD_TXNS	int
SD_DEVICE_ID	varchar(50)

Index Name: **PK_DEVICE_DAILY_PROFILE**

Fields: DTDATE

 SD_DEVICE_ID

Column Descriptions

The following are the descriptions of the Device_Daily_Profile table columns.

DTDATE — Description not available.

FSUM_FRAUD_TXNS — Description not available.

NCNT_FRAUD_TXNS — Description not available.

SD_DEVICE_ID — A unique identifier for the device.

IP Address view

The following tables are specific to the IP Address view:

- IP_3_Days_Profile
- IP_7_Days_Profile
- IP_Daily_Profile

IP_3_Days_Profile Table

Description not available.

The columns in the IP_3_Days_Profile table (IP_3_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM_FRAUD_TXNS	money
AVG_NCNT_FRAUD_TXNS	float
DTDATE	datetime
FSUM_FRAUD_TXNS	money
NCNT_FRAUD_TXNS	int
SD_CLIENT_IP	varchar(50)

Index Name: **PK_IP_3_DAYS_PROFILE**

Fields: DTDATE

 SD_CLIENT_IP

Column Descriptions

The following are the descriptions of the IP_3_Days_Profile table columns.

AVG_FSUM_FRAUD_TXNS — Description not available.

AVG_NCNT_FRAUD_TXNS — Description not available.

DTDATE — Description not available.

FSUM_FRAUD_TXNS — Description not available.

NCNT_FRAUD_TXNS — Description not available.

SD_CLIENT_IP — The client's IP, which can be parsed from the X-Forwarded-For string.

IP_7_Days_Profile Table

Description not available.

The columns in the IP_7_Days_Profile table (IP_7_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM_FRAUD_TXNS	money
AVG_NCNT_FRAUD_TXNS	float
DTDATE	datetime

Column Name	Data Type
FSUM_FRAUD_TXNS	money
NCNT_FRAUD_TXNS	int
SD_CLIENT_IP	varchar(50)

Index Name: **PK_IP_7_DAYS_PROFILE**

Fields: DTDATE

 SD_CLIENT_IP

Column Descriptions

The following are the descriptions of the IP_7_Days_Profile table columns.

AVG_FSUM_FRAUD_TXNS — Description not available.

AVG_NCNT_FRAUD_TXNS — Description not available.

DTDATE — Description not available.

FSUM_FRAUD_TXNS — Description not available.

NCNT_FRAUD_TXNS — Description not available.

SD_CLIENT_IP — The client's IP, which can be parsed from the X-Forwarded-For string.

IP_Daily_Profile Table

The IP_Daily_Profile Table is used by the Analysis and Review system. It contains the daily totals of transaction types for an account.

The columns in the IP_Daily_Profile table (IP_DAILY_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FSUM_FRAUD_TXNS	money
NCNT_FRAUD_TXNS	int
SD_CLIENT_IP	varchar(50)

Index Name: **PK_IP_DAILY_PROFILE**

Fields: DTDAT

SD_CLIENT_IP

Column Descriptions

The following are the descriptions of the IP_Daily_Profile table columns.

DTDATE — Description not available.

FSUM_FRAUD_TXNS — Description not available.

NCNT_FRAUD_TXNS — Description not available.

SD_CLIENT_IP — The client's IP, which can be parsed from the X-Forwarded-For string.

Payee view

The following tables are specific to the Payee view:

- Payee_3_Days_Profile
- Payee_7_Days_Profile
- Payee_Daily_Profile

Payee_3_Days_Profile Table

Description not available.

The columns in the Payee_3_Days_Profile table (PAYEE_3_DAYS_PROFILE) are listed below with the data type.

Column Name	Data Type
AVG_FSUM_FRAUD_TXNS	money
AVG_NCNT_FRAUD_TXNS	float
DTDATE	datetime
FSUM_FRAUD_TXNS	money
NCNT_FRAUD_TXNS	int
SD_SEC_ACCT_NUM	varchar(50)

Index Name: **PK_PAYEE_3_DAYS_PROFILE**

Fields: DTDAT

SD_SEC_ACCT_NUM

Column Descriptions

The following are the descriptions of the Payee_3_Days_Profile table columns.

AVG_FSUM_FRAUD_TXNS — Description not available.

AVG_NCNT_FRAUD_TXNS — Description not available.

DTDATE — Description not available.

FSUM_FRAUD_TXNS — Description not available.

NCNT_FRAUD_TXNS — Description not available.

SD_SEC_ACCT_NUM — Unambiguous identification of the account of the creditor to which a credit entry will be posted as a result of the payment transaction.

Payee_7_Days_Profile Table

Description not available.

The columns in the Payee_7_Days_Profile table (PAYEE_7_DAYS_PROFILE) are listed below with the data type.

<i>Column Name</i>	<i>Data Type</i>
AVG_FSUM_FRAUD_TXNS	money
AVG_NCNT_FRAUD_TXNS	float
DTDATE	datetime
FSUM_FRAUD_TXNS	money
NCNT_FRAUD_TXNS	int
SD_SEC_ACCT_NUM	varchar(50)

Index Name: **PK_PAYEE_7_DAYS_PROFILE**

Fields: DTDAT

SD_SEC_ACCT_NUM

Column Descriptions

The following are the descriptions of the Payee_7_Days_Profile table columns.

AVG_FSUM_FRAUD_TXNS — Description not available.

AVG_NCNT_FRAUD_TXNS — Description not available.

DTDATE — Description not available.

FSUM_FRAUD_TXNS — Description not available.

NCNT_FRAUD_TXNS — Description not available.

SD_SEC_ACCT_NUM — Unambiguous identification of the account of the creditor to which a credit entry will be posted as a result of the payment transaction.

Payee_Daily_Profile Table

The Payee_Daily_Profile Table is used by the Analysis and Review system. It contains the daily totals of transaction types for an account.

The columns in the Payee_Daily_Profile table (PAYEE_DAILY_PROFILE) are listed below with the data type.

Column Name	Data Type
DTDATE	datetime
FSUM_FRAUD_TXNS	money
NCNT_FRAUD_TXNS	int
SD_SEC_ACCT_NUM	varchar(50)

Index Name: **PK_PAYEE_DAILY_PROFILE**

Fields: DTDAT

SD_SEC_ACCT_NUM

Column Descriptions

The following are the descriptions of the Payee_Daily_Profile table columns.

DTDATE — Description not available.

FSUM_FRAUD_TXNS — Description not available.

NCNT_FRAUD_TXNS — Description not available.

SD_SEC_ACCT_NUM — Unambiguous identification of the account of the creditor to which a credit entry will be posted as a result of the payment transaction.

Section 6: **BASE24 Files Maintenance Considerations**

This section describes the installation and configuration of the BASE24 files and the PRM Interface Process operating under an HP NonStop platform, including the following items:

- Logical Network Configuration File (LCONF) Assigns and Params
- Process configuration information
- Creating the Proactive Risk Manager data files
- ACI Proactive Risk Manager tokens
- Configuring the Real-time Scoring Table
- Pathway configuration information
- Creating the Credit/Debit Master [File](#) (CDMF) records
- Adding the Interchange Configuration File (ICF) record
- Creating the Merchant Master File (MMF) records
- Creating the PTBL entries
- ACI Proactive Risk Management startup and control

Because of the various possible configurations for ACI Proactive Risk Manager, ACI Worldwide, Inc. works closely with each customer to determine the optimal configuration for their environment.

Logical Network Configuration File (LCONF) Assigns and Params

The Scoring Engine and PRM Interface Processes use several Logical Network Configuration File (LCONF) assigns and params for processing. These assigns and params are identified below. For more information on the LCONF, refer to the *BASE24 Logical Network Configuration File Manual*.

Assigns

The following assigns identify the name of files that contain the scoring engine and PRM Interface Process configuration and control information used during processing.

DSAF — The physical file name of the Dump Store-and-Forward File (DSAF). Each PRM Interface Process must have its own DSAF assign defined in the LCONF. The DSAF assigns are linked to PRM Interface Processes by placing the symbolic name of the PRM Interface Process in the PROCESS NAME field of the LCONF assign screen.

The DSAF assigns also require that a fully qualified template file name be specified in the TEMPLATE field of the LCONF assign screen. BASE24 uses the specified template to create the DSAF files.

Example: \B24.\$VOL.SUBVOL.DSAF

ICF — The fully qualified file name of the Interchange Configuration File. This assign is required.

Note: If switch transactions are already processed, this assign already exists.

Example: \B24.\$VOL.SUBVOL.ICF

MMF — The fully qualified name of the Merchant Master File (MMF). This assign is used by the Scoring Engine Input process.

There may be only one MMF per logical network. Multiple PRM Interface Processes can read one MMF. Therefore, the process name can be defaulted to asterisks.

The MMF assigns also require that a fully qualified template file name be specified in the TEMPLATE field of the LCONF assign screen.

The MMF can also be updated through the BASE24 Pathway screen.

Example: \B24.\$VOL.SUBVOL.MMF

PHF — The fully qualified file name of the Proactive Risk Manager History File (PHF). Each PRM Interface Process must have its own PHF assign defined in the LCONF. PHF assigns are linked to PRM Interface Processes by placing the symbolic name of the process in the PROCESS NAME field of the LCONF assign screen.

The PHF assigns also require that a fully qualified template file name be specified in the TEMPLATE field of the LCONF assign screen. BASE24 uses the specified template file to create PHFs.

Note: This assign is optional and is needed if records are to be logged and stored on the HP NonStop platform.

Example: \B24.\$VOL.SUBVOL.PHYMMDD

PRM-CONTROL — The fully qualified name of the Proactive Risk Manager Control File. The control file is an edit file that contains the file assigns used by the scoring engine.

The file assigns within this file must be modified to reflect the customer's volume and subvolume names. Examples of these assigns are shown below:

```
[0]=$vol.pseamodl
[1]=$vol.pseacnfg
[2]=$vol.pseatest
ecf=[1].Ecf
mod_mem=[0].ModMemSc
mod_mem_old=[0].ModMemSc
```

```

mod_con=[0].ModConSc
irinit_file=[0].IrInit
risk_factors=[0].RiskFact
transfile_des=[0].TFDes
fmt_des=[2].FmtDes
fmt_trans=[2].Fmt.Tran
mod_exec=[2].ModExeSc
fscall=[2].Fscalls
log_err=[2].errlog
log_info=[2].infolog

```

The control files shown above also are provided by ACI Worldwide Inc. and should not be modified. Each Scoring Engine process requires its own set of control files.

PRM-PTBL — This assign is used by the ATM and POS authorization processes and by the SVPTBL server. This file identifies whether transactions for a prefix or a bank should be scored and also includes the name of the destination (PIP process).

Example: \B24.\$VOL.SUBVOL.PTBL

SAF — The physical file name of the Store-and-Forward File (SAF). Each PRM Interface Process must have its own SAF assign defined in the LCONF. SAF assigns are linked to interface processes by placing the symbolic name of the interface process in the PROCESS NAME field of the LCONF assign screen.

SAF assigns also require that a fully qualified template file name be specified in the TEMPLATE field of the LCONF assign screen. BASE24 uses the specified template file to create the Store-and-Forward Files.

Example: \B24.\$VOL.SUBVOL.SAF

SEMF — The fully qualified file name of the ~~Credit-Debit~~[Scoring Engine](#) Master File. This assign is used by the PRM Interface Process and the Refresh process. The Master File is named based on the ACI Proactive Risk Manager solution. In this example, SEMF is the assign name for the Credit/Debit Master File. There can be only one Master File per logical network. Since all PRM Interface Processes read the same Master File, the process name in this assign should default to asterisks. The Master File can also be updated through BASE24 Pathway screens. [The Pathway screens are named CREDIT/DEBIT MASTER FILE.](#)

Example: \B24.\$VOL.SUBVOL.SEMF

SIF — The fully qualified file name of the Scoring Input File (SIF). This file is used in a file-based Proactive Risk Manager system. Refer to the ACI Proactive Risk Manager Processing Manual for further information in file-based processing. The SIF is read by the scoring engine process. Each transaction is added to this file in Credit/Debit Input File (CDIF) to be processed by the PRM Scoring Engine process.

If used, each PRM Interface Process must have its own SIF assign defined in the LCONF. The SIF assigns are linked to interface processes by placing the symbolic name of the interface process in the PROCESS NAME field of the LCONF assign screen.

The SIF assigns also require that a fully qualified template file name be specified in the TEMPLATE field of the LCONF assign screen. BASE24 uses the specified template file to create SIF.

Example: \B24.\$VOL.SUBVOL.SIDDDHMM

Params

Several params are used by the ACI Proactive Risk Manager solution during processing. These params are as follows.

ATM-LN-CUTOVER — This param indicates the time of the ATM logical network cutover.

Note: This param already exists if the BASE24-atm product is installed.

Example: 18:30

POS-LN-CUTOVER — This param indicates the time of the POS logical network cutover.

Note: This param already exists if the BASE24-pos product is installed.

Example: 15:30

PRM-LOG — This param contains the name of an EMS collector the customer should use as an alternate to the default of \$0.

Note: This param is read by the PRM Scoring Engine process. This param is optional.

Example: \$EMS

PRM-REAL-TIME — This parameter is used by ATM Authorization and POS RTAU to indicate if real-time processing (score and/or rules) is to be performed. When set to a "Y", the authorization process adds the Real-time Token (Token ID 32) to the STM or PSTM. Valid values are:

Y = Real-time rules processing is performed

N = Real-time rules processing is not performed

Default: N

PRM-PHF-RETENTION — This param indicates the number of days the PRM History File (PHF) should be retained on the system.

Example: 7

PRM-SEND-TRACK2 — This param indicates the whether the PRM Interface Process (PIP) should send the Track2 data to the Analysis and Review system.

Example: N

SAF-NOTIFY-INTERVAL — This param specifies the number of writes made to the Store- and-Forward File (SAF) between calculating the percentage of file full. Each time a write is made to the SAF, a counter is used. When the counter is equal to the value in this param, a calculation is performed to determine how full the file is. The counter is then reset to zero. When the file reaches the percent full specified in the SAF-NOTIFY-PERCENTAGE param, a message is logged indicating the file is becoming full. Until more space is made available, the interface process continues to log

messages that the file is becoming full at the interval specified in this param. If other BASE24 switches are installed, this param might already exist. Valid values are 10 through 32766.

Default value: 50

Example: 50

SAF-NOTIFY-PERCENTAGE — This param specifies the percentage of used file space at which the interface process logs a message indicating the SAF is becoming full. If other BASE24 switches are installed, this param may already exist. Valid values are 10 through 99 percent.

Default: 70

Example: 70

SEMF-NOTIFY — This param is used by the Refresh process. The param is used to send notify messages to the PIP processes to indicate that a full file refresh has been completed and the PIP should begin using the new Master File. Up to 10 different interfaces can be notified by changing the nn sequence number.

Example: CDMFQ1

Process Configuration

The minimum XPNET release requirement is XPNET 2.1. In order to use the prioritized queueing of messages to the PRM Interface Process option, the minimum release requirement is XPNET 3.0. The XPNET release can be determined by issuing the following TACL command:

```
BIND LIST CODE REL FROM $SYS1.XPNET.NETWORK
```

Examine the REL3^VER0^RELnn^yymmdd proc where nn is the release number.

Refer to the *Net24- XPNET Network Control Operations Guide* for additional information regarding XPNET Node configuration.

XPNET 3.0 Userdata Example

The following is an example of the XPNET 3.0 Userdata:

```
SET STATION USERDATA (refer to station declarations)
```

XPNET 3.0 Process NCPCOM Obey File

The following is an example of a process definition for a PRM Interface Process (PIP).

```
RESET PROCESS
SET PROCESS BCPU 0
SET PROCESS LIBRARY $SYS1.XPNET.SKELB
SET PROCESS PROGRAM $VOL.PIXXOBJ.PIP
SET PROCESS PPD $P118
SET PROCESS PRIORITY 158
SET PROCESS CPU 1
```

```

SET PROCESS QAT 50
SET PROCESS QMT 100
SET PROCESS QMI 10
SET PROCESS SMT -1
SET PROCESS SERVICE PIP1Q
ADD PROCESS P1A^PIP1, UNDER SYSNAME \SYS1,
                UNDER NODE P1A^NODE
RESET PROCESS

```

The following is an example of a process definition for a PRM Scoring Engine (PSE):

```

RESET PROCESS
SET PROCESS BCPU 0
SET PROCESS LIBRARY $SYS1.XNLIBN.XNLIBN
SET PROCESS PROGRAM $VOL.PSxxOBJ.PSEXP
SET PROCESS PPD $P1NM1
SET PROCESS PRIORITY 159
SET PROCESS CPU 1
SET PROCESS QAT 50
SET PROCESS QMT 100
SET PROCESS QMI 10
SET PROCESS NSKSTARTSEQ ON
ADD PROCESS P1A^PSE1, UNDER SYSNAME \SYS1, UNDER NODE P1A^NODE

```

XPNET 3.0 Device Obey File

The following is an example of a device obey file for the TCP Server.

```

RESET DEVICE
SET DEVICE INPUTFORMAT TXT
SET DEVICE OUTPUTFORMAT TXT
SET DEVICE POLLFORMAT S
SET DEVICE RECVLEN 2048
SET DEVICE SELECTFORMAT
SP SET DEVICE TYPE 1
SET DEVICE XMITLEN 2048
ADD DEVICE TCP^SERVER, UNDER SYSNAME \SYS1, UNDER NODE P1A^NODE

```

XPNET 3.0 Input Station Obey File

The following example is the input station on the Tandem used to receive responses from an PRM Scoring Engine or an Analytic Gateway. The input side is always considered the client and always establishes the TCP/IP connection.

Note: The RADDR value must be set to the agreed upon port number and the IP address of the PRM Scoring Engine or Analytic Gateway server.

```

RESET STATION
SET STATION DESTINATION P1A^PIP1
SET STATION ERRORACT REINEVERY

```

```

SET STATION REINSTATE 45
SET STATION RETRY 2
SET STATION QAT 50
SET STATION UCQUEUE STAQ
SET STATION UCRATE STARATE
SET STATION UCSTATE STASTATE
SET STATION QMT 50
SET STATION CLASS TCPIP
SET STATION DEVICE TCP^SERVER
SET STATION LINENAME \SYS1.P1A^NODE.L1A^TCPI
SET STATION USERDATA OFFSET 0 "-0 -K+" 0
SET STATION RADDR 7999:172.61.21.68
ADD STATION S1A^TCPI, UNDER SYSNAME \SYS1, UNDER NODE P1A^NODE
RESET STATION

```

XPNET 3.0 Output Station Obey File

The following is the output station on the Tandem used to send messages to a PRM Scoring Engine or an Analytic Gateway. The output side is always considered the server and always listens on the port number defined in the TCP/IP startup obey file.

```

SET STATION DESTINATION P1A^PIP1
SET STATION ERRORACT REINEVERY
SET STATION REINSTATE 45
SET STATION RETRY 2
SET STATION QAT 50
SET STATION UCQUEUE STAQ
SET STATION UCRATE STARATE
SET STATION UCSTATE STASTATE
SET STATION QMT 100
SET STATION CLASS TCPIP
SET STATION DEVICE TCP^SERVER
SET STATION LINENAME \SYS1.P1A^NODE.L1A^TCPO
SET STATION USERDATA OFFSET 0 "-0 -K+" 0
ADD STATION S1A^TCPO, UNDER SYSNAME \SYS1, UNDER NODE P1A^NODE

```

XPNET 3.0 Input Line File

The following example is the input file on the Tandem used to receive responses from a PRM Scoring Engine or an Analytic Gateway. The input side is always considered the client and always establishes the TCP/IP connection.

```

RESET LINE
SET LINE ERANALYSIS 200
SET LINE PORT $SIP1
SET LINE UCRATE STARATE
SET LINE UCSTATE STASTATE
SET LINE UCQUEUE STAQ

```

```

SET LINE CMETHOD ALLOCATE
SET LINE EXPDATA ALTROUTE
SET LINE FMM STATUS
SET LINE CLASS TCPIP
SET LINE PROTOCOL CTS
SET LINE DATATIMEOUT 0
SET LINE RESPTIMEOUT 0
SET LINE PARITY OFF
ADD LINE L1A^TCPI, UNDER SYSNAME \SYS1, UNDER NODE P1A^NODE

```

XPNET 3.0 Output Line File

The following example is the output line on the Tandem used to send messages to a PRM Scoring Engine or an Analytic Gateway. The output side is always considered the server and always listens on the port number defined in the TCP/IP obey file.

```

RESET LINE
SET LINE ERANALYSIS 200
SET LINE PORT $SOP1
SET LINE UCRATE STARATE
SET LINE UCSTATE STASTATE
SET LINE UCQUEUE STAQ
SET LINE CMETHOD ACCEPT
SET LINE EXPDATA ALTROUTE
SET LINE FMM STATUS
SET LINE CLASS TCPIP
SET LINE PROTOCOL CTS
SET LINE DATATIMEOUT 0
SET LINE RESPTIMEOUT 0
SET LINE PARITY OFF
ADD LINE L1A^TCPO, UNDER SYSNAME \SYS1, UNDER NODE P1A^NODE

```

XPNET 3.0 Node Parameter Example

The following is an example of the Unavailable Service Queue Management Threshold parameter. It should be set high enough to avoid dropping transactions in the event that the PRM Interface Process (PIP) service is not available.

```

ALTER NODE *, USMQT 1000

```

ACI Proactive Risk Manager Data Files

Using the HP NonStop File Utility Program (FUP), after reviewing the file extent sizes and partitions, the following data files should be created:

```

SAFPIP
    RESET
    SET ALTKEY ( "PK", KEYOFF 0, KEYLEN 56, FILE 0 )

```

```

SET NO ALTCREATE
SET ALTFIL ( 0,  SAFPIPO)
SET TYPE R
SET REC 2030
SET BLOCK 4096
SET EXT ( 4, 32 )
SET MAXEXTENTS 100
CREATE SAFPIP

```

```

SAFPIPO
  RESET
  SET TYPE K
  SET KEYLEN 62
  SET REC 62
  SET BLOCK 4096
  SET IBLOCK 4096
  SET EXT ( 4, 32 )
  SET MAXEXTENTS 100
CREATE SAFPIPO

```

```

DSAF  -SET TYPE K
      -EXT (NNNN, NNNN)
      -SET KEYLEN 56
      -SET KEYOFF 0
      -SET REC 2030
      -SET BLOCK 4096
      -SET IBLOCK 4096
      -SET MAXEXTENTS NNNN
      -CREATE DSAF

```

```

SEM  -SET TYPE K
      -SET KEYLEN 28
      -SET KEYOFF 0
      -SET REC 684
      -SET BLOCK 4096
      -SET IBLOCK 4096
      -SET MAXEXTENTS 16 (CAN BE MORE IF NOT PARTITIONED)
      -SET EXT (NNN,NNN)
      -SET PART (1,$VOL1,NNNN,NNNN,"BNK1") !use cust fiid/card #!
      -SET PART (2,$VOL2,NNNN,NNNN,"BNK2")
      -CREATE CDMF

```

```

MMF  -SET TYPE K
      -SET KEYLEN 23
      -SET KEYOFF 0
      -SET REC 937
      -SET BLOCK 4096
      -SET IBLOCK 4096
      -SET MAXEXTENTS 16 (CAN BE MORE IF NOT PARTITIONED)

```



```

-SET EXT (NNN,NNN)
-SET PART (1,$VOL1,NNNN,NNNN,"BNK1") !use cust fiid/card #!
-SET PART (2,$VOL2,NNNN,NNNN,"BNK2")
-CREATE MMF

```

```

PTBL -SET TYPE K
      -SET KEYLEN 14
      -SET KEYOFF 0
      -SET REC 132
      -SET BLOCK 4096
      -SET IBLOCK 4096
      -SET MAXEXTENTS 100
      -SET EXT (50, 50)
      -CREATE PTBL

```

The ACHDTPLT template file must be created in the ACHD subvolume that is defined in the ECF score files.

```

-SET TYPE K
-SET KEYLEN 33
-SET KEYOFF 0
-SET REC 2030 - (Configurable and must match size in ECF)
-SET BLOCK 4096
-SET IBLOCK 4096
-SET MAXEXTENTS 16 (CAN BE MORE IF NOT PARTITIONED)
-SET EXT (NNNN,NNNN)
-SET PART (1,$VOL1,NNNN,NNNN,"561111") !use entire key!
-SET PART (2,$VOL2,NNNN,NNNN,"562222")
-CREATE ACHDTPLT

```

The ACI Proactive Risk Manager History File Template (if used), must be created on a template subvolume.

```

-SET TYPE E
-SET REC 1250
-SET BLOCK 4096
-SET IBLOCK 4096
-SET MAXEXTENTS NNN
-SET EXT (NNNN, NNNN)
-CREATE PHYMMDD

```

Note: Extent sizes and number of extents should be set appropriately to hold an entire day's worth of IF records.

The ACI Proactive Risk Manager Score Transaction Input File Template (if used), must be created

```

-SET ODDUNSTR
-SET MAXEXTENTS NNN
-SET EXT (NNNN, NNNN)
-CREATE SIDDHMM

```

Note: Extent sizes and number of extents should be set appropriately to hold an entire scoring period's worth of IF records. This value is generally ten minutes.

ACI Proactive Risk Manager Tokens

The ACI Proactive Risk Manager tokens contain data used as input to the Scoring Engine Input process. These tokens and their description are described below.

ACI Proactive Risk Manager Token ID - 28

This token is used to pass information from the Card Account File (CAF), Card Prefix File (CPF), and Positive Balance File (PBF) to the Scoring Engine Input process. The token is added by the Authorization process. The fields in token 28 are described below.

Position	Level	Field Name	Data Type	Description
1-88		PRISM-TKN		The ACI Proactive Risk Manager token is used to pass information from the CAF, CPF, and PBF to the Scoring Engine Input process. The token is added by the Authorization process or module.
1-4	02	EXP-DAT	PIC X(12)	The card expiration date.
5-16	02	CUR-AUTH-AMT	PIC X(12)	The total amount of cash advanced against credit accounts using the BASE24-atm product or the total amount of purchases and cash advances made against credit accounts using the BASE24-pos product during the current usage accumulation period.
17-28	02	PEND-AUTHS	PIC X(12)	The number of times the card has been used by the BASE24-atm and BASE24-pos products during the current usage accumulation period.
29-30	02	PREFIX-LGTH	PIC X(12)	The length of the card prefix. The maximum value that can be placed in this field is 11.
31-42	02	OPENTO-BUY	PIC X(12)	The open-to-buy amount is the amount of available credit for credit accounts and the available balance

				for debit accounts at the time of authorization.
43-54	02	AUTH-LMT	PIC X(12)	The credit limit for credit accounts.
55-66	02	AUTH-BAL	PIC X(12)	The current credit balances for credit accounts. The amount in this field is the total amount of charges on the account. Purchases and cash advances made from credit accounts are added to this amount. The amount of refunds for purchases from a credit account is subtracted from this amount.
67-72	02	LAST-PMNT-DAT	[DATE]	The date (YYMMDD) of the last payment to the account.
67-68	04	YY	PIC X(2)	part of [DATE].
69-70	04	MM	PIC X(2)	part of [DATE].
71-72	04	DD	PIC X(2)	part of [DATE].
73-84	02	LAST-PMNT-AMT	PIC X(12)	The amount of the last payment to the account.
85	02	ACCT-STAT	PIC X(1)	The current status of the application account. For valid values, please refer to the following field in the PBF: PBFBASE.ACCT-STAT.
86	02	CRD-STAT	PIC X(1)	The card status. For valid values, please refer to the following field in the CAF: CAFBASE.CRD-STAT.
87	02	AUTH-LMT-IND	PIC X(1)	Indicates whether this token contains limit data from the CPF, CAF only, CAF/PBF, NEG only, NEG/UAF, or from the host. Valid values are: 0 = CPF data only C = CAF data included P = CAF and PBF data included N = NEG only U = NEG/UAF H = Host

88	02	SEND-MSG-TO-PRM	PIC X(1)	Indicates whether the message should be forwarded to PRM. Valid values are: Blank = No information available N = Do not forward message to PRM merchant destination Y = Forward message to appropriate destinations T = Message forwarded to PRM, but timed out
----	----	-----------------	----------	---

ACI Proactive Risk Manager Real Time Token - 32

The PRM Real-time Token is used to pass and store information for real-time processing. The token is initially added by the authorization system (ATM or POS). The fields in token 32 are described below.

Position	Level	Field Name	Data Type	Description
1-12		PRM-RT-TKN		The PRM Real-time Token is used to pass and store information for the real time processing features of PRM. The token is initially added by the authorization system (ATM or POS).
1	02	REAL-TIME-REQ-TYPE	PIC X	The type of real-time request. Valid values are: Blank = Allow interface process to set and control this token field. 0 = Real-time score only 1 = Real-time rules only 2 = Both real-time score and real-time rules
2	02	PIP-RESPONSE-REQUEST	PIC X	The type of message that should be returned to the Authorization system. Valid values include: Blank = Allow interface process to set and control this token field. 0 = Response back to Authorization should be a 0200 1 = Response back to Authorization should be a 0210

3	02	REAL-TIME-STATUS	PIC X	A processing control field to assist with the type of processing required. Valid values include: Blank = Allow interface process to set and control this token field. 0 = Initial state. Transaction not yet processed in real time. 1 = Transaction should be processed by PSE in real time 2 = Transaction should be processed by RTR in real time 3 = Transaction processed by both PSE and RTR in real-time
4-6	02	REAL-TIME-SCORE	9(3)	This field holds the real-time fraud score generated by the Scoring Engine.
7-10	02	REAL-TIME-RULE-FIRE	9(4)	This field holds the real-time rule number that was fired during the real-time rules processing.
11	02	RTR-DISPOSITION	PIC X	This field holds the PRM recommended disposition of the real-time transaction. Valid values include: A = Authorization recommended D = Decline recommended R = Referral recommended
12	02	RTR-FILLER	PIC X	This field will be used for future use.

Real Time Scoring Table

The Real-time Scoring Table (RTSFIID) is used to determine the values for authorization for real-time scoring transactions.

Sample RTSFIIDS Table

The RTSFIID Table contains one entry for each card prefix that wants to establish its own RTS fraud score thresholds. If the card prefix is not in the table, the PRM Interface Process reads the card FIID table below:

```
string rts^prefix^tbl = 'p' := [
```

```
!      card      atm      pos      pos
```

```

!   prefix      approve  approve  deny
!
!   "000000",    "100",    "200",    "300",
!   "111111",    "400",    "500",    "600",
!   "222222",    "700",    "800",    "900",
!   0 ];

```

The RTS^FIID^TBL contains one entry for each card FIID that wants to establish it's own RTS fraud score thresholds. If the card FIID is not in the table, the ICF's thresholds are used.

```
string rts^prefix^tbl = 'p' := [
```

```

!   card        atm      pos      pos
!   fiid        approve  approve  deny
!
!   "0000",      "100",    "200",    "300",
!   "0001",      "400",    "500",    "600",
!   "0002",      "700",    "800",    "900",
!   0 ];

```

Pathway Configuration

When running the BASE24 and ACI Proactive Risk Manager solutions, the following Pathway servers are required to be configured in the Pathconf File:

- Server PRM Routing Table (SVPTBL)
- Server Scoring Engine Master File (SVSEMF)
- Merchant Master File Server (MMF)

Pathconf Entries

The following example identify the ACI Proactive Risk Manager Pathconf entries that should be included in the Pathway Configuration File (PATHCONF).

```
[PTBL - PROACTIVE RISK MANAGER ROUTING TABLE FILE SERVER]
```

```

RESET SERVER
SET SERVER CPUS          1:0
SET SERVER PROGRAM       $VOL.PInnOBJ.SVPTBL
SET SERVER DELETEDDELAY   10 MINS
SET SERVER TIMEOUT       60 SECS

SET SERVER PRI           145
SET SERVER HOMETERM      $SUDO
ADD SERVER SERVER-PTBL

```

```
[SEMF - PROACTIVE RISK MANAGER CREDIT/DEBIT MASTER FILE SERVER]
```

```

RESET SERVER
SET SERVER CPUS          1:0
SET SERVER PROGRAM       $VOL.PInnOBJ.SVSEMF
SET SERVER DELETEDELAY   10 MINS
SET SERVER TIMEOUT       60 SECS
SET SERVER PRI           145
SET SERVER HOMETERM      $SUDO
ADD SERVER SERVER-CDMF

[MMF - PROACTIVE RISK MANAGER MASTER FILE SERVER]

```

```

RESET SERVER
SET SERVER CPUS          1:0
SET SERVER PROGRAM       $VOL.PInnOBJ.SVMMF
SET SERVER DELETEDELAY   10 MINS
SET SERVER TIMEOUT       60 SECS
SET SERVER PRI           145
SET SERVER HOMETERM      $SUDO
ADD SERVER SERVER-MMF

```

Pathway Screen Layouts

This section provides an introduction to the files and functions specific to the Proactive Risk Manager product and the file maintenance screens and function keys used to access them. The following screens and the field descriptions will be discussed:

Screen Acronym	Description
SEMF	Credit/Debit Master File (Credit/Debit solutions only) This file is read by the PRM Interface Process during initialization. It adds the appropriate fields to the appropriate input format to be sent on to the designated location. In this scenario, the solution is Credit/ Debit. Note: These fields can also be added using the BASE24 Master File Refresh (full or partial) process.
ICF	Interchange Configuration File This file contains parameters relevant to transaction processing. It is used by the institution to define settlement information, timer limits, and transactions allowed to switch. Screen 12 is used by the PRM Interface Process to determine the routing logic to the PRM Scoring Engine for the proper model.
MMF	Merchant Master File (Merchant solution only) This file is read by the PRM Interface Process during initialization. It adds the appropriate fields to the appropriate

	input format to be sent on to the designated location. In this scenario, the solution is Merchant. Note: These fields can also be added using the BASE24 Master File Refresh (full or partial) process.
PTBL	Proactive Risk Manager Routing Table This table contains entries that are used by both BASE24-atm and BASE24-pos ATM and POS Authorization processes to route copies of the STM and PSTM to the appropriate PRM Interface Process.

Credit/Debit Master File (**SEMFCDMF**)

The Credit/Debit Master File (**SEMFCDMF**) contains cardholder information that is not found in any BASE24-atm or BASE24-pos file. This file is used ~~only~~ by only the ACI Proactive Risk Manager Card action level. This file is read by the PRM Interface Process and is created at installation.

Data from this file and the STM/PSTM is used to create records that are passed to the Scoring Engine. This file may be updated by a full-file refresh, a partial refresh, by using the BASE-24 from host maintenance product, or through the Pathway user screens.

Described below are the fields on the SEMF screens, which are named CREDIT/DEBIT MASTER FILE.

SEMF Screen 1

The fields on SEMF Screen 1 are described below.

FIID — The FIID or ABA number of the financial institution that issued the card. This value must be unique within the logical network.

Field Length: 9 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: SEMF.PRIKEY.FIID

CARD NUMBER/PAN — The card number (PAN) identifying the card (left-justified and blank-filled). This field contains the card number carried in the Track 2 of the card. BASE24 currently supports a 19-digit maximum PAN length.

Field Length: 19 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: SEMF.PRIKEY.PAN

PRIMARY NAME — The name of the primary cardholder.

Field Length: 40 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: SEMF.USER.PRI-NAM

SECONDARY NAME — The name of the secondary cardholder.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.SEC-NAM

ADDITIONAL NAME — The name of a third authorized user.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.ADNL-NAM

ADDRESS LINE 1 — The first line of the primary cardholder's street address.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.ADDR-1

ADDRESS LINE 2 — The second line of the primary cardholder's street address.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.ADDR-2

CITY — The primary cardholder's city of residence.

Field Length: 30 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.CITY

STATE/REGION — The alphabetic representation of the primary cardholder's state of residence. This field also can contain the province or region where the primary cardholder resides.

Field Length: 30 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.ST

COUNTRY — The alphabetic representation of the primary cardholder's country of residence. Refer to the ISO 3166:1988 standard, *Codes for the Representation of Names of Countries* for valid values.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.CNTRY

POSTAL CODE — The postal code or ZIP code for the primary cardholder's residence.

Field Length: 40 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: SEMF.USER.POSTAL-CDE

HOME PHONE — The primary cardholder's home telephone number. The data in this field is left-justified.

Field Length: 20 numeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.HOME-PHN

WORK PHONE — The primary cardholder's work telephone number. The data in this field is left-justified.

Field Length: 20 numeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.WRK-PHN

MOBILE PHONE — The third telephone number for the primary cardholder. This field may be used for a mobile or cellular telephone number.

Field Length: 20 numeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.MOB-PHN

EMAIL ADDRESS — The e-mail address for the primary cardholder.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.EMAIL^ADDR

CUSTOMER ID — The customer identification that can be used for a customer reference number, password, place of birth, or other security or identifying information.

Note: The customer reference number value can be a customer reference.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.ID

GOVERNMENT ID — The social security number of the primary cardholder.

Field Length: 20 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.PRI-GOVT-ID

DATE OF BIRTH — This field contains the primary cardholder's date of birth.

Field Length: 8 numeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.PRI-DOB

OTHER NAME — The primary cardholder's unique information.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.OTHR-NAM

PREV CARD NUM — The card number (PAN) that was replaced by the card that was used for the current transaction. This field is left-justified and blank filled.

Field Length: 19 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.USER.PREV-CRD-NUM

SEMF Screen 2

The fields on SEMF Screen 2 are described below.

FIID — The FIID or ABA number of the financial institution that issued the card. This value must be unique within the logical network.

Field Length: 4 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.PRIKEY.FIID

CARD NUMBER/PAN — The card number (PAN) identifying the card. This field contains the card number carried in the Track 2 of the card. BASE24 currently supports a 19-digit maximum PAN length. This value is left-justified and blank filled.

Field Length: 19 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: SEMF.PRIKEY.PAN

NUMBER ISSUED — The number of cards that have been issued with the same PAN as the card used for this transaction that are currently active.

Field Length: 2 numeric characters

Required Field: No

Default Value: 00

Data Name: SEMF.CRD.NUM-ISS

PRODUCT/MBR TYPE — A code indicating the product or member type associated with this card (e.g., gold or classic card). This code also can indicate the internal organization that owns the account.

Field Length: 2 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.CRD.PROD-TYP

PLASTIC TYPE — The type of plastic card or the cardholder agreement.

Field Length: 2 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: SEMF.CRD.PLASTIC-TYP

BLOCK CODE — A code indicating whether a card has been blocked and the reason why. These values are user defined.

Field Length: 1 alphanumeric character

Required Field: No

Default Value: No default value

Data Name: SEMF.CRD.BLK-CDE

RECLASS/ALT BLOCK CODE — A code indicating the reclassification code. It is also known as the alternate block code.

Field Length: 1 alphanumeric character

Required Field: No

Default Value: No default value

Data Name: SEMF.CRD.RECLASS-CDE

BEHAVIORAL SCORE — A value indicating the behavior score. Valid values are 0000-9999. Scores that range from 650-750 are good. If the score is less than 650, the risk is higher.

Field Length: 4 alphanumeric characters

Required Field: No

Default Value: 0000

Data Name: SEMF.CRD.BHVR-SCORE

CUSTOM MSTR AMT — The amount field to hold any customized user amount.

Field Length: 16 Numeric characters

Required Field: No

Data Name: SEMF.CUST.MSTR-AMT

CUSTOM MSTR DATE — The date field to hold any customized user date.

Field Length: 8 Numeric characters

Required Field: No

Data Name: SEMF.CUST.MSTR-DAT

CUSTOM MSTR FLD1 — A field to hold any customized user information.

Field Length: 2 Numeric characters

Required Field: No

Data Name: SEMF.CUST.MSTR-FLD1

CUSTOM MSTR FLD2 — A field to hold any customized user information.

Field Length: 4 Numeric characters

Required Field: No

Data Name: SEMF.CUST.MSTR-FLD2

REQUEST DATE — The date of the last card request.

Field Length: 8 Numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: SEMF.CRD.RQST-DAT

PIN CHANGE DATE — The date of the last PIN change transaction.

Field Length: 8 numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: SEMF.CRD.PIN-CHNG

LAST ISSUED — The last issue date of the card. This field is also known as the begin or commence date.

Field Length: 8 numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: SEMF.CRD.LAST-ISS

EMBOSSING DATE — The date the card was embossed.

Field Length: 8 numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: SEMF.CRD.EMBOSS

CRV MAINTENANCE — The date of the last CRV maintenance.

Field Length: 8 numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: SEMF.CRD.LAST-CRV

LAST ADDRESS CHNG — The date of the last address change.

Field Length: 8 numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: SEMF.CRD.LAST-ADDR-CHNG

STATUS CHNG DATE — The date of the last status change.

Field Length: 8 numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: SEMF.CRD.LAST-STAT-CHNG

DATE ACCT OPENED — The date the account was opened.

Field Length: 8 numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: SEMF.ACCT.OPN-DAT

LIFETIME HIGH CASH ADV/WITHDRAWAL AMT — The lifetime high cash advance amount.

Field Length: 12 numeric characters

Required Field: No

Default Value: 0

Data Name: SEMF.LIFE-HIGH.CASH-ADV-AMT

LIFETIME HIGH PURCHASE AMT — The lifetime high purchase amount.

Field Length: 12 numeric characters

Required Field: No

Default Value: 0

Data Name: SEMF.LIFE-HIGH.PURCH-AMT

LIFETIME HIGH BALANCE AMT — The lifetime high balance amount.

Field Length: 12 numeric characters

Required Field: No

Default Value: 0

Data Name: SEMF.LIFE-HIGH.BAL-AMT

SEMF Refresh and Extract Processing

The BASE24 Refresh process allows full-file and partial file refresh of the SEMF using the Refresh screens or a network control facility. The Refresh File Header APPL field should be set to SM.

The refresh file format can be found in the DDLFSEMF file located on the PInnDDL subvolume.

The SEMF can be extracted using the BASE24 OMF Extract process.

For additional information regarding the Refresh and Extract screens, refer to the *BASE24 Refresh and Extract Operators Manual*.

~~CDMF~~SEMF from Host Maintenance Processing

Messages can be sent from the host to BASE24 to add, update or delete records from the SEMF ~~CDMF~~ using the BASE24-from host maintenance product.

The BASE24-from host maintenance report programs are responsible for reporting all of the accepted, rejected application file or table changes, additions, or deletions to the SEMF.

For additional information regarding BASE24-from host maintenance processing and reports, refer to the *BASE24-from host maintenance Reference Manual*.

Interchange Configuration File (ICF)

The Interchange Configuration File (ICF) contains parameters relevant to the PRM Interface Process transaction processing. It is used by the institution to define transaction handling, in offline and online situations and timer limits. There is one ICF record for each PRM Interface Process that uses the ICF.

The following screens are used to access records in the ICF:

- Screen 1 contains BASE24 PRM Interface Process names and information.
- Screen 2 contains the PRM Interface Process settlement information.
- Screen 3 contains the PRM Interface timer limits and processing options.
- Screen 7 identifies the BASE24-atm transactions that should be sent to the ACI Proactive Risk Manager Scoring Engine.
- Screen 8 contains BASE24-atm ICF data and is not used for transaction processing.
- Screen 9 identifies the BASE24-pos transactions that should be sent to the ACI Proactive Risk Manager Scoring Engine.
- Screen 10 contains the PRM Interface timer limits.
- Screen 11 contains BASE24-pos product data and is not used for PRM transaction processing.
- Screen 12 contains ACI Proactive Risk Manager-specific parameters and controls the operating mode of the PRM Interface.

Operating Modes

There are four different operating modes in which the ACI Proactive Risk Manager process runs in:

- File-based mode
- Triangle mode
- L mode
- Rules-based mode

File-Based Mode

The file-based mode is invoked by configuring the FILE BASED parameter on ICF Screen 12 to the value Y and the CUTOVER parameter on ICF Screen 12 to the value Minutes. This mode causes the Scoring Input File (SIF) to be built. The format of the records in the SIF depends on the value of the SCORING ENGINE PRESENT field on ICF Screen 12. If this the value in this field is set to the value Y, the Scoring Input File is read in batch mode by the PRM Scoring Engine process. If the value in this field is set to the value N, the SIF is formatted for processing by the Analytic Gateway process.

Note: It is not necessary to configure any fields on ICF screen 12, other than those listed above when running in File Based Mode.

Triangle Mode

The Triangle mode is the preferred online message-based environment and must be used for real-time processing. The PRM Scoring Engine can reside on either the HP NonStop platform, or a Windows processor. If the PRM Scoring Engine resides on the HP NonStop platform, the SCORING ENGINE parameter on ICF Screen 12 should reflect the process name of the PRM Scoring Engine (e.g., P1A^PSE1). If the PRM Scoring Engine resides on a Windows processor, this parameter identifies the outbound station of the scoring engine (e.g. S1A^TCP0).

When the scoring engine resides on a HP NonStop platform, the PRM Scoring Engine's Execution Control File parameter XPNET_DEST value should be configured to the Analytic Gateway process outbound station name (e.g., S1A^TCPO).

L Mode

The L mode is an online message-based environment. The PRM Interface Process communicates with both the PRM Scoring Engine and the Analytic Gateway process. The scoring engine can reside on an HP NonStop platform. A value in the PRM Scoring Engine field is required.

If the scoring engine resides on an HP NonStop platform, the PRM Scoring Engine's Execution Control File parameter XPNET_SEND identifies the PRM Interface Process.

The Analytic Gateway process destination reflects the name of the outbound station used for communications to the resident Analytic Gateway process (e.g., S1A^TCPO).

Rules-Based Mode

The rules-based mode environment does not utilize a PRM Scoring Engine. An input format message that includes default fraud and reason codes is sent directly to the Analytic Gateway process. The SCORING ENGINE field on ICF Screen 12 should be left blank and the SCORING ENGINE PRESENT field on ICF Screen 12 should be set to a value of N. The Analytic Gateway process destination should reflect the name of the outbound station used for communications to the resident Analytic Gateway process (e.g., S1A^TCPO).

ICF Screen 1

ICF screen 1 identifies the ACI Proactive Risk Manager FIID name and process name along with the switch type (PRM Interface Process). The fields on ICF Screen 1 that are used by PRM are described below.

INTERCHANGE FIID — The institution identifier uniquely distinguishing the PRM Interface Process. This field and the PROCESS field combine to make the primary key to the ICF.

Field Length: 1–4 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: ICF.PRIKEY.FIID

PROCESS — The name of the PRM Interface Process. This field and the INTERCHANGE FIID field combine to make the primary key.

Field Length: 1-16 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: ICF.PRIKEY.SWI-PRO

SWITCH TYPE — A code identifying the PRM Interface Process. The code entered in this field accesses ICF screen 12 if it matches an entry in the POBJ (ICF-SEIP).

Field Length: 1–4 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: ICF.SWI-TYP

ICF Screen 2

ICF Screen 2 contains settlement information. The fields on ICF Screen 2 that are used by PRM are described below.

Settlement Information

The following fields contain interchange settlement information used for recovery processing.

SETTLEMENT HOUR — The hour (local time) to cutover the Proactive Risk Manager History File (PHF). Valid values are 00 through 23.

Field Length: 2 numeric characters

Required Field: Yes

Default Value: 00

Data Name: ICF.SWI-SETL.SETL-HH

SETTLEMENT MINUTE — The minute (local time) to cutover the Proactive Risk Manager History File (PHF). If the PHF is not used, this field should be set to the default value 00. Valid values are 00 through 59.

Field Length: 2 numeric characters

Required Field: Yes

Default Value: 00

Data Name: ICF.SWI-SETL.SETL-MM

ICF Screen 3

ICF Screen 3 contains the timers and processing parameters. The fields on ICF Screen 3 that are used by PRM are described below.

Timer Limits

The following timer value fields are used to control specific transaction message activity between the BASE24 transaction processing network and this interchange.

NETWORK MANAGEMENT — The maximum number of seconds that the process waits for a response before setting an extended network timer for an outstanding network management message (that is, logon, logoff, or echo-test message). Valid values are 0 through 9999.

Field Length: 1–4 numeric characters

Required Field: Yes

Default Value: 30

Data Name: ICF.TIMER-LMTS.NMM

EXTENDED NETWORK — The maximum number of seconds that the process waits before attempting to retry a network management message during periods when the line to the interchange is down. Valid values are 0 through 9999.

Field Length 1–4 numeric characters

Required Field: Yes

Default Value: 60

Data Name: ICF.TIMER-LMTS.XNMM

WAIT FOR TRAFFIC — The maximum number of seconds that the process waits for traffic on the line from the interchange before initiating a network management message. Valid values are 0 through 9999.

Field Length: 1–4 numeric characters

Required Field: Yes

Default Value: 60

Data Name: ICF.TIMER-LMTS.WFT

PERFORMANCE PERIOD — The duration, in minutes, of the interchange performance monitoring period. Valid values are 0 through 9999.

Field Length: 1–4 numeric characters

Required Field: Yes

Default Value: 20

Data Name: ICF.TIMER-LMTS.PERFORMANCE

Processing Options

AUTO SIGNON START — Specifies whether the Interchange Interface process is set to programmatically sign on at startup or log on to the interchange without operator intervention. Valid values are:

Y = Automatically issue a logon when the process is started

N = Logons must be performed manually via NCPCOM/NCS commands

Field Length: 1 alphabetic character

Required Field: Yes

Default Value: No default value

Data Name: ICF.PROCESSING-OPTIONS.AUTO-SIGNON-ON-STRT

MAXIMUM TIMEOUTS — Specifies the maximum number of consecutive network management echo message timeouts before marking the PRM Scoring Engine or Analytic Gateway station down. Valid values are 0 through 9999.

Y = Yes, startup is set to programmatically sign on or log on.

N = No, startup is not set to programmatically sign on or log on.

Note: Once marked down, manual operator intervention must be performed.

Field Length: 1–4 numeric characters

Required Field: Yes

Default Value: None

Data Name: ICF.PROCESSING-OPTIONS.MAX-TIMEOUTS

ICF Screen 7

ICF screen 7 defines the allowable transactions for the BASE24-atm product. The fields on ICF Screen 7 that are used by PRM are described below.

TRANSACTIONS ALLOWED TO SWITCH — Codes defining whether the listed BASE24-atm transactions can be sent to the PRM Scoring Engine. Valid codes are as follows:

Y = Yes, BASE24-atm transactions can be sent

N = No, BASE24-atm transactions cannot be sent

The values in these fields are used for outgoing transactions to determine whether the BASE24-atm product allows the transactions to be sent to the PRM Scoring Engine.

Field Length: 1 alphabetic character

Required Field: No

Default Value: N

Data Name: ICF.ATMICF.TRANS-ALLOWED

ICF Screen 9

The ICF screen 9 defines the allowable transactions for the BASE24-pos product. The fields on ICF Screen 9 that are used by PRM are described below.

TRANSACTIONS ALLOWED TO SWITCH — Codes defining whether the listed BASE24-pos transactions can be sent to the PRM Scoring Engine. Valid codes are as follows:

Y = Yes, BASE24-pos transactions can be sent

N = No, BASE24-pos transactions cannot be sent

The values in these fields are used for outgoing transactions to determine whether the BASE24-pos product allows the transactions to be sent to the PRM Scoring Engine.

Field Length: 1 alphabetic character

Required Field: No

Default Value: N

Data Name: ICF.POSICF.TRANS-ALLOWED

ICF Screen 10

The ICF screen 10 contains the timer limits that are used for both BASE24-atm and BASE24-pos transactions. The fields on ICF Screen 10 that are used by PRM are described below.

Timer Limits

The following field sets the time limits for BASE24-atm and BASE24-pos transactions.

OUTBOUND — The time limit in seconds, the PRM Interface Process waits for a response from the interchange for a BASE24-atm, BASE24-pos transaction and store and forward transactions. Valid values are 0 through 9999.

Field Length: 1–4 numeric characters

Required Field: Yes

Default Value: 15

Data Name: ICF.POSICF.TIMER-LMTS.OUTBOUND

ICF Screen 12

ICF screen 12 contains parameters specific to the ACI Proactive Risk Manager solutions. These parameters control the operating mode of the PRM Interface Process. For more information about the different operating modes, reference the Operating Modes topic at the beginning of this section. The fields on ICF Screen 12 are described below.

PIP Processing Parameters

The following fields contain configuration information for the PRM Interface Process (PIP).

PRM PRODUCT — The product indicator identifying the product the specific PRM Interface Process is used for. Valid values are:

- 1 = Credit
- 2 = Debit
- 3 = Merchant
- 4 = Enterprise Risk
- 5 = CRD & MERC
- 6 = UAN & MERC

Field Length: 1 alphanumeric character

Required Field: Yes

Default Value: 1

Data Name: ICF-SEIP.PROD.PRM-PROD

Process/Station

The following fields set the timer limits for the BASE24-atm and BASE24-pos transactions. They include the process and station configuration information.

SCORING ENGINE — The name of the PRM Scoring Engine process to which the ACI Proactive Risk Manager transactions are sent by the PRM Interface Process. This field can also be the name of a queue location associated with a group of PRM Scoring Engine processes.

Field Length: 16 alphanumeric characters

Required Field: Yes (if the ACI Proactive Risk Manager product is not running in File Based mode)

Default Value: Spaces

Data Name: ICF-SEIP.COMM.PSE-SEND

REAL TIME REQ TYPE — A value indicating the type of real-time request to forward to the PRM Scoring Engine and or the real-time rules Analytic Gateway process. This field is only used when the Real-time Token field REAL-TIME-REQ-TYPE is blank. If the token field is blank, it indicates that the PRM Interface Process will set the token field using this ICF field value. Valid values are:

Blank = No real-time processing

- 0 = Real-time score only

1 = Real-time rules only

2 = Both real-time score and real-time rules

Field Length: 1 alphanumeric character Required Field:

Default Value: 0

Data Name: ICF-SEIP.RTR.REAL-TIME-REQ-TYPE

AUTHPROC — The name of the Authproc station to which ACI Proactive Risk Manager transactions are to be sent by the PRM Interface Process if the system is running in L mode.

Note: This field value is blank if the system is running in Triangle mode.

Field Length: 16 alphanumeric characters

Required Field: Yes (if in L mode)

Default Value: Spaces

Data Name: ICF-SEIP.COMM.AP-SEND

REAL TIME RETURN — A one-byte field that indicates whether the PRM Interface Process is to respond back to the Authorization process with a 0210 response message or with a 0200 request. This field is only used when the PRM Real-time Token field PIP-RESPONSE- REQUEST is blank. A blank value in this token field indicates that the PRM Interface will set the token field using the ICF field value. Valid values are:

0 = PIP will return the message as an 0200 request

1 = PIP will return the message as an 0210 response

Field Length: 1 alphanumeric character

Required Field: Yes (if not in File Based Mode)

Default Value: 0

Data Name: ICF-SEIP.RTR.RT-RETURN

FILE BASED — A code indicating whether the Analytic Gateway process is operating in File Based mode. Valid values are:

Y = Yes, Analytic Gateway is operating in File Based mode. The PRM Interface Process writes to the Scoring Input File on every transaction

N = No, Analytic Gateway is not operating in File Based mode. It is operating in Message based mode.

Field Length: 1 alphanumeric character

Required Field: Yes

Default Value: N

Data Name: ICF-SEIP.PROC-MODE.FILE-MODE

CUTOVER — The number of minutes that pass before cutting over if the FILE BASED field value is Y. This field indicates the length of time before the SIF cuts over to a new file. The field value is specified in minutes.

Field Length: 4 numeric characters

Required Field: Yes

Default Value: 0

Data Name: ICF-SEIP.PROC-MODE.SIF-CUTOVER

REAL TIME TIMER — When the incoming PRM Interface Process transaction is specified as being a real-time transaction, this field is the timer for acknowledgement back from the PRM Scoring Engine. The field value is specified in seconds format.

Field Length: 4 numeric characters

Required Field: Yes

Default Value: 0

Data Name: ICF-SEIP.RTS.RT-TIMER

SCORING ENGINE PRESENT — The PRM Scoring Engine destination. Valid values are:

Y = Yes, the PRM Scoring Engine is present; the message is sent to the scoring engine with a format that does not include the score and reason code.

N = No PRM Scoring Engine present; the message is sent to the Analytic Gateway process with a format that includes a null score and reason codes.

Note: If the PRM Scoring Engine resides on a Windows Platform, this field identifies the outbound station of the PRM Scoring Engine (e.g., S1A^TCP0). If the PRM Scoring Engine resides on the HP NonStop platform, this field reflects the PRM Scoring Engine process name e.g., P1A^PSE1). When the PRM Scoring Engine resides on a HP NonStop platform, the PRM Scoring Engine's Execution Control File parameter XPNET_DEST should be set to the Analytic Gateway's outbound station name (e.g., S1A^TCP0).

Field Length: 1 alphanumeric character

Required Field: Yes

Default Value: N

Data Name: ICF-SEIP.PROC-MODE.PRESENT-MODE

ATM APPROVAL — The threshold for ATM transactions during real-time scoring processing. If a transaction score is greater than or equal to this value, the transaction is declined.

Field Length: 3 numeric characters

Required Field: Yes

Default Value: 0

Data Name: ICF-SEIP.RTS.ATM-APPROVE

PRM LOGGING ENABLED — A code indicating whether transactions are being logged to the ACI Proactive Risk Manager Log File. Valid values are:

Y = Yes, the PRM Interface Process logs each incoming transaction to the PRM log file.

N = No, the PRM Interface Process does not log transactions to the PRM log file.

Field Length: 1 numeric character

Required Field: Yes

Default Value: N

Data Name: ICF-SEIP.PROC-MODE.LOGGING

POS APPROVAL — A code indicating the threshold for BASE24-pos transactions during real- time scoring processing. If a transaction score is less than or equal to the first value, the transaction is approved.

Field Length: 3 numeric characters

Required Field: Yes

Default Value: 0

Data Name: ICF-SEIP.RTS.POS-APPROVE

POS DENIAL — A code indicating the threshold for BASE24-pos transactions during real- time scoring processing. If a transaction score is greater than or equal to the first value, the transaction is declined.

Field Length: 3 numeric characters

Required Field: Yes

Default Value: 0

Data Name: ICF-SEIP.RTS.POS-DENY

NRT TIMER — The name of the timer that is set when sending an external message to the PRM Near Real Time process.

Field Length: 3 numeric characters

Required Field: Required for NRT

Default Value: 30 (seconds)

Data Name: ICF-SEIP.NRT.NRT-TIMER

PERFORMANCE EMS LOG — An indicator to send performance messages to the EMS log according to the performance timer on ICF Screen 3. Valid values are:

Y = Yes, send performance messages to the EMS log.

N = No, do not send performance messages to the EMS log.

Field Length: 1 numeric character

Required Field: Yes

Data Name: ICF-SEIP.PERF.LOG-ON

TRANSACTION ACKNOWLEDGMENTS/SCORING ENGINE — Indicates whether the PRM Interface Process sends network management messages to the PRM Scoring Engine or implements the Store and Forward capability if the PRM Scoring Engine is not available. Valid values are:

Y = Yes, the PRM Interface Process sends network management messages to the PRM Scoring Engine implements Store and Forward processing.

N = No, the PRM Interface Process does not set timers when sending transactions to the PRM Scoring Engine. Store and Forward processing is not used for timed out transactions. An initial 0800 logon message is sent.

Field Length: 1 alphanumeric character

Required Field: Yes

Default Value: Y

Data Name: ICF-SEIP.PROC-MODE.PSE-ACK

TRANSACTION ACKNOWLEDGMENTS/AUTHPROC — A code indicating whether the PRM Interface Process sends network management messages to the Analytic Gateway process or implements the Store and Forward capability if the Analytic Gateway process is not available. Valid values are:

Y = Yes, the PRM Interface Process sends network management messages to the Analytic Gateway process; implements Store and Forward processing.

N = No, the PRM Interface Process does not set timers when sending transactions to the Analytic Gateway process. Store and Forward processing is not used for timed out transactions. An initial 0800 logon message is sent.

Field Length: 1 alphanumeric character

Required Field: Yes

Default Value: N

Data Name: ICF-SEIP.PROC-MODE.AP-ACK

MAXIMUM OUTSTANDING TRANS/SCORING ENGINE — The maximum number of outstanding transactions that can be sent to the scoring engine without an acknowledgement before the PRM Interface Process starts Store and Forward transaction processing. Valid ranges are 0-100.

Field Length: 3 Numeric character

Required Field: Yes

Default Value: 50

Data Name: ICF-SEIP.PROC-MODE.PSE-OUT

MAXIMUM OUTSTANDING TRANS/AUTHPROC — The maximum number of outstanding transactions that can be sent to the Authproc process without an acknowledgement before the PRM Interface Process begins Store and Forwarding transaction processing. Valid ranges are: 0-100.

Field Length: 3 numeric character

Required Field: Yes

Default Value: 50

Data Name: ICF-SEIP.PROC-MODE.AP-OUT

MAXIMUM SAF RETRIES/SCORING ENGINE — The maximum number of times a single transaction can be sent to the scoring engine before it is logged to the Dump Store and Forward File (DSAF) for further investigation.

Field Length: 3 numeric character

Required Field: Yes

Default Value: 3

Data Name: ICF-SEIP.PROC-MODE.PSE-SAF

MAXIMUM SAF RETRIES/AUTHPROC — The maximum number of times a single transaction can be sent to the Authproc process before it is logged to the Dump Store and Forward File (DSAF) for further investigation.

Field Length: 3 numeric character

Required Field: Yes

Default Value: 3

Data Name: ICF-SEIP.PROC-MODE.AP-SAF

Merchant Master File (MMF)

The Merchant Master File contains merchant information and is used solely by the ACI Proactive Risk Manager for Merchant Acquiring Fraud solution. This file is read by the PRM Interface Process and is created at installation.

Data from this file and the POS Standard Internal Message (PSTM) is used to create records that are passed to the scoring engine. This file is updated using the MMF Pathway user screen.

MMF Screen 1

The fields on MMF Screen 1 are described below.

FIID — The FIID of the financial institution that issued the card. This value must be unique within the logical network.

Field Length: 4 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: MMF.PRIKEY.FIID

RETAILER ID — The retailer or merchant that owns or operates the terminal where the transaction originated. It equates to a single physical location or Internet store front. This field is populated with the terminal ID for ATM transactions and can be used to monitor ATM transactions

Note: For merchants with multiple store locations, each store location must have a unique retailer ID.

Field Length: 4 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: MMF.PRIKEY.RETL-ID

CLASS — An identifier to group or classify retailers. For example, this can be a concatenation of the corporate, region, principal, associate, or chain IDs.

Field Length: 15 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.RETL-CLASS

FILTER — The portfolio or filter identification in the Analysis and Review System.

Field Length: 15 alphanumeric characters

Required Field: Yes

Default Value: Yes

Data Name: MMF.USER.FILTER-FLD

DBA NAME — The merchant's *Doing Business As* name.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.RETL-DBA-NAM

BUSINESS NAME — The merchant's business name.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.RETL-DBA-NAM

STORE NUMBER — The store number or identifier.

Field Length: 9 alphanumeric characters

Required Field: No

Default Value: None

Data Name: MMF.USER.STORE-NUM

SIC CODE — The Standard Industrial Classification (SIC) code indicating the retailer's line of business. Valid values are industry standards.

Field Length: 4 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.SIC-CODE

E-COM IND — A code indicating whether the merchant can accept e-commerce transactions.

Field Length: 2 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.E-COM-IND

ADDRESS1 — The first line of the retailer's street address.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.RETL-ADDR-1

ADDRESS2 — The second line of the retailer's street address.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.RETL-ADDR-2

CITY — The city in which the retailer is located.

Field Length: 13 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.RETL-CITY

STATE — The alphabetic representation of the retailer's state of residence. This field also can contain the province or region where the retailer resides.

Field Length: 13 alphanumeric characters

Required Field: No

Default Value: N/A

Data Name: MMF.USER.RETL-ST

CNTRY — The alphabetic representation of the retailer's country of residence. Refer to the ISO 3166:1988 standard, *Codes for the Representation of Names of Countries* for valid values.

Field Length: 13 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.RETL-CNTRY

POSTAL CODE — The postal or ZIP code for the retailer's residence.

Field Length: 16 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.RETL-POSTAL-CDE

CONTACT NAME — The name of the merchant contact.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.CNTCT-NAM

EMAIL ADDR — The merchant contact e-mail address.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.CNTCT-EMAIL-ADDR

PHONE1 — The merchant contact's telephone number.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.CNTCT-PHONE-1

PHONE2 — The merchant contact's alternate telephone number (e.g., facsimile number).

Field Length: 20 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.CNTCT-PHONE-2

OWNER NAME — The name of the owner of the business.

Field Length: 40 alphanumeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.OWN-NAM

OWNER TYP — The ownership type. Some examples are:

C = Corporation

S = Sole proprietorship

P = Partnership

Field Length: 1 alphanumeric character

Required Field: No

Default Value: No default value

Data Name: MMF.USER.OWN-TYP

OWNER CHANGE DATE — The merchant ownership changed.

Field Length: 8 numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: MMF.USER.OWN-CHNG-DAT

GOVT ID — The merchant's tax or government ID.

Field Length: 20 numeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.OWN-GOVT-ID

MMF Screen 2

The fields on MMF Screen 2 are described below.

STATUS — A code indicating the merchant status. Some examples are:

O = Open

C = Closed

Field Length: 1 alphanumeric character

Required Field: No

Default Value: No default value

Data Name: MMF.USER.STAT

ACTIVITY STATUS — A code indicating the merchant activity status. Some examples are:

0 = Inactive

1 = Active

Field Length: 1 alphanumeric character

Required Field: No

Default Value: No default value

Data Name: MMF.USER.ACTVTY-STAT

OPEN DATE — The date the account was opened.

Field Length: 8 numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: MMF.USER.OPN-DAT

FIRST ACTIVE DATE — The date the account was first operated.

Field Length: 8 numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: MMF.USER.FIRST-ACTV-DAT

LAST ACTIVE DATE — The date the account was last traded.

Field Length: 8 numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: MMF.USER.LAST-ACTV-DAT

LAST ACTIVE AMT — The amount of the last deposit or refund to the merchant account.

Field Length: 14 numeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.LAST-ACTV-AMT

CLOSE DATE — The date the account was closed.

Field Length: 8 numeric characters

Required Field: No

Default Value: 00/00/0000

Data Name: MMF.USER.CLOS-DAT

CLOSE REASON CODE — The reason code indicating why the account was closed.

Field Length: 2 numeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.CLOS-RSN-CDE

SEASONAL CODE — The seasonal billing code. Some examples are:

D = Seasonal, do not bill

B = Seasonal, bill

N = Not seasonal

Field Length: 1 alphanumeric character

Required Field: No

Default Value: No default value

Data Name: MMF.USER.SEASNL-CDE

SETL ACCT DETAIL1 — The bank and branch number of the settlement account.

Field Length: 25 numeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.SETL-ACCT-DETL-1

SETL ACCT DETAIL2 — The bank and branch number of the settlement account.

Field Length: 25 numeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.SETL-ACCT-DETL-2

EXPECT ANNUAL VOL — The expected annual volume for the retailer.

Field Length: 14 numeric characters

Required Field: No

Default Value: 0

Data Name: MMF.USER.EXPECT-YY-VOL

EXPECT MNTLY VOL — The expected monthly volume for the retailer.

Field Length: 14 numeric characters

Required Field: No

Default Value: 0

Data Name: MMF.USER.EXPECT-MM-VOL

FLOOR LIMIT — The retailer's floor limit.

Field Length: 10 numeric characters

Required Field: No

Default Value: 0

Data Name: MMF.USER.FLR-LMT

BUSINESS HOURS START — The normal business hours start time.

Field Length: 4 numeric characters

Required Field: No

Default Value: 0000

Data Name: MMF.NORM.BUS.HH.STRT

BUSINESS HOURS END — The normal business hours end time.

Field Length: 4 numeric characters

Required Field: No

Default Value: 0000

Data Name: MMF.NORM.BUS.HH.END

INTERNAL INDICATOR — The internal identifier.

Field Length: 10 numeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.FI-IND

CUST NUM1 — The internal defined customer number, electronic banking number, or checking account number.

Field Length: 20 numeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.CUST-NUM-1

CUST NUM2 — The internal defined customer number, electronic banking number, or checking account number.

Field Length: 20 numeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.CUST-NUM-2

USERDEFINED1 — This field is user defined.

Field Length: 20 numeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.USR-DEF-1

USERDEFINED2 — This field is user defined.

Field Length: 20 numeric characters

Required Field: No

Default Value: No default value

Data Name: MMF.USER.USR-DEF-2

MMF Refresh and Extract Processing

The BASE24 Refresh process allows full-file and partial file refresh of the MMF using the Refresh screens or a network control facility.

The MMF can be extracted using the BASE24 OMF Extract process.

For additional information regarding the Refresh and Extract screens, refer to the *BASE24 Refresh and Extract Operators Manual*.

ACI Proactive Risk Manager Routing Table (PTBL)

The ACI Proactive Risk Manager Routing Table (PTBL) contains information used by the ACI Proactive Risk Manager modules within the BASE24-atm and BASE24-pos Authorization processes to determine whether a transaction is scored and the destination to which it is sent to get scored. The PTBL is used only for near real time scoring transaction processing. There are three types of records in the PTBL:

- Routing by card prefix
- Routing by FIID
- Routing by merchant ID

During initialization, the PTBL records are read and stored in a table in extended memory. After each transaction is authorized and the transaction response is returned to the acquirer, the BASE24-atm Authorization process or the BASE24-pos Router Authorization module checks the PTBL entries in memory. The card prefix is read, followed by the FIID and the merchant ID. If the

cardholder FIID or BIN in the transaction matches an entry in the PTBL, a copy of the transaction is sent to the PRM Interface Process specified in the PTBL entry.

PTBL Screen 1

The fields on PTBL Screen 1 are described below.

RECORD TYPE — The record type indicator for this PTBL record. The BASE24-atm Authorization or BASE24-pos Router Authorization process determines if a transaction should be routed to the ACI Proactive Risk Manager solution by reading the entries in this table.

The two ways to determine routing for the Credit and or Debit solutions are by the card prefix or the FIID. The Merchant solution determines routing by the Merchant ID. Valid values are:

- 01 = Card prefix routing parameters
- 02 = Financial institution (FIID) routing parameters
- 03 = Merchant (FIID, GRP, and REGN) routing parameters

Field Length: 2 numeric characters

Required Field: Yes

Default Value: 00

Data Name: PTBL.PRIKEY.REC-TYP

PTBL Screen 2

The fields on PTBL Screen 2 are described below.

PRM Card Prefix Routing Table

The following fields define the prefix, pan length, and destination for this card.

PREFIX — The card prefix to which this record information applies. The value in this field is used to identify the scoring criteria for the cardholder whose card prefix numbers match the value contained in this field.

Field Length: 1–11 alphanumeric characters

Required Field: Yes

Default Value: 0

Data Name: PTBL.PRIKEY.CPF-KEY.PREFIX

PAN LENGTH — The length of the entire PAN (i.e., the prefix length plus the length of the cardholder's account number). The value in this field is used by the Authorization process as an additional check to ensure a card belongs to a valid prefix family.

Note: Valid values must be greater than 4 and less than 20.

Field Length: 2 alphanumeric characters

Required Field: Yes

Default Value: 00

Data Name: PTBL.PRIKEY.CPF-KEY.ALTKEY.PAN-LENGTH

PRODUCT SCORING FLAGS/ATM — A code indicating whether this card prefix is used for BASE24-atm authorization routing. This value is loaded into an internal routing table during the Authorization process initialization. Valid values are:

Y = Yes, the card prefix for BASE24-atm transactions is scored.

N = No, the card prefix for BASE24-atm transactions are not scored.

Field Length: 1 alphanumeric character

Required Field: Yes

Default Value: Y

Data Name: PTBL.PRM-RTBL.CARD-PREFIX.SCORE-ATM

PRODUCT SCORING FLAGS/POS — A code indicating whether this card prefix is used for BASE24-pos authorization routing. This value is loaded into an internal routing table during the Authorization module initialization. Valid values are:

Y = Yes, the card prefix for BASE24-pos transactions is scored.

N = No, the card prefix for BASE24-pos transactions are not be scored.

Field Length: 1 alphanumeric character

Required Field: Yes

Default Value: Y

Data Name: PTBL.PRM-RTBL.CARD-PREFIX.SCORE-POS

SCORING DESTINATION — The scoring engine process destination that the BASE24-atm or BASE24-pos Authorization process sends the STM/PSTM to.

Note: This field can contain a queue process (XPNET release 2.1) or a service (XPNET release 3.0 or beyond).

Field Length: 16 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: PTBL.PRM-RTBL.CARD-PREFIX.SCORING-DEST

PTBL Screen 3

The fields on PTBL Screen 3 are described below.

PRM FIID Routing Table

The following fields contain the product scoring flags and the scoring destination for this FIID.

FIID — The financial institution ID (FIID) that will route the transaction to the ACI Proactive Risk Manager system. This value is loaded into an internal routing table during the Authorization process initialization.

Field Length: 1–4 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: PTBL.PRIKEY-FIID-KEY.FIID

PRODUCT SCORING FLAGS/ATM — A code indicating whether this FIID prefix is used for BASE24-atm Authorization routing. This value is loaded into an internal routing table during the Authorization process initialization. Valid values are:

Y = Yes, the FIID for a BASE24-atm transactions is scored.

N = No, the FIID for a BASE24-atm transactions is not scored.

Field Length: 1 alphanumeric character

Required Field: Yes

Default Value: Y

Data Name: PTBL.PRM_RTBL.FIID.SCORE-ATM

PRODUCT SCORING FLAGS/POS — A code indicating whether this FIID is used for BASE24-pos Authorization routing. This value is loaded into an internal routing table during the Authorization module initialization. Valid values are:

Y = Yes, the FIID for BASE24-pos transactions are scored

N = No, the FIID for BASE24-pos transactions will not be scored

Field Length: 1 alphanumeric character

Required Field: Yes

Default Value: Y

Data Name: PTBL.PRM-RTBL.FIID.SCORE-POS

SCORING DESTINATION — The scoring engine process destination that the BASE24-atm or BASE24-pos Authorization process sends the STM/PSTM to.

Note: This field can contain a queue process (XPNET release 2.1) or a service (XPNET release 3.0 or beyond).

Field Length: 16 alphanumeric character

Required Field: Yes

Default Value:

Data Name: PTBL.PRM-RTBL.FIID.SCORING-DEST

PTBL Screen 4

The fields on PTBL Screen 4 are described below.

PRM Merchant Routing Table

MERCHANT FIID — The financial institution ID (FIID) that routes transactions to the ACI Proactive Risk Manager system.

Field Length: 4 alphanumeric characters

Required Field: Yes

Default Value: No default value

Data Name: PTBL.PRIKEY-MERCH-KEY.FIID

GROUP — The merchant group number that routes transactions to the ACI Proactive Risk Manager system.

Field Length: 1 alphanumeric character

Required Field: Yes

Default Value: No default value

Data Name: PTBL.PRIKEY.MERCH-KEY-GRP

REGION — The merchant region number that routes transactions to the ACI Proactive Risk Manager system.

Field Length: 1 alphanumeric character

Required Field: Yes

Default Value: No default value

Data Name: PTBL.PRIKEY.MERCH-KEY-REGN

SCORING DESTINATION — The scoring engine process destination that the BASE24-atm or BASE24-pos authorization process sends the STM or PSTM to.

Note: This field can contain a queue process (XPNET release 2.1) or a service (XPNET release 3.0 or later).

Field Length: 16 alphanumeric character

Required Field: Yes

Default Value: No default value

Data Name: PTBL.PRM-RTBL.MERCHANT.SCORING-DEST

ONUS DESTINATION - The PRM Interface Process (PIP) destination. The BASE24 PRM POS Router Auth process uses this field to route the on-us PRM merchant transactions to the PIP.

Field Length: 16 alphanumeric characters

Required Field: Required when the RECORD TYPE field on PTBL Screen 1 is set to 03 (MERCHANT ROUTING PARAMETERS)

Default Value: No default value

Data Name: PTBL.PRM-RTBL.MERCHANT.ONUS-DEST

Proactive Risk Manager Startup and Control

The following pages cover these startup and control topics:

- Network control commands (NCPCOM)
- Network control supervisor (NCS) screen
- Establish and start the TCP/IP processes
- Starting the ACI Proactive Risk Manager system

Network and Control Commands

This section provides a list of the BASE24 commands that can be received by the PRM Interface Process. Many of these commands can be entered by an operator using a network control facility and serve as a tool that operators can use to perform network management functions such as changing processing parameters, warmbooting processes, and monitoring processes.

Network and control commands can be issued from a network control facility. The format of the command being issued varies depending on the network control interface in use.

For detailed descriptions and the syntax of all network control commands, refer to the *BASE24 Text Command Reference Manual*.

Network Control Point Communications (NCPCOM) Utility

The Network Control Point Communications (NCPCOM) utility provides an interactive prompt for entering network control commands. The NCPCOM utility is started by issuing a RUN command from the TACL prompt. The general syntax is shown below:

Syntax

DELIVER PROCESS process name, "Message Format"

NCPCOM Commands

The commands described below can be sent to the PRM Interface Process. Each description includes the command format and a description of what happens to the PRM Interface Process when the message is received.

DEBUG — This command places the interface process in the DEBUG facility. This command should only be used in a test environment due to the negative performance impacts.

DUMP — This command initiates a programmatic dump of the interface process. This command should only be used in a test environment or upon the request of ACI Worldwide Inc. personnel.

LOGOFF — This command initiates a logoff sequence to the scoring engine process or to the Analytic Gateway process.

Example:

```
LOGOFFSE
LOGOFFAP
```

LOGON — This command initiates a logon sequence of the scoring engine process or to the Analytic Gateway process.

Example:

```
LOGONSE
LOGONAP
```

PERFORMANCE — This command requests a display of the performance statistics kept in memory by the PIP process. These performance statistics are written to the log using a series of log messages that are generated by the process. The following is an example of a performance display:

```
No. of PSE Transaction Requests:  $$$$$$
No. of PSE Transactions Processed: $$$$$$
No. of PSE Late Responses:         $$$$$$
No. of PSE Records in DSAF File:   $$$$$$
No. of PSE Transactions Timed out: $$$$$$
No. of A/R Transaction Requests:   $$$$$$
No. of A/R Transactions Processed: $$$$$$
No. of A/R Late Responses:         $$$$$$
No. of A/R Records in DSAF File:   $$$$$$
No. of A/R Transactions Timed out: $$$$$$
No. of R/T Transaction Requests:   $$$$$$
No. of R/T Transaction Processed:  $$$$$$
No. of R/T Late Responses:         $$$$$$
No. of R/T Transactions Timed out: $$$$$$
```

STATUS — This command requests the current status of the PRM Interface process. The status information is written to the log using a series of log messages generated by the process. The following is an example of the status information:

```
<#> requests pending, maximum of <#> for <PSE/AP>
<Scoring Engine/Authproc> is LOGGED <OFF/ON>
Positive ACK required from <PSE/AR>: <Y/N>
File: <SAF filename>, <#> Records, <#> Percent Full
Records queued for <Scoring Engine/Authproc>: <#>
File: <DSAF filename>, <#> Records, <#> Percent Full
```

TRACE OFF — This command stops the trace function within the interface process. The trace function generates event messages at periodic intervals while the trace function is enabled. The event messages display the name of the procedure from which it was written or other helpful processing information. The trace log messages should be requested only in a test environment due to negative performance impacts.

TRACE ON — This command starts a trace function within the interface process and sends log messages to the current logging device. The event messages display the name of the procedure from which it was written or other helpful processing information. The trace log messages should be requested only in a test environment due to negative performance impacts.

WARMBOOT — In this command, a 9501 command is issued and a warmboot is performed to the PRM Interface Process. A message is logged to indicate whether the warmboot completes or aborts.

Network Control Supervisor (NCS) Screen

The NCS screen provides a formatted interface for entering network control commands. Commands are entered by filling in the fields on the screen and pressing the F1 function key. Refer to the NET24-XPNET Network Control Operations Guide for detailed information on the NCS Screen.

Establish and Start the TCP/IP Processes

A TCP/IP server and client process is needed for TCP/IP stations.

The HP NonStop outbound line or station is considered the server and always receives to the port number defined in the TCP/IP server startup obey file.

The HP NonStop inbound line or station is considered the client and (using XPNET) establishes the connection.

The above inbound and outbound configurations are used for online communications to the scoring engine and the Analytic Gateway process.

HP NonStop Scoring Engine Environment

This section contains configuration information for an HP NonStop scoring engine environment. The HP NonStop XPNET outbound server station connects with the scoring engine's receive client port. The Analytic Gateway process' receive port connects with the scoring engine's send port.

In the [th_readtcp] section of the Analytic Gateway process prismsrv.ini file, the receive parameters define the client side of the IP connection. The send parameters define the server side of the IP connection. The Analytic Gateway client (receive) connects with the HP NonStop server (outbound), and the HP NonStop client (inbound) connects with the Analytic Gateway server (send).

The sendhost parameter is the IP address of the Analytic Gateway server. The receivehost parameter is the IP address of the HP NonStop. The sendport parameter must match the RADDR parameter of the outbound station. The sendhost parameter is the IP address of the server. The receiveport parameter must match the port parameter specified to the gotcpsrv macro as shown in the example below.

PRISMSRV.INI File Example

For the example in this document, the prismsrv.ini file would contain the following parameters:

```
Server sendhost=172.61.21.68 ; The Authproc IP Address.
```

```
Server sendport=7999
Client receivehost=172.x.x.x ; The IP Address of PSE.
Client receiveport=8001
```

ACI Worldwide Inc. provides both a TACL macro and an obey file to start the TCP/IP server processes. The name of the obey file is PInnPIP.STRTTCP, where nn is the release number.

STRTTCP Obey File Example

```
Run gotcpcli $sip1 0
Run gotcpsrv $sop1 1 8001
Where: gotcpcli = TCP/IP client macro
      $sip1 = input line port name (also appears in the XPNET line declaration)
          0 = CPU number where process is to run gotcpsrv = TCP/IP server
              macro
      $sop1 = output line port name (also appears in the XPNET line declaration)
          1 = CPU number where process is to run
      8001 = agreed upon port number (the listener port number)
```

Note: The gotcpcli macro is used for the input line while the gotcpsrv macro is used for the output line. The gotcpsrv TACL macro is located on the PInnPIP subvolume.

GOTCPSRC TACL Macro Example

For the example in this document, the gotcpsrc TACL macro would contain the following information:

```
?TACL ROUTINE
#FRAME
#PUSH #INFORMAT
#SET #INFORMAT TACL
#PUSH ppd cpu object ip_port
[#IF [#ARGUMENT/VALUE ppd/ PROCESSNAME/SYNTAX/]]
[#IF [#PROCESSEXISTS [ppd]]
|THEN|
    #OUTPUT ALREADY STARTED: [ppd]
    #UNFRAME
    #RETURN
]
[#IF [#ARGUMENT/VALUE cpu/ NUMBER ]]
[#IF NOT [#EMPTY [cpu]]
|THEN|
    #SET cpu , cpu [cpu]
]
[#IF [#ARGUMENT/VALUE ip_port/ NUMBER END]]
[#IF [#EMPTY [ip_port]]
|THEN|
    #SET ip_port 2001
]
clear param prilog
clear param altlog
clear param maxbuflen
```

```

clear param inaddr
clear param timeout
clear param service
clear param tcpip^host^file
clear param tcpip^resolver^name
clear param tcpip^process^name

==== Set the name of the object file
#SET object $TEDDY.XPNET.tcpsrv

==== Assign the primary and alternate log files
==== The default is prilog $0, no alternate log
    assign prilog, $0
== assign altlog, $0

==== Specify the length of the I/O buffers. The
==== default is:
param maxbuflen 2000
==== Specify the port number on which the server
==== listens. No default. For port numbers less
==== than 1024 the user must be a member of the
==== super group.
param service [ip_port]

==== Specify the Internet Address to which the
==== server will bind. The default is INADDR-ANY.
== param inaddr 127.0.0.1

==== Specify the number of seconds to wait before
==== clearing a caller when no opener is available
==== to service them. The default is to allow
==== callers to queue at the Tandem TCP/IP process.
== param timeout 1

==== Assign the name of the file to be used to
==== resolve host aliases when a name server is
==== unavailable. No default.
param tcpip^host^file $SYSTEM.ZTCPIP.HOSTS

==== Specify the resolver name used by GETHOSTBYNAME and GETHOSTBYADDR
==== The default is:
== param tcpip^resolver^name $SYSTEM.ZTCPIP.RESCONF

==== Specify the name of the tcpip process used by the
==== sockets library. The default is:
== param tcpip^process^name $ZTC0

```

```

==== Run the process. Priority should be between
==== the Tandem TCP/IP process and the nucleus.
run [object] /name [ppd], nowait, out $0, pri 170 [cpu]/
#OUTPUT STARTED: [ppd]

```

```
#UNFRAME
```

The GOTCPCLI TACL macro is located on the PInnPIP subvolume and appears as follows:

```

?TACL ROUTINE
#FRAME

#PUSH #INFORMAT
#SET #INFORMAT TACL

#PUSH ppd cpu object

[#IF [#ARGUMENT/VALUE ppd/ PROCESSNAME/SYNTAX/]] [#IF [#PROCESSEXISTS [ppd]]
|THEN|
#OUTPUT ALREADY STARTED: [ppd]
#UNFRAME
#RETURN
]

[#IF [#ARGUMENT/VALUE cpu/ NUMBER END]]
[#IF NOT [#EMPTY [cpu]]
|THEN|
    #SET cpu , cpu [cpu]
]

clear param prilog
clear param altlog
clear param maxbuflen
clear param tcpip^host^file
clear param tcpip^resolver^name
clear param tcpip^process^name

==== Set the name of the object file
== #SET object $data14.n20tcpc.tcpc00
#SET object $sysaci.xpnet.tcpcli

==== Assign the primary and alternate log files
==== The default is prilog $0, no alternate log
== assign prilog, $0
== assign altlog, $0

==== Specify the length of the I/O buffers. The

```

```

==== default is:
== param maxbuflen 4095

==== Assign the name of the file to be used to
==== resolve host aliases when a name server is
==== unavailable. No default.
param tcpip^host^file $SYSTEM.ZTCPIP.HOSTS

==== Specify the resolver name used by GETHOSTBYNAME and GETHOSTBYADDR
==== The default is:
== param tcpip^resolver^name $SYSTEM.ZTCPIP.RESCONF

==== Specify the name of the tcpip process used by the
==== sockets library. The default is:
== param tcpip^process^name $ZTC0

==== Run the process. Priority should be between
==== the Tandem TCP/IP process and the nucleus.
run [object] /name [ppd], nowait, out $0, pri 170 [cpu]/
#OUTPUT STARTED: [ppd]

#UNFRAME

```

TCP/IP Obey File Example

A stop TCP/IP obey also can be created to stop these TCP/IP processes.

```

STOP $TCPI
STOP $TCPO

```

Starting the ACI Proactive Risk Manager System

Once all of the configurations have been made, perform the following steps to start the ACI Proactive Risk Manager system:

1. Start the XPNET node (if not already started).
2. Start the server's Analytic Gateway process.
3. Start the XPNET stations. The stations' states should be STARTED. Verify that the Analytic Gateway process is started and connected by checking the Analytic Gateway's PLOG File.
4. Start the scoring engine process. Check the process hometerm, the EMS log, and the log_err and log_info (ECF file assigns) for errors.
5. Start the PRM Interface Process. An Event Management Service (EMS) log message indicating that the SCORING ENGINE is up should appear in EMS log.
6. Issue a STATUS command to the PRM Interface Process.