














Bug ID	Title	Steps to Reproduce	Expected Result	Actual Result	Environment	Screenshot/Video	Severity	Priority
BUG-001	Template card is not fully clickable despite showing a pointer cursor	1. Open the Home page of the Website Templates section. 2. Scroll to the template card section. 3. Hover over different areas of a template card and observe the pointer cursor. 4. Click on the card body (excluding the Preview and Details buttons). 5. Click on the bottom area of the template image.	The entire template card should behave consistently. If the pointer cursor is displayed, clicking anywhere on the card should open the template details or preview.	Clicking most areas of the template card has no effect, even though the pointer cursor is displayed. Only clicking the bottom portion of the template image opens the template preview, creating inconsistent and confusing behavior.	Windows 10 Google Chrome (Latest) Desktop		Minor	Medium
BUG-002	Inconsistent template card click behavior between Home page and Details page	1. Open the Website Templates Home page. 2. Scroll to the template cards. 3. Click the bottom area of any template image. 4. Observe that the template Preview page opens. 5. Return and open the Details page of any template. 6. Scroll to the "Related/Other Templates" section at the bottom. 7. Click the bottom area of another template image.	Template cards should provide consistent behavior across the website. Clicking the same clickable area should perform the same action (either always open the Preview or always open the Details page).	The same interaction produces different results depending on the page. On the Home page, clicking the bottom area of the template image opens the Preview page, while on the Details page, clicking the same area opens the Details page of the selected template.	Windows 10 Google Chrome (Latest) Desktop		Minor	Medium

Bug ID	Title	Steps to Reproduce	Expected Result	Actual Result	Environment	Screenshot/Video	Severity	Priority
BUG-003	Current template appears again in the "Other Templates" suggestion section	1. Open any template's Details page. 2. Scroll down to the Other Templates (or related templates) section. 3. Observe the first template displayed in the suggestion list.	The "Other Templates" section should display different, relevant template recommendations and exclude the currently viewed template.	The currently opened template is displayed again as the first item in the "Other Templates" section instead of showing a different recommendation.	Windows 10 Google Chrome (Latest) Desktop		Minor	Low
BUG-004	Duplicate templates displayed when filtering by "Spectra All"	1. Open the Website Templates page. 2. Apply the Spectra All filter. 3. Browse the filtered template list. 4. Observe the displayed templates.	Each template should appear only once in the filtered results.	Several templates are displayed multiple times after applying the Spectra All filter, resulting in duplicate entries and a cluttered browsing experience.	Windows 10 Google Chrome (Latest) Desktop		Minor	Medium
BUG-005	Template card heights become inconsistent when browser is zoomed out	1. Open the Website Templates page. 2. Reduce the browser zoom level (e.g., 30% or 25%). 3. Scroll through the template cards. 4. Compare the height and layout of the cards.	All template cards should maintain a consistent size and alignment regardless of the browser zoom level.	When the browser is zoomed out, some template cards become noticeably taller than others, resulting in an inconsistent and unbalanced grid layout.	Windows 10 Google Chrome (Latest) Desktop		Minor	Low
BUG-006	No option available to reset or clear applied filters	1. Open the Website Templates page. 2. Apply one or more filters 3. Try to clear all applied filters and return to the default template listing.	A visible Reset or Clear Filters option should be available, allowing users to remove all applied filters with a single click.	There is no dedicated Reset or Clear Filters option. Users must manually change or remove each filter to return to the default view.	Windows 10 Google Chrome (Latest) Desktop		Minor	Medium
BUG-007	Latest filter behavior is unclear and does not match user expectations	1. Open the Website Templates page. 2. Locate the All and Latest options above the template grid. 3. Select Latest.	If Latest is presented as a filter, only the latest templates should be displayed. Alternatively, if it is intended to sort the templates, the UI should clearly indicate that it is a sorting option.	Selecting Latest moves newer templates to the top of the list but still displays older templates below. The interface does not indicate that this is a sorting option, which may confuse users.	Windows 10 Google Chrome (Latest) Desktop		Minor	Low

Bug ID	Title	Steps to Reproduce	Expected Result	Actual Result	Environment	Screenshot/Video	Severity	Priority
		4. Observe the displayed template list.	option (e.g., "Sort by: Latest").	who expect it to filter the results.				
BUG-008	Template card action buttons are not responsive on mobile view	1. Open the Website Templates page. 2. Open the browser's Developer Tools and switch to a mobile device view (or access the page on a mobile device). 3. Navigate to the template card section. 4. Tap or hover over a template card to display the Preview and Details buttons. 5. Observe the appearance and responsiveness of the action buttons.	The Preview and Details buttons should be fully visible, properly aligned, and responsive on mobile devices.	In the mobile view, the action buttons are not fully responsive. The Preview button appears partially cut off, and the button layout is broken. This issue does not occur on the Template Details page, where the buttons display correctly.	Device: Mobile View (Chrome DevTools - iPhone 14 Pro) Browser: Google Chrome (Latest) OS: Windows 10		Major	High
BUG-009	Mobile navigation menu pushes page content down instead of opening as an overlay	1. Open the Website Templates page. 2. Switch to a mobile view using a mobile simulator or browser responsive mode. 3. Tap the hamburger menu icon. 4. Observe the behavior of the navigation menu and the hero section.	The navigation menu should open as an overlay on top of the existing page content without affecting the layout or pushing content downward.	Opening the hamburger menu pushes the hero section (e.g., "Find Your Ideal Website Template") downward, causing the page layout to shift instead of displaying the menu as an overlay.	Device: Mobile View (Mobile Simulator/Responsive Mode) Browser: Google Chrome (Latest) OS: Windows 10		Minor	Medium

Bug ID	Title	Steps to Reproduce	Expected Result	Actual Result	Environment	Screenshot/Video	Severity	Priority
BUG-010	Parent navigation item does not expand submenu when tapped on mobile	1. Open the Website Templates page in mobile view. 2. Tap the hamburger menu to open the navigation menu. 3. Tap the Astra navigation item. 4. Observe the navigation behavior.	Tapping the Astra menu item should expand its submenu, or clearly indicate that it will navigate to another page if that is the intended behavior.	Tapping the Astra menu item navigates to the Home page instead of expanding the submenu. The submenu only opens when the user taps the adjacent dropdown (▼) icon, which is not intuitive. Severity	Device: Mobile View (Mobile Simulator/Responsive Mode) Browser: Google Chrome (Latest) OS: Windows 10		Minor	Medium
BUG-011	Insufficient horizontal padding in the mobile hero section	1. Open the Website Templates page in mobile view. 2. Navigate to the hero section. 3. Observe the spacing around the heading and content.	The hero section content should have adequate left and right padding to provide a balanced and readable layout on mobile devices.	The hero section has very little horizontal spacing on the left and right sides. The content appears too close to the screen edges, making the layout look crowded and visually unbalanced.	Device: Mobile View (Mobile Simulator/Responsive Mode) Browser: Google Chrome (Latest) OS: Windows 10		Minor	Low
BUG-012	Inconsistent horizontal padding between Home page and Template Details page	1. Open the Website Templates Home page. 2. Observe the left and right spacing of the page content. 3. Open any Template Details page. 4. Compare the horizontal padding between the two pages.	The Home page and Template Details page should use consistent horizontal padding to maintain a uniform layout and visual consistency across the website.	The horizontal (left and right) padding differs between the Home page and the Template Details page, resulting in an inconsistent layout and visual appearance. Severity	Browser: Google Chrome (Latest) OS: Windows 10 View: chrome devtool		Minor	Low

Bug ID	Title	Steps to Reproduce	Expected Result	Actual Result	Environment	Screenshot/Video	Severity	Priority
								
BUG-013	"Get Started" button text breaks in tablet view	1. Open the Website Templates page. 2. Open the browser's Developer Tools and switch to a tablet view (e.g., iPad Air or iPad Mini). 3. Observe the navigation bar. 4. Check the Get Started button.	The Get Started button text should remain on a single line and be fully visible without breaking or overflowing.	In tablet view, the Get Started button text wraps onto multiple lines, making the button appear broken and visually inconsistent.	Device: Tablet View (Chrome DevTools - Browser: Google Chrome (Latest) OS: Windows 10		Minor	Medium
BUG-014	Inconsistent Premium badge tooltip styling between Home page and Template Details page	1. Open the Website Templates Home page. 2. Hover over the Premium crown icon on any premium template card. 3. Observe the size and padding of the Premium tooltip. 4. Open the Details page of the same premium template. 5. Hover over the Premium crown icon again and compare the tooltip.	The Premium tooltip should have consistent styling, including padding, height, and overall size, across both the Home page and the Template Details page.	The Premium tooltip displayed on the Template Details page has different padding and height compared to the Home page, resulting in an inconsistent UI appearance.	Browser: Google Chrome (Latest) OS: Windows 10 View: Desktop		Minor	Low
BUG-015	Navigation dropdown cannot be collapsed by clicking the same menu item again	1. Open the Website Templates Home page. 2. Click the Astra Group	Clicking the same navigation menu a second time should collapse the open dropdown. The active menu item should	The dropdown remains open when the Astra Group menu is clicked again. It only closes	Browser: Google Chrome (Latest) OS: Windows 10 View: Desktop		Minor	Low

Steps to Reproduce	Expected Result	Actual Result	Environment	Sc
navigation menu to expand its dropdown. Click the Astra Group menu again. Observe the dropdown behavior.	also have a visual indicator (e.g., a highlighted background) to show that it is currently expanded.	when another navigation menu is opened. Additionally, there is no active background or visual state indicating which navigation item is currently expanded.		