Keras as a simplified interface to TensorFlow: tutorial

A complete guide to using Keras as part of a TensorFlow workflow

Sun 24 April 2016 By <u>Francois Chollet</u> In <u>Tutorials</u>.

If TensorFlow is your primary framework, and you are looking for a simple & high-level model definition interface to make your life easier, this tutorial is for you.

Keras layers and models are fully compatible with pure-TensorFlow tensors, and as a result, Keras makes a great model definition add-on for TensorFlow, and can even be used alongside other TensorFlow libraries. Let's see how.

Note that this tutorial assumes that you have configured Keras to use the TensorFlow backend (instead of Theano). Here are instructions on how to do this.


We will cover the following points:

I: Calling Keras layers on TensorFlow tensors

II: Using Keras models with TensorFlow

III: Multi-GPU and distributed training

IV: Exporting a model with TensorFlow-serving



I: Calling Keras layers on TensorFlow tensors

Let's start with a simple example: MNIST digits classification. We will build a TensorFlow digits classifier using a stack of Keras Dense layers (fully-connected layers).

We should start by creating a TensorFlow session and registering it with Keras. This means that Keras will use the session we registered to initialize all variables that it creates internally.

```
import tensorflow as tf
sess = tf.Session()

from keras import backend as K
K.set session(sess)
```

Now let's get started with our MNIST model. We can start building a classifier exactly as you would do in TensorFlow:

```
# this placeholder will contain our input digits, as flat vectors
img = tf.placeholder(tf.float32, shape=(None, 784))
```

We can then use Keras layers to speed up the model definition process:

```
from keras.layers import Dense

# Keras layers can be called on TensorFlow tensors:
x = Dense(128, activation='relu')(img) # fully-connected layer with 128 units and ReLU activation
x = Dense(128, activation='relu')(x)
preds = Dense(10, activation='softmax')(x) # output layer with 10 units and a softmax activation
```

We define the placeholder for the labels, and the loss function we will use:

```
labels = tf.placeholder(tf.float32, shape=(None, 10))
from keras.objectives import categorical_crossentropy
loss = tf.reduce mean(categorical crossentropy(labels, preds))
```

Let's train the model with a TensorFlow optimizer:

We can now evaluate the model:

In this case, we use Keras only as a syntactical shortcut to generate an op that maps some tensor(s) input to some tensor(s) output, and that's it. The optimization is done via a native TensorFlow optimizer rather than a Keras optimizer. We don't even use any Keras Model at all!

A note on the relative performance of native TensorFlow optimizers and Keras optimizers: there are slight speed differences when optimizing a model "the Keras way" vs. with a TensorFlow optimizer. Somewhat counterintuitively, Keras seems faster most of the time, by 5-10%. However these differences are small enough that it doesn't really matter, at the end of the day, whether you optimize your models via Keras optimizers or native TF optimizers.

Different behaviors during training and testing

Some Keras layers (e.g. Dropout, BatchNormalization) behave differently at training time and testing time. You can tell whether a layer uses the "learning phase" (train/test) by printing layer.uses_learning_phase, a boolean: True if the layer has a different behavior in training mode and test mode, False otherwise.

If your model includes such layers, then you need to specify the value of the learning phase as part of feed_dict, so that your model knows whether to apply dropout/etc or not.

The Keras learning phase (a scalar TensorFlow tensor) is accessible via the Keras backend:

```
from keras import backend as K
print K.learning_phase()
```

To make use of the learning phase, simply pass the value "1" (training mode) or "0" (test mode) to feed dict:

```
# train mode
train step.run(feed dict={x: batch[0], labels: batch[1], K.learning phase(): 1})
```

For instance, here's how to add propout layers to our previous MNIST example:

```
from keras.layers import Dropout
from keras import backend as K
img = tf.placeholder(tf.float32, shape=(None, 784))
labels = tf.placeholder(tf.float32, shape=(None, 10))
x = Dense(128, activation='relu')(img)
x = Dropout(0.5)(x)
x = Dense(128, activation='relu')(x)
x = Dropout(0.5)(x)
preds = Dense(10, activation='softmax')(x)
loss = tf.reduce mean(categorical crossentropy(labels, preds))
train_step = tf.train.GradientDescentOptimizer(0.5).minimize(loss)
with sess.as_default():
    for i in range(100):
        batch = mnist data.train.next batch(50)
        train step.run(feed dict={img: batch[0],
                                  labels: batch[1],
                                  K.learning phase(): 1})
acc value = accuracy(labels, preds)
with sess.as default():
   print acc value.eval(feed dict={img: mnist data.test.images,
                                    labels: mnist data.test.labels,
                                    K.learning phase(): 0})
```

Compatibility with name scopes, device scopes

Keras layers and models are fully compatible with TensorFlow name scopes. For instance, consider the following code snippet:

```
x = tf.placeholder(tf.float32, shape=(None, 20, 64))
with tf.name_scope('block1'):
    y = LSTM(32, name='mylstm')(x)
```

The weights of our LSTM layer will then be named block1/mylstm W i, block1/mylstm U i, etc...

Similarly, device scopes work as you would expect:

```
with tf.device('/gpu:0'):
    x = tf.placeholder(tf.float32, shape=(None, 20, 64))
    y = LSTM(32)(x) # all ops / variables in the LSTM layer will live on GPU:0
```

Compatibility with graph scopes

Any Keras layer or model that you define inside a TensorFlow graph scope will have all of its variables and operations created as part of the specified graph. For instance, the following works as you would expect:

```
from keras.layers import LSTM
import tensorflow as tf
```

```
my_graph = tf.Graph()
with my_graph.as_default():
    x = tf.placeholder(tf.float32, shape=(None, 20, 64))
    y = LSTM(32)(x) # all ops / variables in the LSTM layer are created as part of our graph
```

Compatibility with variable scopes

To summarize quickly how weight sharing works in Keras: by reusing the same layer instance or model instance, you are sharing its weights. Here's a simple example:

```
# instantiate a Keras layer
lstm = LSTM(32)

# instantiate two TF placeholders
x = tf.placeholder(tf.float32, shape=(None, 20, 64))
y = tf.placeholder(tf.float32, shape=(None, 20, 64))
# encode the two tensors with the *same* LSTM weights
x_encoded = lstm(x)
y encoded = lstm(y)
```

Collecting trainable weights and state updates

Some Keras layers (stateful RNNs and BatchNormalization layers) have internal updates that need to be run as part of each training step. There are stored as a list of tensor tuples, layer.updates. You should generate assign ops for those, to be run at each training step. Here's an example:

```
from keras.layers import BatchNormalization
layer = BatchNormalization()(x)

update_ops = []
for old_value, new_value in layer.updates:
    update ops.append(tf.assign(old value, new value))
```

Note that if you are using a Keras model (Model instance or sequential instance), model.udpates behaves in the same way (and collects the updates of all underlying layers in the model).

In addition, in case you need to explicitly collect a layer's trainable weights, you can do so via layer.trainable_weights (or model.trainable_weights), a list of TensorFlow variableinstances:

```
from keras.layers import Dense
layer = Dense(32)(x) # instantiate and call a layer
print layer.trainable weights # list of TensorFlow Variables
```

Knowing this allows you to implement your own training routine based on a TensorFlow optimizer.

II: Using Keras models with TensorFlow

Converting a Keras sequential model for use in a TensorFlow workflow

You have found a Keras sequential model that you want to reuse in your TensorFlow project (consider, for instance, this VGG16 image classifier with pre-trained weights). How to proceed?

First of all, note that if your pre-trained weights include convolutions (layers convolution2D or convolution1D) that were trained with **Theano**, you need to flip the convolution kernels when loading the weights. This is due

Theano and TensorFlow implementing convolution in different ways (TensorFlow actually implements correlation, much like Caffe). Here's a short guide on what you need to do in this case.

Let's say that you are starting from the following Keras model, and that you want to modify so that it takes as input a specific TensorFlow tensor, my_input_tensor. This input tensor could be a data feeder op, for instance, or the output of a previous TensorFlow model.

```
# this is our initial Keras model
model = Sequential()
model.add(Dense(32, activation='relu', input_dim=784))
model.add(Dense(10, activation='softmax'))
```

You just need to use keras.layers.InputLayer to start building your Sequential model on top of a custom TensorFlow placeholder, then build the rest of the model on top:

At this stage, you can call model.load_weights(weights_file) to load your pre-trained weights.

Then you will probably want to collect the sequential model's output tensor:

```
output tensor = model.output
```

You can now add new TensorFlow ops on top of output tensor, etc.

Calling a Keras model on a TensorFlow tensor

A Keras model acts the same as a layer, and thus can be called on TensorFlow tensors:

```
from keras.models import Sequential

model = Sequential()
model.add(Dense(32, activation='relu', input_dim=784))
model.add(Dense(10, activation='softmax'))

# this works!
x = tf.placeholder(tf.float32, shape=(None, 784))
y = model(x)
```

Note: by calling a Keras model, your are reusing both its architecture and its weights. When you are calling a model on a tensor, you are creating new TF ops on top of the input tensor, and these ops are reusing the TF variable instances already present in the model.

III: Multi-GPU and distributed training

Assigning part of a Keras model to different GPUs

TensorFlow device scopes are fully compatible with Keras layers and models, hence you can use them to assign specific parts of a graph to different GPUs. Here's a simple example:

```
with tf.device('/gpu:0'):
    x = tf.placeholder(tf.float32, shape=(None, 20, 64))
    y = LSTM(32)(x) # all ops in the LSTM layer will live on GPU:0
```

```
with tf.device('/gpu:1'):
    x = tf.placeholder(tf.float32, shape=(None, 20, 64))
    y = LSTM(32)(x) # all ops in the LSTM layer will live on GPU:1
```

Note that the variables created by the LSTM layers will not live on GPU: all TensorFlow variables always live on CPU independently from the device scope where they were created. TensorFlow handles device-to-device variable transfer behind the scenes.

If you want to train multiple replicas of a same model on different GPUs, while sharing the same weights across the different replicas, you should first instantiate your model (or layers) under one device scope, then call the same model instance multiple times in different GPU device scopes, such as:

```
with tf.device('/cpu:0'):
    x = tf.placeholder(tf.float32, shape=(None, 784))
    # shared model living on CPU:0
    # it won't actually be run during training; it acts as an op template
    # and as a repository for shared variables
    model = Sequential()
    model.add(Dense(32, activation='relu', input dim=784))
    model.add(Dense(10, activation='softmax'))
# replica 0
with tf.device('/gpu:0'):
    output 0 = model(x) # all ops in the replica will live on GPU:0
with tf.device('/gpu:1'):
    output 1 = model(x) # all ops in the replica will live on GPU:1
# merge outputs on CPU
with tf.device('/cpu:0'):
    preds = 0.5 * (output_0 + output_1)
# we only run the `preds` tensor, so that only the two
# replicas on GPU get run (plus the merge op on CPU)
output_value = sess.run([preds], feed_dict={x: data})
```

Distributed training

You can trivially make use of TensorFlow distributed training by registering with Keras a TF session linked to a cluster:

```
server = tf.train.Server.create_local_server()
sess = tf.Session(server.target)

from keras import backend as K
K.set session(sess)
```

For more information about using TensorFlow in a distributed setting, see this tutorial.

IV: Exporting a model with TensorFlow-serving

TensorFlow Serving is a library for serving TensorFlow models in a production setting, developed by Google.

Any Keras model can be exported with TensorFlow-serving (as long as it only has one input and one output, which is a limitation of TF-serving), whether or not it was training as part of a TensorFlow workflow. In fact you could even train your Keras model with Theano then switch to the TensorFlow Keras backend and export your model.

Here's how it works.

If your graph makes use of the Keras learning phase (different behavior at training time and test time), the very first thing to do before exporting your model is to hard-code the value of the learning phase (as 0, presumably, i.e. test mode) into your graph. This is done by 1) registering a constant learning phase with the Keras backend, and 2) re-building your model afterwards.

Here are these two simple steps in action:

```
from keras import backend as K

K.set_learning_phase(0) # all new operations will be in test mode from now on

# serialize the model and get its weights, for quick re-building
config = previous_model.get_config()
weights = previous_model.get_weights()

# re-build a model where the learning phase is now hard-coded to 0
from keras.models import model_from_config
new_model = model_from_config(config)
new model.set weights(weights)
```

We can now use TensorFlow-serving to export the model, following the instructions found in the official tutorial:

Want to see a new topic covered in this guide? Reach out on Twitter.