

Lancer1911 ASR Offline

Fully Offline Audio File Transcription

离线音频文件转写 · LLM 矫正 · 多语言翻译 · 字幕编辑

Installation & User Guide v1.0 · 安装与使用说明

1. System Requirements 系统要求

Item	Requirement
项目	要求
Hardware	Apple Silicon Mac (M1 / M2 / M3 / M4 or later)
硬件	Apple Silicon Mac (M1 / M2 / M3 / M4 及以上)
Memory	24 GB minimum, 48 GB recommended
内存	最低 24GB, 推荐 48GB
macOS	13 Ventura or later; 14 Sonoma or later recommended
系统	macOS 13 Ventura 或更高, 推荐 macOS 14 Sonoma 及以上
Storage	~12–25 GB for AI models and working files
存储空间	AI 模型与临时工作文件约需 12–25GB
Internet	Only needed for first-time model download
网络	仅首次下载模型需要联网
Audio formats	Common ffmpeg-readable formats: MP3, WAV, M4A, AAC, FLAC, OGG, OPUS, and audio streams in MP4/MOV
音频格式	支持 ffmpeg 可读取的常见格式: MP3、WAV、M4A、AAC、FLAC、OGG、OPUS, 以及 MP4/MOV 中的音轨

⚠ Lancer1911 ASR Offline runs entirely on-device. Your audio files and transcript text never leave your Mac.

⚠ Lancer1911 ASR Offline 完全在本地运行, 音频文件和转写文字不会上传到任何服务器。

2. Installation 安装步骤

2.1 Install Homebrew 安装 Homebrew (已安装可跳过)

Open Terminal and run:

打开终端, 运行以下命令:

```
/bin/bash -c "$(curl -fsSL
https://raw.githubusercontent.com/Homebrew/install/HEAD/install.sh)"
```

2.2 Install ffmpeg 安装 ffmpeg

Required for reading, converting, and normalizing audio files:

读取、转换和标准化音频文件需要此工具:

```
brew install ffmpeg
```

2.3 Set Up Python Environment 配置 Python 虚拟环境

Run these commands once in Terminal:

在终端依次运行以下命令（只需执行一次）：

```
# Create virtual environment
python3 -m venv ~/asr-env

# Activate it
source ~/asr-env/bin/activate

# Install dependencies
pip install -r requirements.txt
pip install onnxruntime pywebview
```

If you use the packaged .app, the app is lightweight and still relies on the local Python environment and downloaded models.

如果使用打包后的 .app，应用本体较小，仍依赖本地 Python 环境和已下载模型。

3. Download AI Models 下载 AI 模型

Lancer1911 ASR Offline uses an ASR model for transcription and a Qwen3 LLM for correction, segmentation, translation, and optional retranslation. Download them once; after that they are cached locally and work offline.

Lancer1911 ASR Offline 使用 ASR 模型进行转写，并使用 Qwen3 LLM 进行文本矫正、切句、翻译和可选重译。模型下载一次后缓存在本地，之后可完全离线使用。

Speech Recognition Model — Whisper / SenseVoice 语音识别模型

Model 模型	Size 大小	Speed 速度	Recommended for 适用场景
whisper-large-v3-turbo	~3 GB 约3GB	Fast 较快	Default; high accuracy for multilingual audio files 默认；适合多语言音频文件
whisper-large-v3-mlx	~6 GB 约6GB	Slower 稍慢	Maximum Whisper accuracy 追求 Whisper 最高精度
SenseVoiceSmall	~0.5 GB 约0.5GB	Fast 快	Optional; Chinese / English / Japanese / Korean, emotion/event tags 可选；支持中英日韩及情绪/事件标签

```
source ~/asr-env/bin/activate

# Recommended Whisper model
hf download mlx-community/whisper-large-v3-turbo

# Optional alternatives
# hf download mlx-community/whisper-large-v3-mlx
# pip install mlx-audio
# hf download mlx-community/SenseVoiceSmall
```

Correction & Translation Model — Qwen3 矫正与翻译模型

Model 模型	Size 大小	Recommended for 适用场景
Qwen3-14B-4bit	~8 GB 约8GB	Default balance of speed and quality 速度与质量较均衡，推荐默认使用
Qwen3-8B-4bit	~5 GB 约5GB	24 GB RAM or speed-first processing 24GB 内存或速度优先场景
Qwen3-30B-A3B-Instruct-2507-4bit	~16 GB 约16GB	Higher quality; ≥48 GB RAM recommended 质量更高；建议 48GB 以上内存

```
# Recommended
hf download mlx-community/Qwen3-14B-4bit

# Optional smaller / larger models
# hf download mlx-community/Qwen3-8B-4bit
# hf download mlx-community/Qwen3-30B-A3B-Instruct-2507-4bit
```

If downloads are slow or failing, try the mirror: `export HF_ENDPOINT=https://hf-mirror.com`
 下载缓慢或失败时，可使用镜像：`export HF_ENDPOINT=https://hf-mirror.com`

4. Install Lancer1911 ASR Offline.app 安装应用

4.1 Copy to Applications 拷贝到应用程序文件夹

Open the DMG file and drag Lancer1911 ASR Offline into the Applications folder.
 打开 DMG 文件，将 Lancer1911 ASR Offline 拖入 Applications（应用程序）文件夹。

4.2 Bypass Gatekeeper 绕过安全限制

Because Lancer1911 ASR Offline is not notarized by Apple, macOS may block it on first launch.
 由于 Lancer1911 ASR Offline 未经 Apple 公证，首次打开可能被系统拦截。

Option A — Right-click Lancer1911 ASR Offline in Applications → Open → click Open.

方法 A — 在 Applications 中右键 Lancer1911 ASR Offline → 打开 → 在弹窗中点击「打开」。

Option B — Terminal:

方法 B — 终端命令：

```
xattr -cr /Applications/Lancer1911\ ASR\ Offline.app
```

5. Using Lancer1911 ASR Offline 使用说明

5.1 First Launch 首次启动

Allow 30–90 seconds on first launch for the ASR and LLM models to load into memory. The status bar will show Ready when the app is fully loaded.

首次启动需要 30–90 秒加载 ASR 和 LLM 模型，状态栏显示「就绪」后即可使用。

5.2 Process an Audio File 处理音频文件

Step	Action
步骤	操作
1	Drag an audio file into the upload area or click to select a file. 将音频文件拖入上传区域，或点击选择文件。
2	The app checks the file with ffprobe, then converts it to 16 kHz mono float audio for ASR. 程序先用 ffprobe 检查文件，再用 ffmpeg 转为 16kHz 单声道浮点音频供 ASR 使用。
3	ASR produces raw segments; Qwen3 then corrects, splits, translates, and optionally re-translates missing languages. ASR 先生成原始片段；Qwen3 随后进行矫正、切句、翻译，并可自动补译缺失语言。
4	Use the playback bar to review the original audio and follow the transcript. 使用播放栏回听原始音频，并让字幕跟随播放位置滚动。
5	Edit subtitle cards manually, translate individual lines, rename speakers, and export when finished. 可手工校对字幕卡片、单句翻译、重命名发言人，并在完成后导出。

5.3 Interface Overview 界面说明

Area	Function
区域	功能
Top bar	Status, Export, Clear, Theme toggle, language switch, Advanced Settings
顶栏	状态、导出、清空、主题切换、语言切换、高级设置
Upload area	Drag-and-drop or click to select audio files
上传区域	拖放或点击选择音频文件
Subtitle cards	ASR text, corrected text, translations, speaker labels, editing controls
字幕卡片	ASR 原文、矫正文本、译文、发言人标签与编辑操作
Playback bar	Play/pause, seek, volume, follow playback, jump to subtitle
播放栏	播放/暂停、进度拖动、音量、跟随回放、跳转字幕
Sci-fi display	Aurora Flow or Matrix Trail display mode
科幻展示	流光溢彩或黑客帝国展示模式

5.4 Settings 设置说明

Model Selection 模型选择

The app scans local HuggingFace / ModelScope caches and lists available ASR and LLM models. No manual path entry is normally required.

应用会扫描本地 HuggingFace / ModelScope 缓存并列出了可用 ASR 与 LLM 模型，通常无需手动填写路径。

Advanced ASR & LLM Parameters ASR 与 LLM 高级参数

Parameter	Default	Simple guidance
参数	默认值	简单指导
condition_on_previous_text	False	Keep False for poor or distant recordings to avoid error propagation. 远距离或音质差时建议保持 False，避免前文错误传染。
no_speech_threshold	0.45	Lower if real speech is missed; raise if noise is recognized as speech. 漏识别时调低；噪声被识别成语音时调高。
compression_ratio_threshold	1.8	Lower to suppress repetition; raise slightly if valid speech is filtered. 重复幻觉多时调低；真实语音被过滤时可略调高。

logprob_threshold	-1.0	Lower to allow low-confidence speech; raise to reduce hallucination. 音质差可调低；幻觉多可调高。
LLM token / chunk limits	Various 多项	Higher values may improve long text quality but increase latency and memory use. 数值越高越可能提升长文本质量，但会增加延迟和内存占用。

Presets 参数预设

Built-in presets include Default / Balanced, Distant or muffled recording, Noisy / hallucination suppression, Long sentence / multilingual translation, Speed first, and Quality first. You can also save or delete custom presets.

内置预设包括默认/平衡、远距离/声音闷、噪声多/抑制幻觉、长句/多语种翻译、速度优先、质量优先。用户也可以保存或删除自定义预设。

Display Effects 展示效果

The sci-fi display can switch between Aurora Flow and Matrix Trail. Both affect the text foreground only; the background remains unchanged.

科幻展示可在「流光溢彩」和「黑客帝国」之间切换。两者均作用于字符前景色，背景保持不变。

5.5 ASO Session Files ASO 会话文件

ASO files save the transcript, translations, speaker labels, display state, and the associated audio reference. When an ASO file is reopened, the app attempts to reload the original audio for playback and follow mode.

ASO 文件保存转写文本、译文、发言人标签、展示状态以及关联音频引用。重新打开 ASO 时，程序会尝试重新加载原始音频，以恢复播放和跟随功能。

5.6 Export 导出

Click Export in the top bar, choose a language filter and format, then save through the native macOS save dialog.

点击顶栏「导出」，选择语言筛选和格式，通过 macOS 原生保存面板保存文件。

Format 格式	Description 说明
TXT 纯文本	Plain text with timestamps 每条含时间戳的纯文本
SRT 字幕文件	Standard subtitle format for video editors 标准字幕格式，可导入视频软件
JSON 结构化数据	Full metadata: timestamps, raw ASR, corrected text, translations, speakers 含时间戳、ASR 原文、矫正文本、译文和发言人信息
Markdown Markdown	Suitable for Obsidian, Notion, or review notes 适合 Obsidian、Notion 或校对笔记
ASO 会话文件	Project/session file for reopening and continued editing 项目/会话文件，可重新打开继续校对

6. Troubleshooting 常见问题

Issue 问题	Solution 解决方法
Window shows "Connecting" for a long time 窗口长时间显示「连接中」	Wait 30–90 s for models to load. The status bar shows Ready when done. 等待 30–90 秒，状态栏显示「就绪」后即可操作。
Audio file cannot be loaded 音频文件无法加载	Confirm ffmpeg and ffprobe are installed: brew install ffmpeg. Try converting unusual formats to MP3 or WAV first. 确认已安装 ffmpeg/ffprobe: brew install ffmpeg。特殊格式可先转为 MP3 或 WAV。
No translations appear 没有翻译输出	Check target languages and ensure the LLM model is loaded. Use "Translate all" or retranslate missing languages if needed. 检查翻译目标语言并确认 LLM 已加载。必要时点击「全部翻译」或补译缺失语言。
Repeated words or hallucination 出现大量重复词或幻觉	Use the noisy/hallucination preset, lower compression_ratio_threshold, or raise logprob_threshold / no_speech_threshold. 使用「噪声多/抑制幻觉」预设，或降低 compression_ratio_threshold，并提高 logprob_threshold / no_speech_threshold。
Distant or muffled recording has missing speech 远距离或声音闷导致漏识别	Use the distant/muffled preset. Lower no_speech_threshold and logprob_threshold slightly. 使用「远距离/声音闷」预设，适当降低 no_speech_threshold 和 logprob_threshold。
LLM correction is slow LLM 矫正时间过长	Switch to a smaller Qwen model, reduce target languages, or use the speed-first preset. 换用更小的 Qwen 模型，减少目标语言，或使用「速度优先」预设。
ASO reopens but audio playback is missing ASO 打开后没有音频回放	Keep the original audio file in the recorded path or reload the audio file manually if it was moved. 保持原始音频位于记录路径；如已移动，请手动重新加载音频。
Speaker ID shows "Not installed" 发言人识别显示「未安装」	Install optional pyannote dependencies and models, then restart the app. 安装可选 pyannote 依赖和模型后重启应用。