Lecture 25

niceguy

March 11, 2024

1 Reflection/Transmission at Material Interfaces

We first start with a normal incidence, where the wave vector \hat{k}_c propagates in a direction normal to the plane of material interface.

1.1 EM Field Boundary Conditions

There are conditions that determine the abrupt change of \vec{E} , \vec{H} across an interface. If we go from $\varepsilon_1, \mu_1, \sigma_1$ to $\varepsilon_2, \mu_2, \sigma_2$. If the interface is small enough, we can always approximate it as a plane. Then \vec{E} can be split into a normal and tangential component with respect to this tangent plane.

Applying Faraday's law for a contour with width (along plane) w and height h, we have

$$\oint_C \vec{E} \cdot d\vec{l} = -\frac{d}{dt} \int_S \vec{B} \cdot d\vec{s}$$

As $h \to 0$, the right hand side vanishes. For a small region, we can take \vec{E} to be constant on each side respectively. The only way for the path integral to vanish is for the tangential components to agree across the boundary. The normal components don't matter, since they are scaled by height h which vanishes.

An aside is that if the second medium is a perfect conductor, $\vec{E}_2 = 0$, wich means all electric fields become normal to the surface, else the tangential electric field is not conserved.

Applying Ampere-Maxwell law on the same contour, and taking the limit $h \to 0$,

$$\oint_{c} \vec{H} \cdot d\vec{l} = \int_{S} \vec{J} \cdot d\vec{s} + \frac{d}{dt} \int_{S} \vec{D} \cdot d\vec{s}$$
$$(H_{2,t} - H_{1,t})w = J_{s}w$$
$$H_{2,t} - H_{1,t} = J_{s}$$

Generally,

$$\hat{n} \times (\vec{H}_2 - \vec{H}_1) = \vec{J}_s$$

Setting $\hat{n} = \hat{z}$, we get

$$\vec{J}_s = (H_{1,y} - H_{2,y})\hat{x} + (H_{2,x} - H_{1,x})\hat{y}$$

and so

$$\begin{cases} H_{2,x} - H_{1,x} &= J_{s,y} \\ H_{1,y} - H_{2,y} &= J_{s,x} \end{cases}$$

Example 1.1 (Normal Incidence on a Conductor). \vec{E} is tangential to the plane of incidence, so it has to vanish. If we define the wave and reflected wave to be

$$\tilde{\vec{E}}_i = E_0 e^{-jk_1 z} \hat{x}$$

$$\tilde{\vec{E}}_r = \Gamma E_0 e^{jk_1 z} \hat{x}$$

At z = 0, we have

$$E_x(z=0) = 0$$

$$E_0 + \Gamma E_0 = 0$$

$$\Gamma = -1$$