Using Aspera API for Integration and Automation

Unofficial document

Laurent MARTIN

2026/11/10

Contents

1 Introduction **3**
- 1.1 Components and their APIs . . . 3
- 1.2 API definitions . . . 5
- 1.3 Choose your integration . . . 5
- 1.4 Where to start . . . 6
- 1.5 Addresses and Credentials . . . 7

2 Concepts **8**
- 2.1 Base rules for a transfer . . . 8
- 2.2 Client and server roles . . . 8
- 2.3 Server-side storage access (docroot / storage root) . . . 8
- 2.4 Client types and storage capabilities . . . 9
- 2.5 Remote control of clients . . . 9
- 2.6 Transfer authorization . . . 9
- 2.7 Transfer specification . . . 10
  - 2.7.1 Transfer spec version 2 . . . 10

3 Transfer clients and tools **12**
- 3.1 `ascp` . . . 12
  - 3.1.1 Client-side minimum components . . . 12
  - 3.1.2 First `ascp` invocation . . . 12
  - 3.1.3 Sample optional config file for client `ascp` . . . 12
- 3.2 Transfer Daemon: `transferd` . . . 13
  - 3.2.1 Starting up . . . 13
  - 3.2.2 Examples . . . 13
- 3.3 Web SDK . . . 13
- 3.4 Mobile: Android, iOS . . . 13
- 3.5 CLI: `ascli` . . . 13

4 Integration Scenarios **15**
- 4.1 S1- The simplest integration: start a transfer with a script and `ascp` . . . 15
- 4.2 S2- Start a transfer with Transfer SDK and listen for events . . . 16
- 4.3 S3- Start a transfer in a web browser . . . 19
- 4.4 S4- Start a Server-Server transfer with Node API and SSH credentials . . . 19
- 4.5 S5- Start a transfer with Token Authorization . . . 21
- 4.6 S6- Start a Server-Server transfer with Node API and Transfer token . . . 22
- 4.7 S7- Polling on transfer status on Node API . . . 24

5 Transfer authentication and authorization **26**
- 5.1 Choosing the Right Token Type . . . 26
  - 5.1.1 Architecture comparison . . . 26
  - 5.1.2 Decision guide . . . 27
- 5.2 A1- SSH Authentication . . . 27
- 5.3 A2- Aspera Transfer Token Authorization . . . 27
  - 5.3.1 Token generation . . . 28
- 5.4 A3- Aspera Bearer Token Authorization . . . 29
  - 5.4.1 A3: Scenario . . . 30

6 Aspera applications **32**
6.1 Pattern for all applications . . . 32
6.2 Faspex 5 . . . 32
6.2.1 Authentication . . . 33
6.2.2 Transfers (send/receive packages) . . . 34
6.3 IBM Aspera on Cloud . . . 34
6.4 IBM Aspera Shares . . . 35

7 Node API **36**
7.1 Overview . . . 36
7.2 What Can You Do With the Node API? . . . 36
7.3 Supported Node Types . . . 36
7.4 Network Interface & Port Configuration . . . 37
7.5 Authentication . . . 37
7.5.1 Basic Authentication . . . 37
7.5.2 Node Users . . . 37
7.5.3 Transfer Node User . . . 37
7.5.4 Master Node User . . . 38
7.5.5 Access Keys . . . 38
7.5.6 Primary Access Keys . . . 38
7.5.7 Sub Access Keys . . . 38
7.5.8 OAuth2 Bearer Tokens . . . 38
7.6 API Endpoint Reference . . . 38
7.6.1 File Management Endpoint Groups . . . 38
7.7 Requests & Responses . . . 39
7.7.1 HTTP Methods . . . 39
7.7.2 Request Format . . . 39
7.7.3 Response Codes . . . 40
7.8 Error Handling . . . 40
7.8.1 Developer Notes . . . 40
7.9 Typical Use Cases . . . 40
7.9.1 Health Check . . . 40
7.9.2 Node Configuration Discovery . . . 41
7.9.3 Access Management . . . 41
7.9.4 File System Operations . . . 41
7.9.5 Transfer Operations . . . 41
7.9.6 Monitoring & Reporting . . . 41

8 Troubleshooting **42**
8.1 Find where the problem is . . . 42
8.2 Common problems . . . 42
8.3 Before asking for help . . . 43

Chapter 1


Introduction

This document examines the various methods for integrating with IBM Aspera APIs to harness their high-performance file transfer capabilities.

IBM Aspera data transfer technology is delivered through a suite of products, each comprising components that expose APIs for integration.

Ultimately, most integrations aim to leverage the IBM Aspera FASP protocol to achieve maximum transfer speeds.

All Aspera transfers involve a client connecting to a server to either push or pull files. The client component is either one of Aspera's client applications, a server, or a custom application built using Aspera's client libraries. The server component is always the IBM Aspera High-Speed Transfer Server (HSTS) or Endpoint (HSTE), or the SaaS version: Aspera Transfer Service (ATS).




Aspera transfer: client, server and storage

1.1 Components and their APIs

These three types of software components provide APIs:

- **Transfer Server (HSTS)**: Node API (REST)
  - Monitor and manage transfers (`GET /ops/transfers`)
  - Start server-to-server transfer (as "transfer client" to remote server) (`POST /ops/transfers`)
  - Get authorization for transfer (typically for web) (`POST /files/*_setup`)
  - Basic file system operations (list files, create folder, etc.) (`GET`/`POST /files/...`)



Overview of the Aspera APIs: your application, applications, transfer agents and servers

  - Supports ”watch folder” (includes growing file transfer) (`/watchfolders/`...), `async`, stream, etc.
  - Also provides the server side for FASP transfer (UDP, `ascp`)
- **Applications**: Faspex, Shares, AoC, Console, Orchestrator API (REST)
  - Provide REST API
  - Do not embed the FASP protocol, but the web app uses the Node API of Transfer Servers
  - Can control and use several Transfer Servers
  - Applications authenticate users, manage users, manage file resources, authorize users for transfers
- **Transfer Clients**: SDKs
  - Transfer Daemon provides a **gRPC** interface that can be used from virtually any language.
  - Provides transfer session management (start, monitor)
  - Internally starts one `ascp` process per transfer session.
  - Web SDK: provides the equivalent of Transfer SDK API in the browser (JavaScript), with Aspera for Desktop, Connect or HTTP Gateway. It replaces the former Connect SDK, HTTP Gateway SDK and Desktop SDK.
  - Mobile SDK: the equivalent of Transfer SDK for mobile (Swift for iOS, or Java for Android) (under review)

> **Note**
>
> The Aspera legacy client SDK was called ”FaspManager” and is now deprecated (do not use). It provided language-specific implementations: C/C++, Java, Go, Python, .NET, C# (, Ruby). FaspManager2 (based on SWIG) is also deprecated.

1.2 API definitions

Official definitions are published on the Aspera API Hub. This repository also maintains a copy of the OpenAPI specifications in the folder openapi, and a viewer (Swagger-like, searchable) here: https://ibm.biz/aspera_openapi.

For each API there are up to two kinds of files:

- The original file, as published by IBM (or the closest available).
- The `-enhanced` file: corrected and completed by this repository, and checked with the IBM `openapi-validator` (`npm run lint` in the folder `openapi`). Prefer it, and prefer it when generating a client or code with an AI agent.

API	Files in this repository
Node API (HSTS, HSTE, ATS)	4.4.6, 4.4.1
Faspex 5	5.0 enhanced, 5.0
Aspera on Cloud	0.2.6 enhanced, 0.2.6
Aspera on Cloud Automation	1.0.5 enhanced, 1.0.5
Shares	Shares
Orchestrator	v1 enhanced, v1
Console	enhanced
faspio Gateway	1.0.0 enhanced, 1.0.0
Transfer Daemon configuration	JSON Schema transferd-config.schema.json

The gRPC definition of the Transfer Daemon, `transferd.proto`, is not in this repository: it is in the Transfer SDK archive (see Transfer clients and tools). The Web SDK is documented in its TypeDoc.

The guide explains concepts and flows. The reference of a REST call (parameters, schemas, errors) is in these definitions: use them rather than the guide.

1.3 Choose your integration

Find the row that matches what you want to build. Each row gives the client, the authorization, the guide section to read and the samples of this repository (the samples exist in several languages: see Available samples).

I want to...	Transfer client	Authorization	Read	Sample
Send or receive files from a script, with an account on a server I own	`ascp` or `ascli`	SSH	S1	
Transfer from my own desktop or server application (any language), with an account on a server I own	Transfer Daemon (gRPC)	SSH	S2	`server`
Let users of my web application transfer from their browser	Web SDK	Token, generated by my back end	S3, A2	`web/`
Authenticate my own users and decide what they can transfer, from a custom application	Transfer Daemon, or Web SDK	Transfer token (ATx), generated by my back end	S5, A2	`node`, `node_v2`
Transfer between two servers I own, with SSH accounts	Node API on the source server	SSH	S4	
Transfer between two servers I own, without SSH accounts	Node API on the source server	Transfer token	S6	`node_v2`
Follow or list the transfers of a server	Node API	Node user or access key	S7	
Send or receive a package with Faspex 5	Transfer Daemon, or Web SDK	Faspex 5 OAuth bearer token, gives a transfer spec with token	Faspex 5	`faspex5`
Send or receive a package or files with Aspera on Cloud	Transfer Daemon, or Web SDK	AoC OAuth bearer token, then node bearer token	Aspera on Cloud, A3	`aoc`
Use Aspera Shares	Transfer Daemon	Same as Node API	Shares	`shares`
Use IBM Cloud Object Storage	Transfer Daemon	COS credentials	README	`cos`

If the table does not settle it, answer these questions in order:

1. **Do you already have an Aspera application** (Faspex, AoC, Shares)? Yes: use its REST API to get the transfer spec, never generate tokens yourself.
2. **Does the transfer start in a web browser?** Yes: use the Web SDK, and a token (SSH credentials must not reach the browser).
3. **Do you have your own users to authenticate?** Yes: use a token, see Choosing the Right Token Type. No, only a server account: use SSH credentials.
4. **Is the client a server?** Yes: use the Node API (`POST /ops/transfers`), else use the Transfer Daemon.

1.4 Where to start

There are many scenarios to use Aspera to send files. A typical path:

1. Get familiar with what an Aspera transfer is: see Concepts.
2. Get the `ascp` executable and the free license file, from the Transfer SDK or one of the free clients: see Transfer clients and tools.
3. Execute command line transfers with `ascp` or `ascli` to a test server using SSH credentials: see S1.
4. Do the same with the client method chosen, for example `transferd` with gRPC: see S2, and the samples of this repository.
5. If you send to an Aspera application (Faspex, AoC), use its REST API to create a **transfer spec** (with token authorization): see Aspera applications.
6. If you need to receive files on your own Aspera server, install an Aspera Transfer Server to test with (evaluation or development license), and initiate transfers to it using the chosen methods (Web SDK, Node API, etc.).

If something fails, see Troubleshooting.

In order to test, one needs:

- Client-side libraries (Transfer SDK, Web SDK, Mobile SDK) or API definitions (Node API, web app API)
- Server-side testing server

1.5 Addresses and Credentials

Examples provided in this document use the following virtual connection information:

- `hsts1.example.com`: Address of HSTS 1.
- `<HSTS1_XFER_USER>`: A transfer user with SSH credentials on HSTS 1.
- `<HSTS1_XFER_PASSWORD>`: Password for `<HSTS1_XFER_USER>`.
- `<HSTS1_NODE_USER>`: A Node API user (or access key ID).
- `<HSTS1_NODE_PASSWORD>`: Password for `<HSTS1_NODE_USER>` (or access key secret).
- `hsts2.example.com`: Address of HSTS 2.
- `<HSTS2_NODE_USER>`: A Node API user (or access key ID).
- `<HSTS2_NODE_PASSWORD>`: Password for `<HSTS2_NODE_USER>` (or access key secret).

Chapter 2

Concepts

When using Aspera to transfer data between two storage systems, a few fundamental concepts always apply. These concepts are independent of the specific API, SDK, or product being used (`ascp`, `ascli`, `transferd`, **Node API**, server REST API, etc.).

2.1 Base rules for a transfer

100% of transfers using Aspera consist of:

- An `ascp` process started in client mode, connecting to a transfer server (SSH or WSS).
- Upon successful connection, an `ascp` process in server mode is started and listens on UDP.
- The connection is direct between client and server using the IP protocol (there can be Aspera proxies in the middle (reverse, forward)), with one TCP connection per transfer session (`ascp` process), and one UDP session.
- Some sort of authorization is required (either just SSH credentials, or a transfer token).
- If the client sends the files, then it is an upload. If the client receives the files, it is a download.
- In all cases, a transfer session is initialized using a ”transfer specification”, a JSON structure (except direct execution of `ascp` which uses command line options).

2.2 Client and server roles

An Aspera transfer always involves two distinct roles:

- Client: the side that initiates the transfer.
- Server: the side that accepts the transfer.

The client may either send data to the server (upload) or retrieve data from it (download), but the direction of the data flow does not change the roles: the initiator is always the client.

2.3 Server-side storage access (docroot / storage root)

The server side is always configured with access to a storage backend.

This is done through:

- a docroot, or
- an access key + storage root (conceptually equivalent).

The server is responsible for accessing the underlying storage, which can be:

- local filesystem storage, or
- supported object storage (via **PVCL**, such as S3-compatible storage, cloud object stores, etc.).

To do this, the server must be provided with appropriate credentials, which depend on the storage type:

- filesystem permissions for local storage,

- cloud/object-storage credentials for object storage.

Without this configuration, a server cannot read or write data, regardless of the client.

2.4 Client types and storage capabilities

The client side can take different forms:

- Simple transfer clients

  Examples: `ascp`, `ascli`, `transferd`, Aspera for Desktop, custom SDK-based clients.

  These clients only support local filesystem storage.

  They do not define a docroot or storage root.

  Files are always read from or written to the local machine where the client runs.

- Servers acting as clients

  An Aspera server can also act as a client.

  In that case:

  - The server-as-client is configured exactly like a server:
    - it defines a docroot (or storage root),
    - it may access object storage,
    - it requires storage credentials.
  - Credentials for object storage are provided either:
    - directly in the docroot URL, or
    - via the access key configuration.

  This allows transfers between two non-local storage systems, such as object storage to object storage.

2.5 Remote control of clients

A client does not need to be manually started by a user. Clients can be remotely controlled:

- A simple client (e.g. `ascli`) can be started remotely via SSH.
- `transferd` exposes a gRPC API that allows remote control of transfers.
- An Aspera server acting as a client can be remotely controlled using its REST API:
  - for example, `POST /ops/transfers` to initiate a transfer.
  - access to this API itself requires proper authentication.

In all cases, the entity triggering the transfer is still the client, even if it is controlled remotely.

2.6 Transfer authorization

To initiate a transfer, the client must be authorized to access the server.

This authorization can take different forms, depending on the environment and API:

- SSH-based credentials (user/password or key): the legacy mode, used for example with Desktop Client or server-to-server transfers,
- transfer tokens (Aspera transfer token, JWT, or similar mechanisms): used for example when a web application manages users.

Without valid authorization, a transfer cannot be started, even if both client and server are correctly configured.

Details, and how to choose a token type: see Transfer authentication and authorization.

2.7 Transfer specification

Besides authorization, other parameters are required when starting a transfer, such as transfer direction, while others are optional, such as target speed.

This document will show session parameters using the standardized JSON format "transfer specification" and refer to session parameters as **transfer spec**. Use of transfer spec is pervasive in Aspera to describe and start a transfer session: this is the native format used in Web SDKs, `transferd`, Node API and `ascli`. Only `ascp` does not support transfer spec (yet), and uses regular command line options.

Example of a simple transfer spec for a download using SSH credentials (without token):

```
{
    "remote_host"     :"hsts1.example.com",
    "ssh_port"        :33001,
    "remote_user"     :"<HSTS1_XFER_USER>",
    "remote_password" :"<HSTS1_XFER_PASSWORD>",
    "direction"       :"receive",
    "destination_root":".",
    "paths":[
        {"source":"/aspera-test-dir-tiny/200KB.1"}
    ]
}
```

An example with transfer authorization token is provided in Token generation.

90% of transfer spec parameters are identical between the various APIs (Node API, `transferd`, Web SDK, ...).

Parameters can be found in the various API definitions, or with the CLI:

```
ascli conf ascp spec
```

2.7.1 Transfer spec version 2

The format above is transfer spec version 1, supported by all APIs. The Transfer Daemon (`transferd`) also accepts transfer spec version 2, a structured format where parameters are grouped in modules:

Module	Content
`session_initiation`	How the session is initiated and authorized: `ssh`, `node_api` or `icos`
`assets`	Source and destination: `destination_root`, `paths`, ...
`security`	Security parameters, e.g. `cipher`
`transport`	Rate policy, target rate, ports, ...
`file_system`	Handling of files and directories being transferred
`tracking`	Asset tracking, e.g. tags

Other parameters are at the top level: `direction`, `remote_host` and `title`.

With `node_api` (Node API URL and credentials) or `icos` (IBM Cloud Object Storage credentials), `transferd` gets the transfer authorization itself: the application does not need to call `/files/*_setup` first.

Example of upload with Node API credentials (sample `node_v2`):

```
{
  "title": "send using Node API and ts v2",
  "direction": "send",
  "session_initiation": {
    "node_api": {
      "url": "https://hsts1.example.com:9092",
      "headers": [
        {"key": "Authorization", "value": "Basic <base64 of
        ↪  <HSTS1_NODE_USER>:<HSTS1_NODE_PASSWORD>>"}
      ]
    }
  },
  "assets": {
```

```
    "destination_root": "/Upload",
    "paths": [{"source": "file.txt"}]
  }
}
```

In this repository, samples with suffix `_v2` use transfer spec version 2. The reference of transfer spec version 2 is provided in the Transfer SDK: `api/transferd.md` (`TransferSpecV2`).

Chapter 3

Transfer clients and tools

3.1 `ascp`

`ascp` is the executable that actually transfers files: all Aspera transfers use it (see Base rules for a transfer).

3.1.1 Client-side minimum components

On the client side, the minimum setup for a FASP transfer consists of two files:

- `ascp` (executable)
- `aspera-license` (free license file, in the same folder as `ascp`, or in `../etc`)

Those files can be found in the `transferd` archive.

They can also be found in free clients.

3.1.2 First `ascp` invocation

Test `ascp` with a few useful options:

```
ascp -A
```

```
IBM TransferD version 1.1.9
ascp version 4.4.8.2592 6a5e6bf
Operating System: MacOSX
License max rate=(unlimited), account no.=1, license no.=56
Enabled settings: stream and sync2
```

```
ascp -h
```

```
ascp -hh
```

```
ascp -DDA
```

```
ascp -DDL-
```

3.1.3 Sample optional config file for client `ascp`

On the client side, it is optionally possible to create a configuration file: `aspera.conf` (in the same folder as `ascp`, or in `../etc`).

Example of configuration file: `aspera.conf`, on client side (optional):

```
<?xml version='1.0' encoding='UTF-8'?>
<CONF version="2">
<default>
    <file_system>
        <resume_suffix>.aspera-ckpt</resume_suffix>
        <partial_file_suffix>.partial</partial_file_suffix>
```

```
        <replace_illegal_chars>_</replace_illegal_chars>
    </file_system>
</default>
</CONF>
```

Smallest configuration file:

```
<CONF/>
```

> **Note**
>
> This file is mandatory on the server side. On Transfer servers, this file is easily modified with the command `asconfigurator`, which is not available in client applications and SDKs.

3.2 Transfer Daemon: `transferd`

The transfer daemon `transferd` provides a gRPC interface for managing transfers. A `proto` definition file is included in the `transferd` package.

3.2.1 Starting up

The daemon must be started in order to manage transfers. It's up to the developer to decide how to start the daemon.

For quick development, the daemon can be started manually in a separate terminal.

For server-level applications, the daemon can be started as a system service (`systemd`).

For end-user applications, the daemon can be started as a background process by the main process.

3.2.2 Examples

Examples in various languages are provided as part of the `transferd` SDK, as well as at:

https://github.com/laurent-martin/aspera-api-examples/tree/main/app

3.3 Web SDK

Transfers started in a web browser use the Aspera Web SDK (JavaScript): see S3.

Reference and sample code: Aspera API Hub → IBM Aspera JavaScript SDK.

A sample web application is provided in the folder `web` of this repository.

3.4 Mobile: Android, iOS

The Mobile SDK is the equivalent of the Transfer SDK for mobile apps (Swift for iOS, Java for Android). It is currently under review.

3.5 CLI: `ascli`

To test most Aspera APIs and transfer authorization types, one can use the open-source tool `ascli`.

See manual for installation.

`ascli`:

- Connects to all types of Aspera servers
- Provides a logging capability that traces API calls
- Starts transfers using either:
  - Transfer SDK
  - `ascp`

- Node API
- Web client (Connect, Aspera for Desktop)
- HTTP Gateway

Examples in this document are illustrated with `ascli`. The developer can monitor internal API calls, as well as the generated transfer spec, using option `--log-level=trace2`.

Chapter 4

Integration Scenarios

This section exhibits various file transfer scenarios.

It shows how a FASP transfer is started using a transfer specification.

The transfer is started using various transfer client types/SDKs (CLI, web, app, server).

The transfer specification may contain transfer authorization using either (see Transfer authentication and authorization):

- SSH credentials
- Authorization token

Any client type and SDK can be used with any type of transfer authorization: they are independent, except that HTTP Gateway and WebSocket sessions require token authorization (see A1).

Scenarios contain a typical mix of client SDK and transfer authorization type.

The following table summarizes the scenarios, and the samples of this repository that implement them (names of the Python samples: refer to the `README.md` of the repository for other languages):

Scenario	Client	API	Authorization	Samples
S1: script and `ascp`	Script	Command line	SSH	
S2: application with Transfer SDK	Custom client application	Transfer Daemon gRPC	SSH	`server`, `server_v2` (JS)
S3: web browser	Web browser	Web SDK	Token	`web`
S4: server to server, SSH	Transfer Server	Node API	SSH	
S5: client and server applications	Custom client application	Transfer SDK, Node API	Token	`node`, `node_v2`, `shares`
S6: server to server, token	Transfer Server	Node API	Token	
S7: transfer status		Node API		


Other samples use the APIs of Aspera applications (`faspex5`, `aoc`): see Aspera applications.

4.1 S1- The simplest integration: start a transfer with a script and `ascp`

Scenarios:

- I need to replace `scp` or `sftp` in a script and use my existing SSH credentials (password or key)
- I am provided with bare Aspera Transfer credentials, and I need to transfer to that server using my scripts.

Client	API	Authorization
script	command line	SSH



S1: script with ascp and SSH credentials

The simplest and lowest-level integration consists of starting an Aspera transfer as a transfer client with a Transfer Server (upload or download). Ultimately, this consists of starting the `ascp` executable in client mode, locally. Credentials required: SSH credentials provided by the admin of the HSTS server. This can be done easily in a script. For example, using bash:

```
#!/bin/bash
ASPERA_SCP_PASS=<HSTS1_XFER_PASSWORD> ascp --mode=recv --host=hsts1.example.com -P 33001 \
  --user=<HSTS1_XFER_USER> aspera-test-dir-tiny/200KB.1 .
```

This starts the `ascp` executable with session parameters on the command line (and an environment variable for the password). `ascp` comes with many session options: a manual can be found in `man ascp` or here: HSTS Doc → ascp command reference. This is suitable for a simple script-based integration, but this solution suffers from the following limitations:

- No easy way to get progress feedback programmatically (progress bar on terminal)
- No automatic retry of failed transfers: the script must implement a loop
- No programmatic API: a process must be spawned with arguments

Equivalent with `ascli`: (includes resume)

```
ascli -N server --url=ssh://hsts1.example.com:33001 \
  --username=<HSTS1_XFER_USER> --password=<HSTS1_XFER_PASSWORD> \
  download aspera-test-dir-tiny/200KB.1
```

Note


Display the generated transfer spec with the additional option `--log-level=debug`.

Equivalent with `asession` (from `aspera-cli` gem), using a transfer spec: (includes progress and resume)

```
asession @json:'{"spec":{
  "remote_host":"hsts1.example.com","remote_user":"<HSTS1_XFER_USER>","ssh_port":33001,
  "remote_password":"<HSTS1_XFER_PASSWORD>","direction":"receive","destination_root":".",
  "paths":[{"source":"/aspera-test-dir-tiny/200KB.1"}]}}'
```

4.2 S2- Start a transfer with Transfer SDK and listen for events

Scenarios:



S2: custom application with Transfer Daemon and SSH credentials

- I need to transfer files at high speed from my home-grown application to a central place using basic OS credentials
- I am provided with bare Aspera Transfer credentials, and I need to transfer to that server using my application written in Java, C++, .NET, Python, etc.

Client	API	Authorization
Custom Client Application	Transfer Daemon gRPC	SSH

If the integration to start a simple transfer job is made in an application written in one of the languages C, C++, C#, Java, Python, Go, Rust, etc., then the best option is to use the newer **Transfer Daemon**. This component can be freely downloaded here: Transfer SDK. It is basically a daemon, `transferd`, that wraps the `ascp` executable, and it comes with examples.

The basic usage of the API is:

- Initialize the library (or gRPC stub)
- Optionally create an event listener
- Create a transfer spec (with all transfer session parameters)
- Start the transfer job
- Monitor the transfer job (events)

The event listener callback will be called every second with statistics and information about the transfer. The same `ascp` executable and `aspera-license` file from previous step can be used (`transferd` package or free client).

Note that in these two possibilities, the transfer is run locally. Development of a mobile app is similar, with the Mobile SDK providing a library to start transfers. The Transfer SDK provides several code examples in several languages.

Other examples: `server` and `server_v2` samples of this repository.

Equivalent with `ascli`:

```
ascli -N server --url=ssh://hsts1.example.com:33001 \
  --username=<HSTS1_XFER_USER> --password=<HSTS1_XFER_PASSWORD> \
  download aspera-test-dir-tiny/200KB.1 --log-level=debug
```


```
...
DEBG transfer agent is a Aspera::Agent::Direct
DEBG ts(json)Hash=
{
  "remote_host": "hsts1.example.com",
  "remote_user": "<HSTS1_XFER_USER>",
  "ssh_port": 33001,
  "remote_password": "🔑",
  "direction": "receive",
  "create_dir": true,
  "resume_policy": "sparse_csum",
  "destination_root": ".",
  "paths": [
    {
      "source": "aspera-test-dir-tiny/200KB.1"
    }
  ]
}
...
DEBG ascp args: #<struct Aspera::ExecSpec exec=:ascp, env={"ASPERA_SCP_PASS" => "🔑", ...},
  args=["-q", "-d", "--mode", "recv", "--host", "hsts1.example.com", "--user", "<HSTS1_XFER_USER>",
  "-k", "2", "-P", "33001", "--dest64", "--file-list=...", "Lg=="]>
...
```

Lots of debug information: look for the transfer spec in the logs. Passwords and secrets are masked in logs by default.

Note

Internally `ascli` uses a ”transfer agent” which can be the bare `ascp`, or Transfer Daemon, or other Aspera components.

4.3 S3- Start a transfer in a web browser



S3: web browser with Web SDK and token authorization

Scenarios:

- I need to transfer files at high speed using a web browser, being authorized by some web application (Custom, Faspex, Shares, AoC, ...)

Typically, authentication/authorization is performed in the web app, and a transfer token is used to authorize transfers.

Client	API	Authorization
Web Browser	Web SDK	Token

If the transfer must be started by a user in the context of a web browser, then the **IBM Aspera JavaScript SDK** can be used (for Aspera for Desktop and HTTP Gateway). It consists of a JavaScript library used similarly to the "Transfer SDK" (build session parameters, start transfer, monitor progress).

Reference (includes sample code): Aspera API Hub → IBM Aspera JavaScript SDK: https://developer.ibm.com/apis/catalog/aspera--ibm-aspera-sdk/Introduction


Example using Aspera for Desktop with `ascli` (here, not in a browser):

```
ascli -N server --url=ssh://hsts1.example.com:33001 \
  --username=<HSTS1_XFER_USER> --password=<HSTS1_XFER_PASSWORD> \
  download aspera-test-dir-tiny/200KB.1 --transfer=desktop
```

The transfer spec remains identical to the previous `ascli` example. Only the transfer agent (`--transfer`) is changed from the local transfer SDK to Aspera for Desktop. Aspera for Desktop is almost exclusively used in a web context: `ascli` is used here as an example only.

4.4 S4- Start a Server-Server transfer with Node API and SSH credentials

Scenarios:



S4: server-to-server transfer with Node API and SSH credentials

- I need to transfer files between two servers in an automated manner or using REST APIs.
- I own the system used as client side (an HSTS), but not the remote system for which I have only SSH credentials.

Machine-to-machine transfer.

Client	API	Authorization
Aspera Transfer Server	Node API	SSH

This is the method used for automated server-to-server transfers. A transfer can be started remotely (using its REST API) on a server to another remote server. There are two servers here: one starts the transfer as client, and connects to the other one. The managing application uses the "Node API" to control the client side of the transfer. Basically: `POST /ops/transfers` with a JSON payload containing session parameters: transfer spec with SSH credentials of the remote server.

Equivalent API call, on the client side of the transfer (`hsts2.example.com`):

```
curl -s -u <HSTS2_NODE_USER>:<HSTS2_NODE_PASSWORD> \
  https://hsts2.example.com/ops/transfers \
  -H 'Content-Type: application/json' \
  -d '{"remote_host":"hsts1.example.com","ssh_port":33001,
    "remote_user":"<HSTS1_XFER_USER>","remote_password":"<HSTS1_XFER_PASSWORD>",
    "direction":"receive","destination_root":".",
    "paths":[{"source":"aspera-test-dir-tiny/200KB.1"}]}'
```

Example of use with `ascli`: (for demonstration of use of API)

```
ascli --url=ssh://hsts1.example.com:33001 \
  --username=<HSTS1_XFER_USER> --password=<HSTS1_XFER_PASSWORD> \
  --transfer=node --transfer-info=@json:'{"url":"https://hsts2.example.com",
    "username":"<HSTS2_NODE_USER>","password":"<HSTS2_NODE_PASSWORD>"}' \
  --log-level=debug server download aspera-test-dir-tiny/200KB.1
```

Note

Option `--transfer=node` tells `ascli` to start the transfer remotely.

In this example, the remote server `hsts2.example.com` is used (as client) to download from server `hsts1.example.com`.

4.5 S5- Start a transfer with Token Authorization


Scenarios:

- I need to transfer files between my custom client app and my custom server app, using my own authentication/authorization.

Client	API	Authorization
Custom Client Application	Transfer SDK (client app) Node API (server app)	Token

In previous examples, transfers were started using SSH credentials and no token, using various client application types: command line, Transfer SDK, browser, server (node) or even mobile. Using SSH credentials, the authentication and transfer authorization are provided by the bare Aspera Server and its host operating system. In fact, in many integration cases, a custom (e.g. web) application server takes care of user authentication and transfer authorization (e.g. RBAC). In this case, once the server application has authenticated and authorized a transfer, it will convey this transfer authorization by generating a "transfer authorization token". Then, the transfer client provides this token to the Aspera server to get authorized to transfer to it. Several token types are supported (Aspera transfer token, Basic, Bearer): see Choosing the right token type. The Aspera transfer token is a simple choice, as no authorization needs to be set up in advance: the server application generates it on the fly with the Node API, after it has checked that the application-level user effectively has rights. Token generation is detailed in A2.

The client application uses one of the SDKs for transfer:



S5: custom client and server applications with token authorization

- Transfer (gRPC)
- Web (JavaScript)
- Mobile (Swift, Java)
- Node (REST)

4.6 S6- Start a Server-Server transfer with Node API and Transfer token

Scenarios:


- I own both systems used for the transfer (both are HSTS), and I use the Node API to get transfer authorization on the destination, and the Node API to initiate the transfer on the source system.

Machine-to-machine transfer.

Client	API	Authorization
Aspera Transfer Server	Node API	Token

This is the method used for automated server-to-server transfers if one owns both servers and token-based transfer is preferred. First the managing application must retrieve a transfer authorization (as well as transfer details, such as server address) using the Node API on the **server side of the transfer**: `POST /files/upload_setup` with transfer request, which generates a transfer spec. Then, the managing application uses the Node API to control the **client side of the transfer**. Basically: `POST /ops/transfers` with transfer spec generated previously.

A common mistake is to call both APIs on the same server: client side. Incidentally, this could work if the transfer username is the same on both sides, and if the `token_encryption_key` is the same on both sides for that transfer user. But in general, it will fail, either because the transfer user is different, or the token cannot be decrypted (different encryption key). So, really, authorization shall first be generated on the server side, and the transfer shall be initiated on the client side.



S6: server-to-server transfer with Node API and transfer token

Equivalent API calls (the first result is edited with `jq`):

```
# 1. server side of the transfer (hsts1): get a transfer spec with an Aspera transfer token
curl -s -u <HSTS1_NODE_USER>:<HSTS1_NODE_PASSWORD> \
  https://hsts1.example.com:9092/files/upload_setup \
  -H 'Content-Type: application/json' \
  -d '{"transfer_requests":[{"transfer_request":{"paths":[{"destination":"/"}]}}]}' \
  | jq '.transfer_specs[0].transfer_spec | .paths = [{"source":"aspera-test-dir-tiny/200KB.1"}]' \
  > transfer_spec.json
# 2. client side of the transfer (hsts2): start the transfer with this transfer spec
curl -s -u <HSTS2_NODE_USER>:<HSTS2_NODE_PASSWORD> \
  https://hsts2.example.com/ops/transfers \
  -H 'Content-Type: application/json' -d @transfer_spec.json
```

Example of use with `ascli`: (for demonstration of use of API)

```
ascli --url=https://hsts1.example.com:9092 \
  --username=<HSTS1_NODE_USER> --password=<HSTS1_NODE_PASSWORD> \
  --transfer=node --transfer-info=@json:'{"url":"https://hsts2.example.com",
    "username":"<HSTS2_NODE_USER>","password":"<HSTS2_NODE_PASSWORD>"}' \
  --log-level=debug node upload aspera-test-dir-tiny/200KB.1
```

Note

Option `--transfer=node` tells `ascli` to start the transfer remotely, on the node specified in `--transfer-info`, as client. In this example, the remote server `hsts2.example.com` is used (as client) to upload to server `hsts1.example.com`.

4.7 S7- Polling on transfer status on Node API

The Node API endpoint: `GET /ops/transfers` provides information on past and current transfers. Such information is stored on HSTS in the Redis database.

Activation and retention are controlled by `aspera.conf` parameters:

Parameter	Description
`activity_retention`	Controls how long data is kept in the database. Default: `1d 12h`
`activity_logging`	Enables the logging of transfer activity in the database. Default: `false`
`activity_*`	Other parameters related to activity logging.

Note

Typically, `activity_retention` can be given a shorter value to keep the database smaller.
`asconfigurator -x "set_server_data;activity_retention,2h"`

By default (no query parameter), it returns information on a number of transfers. Such call returns a response with the `Link` header set:

```
Link: <https://hsts.example.com:9092/ops/transfers?iteration_token=1440571>; rel="next"
```

Calling the URL specified in `Link` will return subsequent results, and so on. To get all information, repeat with the response's `Link` URL until the response is an empty array and the `iteration_token` does not change. When new information is available, a new call will return data and a new `iteration_token`. A number of query parameters allow filtering only necessary information, for example: `active_only=true`. Using query `view=id` will return only transfer IDs, and specific information can be retrieved using `GET /ops/transfers/<id>`.

For example, using `ascli`:

```
ascli node transfer list --query.active_only=true
```

Example of an algorithm to get notifications of transfer progress (pseudo-code):

```
iteration_token = 1
transfers = []
loop do
    response = GET /ops/transfers?iteration_token=#{iteration_token}
    next_token = iteration_token found in response header Link
    if next_token == iteration_token
      # all current responses received: process, then wait
      process(transfers)
      transfers = []
      sleep 5
    else
      # additional transfers received (body is an array): store them and try to get more, before
 ↪  processing all
      transfers.concat(response.body)
      iteration_token = next_token
    end
end
```

Chapter 5

Transfer authentication and authorization

Initiating a transfer session in Aspera requires a valid transfer specification (**transfer spec**), which encapsulates all necessary parameters for the transfer, including **authentication and authorization** details. This applies universally, regardless of the method used to start the session.

All transfers are executed on the server under a designated **transfer user**. The method of authorization is mostly independent of the session initiation mechanism (script, Transfer SDK, Node API, mobile, or web applications), with the exceptions listed below.

Aspera supports multiple authorization mechanisms:

- OS-Level Authentication (SSH-based)
  - Similar to SFTP, this method uses the operating system's user accounts and SSH authentication.
  - Authorization is managed via `aspera.conf`.
  - Commonly used in legacy environments or high-performance computing (HPC) systems where OS-level user control is required.
- Token-Based Authorization
  - Used when user authentication is handled externally (e.g., by a third-party application).
  - Required for modules that do not use SSH authentication, such as:
    - WebSocket Session
    - Legacy HTTP Fallback
    - HTTP Gateway

There are three types of tokens: Aspera Transfer Token (ATx), Basic token and Bearer token. They are compared in the next section, and detailed in A2 and A3.

If a token is provided and SSH is used for transport, the transfer user must have Aspera SSH public key authentication enabled. In this case, SSH authentication relies on public keys, while the corresponding private keys are embedded in the SDK or client applications.

5.1 Choosing the Right Token Type

The three token types reflect two fundamentally different architectural patterns for access control. Choosing the wrong one is a common source of integration failures.

5.1.1 Architecture comparison

	ATx (Aspera Transfer Token)	Basic Token	Bearer Token
Node User	Yes	No	No
Access Key	Yes	Yes	Yes
File addressing	Path-based (Gen3 `/files/*`)	ID-based or Path-based	ID-based (Gen4 `/files/{id}`)
Token generated when	Per transfer request	Permanent (AK credentials)	Once, reused during validity period

	ATx (Aspera Transfer Token)	Basic Token	Bearer Token
Token generated by	Web app via Node API	Client app from AK credentials	Client app using /token endpoint of web app (based on app and user private keys)
Access control	The web app (before calling Node API)	Access Key scope	HSTS directly (via `/permissions`)
Typical use case	Custom web app acting as transfer broker	Simple programmatic access	AoC integration, advanced permission model
Complexity	Medium	Low	High

5.1.2 Decision guide

Use ATx when:

- You are building or integrating with a web application that acts as the entry point for users.
- Access control lives in your application layer.
- You want to work with file paths rather than file IDs.
- You use Node API Users or Access Keys.

Use Bearer Token when:

- You are integrating with Aspera on Cloud (AoC).
- You need permissions to be enforced directly by the HSTS, without a broker.
- You are using Access Keys and the Gen4 `/files/{id}` API.
- You need a single token valid across multiple transfer requests.

Use Basic Token when:

- You have programmatic access to an Access Key and need a lightweight token without calling `*_setup` or generating bearer tokens.
- You are in a controlled environment where the Access Key itself provides sufficient access scoping.

5.2 A1- SSH Authentication

For simple transfer initiation in the client-server or server-server case, no prior application-provided authorization is required. The username / pass or key has been pre-arranged between the server provider and client. See the transfer spec example earlier. This is often used in machine-to-machine transfers where authentication is based on a technical operating system user on the server side and SSH. Transfer authorization is based on a top-level **docroot** specified in `aspera.conf` on the server.

Typical end-user usage: simple client-server. This is the legacy mode of authentication / authorization, like `scp` or `sftp`. In this mode, authentication/authorization is done directly during the transfer session: the transfer server provides the authentication (with the local SSH server) and access control (with `aspera.conf`). No external web application controls user authentication or file access rights. The authentication uses the SSH server (with username + password or SSH private key). File transfers are limited to the user's ”docroot” (`aspera.conf`) and access rights on storage. Only sessions started with SSH support this mode (not WebSocket Session/HTTPS, or HTTP Gateway). Once SSH authentication is done, typically the user can transfer any file with possible limits in `aspera.conf` and file system rights.

5.3 A2- Aspera Transfer Token Authorization

This is the recommended pattern when a **custom web application** (or an Aspera application such as Faspex or Shares) sits between the end user and the HSTS.


The client application **never calls the Node API directly**. Instead:

1. The client authenticates with the web app using whatever mechanism the app supports (SSO, OAuth, cookie, etc.).
2. The client requests a transfer through the web app's own API.
3. The web app enforces its own access control logic, then calls the Node API (`POST /files/upload_setup` or `POST /files/download_setup`) to generate a transfer spec containing a signed ATx token.
4. The web app returns that transfer spec to the client.

5. The client passes the transfer spec directly to the transfer engine (`transferd`, Web SDK, etc.) to execute the transfer.

The HSTS only sees a valid token — it does not know anything about the web app's user model. Access control is entirely the web app's responsibility.

This works with both **Node API Users** and **Access Keys** on the HSTS side.



A2: Aspera transfer token authorization

```
Client App                          Server App                          HSTS
    |──────── app API call ──────────>|                                   |
    |                                 | checks own ACL                    |
    |                                 |──── POST /files/upload_setup ────>|
    |                                 |            Node API               |
    |                                 |                                   |
    |                                 |                  generates ATx token
    |                                 |                                   |
    |                                 |<──── transfer spec + token ───────|
    |<──────── transfer spec ─────────|                                   |
    |                                 |                                   |
    |──── FASP transfer (with token) ──────────(ascp)──────────────────────>|
```

5.3.1 Token generation

When user authentication and authorization are managed by a third-party application, then the application needs to provide the client side with a secure ”token” that will carry the transfer authorization. The application uses the Node API endpoints:

- `/files/upload_setup`
- `/files/download_setup`
- `/files/sync_setup`

This returns a **transfer spec** that can be directly provided to the transfer agent to do the transfer. The authorization is based on an authorization token, generated by the node daemon.

Example:

```
curl -s -u <HSTS2_NODE_USER>:<HSTS2_NODE_PASSWORD> \
  https://hsts2.example.com/files/download_setup \
  -d '{"transfer_requests":[{"transfer_request":{"paths":[{"source":"/aspera/aspera-test-dir-
↪  large/1GB"}]}}]}'
```

```
{ "transfer_specs": [ { "transfer_spec": {
  "paths": [ { "source": "/aspera/aspera-test-dir-large/1GB" } ],
  "source_root": "",
  "destination_root": "",
  "token": "<TOKEN>",
  "direction": "receive",
  "cipher": "aes-128",
  "tags": null,
  "rate_policy_allowed": "fixed",
  "rate_policy": "fair",
  "target_rate_kbps": 100000,
  "min_rate_kbps": 0,
  "remote_host": "hsts2.example.com",
  "remote_user": "xfer",
  "sshfp": "b42dcb718dd3a04c90e160817d40da9af6e8895a",
  "ssh_port": 33001,
  "fasp_port": 33001,
  "http_fallback": true,
  "http_fallback_port": 8443
} } ] }
```

Aspera Transfer tokens start with `AT` and end with `TA`. They are generated using the **Gen3** Node API (`/files/*_setup`). They can also be generated using the utility `astokengen`, but this shall be avoided (legacy).

Generation of Aspera Transfer tokens requires the use of a token encryption key (symmetric) which is either configured statically in `aspera.conf` (`token_encryption_key`) or uses `askms` (dynamic keys). This type of token is simply binary metadata encrypted (and then decrypted) with that key and includes:

- Transfer direction (send/receive, as seen from the server)
- Transfer user
- Date validity
- Hash of authorized file list

When a transfer is initiated with a server and contains such a token, that server checks that each of these elements is valid, otherwise the transfer is refused. This means that in order to be authorized to transfer with a transfer server using such token, the token (and transfer spec) must be generated on that same server (or cluster) using the Node API. The validity period is specified in `aspera.conf` (`token_life_seconds`): 1 day by default.

5.4 A3- Aspera Bearer Token Authorization


This is the more advanced pattern, used when access control should be managed **directly inside the HSTS** rather than in a broker application. It is required for **Aspera on Cloud (AoC)** integration and any integration using the Gen4 file ID API.

Key characteristics:

- An application (Aspera or custom web app) authenticates users and grants access to its OAuth API in web or API context (possibly with an external auth system, like SSO).
- Files are addressed by **file ID**, not by path. The client must first resolve paths to IDs via `GET /files/{id}/files` before transferring.
- **Permissions are set in advance** on the HSTS using `POST /permissions`, associating user identifiers (and optional group identifiers) with specific file IDs and access levels.
- The application generates a **JWT Bearer token** signed with its private key, and provides it to the client. The HSTS validates it using the corresponding public key, configured in advance in the access key. The Bearer token contains the user identifier and group memberships.
- A single token can be generated **once** and reused for its entire validity period — the client does not need to call the Node API per transfer.


When a transfer starts, the HSTS checks that the resource (folder/file) is granted access to the user and group IDs found in the bearer token.

Application	HSTS



The added complexity is the trade-off for eliminating the broker intermediary and gaining a richer, ID-stable permission model suitable for multi-tenant or cloud storage environments.

5.4.1 A3: Scenario



A3: Bearer token authorization

1. The user gets a transfer bearer token for a specific HSTS after authentication to the app.
2. The user uses that bearer token to start transfers. There is no need to re-generate a token for each transfer.
3. The user can also use the bearer token to list files on HSTS directly.
4. Permissions to access files on HSTS are managed out of band, beforehand.

There is no API to generate a full transfer spec directly, but one can use the Gen3 API to generate a base transfer spec on the HSTS, and then change the token in it with the bearer token.

An example of how to configure and generate a bearer token is provided in the `ascli` manual.

The scenario to prepare is:

1. Prepare an Aspera HSTS for use with access keys, and create an access key, for example using the API or `ascli`: https://github.com/IBM/aspera-cli/blob/main/docs/README.md#creating-an-access-key
2. Follow: https://github.com/IBM/aspera-cli/blob/main/docs/README.md#generating-and-using-a-bearer-token

Chapter 6

Aspera applications

For integration with IBM Aspera applications, use their embedded authentication/authorization and APIs: these, in turn, provide the transfer spec (with token) necessary to initiate a transfer.

For more details, refer to Aspera API Hub.

The general flow is the same as seen earlier with the custom client and server.

Aspera Web Apps provide REST APIs. Some are related to transfer authorization, and others are not directly (e.g. list files, create a user, etc.).

6.1 Pattern for all applications

Whatever the application, a transfer follows the same three steps:

1. **Authenticate** to the REST API of the application (OAuth 2.0 bearer token).
2. **Get a transfer spec** with a token from the application (Faspex 5), or build it (AoC), after creating or selecting the resource to send to or receive from (package, shared inbox, folder).
3. **Start the transfer** with a transfer client (Transfer Daemon or Web SDK), using that transfer spec, adding only the local files.

The application authorizes the transfer: do not try to reach the transfer server directly with other credentials.

6.2 Faspex 5

API reference: Faspex 5 OpenAPI (see API definitions).

The sample `faspex5` implements the whole sequence. Implementations (same steps and same log messages in each language):

Language	Sample
Python	faspex5.py
JS	faspex5.js
Go	faspex5.go
Java	Faspex5Send.java
Ruby	faspex5.rb
Rust	faspex5.rs
C++	faspex5.cpp
C#	faspex5.cs

Sending local files in a package, step by step (base URL: `https://<FASPEX5_HOST>/aspera/faspex`):

Step	Call	Result
1. Get a bearer token	`POST /auth/token` with a JWT assertion	Bearer token (re-use until it expires)
2. Find the recipients	`GET /api/v5/contacts?q=<EMAIL>&context=packages`	Recipient name and type; unknown email: `external_user`
3. Create the package	`POST /api/v5/packages` with `title` and `recipients`	Package `id`: this allocates the reception folder
4. Get the transfer spec	`POST /api/v5/packages/{id}/transfer_spec/upload?transfer_type=connect`	Transfer spec with token
5. Prepare the transfer spec	Add `paths` (local files), delete the `authentication` key	Transfer spec for the Transfer Daemon
6. Start the transfer	Transfer Daemon `StartTransfer` (or Web SDK `startTransfer`)	Upload to the package folder

To receive a package, step 4 becomes `POST /api/v5/packages/{id}/transfer_spec/download?transfer_type=connect&type=received`, and the direction of the transfer spec is `receive`. List the packages to receive with `GET /api/v5/packages`.

To send files that are already on a Faspex 5 shared folder (server-side, no local file): after step 3, `POST /api/v5/packages/{id}/remote_transfer` with `shared_folder_id` and `paths`, then poll `GET /api/v5/packages/{id}/upload_details` until `upload_status` is `completed` (or `failed`). No transfer client is needed: the Faspex 5 server does the transfer.

Points to remember:

- `transfer_type=connect` gives a transfer spec that works with the Transfer Daemon and the Web SDK. Use `http_gateway` only for a client that must use the HTTP Gateway.
- The transfer spec has an `authentication` key that the Transfer Daemon does not use: the samples remove it.
- Check the permissions of the calling user: sending to external users or to some recipient types may be refused.

6.2.1 Authentication

Faspex 5 uses OAuth 2.0 for authentication and authorization: a Bearer token shall be used for REST API calls. For automated operations, the bearer token shall be obtained using a JWT (JSON Web Token) signed with a private key.

The first step for a client application is to get a client ID and secret from Faspex 5. This is done in the Faspex 5 web interface, in the ”API Clients” section.

This client ID and secret, together with the private key, are used to obtain a bearer token by calling the Faspex 5 API endpoint `/token`. Refer to the Faspex 5 documentation for details, or to the `faspex5` sample.

A user generates, once, a private/public key pair. The public key is configured in Faspex 5 in the user's profile or in the API client configuration. The private key is used to sign the JWT token, which is then sent to the Faspex 5 API endpoint `/token` to obtain a bearer token. Refer to the `faspex5` sample.

The JWT assertion sent to `/auth/token` uses these claims, with the key pair of the user:

Claim	Value
`iss`	The client ID of the API client
`aud`	The client ID of the API client
`sub`	`user:<USERNAME>`

Other claims: `iat`, `nbf`, `exp` (short validity) and `jti` (unique identifier). The JWT is signed with RS256, with the private key of the user.

The token request is `POST /auth/token`, with the form parameters `grant_type` (`urn:ietf:params:oauth:grant-type:jwt-bearer`), `client_id` and `assertion` (the signed JWT), and the client ID and client secret of the API client as HTTP Basic authentication. The response contains `access_token`.

Once the bearer token is generated, it can be used to call the Faspex 5 REST API endpoints.

6.2.2 Transfers (send/receive packages)

Faspex 5 provides a REST API to manage transfers, including sending and receiving packages.

The first step is to create a transfer spec using the Faspex 5 API. This transfer spec is either for sending a new package, in that case one must first create a package, or for receiving an existing package, identified by a unique ID. A user can list received packages, and then select one to download. The Faspex 5 API provides endpoints to create a transfer spec for sending or receiving packages.

The second step is to use the transfer spec to start the transfer using one of the Aspera transfer agents (Transfer Daemon, Node API, ...).

6.3 IBM Aspera on Cloud

Similar to Faspex 5, AoC uses OAuth 2.0 for authentication and authorization, using API client ID and secret and `/token` with JWT and private key.

There is no endpoint to create a transfer spec directly, but a transfer spec can be built relatively easily: refer to the `aoc` sample.

API reference: AoC OpenAPI (see API definitions).

AoC uses two levels of bearer tokens (see A3):

- a token for the AoC API (scope `user:all`),
- a token for the transfer server (node) that holds the files (scope `node.<ACCESS_KEY>:user:all`), in the `token` of the transfer spec.

Both are obtained the same way: JWT signed with the private key of the user, sent to the same token endpoint.

Implementations (same steps and same log messages in each language):

Language	Sample
Python	aoc.py
JS	aoc.js
Java	Aoc.java
Ruby	aoc.rb
Rust	aoc.rs
C++	aoc.cpp
C#	aoc.cs

Sending local files to a shared inbox, step by step (base URL: `https://api.ibmaspera.com/api/v1`):

Step	Call	Result
1. Get an API token	`POST /oauth2/<ORG>/token`, JWT assertion, scope `user:all`	Bearer token for the AoC API
2. Get the user	`GET /self`	User name and email (for the cookie)
3. Find the workspace	`GET /workspaces?q=<NAME>`	Workspace `id`
4. Find the shared inbox	`GET /dropboxes?current_workspace_id=<ID>&q=<NAME>`	Shared inbox `id`

Step	Call	Result
5. Create the package	`POST /packages` with `workspace_id`, `recipients` (type `dropbox`), `name`, `sent`, `transfers_expected`	Package `id`, `node_id`, `contents_file_id`
6. Get the node	`GET /nodes/{node_id}`	Node `host` and `access_key`
7. Get a node token	Same token request, scope `node.<ACCESS_KEY>:user:all`	Bearer token for the node
8. Build the transfer spec	See below	Transfer spec
9. Start the transfer	Transfer Daemon `StartTransfer` (or Web SDK `startTransfer`)	Upload to the package folder

The transfer spec of step 8 contains:

Parameter	Value
`direction`	`send`
`token`	The node token of step 7
`remote_host`	`host` of the node
`remote_user`, `ssh_port`, `fasp_port`	`xfer`, `33001`, `33001`
`cookie`	`aspera.aoc:<APP>:<USER_NAME>:<USER_EMAIL>`, each of the three values in base64 (`APP` is `packages`)
`tags.aspera.app`	`packages`
`tags.aspera.node`	`access_key` of the node, `file_id`: `contents_file_id` of the package
`tags.aspera.files`	`node_id`, `package_id`, `package_name`, `package_operation`: `upload`, `files_transfer_action`: `upload_package`, `workspace_id`, `workspace_name`
`paths`	The local files

The `tags` are mandatory: `node` tells the transfer server which access key and folder the token authorizes, and `app` and `files` let AoC link the transfer to the package. `usage_id` and `xfer_retry` are optional.

Points to remember:

- The `aud` claim of the JWT is specific to AoC (see the sample), and `sub` is the email of the user.
- The sample creates the package with `sent: true` and `transfers_expected` (number of transfer sessions). These two parameters can also be set later with `PUT /packages/{id}`.
- The sample generates new tokens at each run: in real code, re-use the token until it expires.

6.4 IBM Aspera Shares

Same API as Node API (internally, Shares calls the Node API for transfer spec generation). API reference: Shares OpenAPI (admin APIs), and the Node API for transfers (see API definitions).

Chapter 7

Node API

7.1 Overview

The **IBM Aspera Node API** is a RESTful web service that runs directly on an Aspera server (referred to as a *node*). It provides full programmatic control over the Aspera transfer server environment, enabling developers to manage files, control transfers, configure access, and monitor activity — all over a standard HTTP/HTTPS interface with a JSON-encoded API.

The Node API is part of **IBM Aspera High-Speed Transfer Server and Endpoint** and acts as a daemon process that exposes endpoints for:

- Remote file operations (browse, create, delete, rename, search)
- Initiating and managing high-speed uploads and downloads (via FASP protocol or HTTP fallback)
- Access and permissions management
- Node monitoring and reporting

The Node API is designed to complement other Aspera APIs, enabling seamless integration with the broader Aspera ecosystem.

API reference: Node API OpenAPI (see API definitions).

7.2 What Can You Do With the Node API?

Capability	Description
Access Management	Manage user access to the node's file system and transfer capabilities
File Transfer	Upload and download files using the FASP protocol or HTTP/HTTPS fallback
Transfer Control	Start, stop, resume, and reconfigure transfers
File Management	Create, delete, rename, search, and browse files and directories
Monitoring	Retrieve node info, available space, transfer events, and bandwidth/volume stats

7.3 Supported Node Types

The Node API is available on several types of Aspera servers:

Node Type	Description
IBM Aspera High-Speed Transfer Server (HSTS)	Self-managed Aspera transfer server
IBM Aspera High-Speed Transfer Endpoint (HSTE)	Self-managed limited version of HSTS
Aspera on Cloud (AoC) Transfer Service (ATS)	Aspera's cloud-based SaaS hosted service (IBM-managed HSTS clusters)

7.4 Network Interface & Port Configuration

The Node API daemon listens on both HTTP and HTTPS interfaces:

Protocol	Default Port	Default Activation
HTTPS	9092	Yes
HTTP	9091	No

> **Note**
>
> Port numbers and activation are configurable through `aspera.conf`. If facing the Internet, it is recommended to place a reverse proxy, such as `nginx`, in front of the Node API.

7.5 Authentication

The Node API supports the following authentication mechanisms and types, described in the next sections:

- Basic Authentication
  - Node Users
    - Transfer Node Users
    - Master Node Users
  - Access Keys
    - Primary Access Keys
    - Sub Access Keys
- Bearer token

7.5.1 Basic Authentication

Standard username + password credentials.

There are two main types of node credentials: Node Users and Access Keys.

7.5.2 Node Users

Managed via the `asnodeadmin` utility.

Example: Creation of a node user with `asnodeadmin`:

```
asnodeadmin -a -u <API username> -p <API password> -x <OS user>
```

Example: List existing node users:

```
asnodeadmin -l
```

Node users are always associated with a **Transfer User**, which is an OS-level user. It represents the OS user under which transfers are executed when started or authorized using the Node API. The file system access rights of this user apply (not applicable to object storage).

There are two types of Node Users: **Transfer Node User** and **Master Node User**. The type is related to the configuration of their Transfer User (exclusive): a docroot, or file restrictions. Refer to the HSTS manual section: ”Docroot vs. File Restriction”. In both cases, Node API calls and transfers are ”jailed” either in the docroot, or in the storage root of the access key.

7.5.3 Transfer Node User

Node Users with a **docroot** (`absolute`): they can be used to manage transfers directly, but not to create Access Keys. The **docroot** is associated with the Transfer user, in `aspera.conf`, modified with `asconfigurator`. The **docroot** is defined as a PVCL URL, which can range from a local file system to object storage (e.g. S3).

! Caution

Cannot be used to integrate with **Aspera on Cloud** which requires Access Keys.

7.5.4 Master Node User

Node Users without a docroot, but with **file restrictions** (which can be open, like `*`). The **file restrictions** are associated with the Transfer user, in `aspera.conf`, modified with `asconfigurator`. It is used to create Access Keys. It cannot be used for transfers. There is usually a single Master Node User, but there can be more if necessary, if distinct restrictions are needed. The Master Node User is usually associated with the transfer (OS) user: `xfer`, but it is not mandatory.

! Caution

If Access Keys created with this Master Node User are to be used with Aspera on Cloud, or Aspera Enterprise Web Apps, then it is mandatory to name the transfer user as `xfer`.

7.5.5 Access Keys

Created and managed through the Node API using a Master Node User. A storage root is associated with it, and must comply with the file restriction associated with the Master Node User used to create it. AoC provides an API (ATS) to create access keys on SaaS nodes.

7.5.6 Primary Access Keys

Those are created using the Node API, using a **Master Node User**.

The **storage root** is defined as a JSON in the `storage` key of the access key. The storage `type` can be `local` (local file system), or object storage (e.g. S3).

7.5.7 Sub Access Keys

Those are created using the Node API, using a **Primary Access Key**. The storage `type` is `local`, and the `path` is relative to the storage root of the associated Primary Access Key. The `path` cannot be `/`: it must be a sub-folder within the Primary Access Key's storage root.

7.5.8 OAuth2 Bearer Tokens

Token-based authentication used for integration with cloud services like **Aspera on Cloud (AoC)**. Bearer tokens are always associated with an Access Key. Use of the newer `/files/{id}` endpoint group is required (aka Gen4). Bearer tokens contain a user "identifier", managed by the upper level managing application, as well as optional group identifiers.

Access to file resources is granted on the Access Key with the `/permissions` endpoint by providing user and group identifiers and access levels. A sample scenario is provided in the aspera-cli manual.

7.6 API Endpoint Reference

7.6.1 File Management Endpoint Groups

The Node API provides two distinct groups of file management endpoints. Understanding the difference is important when choosing the right approach for your integration.

7.6.1.1 Group 1 — `/files/{id}`

The **next-generation, Aspera-recommended** file management endpoints. Manage files by their unique **file ID**. Sometimes referred to as Gen4.

Endpoint	Purpose
`GET /files/{id}`	Get metadata for a file or directory
`GET /files/{id}/files`	List contents of a directory
`POST /files/{id}/files`	Create a file or directory
`PUT /files/{id}`	Rename or modify a file or directory
`DELETE /files/{id}`	Delete a file or directory

This requires the use of an Access Key.

File IDs are automatically managed by the node daemon providing the Node API, and are stored in a Redis Database of HSTS together with permissions.

Advantages:

- Manage files by ID (not path), making operations more robust
- Supports **bearer token authentication** (required for AoC integration)
- Provides more powerful glob filtering for search and browse
- **Strongly recommended for cloud-based nodes** due to significantly better performance

7.6.1.2 Group 2 — `/files/*`

An earlier set of file management endpoints (legacy, still supported). Manage files by their **file path**. Sometimes referred to as Gen3.

Endpoint	Purpose
`POST /files/browse`	Browse a directory by path
`POST /files/create`	Create a file or directory
`POST /files/delete`	Delete a file or directory
`POST /files/rename`	Rename a file or directory
`POST /files/search`	Search for files by path

Limitations:

- Supports only **Node API credentials or access keys** — no bearer token support
- `/files/browse` and `/files/search` can be **very slow** on cloud storage nodes

> **Important**
>
> For cloud-based nodes, always prefer `/files/{id}/files` over `/files/browse`.

7.7 Requests & Responses

The Node API follows standard REST conventions.

7.7.1 HTTP Methods

The API uses standard HTTP verbs: `GET`, `POST`, `PUT`, `DELETE`, and others as appropriate per endpoint.

7.7.2 Request Format

All request bodies must be encoded as **JSON**. For example, the body of `POST /ops/transfers` is a transfer spec, typically generated by `/files/upload_setup` on the remote server (see S6):

```
POST /ops/transfers HTTP/1.1
Host: <node-host>:9092
Authorization: Basic <base64-credentials>
Content-Type: application/json
```

```
{
  "direction": "send",
  "remote_host": "hsts2.example.com",
  "remote_user": "xfer",
  "token": "ATM2_...",
  "paths": [{ "source": "/local/file.txt" }]
}
```

7.7.3 Response Codes

Status Code	Meaning
`200 OK`	Request succeeded
`201 Created`	Resource created successfully
`202 Accepted`	Request accepted, processing is asynchronous
`204 No Content`	Request succeeded, no response body
`400 Bad Request`	Malformed request
`401 Unauthorized`	Missing or invalid credentials
`403 Forbidden`	Valid credentials, but access denied
`404 Not Found`	Resource not found
`409 Conflict`	State conflict (e.g., duplicate resource)
`500 Internal Server Error`	Server-side failure
`503 Service Unavailable`	Service temporarily unavailable

7.8 Error Handling

When a request fails, the server returns a structured JSON error object:

```
{
  "error": {
    "code": 404,
    "reason": "Not Found",
    "user_message": "Transfer activity logging disabled"
  }
}
```

7.8.1 Developer Notes

- Always check the returned JSON for an `error` field when the HTTP status code is not `2xx`.
- Some known errors may cause the API to return an **empty JSON object** `{}` instead of an error body — your client code should handle this case explicitly.
- Do not rely solely on the HTTP status code for error detection.

```
// Example: defensive error checking in JavaScript
// (the body is empty for 204 No Content)
const text = await response.text();
const data = text ? JSON.parse(text) : {};
if (!response.ok || data.error || (response.status !== 204 && Object.keys(data).length === 0)) {
  throw new Error(data?.error?.user_message ?? `Unknown error from Node API: HTTP
  ↪ ${response.status}`);
}
```

7.9 Typical Use Cases

7.9.1 Health Check

Verify the node is responsive before initiating operations.

```
GET /ping
```

7.9.2 Node Configuration Discovery

Retrieve node configuration — important because some nodes require specific key-value pairs in requests.

```
GET /info
```

7.9.3 Access Management

Create access keys and configure permissions for bearer token users.

```
POST /access_keys
POST /permissions
```

7.9.4 File System Operations

Browse and manage files on the node.

```
GET    /files/{id}/files    → list directory contents
POST   /files/{id}/files    → create a file or directory
PUT    /files/{id}          → rename a file or directory
DELETE /files/{id}          → delete a file or directory
```

7.9.5 Transfer Operations

Initiate transfers between nodes or stream data.

```
POST /ops/transfers         → start a transfer
GET  /ops/transfers/{id}    → monitor transfer progress
GET  /ops/transfers/bandwidth → monitor bandwidth usage
```

7.9.6 Monitoring & Reporting

```
GET  /events      → node events (transfer start, file creation, permission changes)
GET  /usage       → transfer volume
POST /space       → available disk space (HSTS only)
```

Chapter 8

Troubleshooting

8.1 Find where the problem is

A transfer involves three steps, and each one fails in its own way:

1. **Get authorization**: REST calls to an application or to the Node API. Failure: HTTP error, or an error JSON. No transfer has started yet.
2. **Start the session**: the client `ascp` connects to the server (SSH or WSS, TCP). Failure: authentication or authorization error, the session stops at once.
3. **Move the data**: UDP between the two `ascp`. Failure: the session starts, but no data moves, or the rate is very low.

Increase the log level, in this order:

What	How
REST calls of the samples	`misc.level: debug` in the configuration file: shows each request and response (secrets are masked, unless `misc.show_secrets: true`)
Transfer spec	Same: displayed at `debug` level
`transferd`	`trsdk.level: debug`, and the `.out` and `.err` files of the daemon
`ascp`	`trsdk.ascp_level: debug` (or `trace`), or `ascp -DDL-` on the command line
The same transfer spec, outside of your code	`ascli`, for example `ascli -N server --url=ssh://hsts1.example.com:33001 ...` (see S1)

If a transfer works with `ascp` or `ascli` and not in your code, compare the two transfer specs.

8.2 Common problems

Symptom	Likely cause	What to do
`transferd` or `ascp` does not start, or reports a license problem	`ascp` has no license file	Check `ascp -A`: the `aspera-license` file must be in the same folder as `ascp`, or in `../etc` (see Client-side minimum components)
The session starts, then no data moves, or it ends on a timeout	The UDP port (`fasp_port`, `33001` by default) is blocked by a firewall	Open UDP in both directions between client and server. The TCP port (`ssh_port`) works, so authentication succeeds: the problem is only on UDP
Authentication error with a token	Wrong token type for the API, token generated for another access key or node, or expired token	See Choosing the Right Token Type. Do not mix a token of one type with the file addressing of another (path for ATx, file ID for bearer)

Symptom	Likely cause	What to do
Authentication error with a token, while SSH works	The transfer user does not accept token authentication over SSH	Enable Aspera SSH public key authentication for the transfer user (see Transfer authentication and authorization)
HTTP Gateway or WebSocket session refused	These need a token: SSH credentials do not work	Use token authorization (see A1)
The transfer starts then fails with a permission or access error	The destination is outside the docroot or storage root, the user cannot write there, or (bearer token) no permission was granted on the folder	Check the docroot or access key, the transfer user, and `POST /permissions` for the bearer token (see A3)
`401` from `/auth/token` of Faspex 5	API client not set up, public key not configured for the user, or wrong `sub`	Check the client ID and secret, and that `sub` is `user:<USERNAME>` (see Faspex 5)
`401` from the token endpoint of AoC	Wrong `org`, `aud` or `sub`, or public key not set in the AoC user profile	Check the values with the `aoc` sample (see Aspera on Cloud)
The transfer works, but the package does not show the files (AoC)	Missing `tags`, or wrong `package_id` or `node_id` in them	Rebuild the transfer spec as in the `aoc` sample
Faspex 5 transfer spec refused by the Transfer Daemon	The `authentication` key was left in the transfer spec	Remove it, as the samples do
Node API returns `{}` or an unexpected empty body	Some known errors have no error body	Treat an empty JSON as an error (see Error Handling)
Certificate error calling an HTTPS API	Self-signed certificate on a test server	In the samples, set `verify: false` for this server in the configuration file. In production, install the CA certificate: do not disable verification
A rate lower than expected	The license, `aspera.conf` or the transfer spec (`target_rate_kbps`) limit the rate, or the network is the limit	Check the license limit with `ascp -A`, then the rate parameters of the transfer spec and the server

8.3 Before asking for help

Collect:

- the versions: `ascp -A` (shows `transferd` and `ascp`), and the server version,
- the transfer spec, **without secrets and tokens**,
- the `ascp` log at `debug` level (`ascp_level`),
- which step fails: authorization, session start, or data transfer.

End of document