
DISASTER RECOVERY PROCEDURE

For Internal Use Only

MAY 24, 2017

NLYTE SOFTWARE

2800 Campus Drive | Suite 135 | San Mateo, CA 94403

TABLE OF CONTENTS

Acronyms	ii
Document Revision History	iii
Overview	1
Making the Decision to Failover.....	1
Prerequisites and Expectations	1
Identifying the Nlyte Databases	3
Nlyte SQL Engine Databases and SQL Analysis Services Cubes.....	3
Databases to Include in Backup Plan	3
Databases to be Synched via Log Shipping, Database Mirroring, or AlwaysOn	4
Identifying Your Environment.....	5
Shared Alias Name Examples	5
Dedicated Alias, FQDN, IP, and Hostname-Based Environments	5
Dedicated Alias Name Examples	5
Pre-Failover Procedures	7
Failing Over	12
Failover Procedure	12
List of Nlyte Databases.....	13
List of SQL Permissions Required by the SQL and Windows Service Accounts used by Nlyte	14
Post-Failover Procedures.....	15
Testing and Troubleshooting.....	20
Nlyte Support Contact Information	20

TABLE OF FIGURES

Figure 1: Nlyte Configuration Page	7
Figure 2: LDAP Screen	8
Figure 3: Permissions Screen.....	9
Figure 4: Editing User Groups.....	9
Figure 5: LDAP – LDAP Root Page	10
Figure 6: Dashboards and Reports Page	10

For Internal Use Only

Figure 7: Dashboard and Reports – Dashboards URL Page	11
Figure 8: Discover Page	11
Figure 9: Configuration Table	13
Figure 10: Nlyte Vir URL	15
Figure 11: LDAP Authentication Screen	16
Figure 12: Group Locations Page	16
Figure 13: Edit User Groups	17
Figure 14: LDAP Root Screen	17
Figure 15: Dashboard and Reports Screen	18
Figure 16: Dashboards and Reports – Dashboards URL Screen	18
Figure 17: Discover – Service Location Screen	19
Figure 18: Resetting IIS Screen	19

ACRONYMS

Term	Definition
AlwaysOn AG	Availability Groups
AlwaysOn FCI	Failover Clustering Instances
BI	Business Intelligence
DBA	Database Administrator
DNS	Domain Name Servers
DR	Disaster Recovery
FQDN	Fully Qualified Domain Name
IIS	Internet Information Services
LDAP	Lightweight Directory Access Protocol
SQL	Structured Query Language
SSO	Single Sign On
UI	User Interface

DOCUMENT REVISION HISTORY

Version	Date	Author	Comment
0.1	05/16/2017	C. Abaunza	Document creation
0.2	05/17/2017	Documentation Specialist	Format, proof document
1.0	05/24/2017	Documentation Specialist	Finalize and PDF

OVERVIEW

The purpose of this document is to provide the Nlyte Administrator with the needed steps required to switch/failover from the Nlyte PROD environment to the Nlyte disaster recovery (DR) environment (or vice versa). The purpose, reason, or necessity to perform a switch-over is typically caused by a planned or unplanned event.

Event	Example
Planned event	Nlyte installations, upgrades, and patches
Unscheduled event	Unscheduled system outages affecting access to, from, and between Nlyte servers, services, and users.

MAKING THE DECISION TO FAILOVER

Failing over can be an extensive process and may use a lot of time and resources. Establishing rules and procedures for "If and When" to failover is recommended. For example, performing a complete failover may take 30 minutes from start to completion. This may not be the best option if the outage is only scheduled for approximately 10 minutes *or* has a resolution time of approximately 10 minutes (accidental reboot of the primary SQL¹ or IIS² server). Establishing a well-balanced set of rules and procedures is encouraged.

PREREQUISITES AND EXPECTATIONS

The Nlyte Failover guide relies on several prerequisites and expectations from the customer.

Keep in mind the following information:

- Log Shipping, Database Mirroring, and/or AlwaysOn (AG or FCI) Database syncing from the primary environment's (PROD) SQL/business intelligence (BI) servers to the secondary environment's (DR) SQL/BI servers are already set up/in-place and in operational status.
- The Nlyte Failover guide does not include instructions on how to set up, disconnect, reconnect/re-establish, or bringing online Databases when setup for Log Shipping, Database Mirroring, or AlwaysOn (AG or FCI) Database Syncing.
- The Nlyte Failover guide does not provide instructions on SQL Server Database Backup and Restore procedures.
- A Database Administrator or System's Administrator with knowledge of managing Database backups/restores, Log Shipping, Database Mirroring, and/or AlwaysOn (AG or FCI) is recommended to set up, manage, and monitor the primary and secondary SQL server operations.
- Both the PROD and DR environments have their own dedicated Nlyte IIS/App server.
- A full/complete failover is the only recommended procedure.

¹ Structured Query Language

² Internet Information Services

For Internal Use Only

- A Database Backup Plan is a requirement to protect data in the event of data corruption. A failover environment will not protect against data corruption in most cases and therefore should not be a substitute to a Database Backup Plan.

IDENTIFYING THE NLYTE DATABASES

Developing and implementing a backup plan/strategy is recommended.

Backup procedures, schedules, and plans vary from one customer to the next and even between database administrator (DBA) teams. Therefore, it is up to the customer (DBA) to implement a backup plan/strategy. In the event there are no established backup plans or procedures, consider the following minimum recommendations:

- A comprehensive backup plan consists of full daily/nightly backups **or** full native backups taken at least once a week with incremental backups taken daily.
- As previously mentioned, a database backup plan is a requirement to protect data in the event of data corruption. A Failover Environment will not protect against data corruption in most cases and should not be a substitute to a database backup plan.

NLYTE SQL ENGINE DATABASES AND SQL ANALYSIS SERVICES CUBES

The following table displays a list of databases and service cubes.

MS SQL Engine Databases	MS SQL Analysis Service Cube
Nlyte	Nlyte
NlyteContent	
NlyteDataWarehouse	
NlyteDashboard	
NlyteDashboardWarehouse	
NlyteAudit	

DATABASES TO INCLUDE IN BACKUP PLAN

Although not listed below, the Nlyte SQL analysis cube may be optionally backed up. The Nlyte cube can be rebuilt by running the Nlyte Business Intelligence Installer and is, therefore, not as critical as the databases listed below.



Note: Some databases listed below may not exist depending on the customer's Nlyte license.

- Nlyte
- NlyteContent
- NlyteAudit (if Nlyte Audit module is used)
- NlyteDataWarehouse (if Nlyte Business Intelligence module is used)
- NlyteDashboard (if Nlyte Dashboards module is used)
- NlyteDashboardWarehouse (if Nlyte Dashboards module is used)

DATABASES TO BE SYNCHED VIA LOG SHIPPING, DATABASE MIRRORING, OR ALWAYS ON

The following databases should be synched via log shipping, database mirroring, or AlwaysOn:

- Nlyte
- NlyteContent
- NlyteAudit (If Nlyte Audit module is used)
- NlyteDataWarehouse (If Nlyte Business Intelligence module is used)
- NlyteDashboard (if Nlyte Dashboards module is used)
- NlyteDashboardWarehouse (if Nlyte Dashboards module is used)

IDENTIFYING YOUR ENVIRONMENT

For load balancer and shared alias-based environments, proceed to **Failing Over**, page 12, and then **Testing and Troubleshooting**, page 20, if the Nlyte environments (PROD and DR) use shared domain name servers (DNS) aliases for all connections between the Nlyte servers (Nlyte Web UI³, IIS server, SQL server, BI server, etc.).

SHARED ALIAS NAME EXAMPLES

The following table represents an environment where a Load Balancer and/or manual DNS switchover redirects from PROD to DR systems or vice versa. If such an environment applies to your Nlyte Environment, go to **Failing Over**, page 12.

PROD and DR Nlyte Web UI Alias	http://DCIM/nlyte
PROD and DR IS Server Alias name	DCIM
PROD and DR SQL Server Alias name	DCIMSQL
PROD and DR BI Server Alias name	DCIMBI

DEDICATED ALIAS, FQDN, IP, AND HOSTNAME-BASED ENVIRONMENTS

Proceed to **Pre-Failover Procedures**, page 7, and review all sections of this guide if the Nlyte environments (PROD and DR) use fully qualified domain name (FQDN), Hostname, IP, or dedicated DNS aliases for all connections between the Nlyte servers (Nlyte Web UI, IIS server, SQL server, BI server, etc.).

DEDICATED ALIAS NAME EXAMPLES

The following table is an example of aliases; however, it is also applicable to FQDN, Hostname, and IP.

PROD Nlyte Web UI Alias	http://DCIMPROD/nlyte
DR Nlyte Web UI Alias	http://DCIMDR/nlyte
PROD IS Server Alias	DCIMPROD
DR IS Server Alias	DCIMDR
PROD SQL Server Alias	DCIMPRODSQL
DR SQL Server Alias	DCIMDRSQL

³ User Interface

For Internal Use Only

PROD BI Server Alias	DCIMPRODBI
DR BI Server Alias	DCIMDRBI

The scenario above represents an environment where each server-to-server connection is using a dedicated connection name. A Load Balancer may still exist in the above example to disable access to the primary environment and bring online the secondary environment. Users connect to PROD and DR using unique/different Nlyte URLs when accessing PROD vs. DR. This section also applies to an environment where a simpler URL redirects the user to the more complex URL normally used by Nlyte.

For example: the user types *http://DCIM* in a web browser and it redirects the user to URL *http://DCIMPROD.domain.local/nlyte*.

PRE-FAILOVER PROCEDURES

Perform the steps in this section on PROD and DR prior to setting up Log Shipping/DB Mirroring/AlwaysOn (AG or FCI) between PROD and DR prior to a failover.


If Log Shipping/DB Mirroring/AlwaysOn (AG or FCI) are setup and running, replace the server name (FQDN) in the URL from PROD's IIS/App server name to DR's IIS/App server name (or vice versa). The information captured in this section will be used during a failover from PROD to DR or vice versa.

FQDN URL Example: `http://NlytePRODSERVERNAME.domain.local/Nlyte`



*Note: If an alias (DNS/Load Balancer) is used to switch to/from PROD and DR to access the Nlyte URLs, **skip** this section and continue to [Failing Over](#), page 12. Alias URL Example: `http://DNSAliasName/Nlyte`*

1. Login to the PROD Nlyte Web UI.
2. Open the Nlyte Administration module (gear icon).
3. Navigate to **Configuration**.
4. Click **General**.
5. Note the **Nlyte Vir** URL for later use once switching back to PROD from the DR server.
 - a. Verify the end of the URL ends with `"/`.



The screenshot shows the Nlyte Configuration Page with the 'General' tab selected in the left sidebar. The 'Nlyte Vir' field is highlighted with a red box, showing the URL 'http://localhost/nlyte/'. Other fields visible include 'CY symbol' (set to '\$'), 'Datacenter grid references' (set to 'FloorPlanner'), 'Default measurement system' (set to 'Imperial'), 'Location mandatory for new asset' (unchecked), 'Mandated language' (set to 'MandatedLanguage'), 'Network card port name control' (set to 'DropDownList'), and 'Use Google Maps on macOS' (unchecked).

Figure 1: Nlyte Configuration Page

For Internal Use Only

6. In **Configuration**, go to **LDAP**⁴.
7. From **LDAP Authentication**, note the preferred Nlyte UI login method selected to access the Nlyte Application.
 - a. Off = Nlyte Managed/FORMS Authentication
 - b. Mixed = Windows Authentication (SSO⁵) primary and Nlyte Managed/FORMS Authentication secondary
 - c. On = Windows Authentication (SSO) only
 - d. External = Third Party Authentication (example = CA SiteMinder)




Figure 2: LDAP Screen



Note: If not using Windows Authentication or External Authentication with Nlyte, go to Step 13.

⁴ Lightweight Directory Access Protocol

⁵ Single Sign On

For Internal Use Only

8. If using the Nlyte GroupSync Module to Authenticate (SSO), go to **Permissions**.
9. Go to **Group locations**.
10. Click **Edit user groups**.
11. Note each **Nlyte Group Name** and **LDAP URL** string for that group.
12. Verify each URL points to the correct Security Group and Active Directory/LDAP server as it may differ if the PROD and DR systems are in different Domains or communicate to a different LDAP server(s).




Figure 3: Permissions Screen

Edit user groups			
* Name	LDAP	Email	
Admin	LDAP://localhsot:389/CN=NLYTE_A...	NLYTE_...	✗
Full Access			✗
Power Users	LDAP://localhsot:389/CN=NLYTE_P...	NLYTE_...	✗
View Only Users	LDAP://localhost:389/CN=NLYTE,O...	NLYTE_...	✗
			✗


Figure 4: Editing User Groups



*Note: If using the GroupSync module (Steps 8-12) **or** not using Windows Authentication or External Authentication with Nlyte, go to Step 16.*

For Internal Use Only

13. If using the older LDAP sync Module in Nlyte to use Windows or External Authenticate (SSO), click **LDAP** in the **Configuration** section.
14. In **LDAP root**, note the **LDAP URL** string.
15. Verify that the URL points to the correct Active Directory server (if PROD LDAP server differs from DR LDAP server).



Configuration | Customization | Permissions | Policy | Record reset

Q Search ...

Admin
Alarms
Cabinet
Content database
Dashboard and reports
Discover
General
Heat and power
Integration
LDAP
Policy

LDAP authentication: mixed


LDAP root: LDAP://localhost:389/CN=Nlyte,OU=Groups,DC=domain,DC=local,DC=com

Figure 5: LDAP – LDAP Root Page



Note: If not using Nlyte Reporting Module, go to Step 20.

16. Navigate to **Configuration**.
17. Click **Dashboards and reports**.
18. In **Reports URL**, note the Reports URL.
19. The default SSRS instance for report server services URL ends in "ReportServer."



Configuration | Customization | Permissions | Policy | Record reset

Q Search ...

Admin
Alarms
Cabinet
Content database
Dashboard and reports
Discover
General
Heat and power

Dashboards show toolbar: ☐

Dashboards URL: http://localhost/NlyteDashboards

Dashboards viewer URL: DashboardsViewerURL

Report URL: http://localhost/ReportServer


Figure 6: Dashboards and Reports Page



Note: If not using Nlyte Dashboards Module, go to Step 22.

For Internal Use Only

20. From **Configuration**, go to **Dashboards and reports**.
21. In **Dashboards URL**, note the Dashboards URL.




The screenshot shows the 'Configuration' tab selected in the top navigation bar. On the left, a sidebar menu has 'Dashboard and reports' highlighted with a red box. The main content area shows several configuration options: 'Dashboards show toolbar' (checkbox), 'Dashboards URL' (text field with value 'http://localhost/NlyteDashboards', highlighted with a red box), 'Dashboards viewer URL' (text field with value 'DashboardsViewerURL'), and 'Report URL' (text field with value 'http://localhost/ReportServer').

Figure 7: Dashboard and Reports – Dashboards URL Page



Note: If not using Nlyte Discover, skip Steps 22 and 23.

22. In **Configuration**, go to **Discover**.
23. In **Service Location**, verify the URL points to the Discover Service.



The screenshot shows the 'Configuration' tab selected. The sidebar menu has 'Discover' highlighted with a red box. The main content area shows configuration options: 'Automatic creation' (checkbox), 'Automatic mapping' (checkbox checked), 'Max suggestions' (text field with value '5'), 'Service location' (text field with value 'http://localhost:1023/Gdcm.Nlyte.Integration.NlyteControl.IntegrationService/Discover', highlighted with a red box), and 'Service location auto update' (checkbox checked).

Figure 8: Discover Page

FAILING OVER

Depending on the type of failover event, follow the below procedure:

- If the failover event is planned, perform Steps 1-4.
- If the failover event is unplanned, skip Step 1 and perform Steps 2-4.

FAILOVER PROCEDURE

1. The DBA disables/disconnects the Log shipping/DB Mirroring/AlwaysOn (AG or FCI) connection from PROD to DR (or vice versa).
2. The DBA brings online the databases on the DR environment (or PROD if failing over back to PROD from DR).
3. From the active environment, navigate to SQL server agent (or task scheduler if SQL server agent is not used) on the server where the Nlyte ETL jobs reside (SQL or BI).
4. Enable the ETL main job if planning to use the DR environment for longer than a day.



*Note: For Dedicated Alias, FQDN, IP, and Hostname Based Environments **only**, go to Step 5.*

5. Connect to the SQL/BI Server where the nlyteDataWarehouse database resides.
6. Locate the **dbo.SSIS Configuration** table.
7. Right-click the table and select **Edit Top 200 Rows**.

For Internal Use Only

8. Modify the following:

Table	Action
ConnSource	Modify the Data Source to point to the SQL Server hosting the "Nlyte" Database
ConnDW	Modify the Data Source to point to the SQL Server hosting the "NlyteDataWarehouse" Database
ConnNlyteCube	Modify the Data Source to point to the SQL Analysis Server hosting the "Nlyte" Cube
ConnSourceGDCMWorkflow	Modify the Data Source to point to the SQL Server hosting the "Nlyte" Database
ConnArchive	Modify the Data Source to point to the SQL Server hosting the "NlyteDataWarehouse" Database
ETL	Modify the Data Source to point to the SQL Integration Server hosting the "Nlyte" SSIS Package Files
ConnReportServer	Modify the Data Source to point to the SQL Server hosting the "ReportServer" Database
ConnDundasBI	Modify the Data Source to point to the SQL Server hosting the "NlyteDashboard" Database

Configuration-Item	ConfiguredValue
ConnSource	Data Source=LOCALHOST;Initial Catalog=nlyte;Provider=SQLNCLI11;Application Name=nlyte Analytics;Auto Translate=False;Integrated Security=SSPI;
ConnDW	Data Source=LOCALHOST;Initial Catalog=nlyteDataWarehouse;Provider=SQLNCLI11;Application Name=nlyte Analytics;Auto Translate=False;Integrated Security=SSPI;
ConnErrorLog	0
CommonConfiguration	
ConnNlyteCube	Data Source=LOCALHOST;Initial Catalog=nlyte;Provider=MSQLAP4;Integrated Security=SSPI;Impersonation Level=Impersonate;
CommonConfiguration	0
CommonConfiguration	
CommonConfiguration	
ConnSourceGDCMWorkflow	Data Source=LOCALHOST;Initial Catalog=nlyte;Provider=SQLNCLI11;Application Name=nlyte Analytics;Auto Translate=False;Integrated Security=SSPI;
RealtimePartitioning Processing	Uvw Fact Real Time Asset
RealtimePartitioning Processing	nlyte
RealtimePartitioning Processing	DsvNlyteDW
ProjectKeyLastLoaded	0
ConnArchive	Data Source=LOCALHOST;Initial Catalog=nlyteDataWarehouse;Provider=SQLNCLI11;Application Name=nlyte Analytics;Auto Translate=False;Integrated Security=SSPI;
RealtimePartitioning Processing	Uvw Fact Real Time Power Distribution Devices;Uvw Fact Real Time Power Usage Effectiveness
SSASProcess	nlyte
ETL	LOCALHOST
ETL	1
SSASProcess	DsvNlyteDW
SSASProcess	NlyteBI_RealTime
SSASProcess	NlyteBI_Workflow
ConnReportServer	Data Source=LOCALHOST;Initial Catalog=ReportServer;Provider=SQLNCLI11;Application Name=nlyte Analytics;Auto Translate=False;Integrated Security=SSPI;
RunMainETLPowerContainer	1
RunMainETLNetworkContainer	1
RunMainETLWorkflowContainer	1
RunMainETLRealTimeContainer	1
RunMainETLPredictContainer	1
RunMainETLCustomFieldsContainer	1
ConnDundasBI	Data Source=LOCALHOST;Initial Catalog=nlyteDashboard;Provider=SQLNCLI11;Application Name=nlyte Analytics;Auto Translate=False;Integrated Security=SSPI;
ConnNEO	
NULL	NULL

Figure 9: Configuration Table

LIST OF NLYTE DATABASES

- Nlyte
- NlyteContent
- NlyteAudit (if Nlyte Audit module is used)
- NlyteDataWarehouse (if Nlyte Business Intelligence module is used)
- NlyteDashboard (if Nlyte Dashboards module is used)
- NlyteDashboardWarehouse (if Nlyte Dashboards module is used)


LIST OF SQL PERMISSIONS REQUIRED BY THE SQL AND WINDOWS SERVICE ACCOUNTS USED BY NLYTE

- "db_owner" Role for SQL and Service accounts used for running the Nlyte Application, Nlyte Services, IIS Application Pools, and Proxy Accounts
- "db_reader, db_writer, and execute" for accounts used by Nlyte Data Sources in SSRS

POST-FAILOVER PROCEDURES

Follow the post-failover procedures after successfully completing the **Failover Procedure**, page 12.

1. Login to the Nlyte Web UI.
2. Open the **Nlyte Administration** module (Gear icon).
3. Navigate to **Configuration**.
4. Click **General**.
5. Verify the **Nlyte Vir** URL points to the correct alias/web server name.
 - a. Ensure the end of the URL ends with **"/"**.
6. If it does not, click **Edit**, type the correct link, and click **Save**.



Configuration Customization Permissions Policy Record reset

Q Search ...

Admin
Alarms
Cabinet
Content database
Dashboard and reports
Discover
General
Heat and power
Integration
LDAP
Policy
SMTP
Trace
Workflow

CY symbol * \$?

Datacenter grid references FloorPlanner ?

Default measurement system Imperial ?

Location mandatory for new asset ☐ ?

Mandated language MandatedLanguage ?

Network card port name control DropDownList ?

Nlyte Vir * http://localhost/nlyte/ ?

Use Google Maps on macOS ☐ ?

Figure 10: Nlyte Vir URL

For Internal Use Only

7. In **Configuration**, go to **LDAP**.
8. From **LDAP Authentication**, verify the preferred Nlyte UI login method is selected to access the Nlyte Application.
 - a. Off = Nlyte Managed/FORMS Authentication
 - b. Mixed = Windows Authentication (SSO) primary and Nlyte Managed/FORMS Authentication secondary
 - c. On = Windows Authentication (SSO) only
 - d. External = Third Party Authentication (example = CA SiteMinder)




Figure 11: LDAP Authentication Screen



Note: If not using Windows Authentication or External Authentication with Nlyte, go to Step 13.

9. If using the Nlyte GroupSync Module to Authenticate (SSO), go to **Permissions**.
10. Go to **Group locations**.
11. Click **Edit user groups**.
12. Verify the LDAP URL settings are correct for each Nlyte Group. Each URL should point to the correct Security Group and Active Directory/LDAP server.




Figure 12: Group Locations Page


Edit user groups			
* Name	LDAP	Email	
Admin	LDAP://localhost:389/CN=NLYTE_A...	NLYTE_...	✗
Full Access			✗
Power Users	LDAP://localhost:389/CN=NLYTE_P...	NLYTE_...	✗
View Only Users	LDAP://localhost:389/CN=NLYTE,O...	NLYTE_...	✗
			✗

Figure 13: Edit User Groups



*Note: If using the GroupSync module **or** not using Windows Authentication or External Authentication with Nlyte, skip Step 13.*

13. If using the older LDAP sync module in Nlyte to use Windows or External Authenticate (SSO), go to **LDAP** in **Configuration**.
14. In **LDAP root**, verify **LDAP URL** settings are pointing to the correct Active Directory server.



The screenshot shows the Nlyte Configuration interface. The top navigation bar includes 'Configuration', 'Customization', 'Permissions', 'Policy', and 'Record reset'. The left sidebar lists various configuration categories: Admin, Alarms, Cabinet, Content database, Dashboard and reports, Discover, General, Heat and power, Integration, **LDAP** (highlighted with a red box), and Policy. The main content area is titled 'LDAP authentication' and shows a 'mixed' dropdown menu. Below this, the 'LDAP root' field is highlighted with a red box, displaying the URL 'LDAP://localhost:389/CN=Nlyte,OU=Groups,DC=domain,DC=local,DC=com' with a red asterisk and a help icon.


Figure 14: LDAP Root Screen



Note: If not using Nlyte Reporting Module, go to Step 18.

For Internal Use Only

15. Navigate to **Configuration**.
16. Click **Dashboards and reports**.
17. In **Reports URL**, verify the URL points to the correct SQL reporting services server reports service URL.
 - a. The Default SSRS Instance for report server services URL ends in "ReportServer."



Configuration Customization Permissions Policy Record reset

Search ...

Admin
Alarms
Cabinet
Content database
Dashboard and reports
Discover
General
Heat and power

Dashboards show toolbar ☐ ?

Dashboards URL ?

Dashboards viewer URL ?


Report URL ?

Figure 15: Dashboard and Reports Screen



Note: If not using Nlyte Dashboards Module, go to Step 20.

18. From **Configuration**, go to **Dashboards and reports**.
19. In **Dashboards URL**, verify the URL points to the correct dashboards URL.



Configuration Customization Permissions Policy Record reset

Search ...

Admin
Alarms
Cabinet
Content database
Dashboard and reports
Discover
General

Dashboards show toolbar ☐ ?

Dashboards URL ?

Dashboards viewer URL ?

Report URL ?

Figure 16: Dashboards and Reports – Dashboards URL Screen



Note: If not using Nlyte Discover, go to Step 22.

For Internal Use Only

20. From **Configuration**, go to **Discover**.
21. In **Service Location**, verify the URL points to the Discover Service.




Figure 17: Discover – Service Location Screen

22. After all changes have been made and saved, restart IIS and retest accessing the Nlyte Application. Nlyte should function with no errors.




Figure 18: Resetting IIS Screen

TESTING AND TROUBLESHOOTING

1. Login to Nlyte and perform a simple use test of all commonly accessed/used modules.
2. If errors appear, please review the guide again and verify all steps were followed.
3. Last, if all steps were followed and errors are still present, contact Nlyte Support.
4. On the server where the Nlyte ETL jobs reside (SQL or BI), monitor the ETL main job and verify it runs successful the next day.
5. If the job fails or failed during its scheduled run time, contact Nlyte Support.

NLYTE SUPPORT CONTACT INFORMATION

For questions or concerns, contact Nlyte Support via email or phone.

support@Nlyte.com

UK: +44 208 8777 222

US: +1 866 386 5983