
Tranalyzer2

netflowSink



Output to any NetFlow collector



Tranalyzer Development Team

CONTENTS

Contents

1	netflowSink	
	1.1	Description
		Dependencies
	1.3	Configuration Flags
	1.4	Example

1 netflowSink

1.1 Description

This plugin is an interface of Tranalyzer to a NetFlow collector.

1.2 Dependencies

1.2.1 Other Plugins

This plugin requires the basicFlow, basicStats and tcpFlags plugins. In addition, the macRecorder plugin is recommended, but optional.

1.3 Configuration Flags

The following flags can be used to control the output of the plugin:

Name	Default	Description
NF_SERVADD	"127.0.0.1"	Destination address
NF_DPORT	9995	Destination port
NF_SOCKTYPE	0	Socket type: 0: UDP; 1: TCP
NF_VER	9	NetFlow version 9 or 10 (IPFIX)
NF_NUM4FLWS	200	Max # of IPv4 flows in one message
NF_NUM6FLWS	100	Max # of IPv6 flows in one message

1.3.1 Environment Variable Configuration Flags

The following configuration flags can also be configured with environment variables (ENVCNTRL>0):

- NF_NUM4FLWS
- NF_NUM6FLWS
- NF_SERVADD
- NF_DPORT

1.4 Example

To collect T2 flow data with **nfcapd**, use the following command:

nfcapd -T all -B 1000000 -n wurst, 127.0.0.1,.