


(a) A component without sources



(b) Driven by the current J



(c) The current plane




$y_e = c_e\, J$ for every resistor e of T_j:

$$dy_{e,+\dot{+}} \wedge dy_{e,+\dot{-}} = c_e^2\, dJ_{+\dot{+}} \wedge dJ_{+\dot{-}} + c_e\, dc_e \wedge \left(J_{+\dot{+}}\, dJ_{+\dot{-}} - J_{+\dot{-}}\, dJ_{+\dot{+}}\right)$$

$$\implies (dy_{e,+\dot{+}} \wedge dy_{e,+\dot{-}}) \wedge (dy_{f,+\dot{+}} \wedge dy_{f,+\dot{-}}) = 0$$

(d) $|T_j| = 1$: two resistors in series



both resistors carry J;

no current depends on $t_{uA} : t_{uB}$