inst.eecs.berkeley.edu/~cs61c

CS61C: Machine Structures

Lecture 5 – Introduction to MIPS Assembly language: Arithmetic



2014-09-10

Lecturer: Miki Lustig

Reformatting a Machine 125 Million Miles Away! Mars rover "Opportunity" got its flash drive reformatted 9/8/14, reason: rover keeps rebooting.






Happy news: It worked!

Review

- ·Pointers and arrays are virtually same
- •C knows how to increment pointers
- ·C is an efficient language, with little protection
- · Array bounds not checked
- · Variables not automatically initialized
- Use handles to change pointers
- Dynamically allocated heap memory must be manually deallocated in C.
- · Use malloc() and free() to allocate and deallocate memory from heap.
- · (Beware) The cost of efficiency is more overhead for the programmer.
 - · "C gives you a lot of extra rope but be careful not to hang yourself with it!"





Assembly Language

- Basic job of a CPU: execute lots of instructions.
- Instructions are the primitive operations that the CPU may execute.
- Different CPUs implement different sets of instructions. The set of instructions a particular CPU implements is an *Instruction Set Architecture*
 - •Examples: Intel 80x86 (Pentium 4), IBM/Motorola PowerPC (old Macintosh), MIPS, Intel IA64, ...



Book: Programming From the Ground Up



"A new book was just released which is based on a new concept - teaching computer science through assembly language, to be exact). This book teaches how the machine itself operates, rather than just the language. I've found that the key difference between mediocre and excellent programmers is whether or not they know assembly language. Those that do tend to understand computers themselves at a much deeper level. Although [almost!] unheard of today, this concept isn't really all that new -- there used to not be much choice in years past. Apple computers came with only BASIC and assembly language, and there were books available on assembly language for kids. This is why the old-timers are often viewed as 'wizards': they had to know assembly language programming." -- slashdot.org comment, 2004-02-05



Instruction Set Architectures

- Early trend was to add more and more instructions to new CPUs to do elaborate operations
 - VAX architecture had an instruction to multiply polynomials!
- RISC philosophy (Cocke IBM, Patterson, Hennessy, 1980s) ·

Reduced Instruction Set Computing

- ·Keep the instruction set small and simple, makes it easier to build fast hardware.
- ·Let software do complicated operations by composing simpler ones.



MIPS Architecture

- •MIPS semiconductor company that built one of the first commercial RISC architectures
- •We will study the MIPS architecture in some detail in this class (also used in upper division courses CS 152, 162, 164)
- •Why MIPS instead of Intel 80x86?
 - MIPS is simple, elegant. Don't want to get bogged down in gritty details.
 - MIPS widely used in embedded apps, x86 little used in embedded, and more embedded computers than PCs



Most HP Laserjet workgroup printers are driven by MIPS-based™ 64-bit processors.

Garcia, Spr

Assembly Variables: Registers (1/4)

- Unlike HLL like C or Java, assembly cannot use variables
 - ·Why not? Keep Hardware Simple
- Assembly Operands are registers
 - limited number of special locations built directly into the hardware
 - ·operations can only be performed on these!
- Benefit: Since registers are directly in hardware, they are very fast (faster than 1 nano second - light travels 30cm in 1 ns!!!)

Assembly Variables: Registers (2/4)

- •Drawback: Since registers are in hardware, there are a predetermined number of them
 - •Solution: MIPS code must be very carefully put together to efficiently use registers
- •32 registers in MIPS
 - ·Why 32? Smaller is faster
- Each MIPS register is 32 bits wide
 - ·Groups of 32 bits called a word in MIPS

CS61C LO5 Introduction to MIPS Assembly Language : Arithmetic ()

Garcia, Spring 2014 ©

Assembly Variables: Registers (3/4)

- •Registers are numbered from 0 to 31
- •Each register can be referred to by number or name
- Number references:

\$0, \$1, \$2, ... \$30, \$31

Cal

Assembly Variables: Registers (4/4)

- By convention, each register also has a name to make it easier to code
- •For now:

\$16 - \$23→ \$s0 - \$s7

(correspond to C variables)

\$8 - \$15 → \$t0 - \$t7

(correspond to temporary variables)

Later will explain other 16 register names

•In general, use names to make your code more readable

Garcia, Spring 2014 © UC

C, Java variables vs. registers

 In C (and most High Level Languages) variables declared first and given a type

•Example:
int fahr, celsius;
char a, b, c, d, e;

- Each variable can ONLY represent a value of the type it was declared as (cannot mix and match int and char variables).
- In Assembly Language, the registers have no type; operation determines how register contents are treated

CS61C L05 Introduction to MIPS Assembly Language : Arithmetic

Garcia, Spring 2014 © UCI

Comments in Assembly

- Another way to make your code more readable: comments!
- Hash (#) is used for MIPS comments
 - anything from hash mark to end of line is a comment and will be ignored
 - •This is just like the C99 //
- •Note: Different from C.
 - ·C comments have format

/* comment */

so they can span many lines



Garcia, Spring 2014 © U

Assembly Instructions

- In assembly language, each statement (called an Instruction), executes exactly one of a short list of simple commands
- Unlike in C (and most other High Level Languages), each line of assembly code contains at most 1 instruction
- •Instructions are related to operations (=, +, -, *, /) in C or Java
- •Ok, enough already...gimme my MIPS!



MIPS Addition and Subtraction (1/4)

•Syntax of Instructions:

One two, three, four

where:

- 1) operation by name
- 2) operand getting result ("destination")
- 3) 1st operand for operation ("source1")
- 4) 2nd operand for operation ("source2")
- •Syntax is rigid:
 - ·1 operator, 3 operands



Barcia, Spring 2014 © L

Cal

Addition and Subtraction of Integers (2/4)

Addition in Assembly

•Example: add \$s0,\$s1,\$s2 (in MIPS)

Equivalent to: a = b + c (in C)

where C variables ⇔ MIPS registers are:

a ⇔ \$s0, b ⇔ \$s1, c ⇔ \$s2

Subtraction in Assembly

•Example: sub \$s3,\$s4,\$s5 (in MIPS)

Equivalent to: d = e - f (in C)

where C variables \Leftrightarrow MIPS registers are: $d \Leftrightarrow$ \$s3, $e \Leftrightarrow$ \$s4, $f \Leftrightarrow$ \$s5

Addition and Subtraction of Integers (3/4)

•How to do the following C statement?

$$a = b + c + d - e;$$

Break into multiple instructions

add \$t0, \$s1, \$s2 # temp = b + cadd \$t0, \$t0, \$s3 # temp = temp + dsub \$s0, \$t0, \$s4 # a = temp - e

- Notice: A single line of C may break up into several lines of MIPS.
- Notice: Everything after the hash mark on each line
 is ignored (comments)

Garcia, Spring 2014 © UCE

Addition and Subtraction of Integers (4/4)

•How do we do this?

$$f = (g + h) - (i + j);$$

Use intermediate temporary register

add \$t0,\$s1,\$s2 # temp = g + hadd \$t1,\$s3,\$s4 # temp = i + jsub \$s0,\$t0,\$t1 # f = (g+h) - (i+j)



Garcia, Spring 2014 © UCE

Immediates

- •Immediates are numerical constants.
- They appear often in code, so there are special instructions for them.
- •Add Immediate:

```
addi $s0,$s1,10 (in MIPS)

f = g + 10 (in C)

where MIPS registers $s0,$s1 are associated with C variables f, g
```

Sarcia, Spring 2014 © L

Immediates

- •There is no Subtract Immediate in MIPS: Why?
- Limit types of operations that can be done to absolute minimum
 - •if an operation can be decomposed into a simpler operation, don't include it
 - ·addi ..., -X = subi ..., X => so no subi
- *addi \$s0,\$s1,-10 (in MIPS)

f = g - 10 (in C)

where MIPS registers \$s0,\$s1 are associated with C variables f, g



Register Zero

- One particular immediate, the number zero (0), appears very often in code.
- So we define register zero (\$0 or \$zero) to always have the value 0; eg

add \$s0,\$s1,\$zero (in MIPS)

f = g (in C)

where MIPS registers \$s0,\$s1 are associated with C variables f, g

•defined in hardware, so an instruction

add \$zero,\$zero,\$s0



arcia, Spring 2014 ©

Peer Instruction

- Since there are only 8 local (\$s) and 8 temp (\$t) variables, we can't write MIPS for C exprs that contain > 16 vars.
- 2) If p (stored in \$s0) were a pointer to an array of ints, then p++; would be addi \$s0 \$s0 1

a) FF
b) FT
c) TF
d) TT
e) dunno



"And in Conclusion..."

•In MIPS Assembly Language:

- ·Registers replace C variables
- ·One Instruction (simple operation) per line
- ·Simpler is Better
- ·Smaller is Faster

•New Instructions:

add, addi, sub

•New Registers:

C Variables: \$s0 - \$s7

Temporary Variables: \$t0 - \$t9

Garcia, Spring 2014 © UCE