

4 Working With Structure And Internal Table

4.1 Tujuan

Setelah melaksanakan Praktikum ini mahasiswa diharapkan dapat:

- 1. Memahami konsep tipe objek data struktur
- 2. Memahami konsep internal table dalam ABAP
- 3. Membuat program sederhana dengan menggunakan struktur dan internal table.

4.2 Praktek

4.2.1 Membuat program Z##_SELECT_SFLIGHT (select loop)

- 1. Buat Program dengan nama Z##_SELECT_SFLIGHT (## ganti dengan NPM) tanpa "TOP Include".
- Deklarasikan sebuah tipe strukutr lokal dengan nama Z##_SBC400F0CC dengan komponen sebagai berikut:

Komponen	Tipe
Carrid	s_carr_id
connid	s_conn_id
Fldate	s_date
Seatsmax	s_seatsmax
Seatsocc	s_seatcocc
Percentage	P decimals 2, length 3

Solusi:

```
TYPES: BEGIN OF z10578094_sbc400focc,
carrid TYPE s_carr_id,
connid TYPE s_conn_id,
fldate TYPE s_date,
seatsmax TYPE s_seatsmax,
seatsocc TYPE s_seatsocc,
percentage(3) TYPE p DECIMALS 2,
END OF z10578094 sbc400focc.
```

3. Definisikan sebuah work area dengan nama wa flight untuk tipe struktur di atas.

Solusi:

```
DATA wa flight TYPE z10578094 sbc400focc.
```

4. Buar parameter input dengan nama pa_car dengan tipe s_carr_id.

Solusi:

```
PARAMETERS pa car TYPE s carr id.
```

ABAP Programming Modul Praktikum I

5. Buat select loop untuk mengambil data dari tabel sflight lalu disimpan dalam wa_flihgt, dihitung persentasi penumpang pada setiap penerbang, lalu ditampilkan ke layar.

Solusi:

```
SELECT carrid connid fldate seatsmax seatsocc
FROM sflight
INTO CORRESPONDING FIELDS OF wa_flight
WHERE carrid = pa_car.


*menghitung persentase okupasi untuk setiap penerbangan

wa_flight-percentage = wa_flight-seatsocc / wa_flight-seatsmax.


WRITE: / wa_flight-carrid,
wa_flight-connid,
wa_flight-fldate,
wa_flight-seatsmax,
wa_flight-seatsmax,
wa_flight-seatsocc,
wa_flight-percentage.
```

6. Jalankan program tersebut

ENDSELECT.







Solusi lengkap:

```
*& Report Z10578094 SELECT SFLIGHT
*&
* &
* &
* &
REPORT z10578094_select_sflight.
TYPES: BEGIN OF z10578094 sbc400focc,
carrid TYPE s_carr_id,
connid TYPE s_conn_id,
fldate TYPE s_date,
seatsmax TYPE s_seatsmax,
seatsocc TYPE s seatsocc,
percentage (3) TYPE p DECIMALS 2,
 END OF z10578094_sbc400focc.
DATA wa_flight TYPE z10578094_sbc400focc.
PARAMETERS pa car TYPE s carr id.
SELECT carrid connid fldate seatsmax seatsocc
  FROM sflight
  INTO CORRESPONDING FIELDS OF wa flight
  WHERE carrid = pa_car.
*menghitung persentase okupasi untuk setiap penerbangan
  wa flight-percentage = wa flight-seatsocc / wa flight-seatsmax.
```



```
WRITE: / wa_flight-carrid,
    wa_flight-connid,
    wa_flight-fldate,
    wa_flight-seatsmax,
    wa_flight-seatsocc,
    wa_flight-percentage.
ENDSELECT.

IF sy-subrc NE 0.
    WRITE: ' No ', pa_car, 'flight found !'.
ENDIF.
```

4.2.2 Membuat program Z##_SELECT_SFLIGHT_ITAB (menggunakan struktur dan internal tabel)

- 1. Buat Program dengan nama Z##_SELECT_SFLIGHT_ITAB (## ganti dengan NPM) tanpa "TOP Include".
- 2. Deklarasikan sebuah tipe strukutr lokal dengan nama Z##_SBC400F0CC dengan komponen sebagai berikut:

Komponen	Tipe
Carrid	s_carr_id
Connid	s_conn_id
Fldate	s_date
Seatsmax	s_seatsmax
Seatsocc	s_seatcocc

Solusi:

```
TYPES: BEGIN OF z10578094_sbc400focc, carrid TYPE s_carr_id, connid TYPE s_conn_id, fldate TYPE s_date, seatsmax TYPE s_seatsmax, seatsocc TYPE s_seatsocc, END OF z10578094 sbc400focc.
```

3. Buat sebuah local internal table type dengan row type Z##_SBC400FOCC (structure type yang dibuat sebelumnya), dengan key type non-unique, dan key component carrid, connid, dan fldate.

Solusi:

```
TYPES z10578094_t_sbc400focc
TYPE STANDARD TABLE OF z10578094_sbc400focc
WITH NON-UNIQUE KEY carrid connid fldate.
```

4. Definisikan sebuah variabel internal tabel dengan nama ITAB_Z##_SBC400FOCC dari table type lokal Z##SBC400FOCC (table type yang dibuat sebelumnya).



Solusi:

```
DATA itab z10578094 sbc400focc TYPE z10578094 t sbc400focc.
```

5. Definisikan sebuah work area dengan nama wa_flight untuk variabel struktur yang memiliki tipe yang sama dengan line type dari internal tabe ITAB_Z##_SBC400FOCC.

Solusi:

```
DATA wa_flight LIKE LINE OF itab_z10578094_sbc400focc.
```

6. Buar parameter input dengan nama pa car dengan tipe s carr id.

Solusi:

```
PARAMETERS pa_car TYPE s_carr_id.
```

- 7. Lakukan perintah select terhadap tabel sflight untuk field carrid, connid, fldate, seatsmax, seatsocc untuk ditamping dalam wa_flight dimana carrid = pa_car.
- 8. Insert wa_flight ke dalam internal tabel ITAB_Z##_SBC400FOCC untuk menampung semua nilai yang ada

Solusi:

```
SELECT carrid connid fldate seatsmax seatsocc
FROM sflight
INTO CORRESPONDING FIELDS OF wa_flight
WHERE carrid = pa_car.
INSERT wa_flight INTO TABLE itab_z10578094_sbc400focc.
ENDSELECT.
```

9. Lalu tampilkan nilai yang ada pada internal tabel ITAB_Z##_SBC400FOCC tersebut.


Solusi:


```
LOOP AT itab_z10578094_sbc400focc INTO wa_flight.
    WRITE: / wa_flight-carrid,
    wa_flight-connid,
    wa_flight-fldate,
    wa_flight-seatsmax,
    wa_flight-seatsocc.
ENDLOOP.
```

10. Jalankan program tersebut

Solusi:







Solusi lengkap:



```
TYPES: BEGIN OF z10578094 sbc400focc,
carrid TYPE s carr id,
connid TYPE s conn id,
fldate TYPE s date,
seatsmax TYPE s seatsmax,
seatsocc TYPE s seatsocc,
END OF z10578094 sbc400focc.
TYPES z10578094 t sbc400focc
TYPE STANDARD TABLE OF z10578094 sbc400focc
WITH NON-UNIQUE KEY carrid connid fldate.
DATA itab z10578094 sbc400focc TYPE z10578094 t sbc400focc.
DATA wa flight LIKE LINE OF itab z10578094 sbc400focc.
PARAMETERS pa car TYPE s carr id.
SELECT carrid connid fldate seatsmax seatsocc
 FROM sflight
 INTO CORRESPONDING FIELDS OF wa flight
 WHERE carrid = pa car.
 INSERT wa_flight INTO TABLE itab_z10578094_sbc400focc.
ENDSELECT.
IF sy-subrc = 0.
 LOOP AT itab_z10578094_sbc400focc INTO wa flight.
   WRITE: / wa flight-carrid,
   wa flight-connid,
   wa flight-fldate,
   wa flight-seatsmax,
   wa flight-seatsocc.
  ENDLOOP.
ELSE.
 WRITE: ' No ', pa car, 'flight found !'.
ENDIF.
```