

Manifest Operations Manual

How Legend of Toys and Solve Factory run every China import together, and how to do it on the system.

LOT SOLVE FACTORY ADMIN

Version	Updated	Application
1.1.0	2026-06-18	manifest.legendoftoys.com

Contents

GETTING STARTED

Welcome to Manifest	4
Signing In & Getting Around	5
Who Does What	7
The Shared Pool, in Plain English	9

THE ORDER LIFECYCLE

How an Order Flows	12
Step 1 - LOT Requests an Order /orders	14
Step 2 - SF Converts to a PO & Places It /orders	15
Step 3 - Vendor PI & the Advance	17
Step 4 - Production, Pickup & Cancelling	19

SHIPMENTS

How Shipments Work (Air vs Sea)	22
Creating a Shipment /shipments	24
Managing a Shipment /shipments	26
Shipping Costs & Last-Mile Delivery	28

MONEY

LOT to SF Payments & Draw-downs /payments	31
Invoicing & Closing an Order	33
The Running Account & Exchange Rates /recon	35

WORKSPACE & ADMIN

Orders List, Search & Documents /orders	38
Admin - Access, Roles, Timeline & Partners /admin	40
Generating a China PO or Invoice /orders	43

PART 1

Getting Started

What Manifest is, how to sign in and get around, who does what, and the one shared pool of money.

Welcome to Manifest

LOT

SOLVE FACTORY

ADMIN

Manifest is the shared workspace where Legend of Toys (LOT) and Solve Factory (SF) run every China import together. It replaces the old WhatsApp-and-spreadsheet way of tracking orders and money with one live system both sides can see.

WHAT IT'S FOR Tracking China orders end to end, with one shared money pool.	WHO USES IT LOT SOLVE FACTORY	TWO SIDES LOT requests & funds. SF runs the lifecycle.	LIVE Always current; dates stamp automatically.
---	--	--	---

The idea in one paragraph

LOT asks for what it needs and puts money into a shared pool. SF takes it from there: it raises the purchase order with the Chinese vendor, pays the vendor, ships the goods, clears customs, delivers to LOT's warehouse, and finally invoices LOT to close the order. Everything is tracked live, with a full timestamped history on every order and every shipment, so anyone can look back and see exactly what happened and when.

The golden rule of who does what

LOT	Raises the request and funds the shared pool. That is essentially it.
Solve Factory	Owns the entire lifecycle after the request: converting it to a real PO, paying the vendor, shipping, customs, delivery, and invoicing LOT.

What this manual covers

This is a combined **system and process** guide. Each chapter explains what the step *is* in the real import process, and then exactly how to do it on the screen. Read the Getting Started part first; after that, the parts follow the natural order of a shipment, from request to invoice.

NOTE

Manifest is the first LOT system with **external users**. Solve Factory signs in with an email link (no Google account needed), and the system only ever shows SF what it should see.

Signing In & Getting Around

LOT

SOLVE FACTORY

ADMIN

Manifest opens as a single live dashboard with a sidebar. How you sign in depends on which side you are: LOT signs in with Google, Solve Factory signs in with an email link.

LOT SIGN-IN	SF SIGN-IN	LAYOUT	ADDRESS
Sign in with Google (legendoftoys.com).	Partner sign-in by email link.	Left sidebar, top bar, one main screen.	manifest.legendoftoys.com

Signing in

LOT team

Use **Sign in with Google** with your legendoftoys.com account. This is the same login you use for the other LOT systems.

Solve Factory

- 1 Request a link.** On the sign-in screen, choose **Partner sign-in** and enter your email.
- 2 Open the email.** Click the secure link Manifest sends you. No password, no Google account needed.
- 3 First time only.** An LOT admin onboards you once so the system knows who you are. After that, the email link is all you need.

▲ WATCH OUT

If a login link opens Manifest but it says you have no access, you have not been onboarded yet. Ask an LOT admin to add you (Admin chapter).

Getting around

Sidebar	Jump between Dashboard, Orders, Shipments, the money screens (Running Account, Draw-downs, Payments, Exchange Rates), Documents and Admin. SF sees a trimmed set.
Top bar	Shows where you are, the live CNY to INR rate, and a green LIVE dot when data is current.

Detail screens	Click any order or shipment row to open its detail, where all the actions live. A back chip returns you to the list.
Tweaks	The small dial at the bottom-right sets the accent colour and density. It only changes how the app looks for you.

✓ TIP

The app is always live. After you record something, the numbers refresh on their own; you rarely need to reload the page.

Who Does What

LOT

SOLVE FACTORY

ADMIN

Manifest has two parties, LOT and Solve Factory, plus an Admin layer. What you can see and do depends on which party you are and which role you hold.

PARTIES	LOT DOES	SF DOES	COST LENS
LOT and Solve Factory (SF).	Requests, funds the pool, views all.	Runs the whole lifecycle.	SF never sees LOT's internal cost columns.

The roles

ROLE	PARTY	CAN DO
LOT Finance / Founder	LOT	Create requests, record LOT to SF wires, see every order, shipment and the running account.
SOLVE FACTORY Owner	SF	Convert requests to POs, place them, attach the PI, pay the vendor and logistics, run shipments, invoice and close orders.
ADMIN	LOT	Everything, plus manage users and roles, the shipment timeline defaults, and the logistics-partner master.

What each side sees

LOT	The full picture: every order, every shipment, all payments and the running account. LOT funds the pool and watches it.
Solve Factory	A trimmed sidebar focused on running orders and shipments and recording what it pays. SF never sees LOT's internal cost-per-unit or margin columns, by design.

① NOTE

Most of the work after a request belongs to SF. If you are on the LOT side, your main jobs are raising the request and keeping the pool funded.

 IMPORTANT

Admin can act on SF's behalf (for example to drive or correct an order) because LOT runs the system. Use that carefully: the audit trail records who did what.

The Shared Pool, in Plain English

LOT SOLVE FACTORY ADMIN

There is one shared pool of money between LOT and Solve Factory. Think of it as a running tab. Understanding the pool is the key to understanding every money screen in Manifest.

LOT PAYS IN Pool goes up. SF holds LOT's money.	SF SPENDS OUT Pool goes down, the moment it's paid.	BALANCE Can be positive or negative.	TRUTH Always live to what has actually been paid.
--	--	---	--

How the pool moves

Pool positive	Solve Factory is holding LOT's money, ready to spend on the next order.
Pool negative	SF has spent more than LOT has put in, so LOT owes SF . This is allowed and normal; SF recovers it as LOT funds the pool again.

The most important money rule

 **IMPORTANT**

Every payment SF makes is deducted from the pool **the moment it is recorded**, not later at invoice time. So the pool is always accurate to whatever has actually been paid out on LOT's behalf.

Everything SF pays, and when

PAYMENT	WHEN	AGAINST
Vendor advance	After the vendor PI is received	the order
Pickup balance / extra services	At pickup	the order
Shipping	When the goods clear the port	the shipment
Customs / duty	When the goods clear the port	the shipment
Other port fees	When the goods clear the port	the shipment

PAYMENT	WHEN	AGAINST
Last-mile delivery	Port to warehouse	the shipment
SF commission (2.5%)	At invoice	the order

The first two wrap up the **goods purchase**. The middle four are **logistics**. The last is **SF's fee**. Every one of them reduces the pool the moment it is recorded.

① NOTE

Invoicing is a close-out record, not a money move. The money for goods and logistics already left the pool as it was paid. See the Invoicing chapter.

PART 2

The Order Lifecycle

One continuous flow: LOT requests, SF builds the PO and drives it all the way to an invoice.

How an Order Flows

LOT SOLVE FACTORY ADMIN

An order in Manifest flows through one continuous, party-owned lifecycle. LOT starts it with a request; Solve Factory drives it the rest of the way to a closed invoice. This chapter is the map; the next chapters are the steps.

STARTS WITH	DRIVEN BY	ENDS WITH	HISTORY
LOT raises a request.	SF, all the way to invoice.	Invoiced (closed).	Every move is timestamped.

The journey, end to end

- 1 LOT requests it. The order is Requested . This is the only thing LOT does to the order itself.
- 2 SF converts it to a PO. SF fills the vendor, the vendor’s product codes and the prices in Yuan. The order becomes Draft .
- 3 SF places the PO. The order becomes Placed and a printable PO document unlocks. SF sends it to the vendor.
- 4 Vendor sends the PI; SF attaches it. Stored as evidence and stamped on the timeline.
- 5 SF pays the advance. Deducts the pool.
- 6 Production to pickup. Confirmed , Produced , Picked up . At pickup SF pays any balance. Goods purchase is now wrapped up.
- 7 SF ships it. Onto a shipment (air or sea), then sailing, docking, customs, last-mile. Costs paid along the way.
- 8 Delivered. The goods reach the warehouse.
- 9 SF invoices LOT. Partially invoiced , then Invoiced once everything is billed.

The states an order moves through

Lifecycle	Requested → Draft → Placed → Confirmed → Produced → Picked up → Shipped → Received → Delivered , plus Cancelled .
Billing	Runs in parallel near the end: In flight → Delivered → Partially invoiced → Invoiced .

The short version (cheat sheet)

- 1 LOT requests, LOT funds the pool. Everything else is SF.
- 2 One shared pool. Every SF payment deducts it the moment it's recorded.
- 3 SF flow. Convert, place (PO PDF), attach PI, pay advance, produce, pickup (pay balance), ship, clear customs (pay shipping/customs/fees), deliver (pay last-mile), invoice.
- 4 Cancellable until pickup, never after.
- 5 Invoice is a close-out record. Partial allowed; GST editable per line; optional 2.5% commission.

 IMPORTANT

An order can be cancelled at any time up to and including Produced. Once it is Picked up, it can no longer be cancelled, because the goods are paid for and on their way.

Step 1 - LOT Requests an Order

[/orders](#) [LOT](#) [ADMIN](#)

A request is how LOT tells Solve Factory what it needs from China. It is the only thing LOT does to the order itself; SF takes over from there.

WHO LOT ADMIN	WHERE Orders → New Order	CREATES An order in Requested state.	NEXT SF converts it to a PO.
--	-----------------------------	---	---------------------------------

Raising a request

- 1 **Open New Order.** On the Orders screen, click **New Order**.
- 2 **Choose “Request”.** In the Create card, set **Create as** to [request](#).
- 3 **Give it a title.** Plain and recognisable, for example *Ghost 500* or *Nitro restock*.
- 4 **Pick a category.** Product, Part, Sub-part, Mould, Sample or Other.
- 5 **Add the items you want (optional).** Product, quantity and, if you know it, a per-unit price. SF will firm these up.
- 6 **Create request.** The order appears in the list as [Requested](#).

What happens next

The request sits in [Requested](#) until Solve Factory picks it up and **converts it to a PO**. From that point SF owns it: vendor, pricing, shipping, payments and invoicing. You can keep watching it on the Orders list and its detail page.

① **NOTE**

A request is deliberately light. You do not need vendor names, Yuan prices or shipping details; that is SF’s job at conversion. Just describe what you need clearly.

✓ **TIP**

Putting the quantity in the title (for example *Ghost 500*) makes the Orders list easy to scan at a glance.

Step 2 - SF Converts to a PO & Places It

[/orders](#) [SOLVE FACTORY](#) [ADMIN](#)

Converting a request to a PO is where Solve Factory takes ownership. SF fills in the real purchase-order detail in the vendor’s own product codes, then places it and sends the PO document to the vendor.

WHO	WHERE	MOVES	UNLOCKS
SOLVE FACTORY ADMIN	Order detail (open a Requested order)	Requested → Draft → Placed	A printable PO document at Placed .

Convert, then fill the PO

- 1 Open the request.** Click it in the Orders list. While it is [Requested](#) , you see a **Convert to PO** button.
- 2 Convert to PO.** The order moves to [Draft](#) and becomes fully editable by SF.
- 3 Edit the lines.** For each item set the **vendor item code**, a description, the quantity and the unit price in Yuan. A single PO can mix items on different GST codes; set GST per line later at invoice.
- 4 Add costs.** Use Edit on the order to record purchase, shipping and customs as they become known. Goods are priced in Yuan; landed cost builds up as it ships.

Why the PO uses the vendor’s codes

The PO is written in the **Chinese vendor’s product codes**, not LOT’s names. For example, the product LOT calls Flare may appear on the vendor’s PO as [8200](#) . Manifest stores both: the vendor item code and a readable product name.

NOTE

Because the PO speaks vendor codes, Manifest does not push it into Snorkel (LOT’s procurement system) automatically. Bridging the two needs a separate vendor-code to LOT-product connector, which is planned but not built yet. Until then Manifest runs fully on its own.

Place the PO

- 1 **Place order.** When the PO is ready, click **Place order**. The order moves to **Placed** and the timeline starts.
- 2 **Download the PO PDF.** A printable, vendor-facing PO (in Yuan, in vendor codes) becomes available. Send it to the vendor.

WATCH OUT

The PO PDF is a clean placeholder format for now. SF's preferred layout will be folded in later; the numbers and codes are correct, the styling will improve.

Step 3 - Vendor PI & the Advance

SOLVE FACTORY

ADMIN

Once the PO is placed and sent, the vendor replies with a Proforma Invoice (PI). SF attaches it as evidence and then pays the vendor advance out of the shared pool.

WHO	PI	ADVANCE	POOL
SOLVE FACTORY ADMIN	Uploaded as evidence, stamped on the timeline.	Paid from the pool, after the PI.	Drops the moment the advance is recorded.

Attaching the vendor PI

- 1 **Open the order.** Go to the order's detail page.
- 2 **Upload the PI.** Add the vendor's Proforma Invoice as a document of type **PI**.
- 3 **It becomes a milestone.** Manifest stamps a timestamped **PI attached** event on the order timeline, so everyone can see when it landed.

① NOTE

Manifest never generates the PI. It only stores the vendor's, as evidence.

Paying the advance

- 1 **Open Vendor payment.** On the order detail, click **Record** in the Vendor payment card.
- 2 **Choose the type.** Set it to **advance**.
- 3 **Enter the amount.** The amount in Yuan and the actual bank rate you paid at. Manifest shows the rupee value it will deduct.
- 4 **Record payment.** The pool drops immediately by that amount.

🚫 IMPORTANT

Always enter the **actual bank rate** you paid at, not the reference rate. The vendor advance is real money leaving the pool on LOT's behalf.

✓ TIP

If recording the advance pushes the pool negative, Manifest nudges you to **raise a draw-down** so LOT can top the pool up. It is a prompt, not a block: SF can still pay from its own pocket.

Step 4 - Production, Pickup & Cancelling

SOLVE FACTORY

ADMIN

After the advance, SF moves the order through production and pays the balance at pickup. This is also the last point at which an order can be cancelled.

WHO	STAGES	AT PICKUP	CANCEL CUT-OFF
SOLVE FACTORY ADMIN	Confirmed → Produced → Picked up	Pay the balance / extra services.	Up to Produced , never after pickup.

Advancing production

- 1 Advance the stage.** On the order detail, use the **Advance** button to move Confirmed → Produced → Picked up as the vendor progresses. Each step is date-stamped automatically.
- 2 Pay the pickup balance.** At pickup, record any **remaining balance or extra services** as a vendor payment with type pickup balance . It deducts the pool right away.

At this point the **goods purchase is fully wrapped up**: advance plus pickup balance. What follows is logistics.

Cancelling an order

IMPORTANT

An order can be cancelled at any time up to and including Produced . **Once it is Picked up, it can no longer be cancelled**, because the goods are paid for and on their way.

- 1 Open the order.** While it is Requested , Draft , Placed , Confirmed or Produced , a **Cancel** button is shown.
- 2 Give a reason.** A reason is required and is logged on the timeline.
- 3 Confirm.** The order moves to Cancelled .

⚠ WATCH OUT

Cancelling does **not** automatically reverse any payments already made on the order. Those stay as pool debits and are reconciled by hand. This is deliberate; the system stays honest about money that actually moved.

PART 3

Shipments

Getting the goods from the Chinese vendor to the LOT warehouse, by air or by sea.

How Shipments Work (Air vs Sea)

[SOLVE FACTORY](#) [ADMIN](#)

A shipment is one physical container with its own schedule. Once goods are picked up, SF puts them on a shipment and tracks it from the factory to the LOT warehouse. Every shipment is either Air or Sea.

WHO SOLVE FACTORY ADMIN	TWO MODES Air and Sea, same steps.	LOCK POINT Contents lock once it departs.	MIXING One container can carry several POs.
---	---------------------------------------	--	--

The shipment journey

Sea	Planned → Loaded → Sailing → Docked → Cleared → Local transport → Received .
Air	The same steps, read as Planned → Loaded → In Flight → Landed → Cleared → Local transport → Received .

Each milestone is date-stamped automatically as SF advances it.

Air vs Sea, what's different

ASPECT	SEA	AIR
Speed (door to door)	roughly 30 to 40 days	roughly 5 to 8 days
Freight basis	per container or volume	chargeable weight
Carrier document	Bill of Lading (BL)	Air Waybill (AWB)
Wording	Sailing / Docked	In Flight / Landed

The steps are identical; the labels, the costs you record, and the suggested timeline differ by mode. The suggested timeline per mode is editable by SF or Admin in the settings (see Admin chapter).

Allocation and the departure lock

Allocation	SF allocates an order’s items to a shipment. Usually one PO travels on one shipment, but a shipment often carries several POs, and one PO can split across more than one shipment.
Departure Lock	Items can be moved between shipments while the container has not left. Once it departs (Sailing for sea, In Flight for air), the contents lock: nothing can be added, removed or moved.

✓ TIP

A single PO can split across an air shipment and a sea shipment, for example urgent units fly while the bulk sails. Just create two shipments and allocate the right items to each.

Creating a Shipment

/shipments SOLVE FACTORY ADMIN

SF creates a shipment when goods are ready to leave the factory. You capture the carrier and the real loading and sailing dates up front, and Manifest pre-fills the rest of the schedule.

WHO	WHERE	CAPTURE	THEN
SOLVE FACTORY ADMIN	Shipments → New shipment	Mode, carrier, loading & sailing dates, BL/AWB.	Opens the shipment detail to manage it.

Creating a shipment

- 1 New shipment.** On the Shipments screen, click **New shipment**.
- 2 Pick the mode.** sea or air. The carrier list, date labels and the BL/AWB label all follow the mode.
- 3 Choose the carrier.** Pick the freight partner from the list (shown as code and company name). No carrier listed? Add it in Admin → Logistics partners.
- 4 Enter the real dates.** **Loading date** and **Sailing date** (for air, "Departure date"). These are the dates you actually know when booking.
- 5 Add BL/AWB and container.** The Bill of Lading or Air Waybill number, container type and number where known.
- 6 Create shipment.** Manifest opens the new shipment's detail page.

How the dates pre-fill

From the sailing (or departure) date, Manifest suggests the downstream dates, arrival, customs clearance and delivery, using the timeline defaults for that mode. If you only enter a loading date, it works forward from there. These are **suggestions, not locks**: you can change any date afterwards on the detail page.

① **NOTE**

The timeline defaults (how many days each leg usually takes, per mode) are set by SF or Admin in Admin → Shipment timeline defaults. Tune them to match your real experience and every new shipment starts from sensible dates.

✓ **TIP**

You do not have to allocate items at creation. Create the shipment, then attach the orders it carries on the detail page (see Managing a Shipment).

Managing a Shipment

[/shipments](#) [SOLVE FACTORY](#) [ADMIN](#)

The shipment detail page is where SF runs a container: advance its milestones, edit its details, attach the orders it carries, and (before it sails) move items around.

WHO	WHERE	DO	LOCKS
SOLVE FACTORY ADMIN	Shipments → click a shipment	Advance, edit, allocate, move.	Contents freeze once it departs.

Advancing the journey

- 1 **Advance.** The header shows a stage timeline (each milestone as a step, with its date once reached) and the current stage. Click **Advance** to move to the next milestone (mode-aware: Sailing/Docked for sea, In Flight/Landed for air). Each advance date-stamps automatically.
- 2 **Received couples the order.** When all of an order’s shipment legs reach **Received**, the order is recognised as delivered.

Editing details

- 1 **Edit.** Opens the carrier, container, BL/AWB and all expected dates for change. Any date change is logged as a revision; the original plan is kept.
- 2 **Mode lock.** You can change the mode only while the shipment is still **Planned**. Once it is loaded, the mode is fixed.

Allocating and moving items

- 1 **Add an order.** In **Allocated items**, pick an order and click **Add order**; its lines join this container.
- 2 **Move between containers (before departure).** While both shipments are pre-departure, items can be re-allocated. The order’s detail page also has a “Move this PO to another container” control.

 **IMPORTANT**

Once the shipment departs (Sailing or In Flight), its contents lock. Add and move are disabled and the page shows “contents locked”. This mirrors reality: a sailed container cannot be changed.

① **NOTE**

The Timeline card lists every event on the shipment, planned dates, revisions, stage advances and payments, with timestamps, so the full history is always visible.

Shipping Costs & Last-Mile Delivery

SOLVE FACTORY

ADMIN

When goods clear the port and again at last-mile delivery, SF records the logistics costs against the shipment. Each one deducts the shared pool the moment it is recorded. Last-mile also captures who is delivering and in which vehicle.

WHO	WHERE	COST TYPES	POOL
SOLVE FACTORY ADMIN	Shipment detail → Logistics costs & last-mile	Shipping, customs, other fees, last-mile.	Drops immediately on each record.

Recording a logistics cost

- 1 Record cost.** On the shipment detail, in the costs card, click **Record cost**.
- 2 Pick the type.** `shipping`, `customs`, `other_fees` or `last_mile`.
- 3 Enter the rupee amount.** Then confirm. The pool drops by that amount immediately.

Air freight is priced by chargeable weight and sea by container or volume, but you record the final rupee figure either way; Manifest just prompts you for the right set of costs for the mode.

✓ TIP

If a cost pushes the pool negative, Manifest nudges you to raise a draw-down. It is a funding prompt, not a block.

Last-mile: who is bringing it

At the local-transport stage, capture **who is doing the last-mile delivery** and the **vehicle number**, so the store team knows exactly who and what vehicle to expect when the material arrives.

- 1 Last-mile.** Click **Last-mile** on the shipment.
- 2 Pick the partner.** Choose the delivery partner from the list (code and company name).
- 3 Enter the vehicle number.** Then Save. It shows on the shipment for the store team.

 IMPORTANT

Delivery partners are always chosen from the shared list, never typed as loose text. If the partner is not listed, add it once in Admin → Logistics partners, then pick it. This keeps the partner master clean.

PART 4

Money

Funding the pool, asking for funds, invoicing, and reading the running account.

LOT to SF Payments & Draw-downs

[/payments](#) [LOT](#) [SOLVE FACTORY](#) [ADMIN](#)

LOT funds the shared pool by recording its wires to Solve Factory. When the pool runs low, SF (or LOT) raises a draw-down: a request for LOT to top it up.

WHO	WHERE	WIRE EFFECT	UTR
LOT records wires · SF raises draw-downs	Payments · Draw-downs	Pool goes up (a credit).	Required on every new wire.

Recording a LOT to SF wire

- 1 **Open Payments.** Click **Record Wire**.
- 2 **Enter the amount and UTR.** The rupee amount and the bank **UTR** (reference) are both required.
- 3 **Set the channel and method.** Which SF payout channel received it, and how it was sent.
- 4 **Record wire.** The pool goes up by that amount; SF is now holding more of LOT's money.

 IMPORTANT

Every **new** wire must carry a UTR. This is how the wire is matched to the bank later. Older historical payments may not have one, but all new ones do.

Raising a draw-down

A draw-down is a request for LOT to put money into the pool, usually because an upcoming payment (an advance, a balance, shipping) would otherwise push the pool negative.

- 1 **Raise Draw-down.** From the Draw-downs screen, or from the prompt that appears after a payment runs the pool low.
- 2 **Pick the phase and order.** Goods advance, shipping & customs, local, or other; optionally tag it to a specific order.
- 3 **Enter the amount.** Manifest shows the Yuan equivalent at the current rate. Submit.

① **NOTE**

A draw-down is a **funding prompt**, not a payment and not a gate. It does not move the pool by itself; LOT settles it by recording a wire. SF can always pay from its own pocket and let the pool go negative.

Invoicing & Closing an Order

SOLVE FACTORY

ADMIN

Invoicing is how SF closes an order out, with a formal SF to LOT invoice for LOT’s books and GST. It is a record, not the thing that moves the money: goods and logistics already left the pool as they were paid.

WHO	WHERE	PARTIAL	POOL IMPACT
SOLVE FACTORY ADMIN	Order detail → Invoice & close	Bill some lines now, the rest later.	Only the optional commission.

Raising an invoice

- 1
- Open Invoice & close. On a delivered (or partly invoiced) order, the Invoice card lists the goods lines.
- 2
- Tick the lines to bill. Partial invoicing is allowed: bill some now and the rest later. Already-billed lines show their invoice number and cannot be billed twice.
- 3
- Set GST per line. Each line carries its own GST percent (defaults to 18). A single PO can mix items on different GST codes, so set each correctly.
- 4
- Optionally add commission. Toggle the SF 2.5% commission on or off for the invoice.
- 5
- Submit. Manifest assigns the invoice number automatically (the VWINV series), stamps each billed line, and updates the order’s state.

How the invoice is valued

Priced lines	A line with a per-unit Yuan price is valued as price times quantity times the exchange rate.
Lump-cost lines	Some items (moulds, machines, mixed sets) have no per-unit price. Those bill the order’s recorded rupee cost instead, so the order is still closeable.
Invoice number	Auto-assigned from the VWINV series; never typed by hand. The financial year rolls over automatically each April.

What invoicing moves

IMPORTANT

The only thing invoicing debits from the pool is the **2.5% commission** (if you include it). Goods and logistics already left the pool when they were paid. The GST on the invoice is a document and compliance figure; it is not a separate pool movement.

NOTE

The order becomes **Partially invoiced** while some goods lines are still unbilled, and **Invoiced** (closed) once they all carry an invoice number.

The Running Account & Exchange Rates

/recon

LOT

SOLVE FACTORY

ADMIN

The Running Account is the single source of truth for who owes whom. It is the shared pool, shown as a ledger with a live balance. Exchange Rates is the reference rate Manifest uses; the actual bank rate is always set per payment.

WHO LOT SF ADMIN	WHERE Running Account - Exchange Rates	NET Positive = SF holds LOT funds; negative = LOT owes SF.	FX Reference only; bank rate is per payment.
--	---	---	---

Reading the running account

Net position	The headline balance. Positive means Solve Factory holds LOT's money; negative means LOT owes SF.
Credits	LOT to SF wires paid in.
Debits	Goods, logistics charges and commission that SF has spent.
Ledger	Every entry in order, with a running balance. Click a row to see its detail and jump to the linked record.

Opening balance and any carried-forward adjustments from prior years sit in the ledger as their own entries, so the net always reconciles.

Exchange rates

Reference rate	Manifest pulls a daily CNY to INR rate automatically. It is shown in the top bar and on the Exchange Rates screen for reference.
Manual override	An LOT user with FX rights can set a manual rate for a date when needed.
Actual bank rate	The rate that matters for money is the one you enter on each vendor payment. The reference rate never overrides it.

 IMPORTANT

When you record a vendor payment, always enter the **actual bank rate** you paid at. The reference rate is only a guide.

PART 5

Workspace & Admin

Finding orders, the evidence vault, and the settings that keep the system tuned.

Orders List, Search & Documents

[/orders](#) [LOT](#) [SOLVE FACTORY](#) [ADMIN](#)

The Orders screen is where you find any order and open its detail. Documents is the shared evidence vault for PIs, invoices, bills of lading and receipts.

WHO LOT SF ADMIN	WHERE Orders · Documents	SEARCH By order number or title.	VAULT Evidence, downloadable by signed link.
---	-----------------------------	-------------------------------------	---

Finding an order

- 1 Search.** Type an order number or title in the search box; the list filters as you type and the dropdown jumps straight to a match.
- 2 Read the columns.** Order number, title, category, value, the Snorkel PO (if linked), state, balance due and date.
- 3 Open it.** Click any row to open its detail, where all the actions live.

State	Where the order is in its billing axis (in flight , delivered , partially invoiced , invoiced).
Balance	What is still due against the order, or paid when settled.

Documents

Every PI, invoice, bill of lading, packing list and wire receipt can be stored against its order or shipment. Filter by type, and download any file by a short-lived secure link.

Where files attach	From an order or shipment detail; the file is tagged to that record and a milestone is stamped for key types (like the PI).
Access	The vault is private. Downloads use a signed link that expires, so files are never publicly exposed.

✓ **TIP**

Attach the vendor PI and the bill of lading as you get them. They become part of the order's timeline and make closing the order out clean and auditable.

Admin - Access, Roles, Timeline & Partners

/admin

ADMIN

Admin is where access to Manifest is controlled, roles are built, and the shipment timeline defaults and logistics-partner master are kept. Because Manifest holds sensitive cross-company money data, access is locked by default and only a super admin can hand it out.

WHO	WHERE	TABS	DEFAULT
ADMIN	Admin	Access Control, Roles, Operations.	No access until granted.

Two levels of admin

There is a deliberate split between governing access and running day-to-day settings:

- **Super admin** (the "Manifest Super Admin" role): controls who can use Manifest, builds and edits roles, and appoints other super admins. Afshaan holds this, plus anyone he grants the role (for example Vinay).
- **Manifest Admin** (operational): can tune the timeline defaults and the logistics-partner master, but cannot change who has access or what a role can do.

Only super admins see the **Access Control** and **Roles** tabs. Anyone with operational admin sees the **Operations** tab.

The locked door

A person who has signed in but has not been granted a Manifest role sees a full-screen **"No access to Manifest"** message with a Sign out button, and nothing else. The same wall appears the moment someone is disabled. This is normal and safe: access is something a super admin grants on purpose, never the default.

Access Control (super admin)

Lists everyone who has a Manifest role, with their organisation, role, and active status.

- 1 **Grant access.** Type the person's email, pick a role, and click **Grant**. They must have signed in at least once first (Google for LOT staff, the email link for Solve Factory owners) so their account exists; otherwise you get a clear "ask them to sign in once first" message.
- 2 **Change a role.** Use the role dropdown on their row to move them to a different role.

- 3 **Disable or enable.** **Disable** instantly blocks login while keeping the person on the list; **Enable** restores it. Use this for a temporary cut.
- 4 **Remove.** Takes the person off Manifest entirely.

① **NOTE**

Disabling here only affects Manifest. It never touches the person's access to the other Legend of Toys systems.

🚫 **IMPORTANT**

You cannot disable or remove yourself, and you cannot disable, remove, or demote the **last** active super admin. This stops anyone from accidentally locking the whole team out. Always keep at least two super admins.

Roles, the permissions builder (super admin)

A role is a named bundle of permissions. The list shows every role; the built-in ones (Manifest Super Admin, Solve Factory Owner, LOT Finance, LOT Founder) are marked **System** and are view-only.

- 1 **Create a role.** Click **New**, give it a key, a label, and pick its side (LOT or Solve Factory). The side is fixed once created.
- 2 **Tick the permissions.** Each capability (manage orders, record payments, create invoices, manage documents, and so on) is a checkbox, grouped by area. A Solve Factory role can only hold SF capabilities; LOT-only powers (including super admin and the cost view) are never offered on an SF role.
- 3 **Save, or Delete.** Save writes the role. A custom role with nobody assigned can be deleted; an assigned one must be reassigned first.

① **NOTE**

You build roles out of a fixed set of capabilities. You cannot invent a brand-new power here; if a genuinely new capability is ever needed, that is a system change, not a role edit.

Operations: shipment timeline defaults

These are the day-offsets Manifest uses to pre-fill a new shipment's expected dates, set separately for sea and air.

- 1 **Edit the offsets.** For each mode, set how many days after the previous milestone each leg usually takes (loaded, sailing, docked, cleared, local transport, received).
- 2 **Save.** New shipments now pre-fill from these. They are **suggestions only**; SF can change any date on a shipment.

① NOTE

These defaults are edited directly with no audit trail, on purpose; they are tuning knobs, not records. Adjust them whenever your real lead times change.

Operations: logistics partners

The shared list of carriers and last-mile transporters (freight forwarders, shipping lines, couriers). Every carrier and last-mile picker in Manifest reads from this master.

- 1 **Add a partner.** Click **Add partner**, enter the company, country and the modes it supports (sea, air, land), plus IATA or SCAC codes and a tracking URL where relevant.
- 2 **Create.** Manifest assigns the partner code. It is now selectable everywhere.

🚫 IMPORTANT

Partners are **never typed as free text** anywhere in Manifest. If a needed carrier or transporter is missing, add it here once. This keeps the master clean and the pickers reliable.

① NOTE

Vendors come from the shared LOT vendor master and already cover China, international and domestic suppliers, so there is nothing to set up here for vendors.

Generating a China PO or Invoice

[/orders](#) [LOT](#) [SOLVE FACTORY](#) [ADMIN](#)

Manifest can print two formal documents from an order: the China Purchase Order you send the vendor, and the GST tax invoice from Solve Factory. Both open as a clean printable page you save as a PDF, and you can reprint them as many times as you like.

WHO	WHERE	OUTPUT	STORED?
LOT SOLVE FACTORY ADMIN	Order detail.	Print, or Save as PDF.	No. Reprint any time.

How it works

Open any order. In the header (and on the Invoiced card) you will find document buttons. Click one and a clean black-and-white document opens in a new tab and the print dialog appears on its own. From there choose your printer, or pick **Save as PDF** to keep a copy. Nothing is stored on the system: the document is built fresh from the latest order data each time, so it is always current and always available.

China PO

Available once an order has been placed (not while it is still a request or draft). It shows:

- **Buyer:** Legend of Toys, with the company address and GSTIN.
- **Supplier:** the Chinese vendor on the order.
- **Lines:** vendor item code, description, quantity and unit price, in the order's currency (RMB).
- **Totals:** in RMB. No GST is shown, because purchases in RMB are not taxed here.

Click **China PO** in the order header to generate it.

SF Invoice (tax invoice)

Available once an order has been invoiced. The **SF Invoice PDF** button sits on the Invoiced card. It shows:

- **Seller:** the Solve Factory billing entity on the invoice. **Bill to:** Legend of Toys with GSTIN.
- **Charges:** goods value, shipping and customs (whichever apply), totalling the taxable value.
- **Tax:** the GST amount on the goods, shown as a single IGST line.
- **Commission:** the Solve Factory commission line (GST included).
- **Grand total** and the amount written out in words.

① **NOTE**

The invoice is built from the order's recorded totals, so it reflects whatever has been invoiced. If you reopen it later it will show the current figures. If you need a frozen copy of an invoice exactly as it was issued, save the PDF when you generate it.

① **NOTE**

If a button does nothing or shows an error, the order is not at the right stage yet (a China PO needs the order placed; an SF Invoice needs it invoiced), or your role does not include document access.