# fgetc, getc

```
Defined in header <stdio.h>
int fgetc( FILE *stream ); (1)
int getc( FILE *stream ); (2)
```

- 1) Reads the next character from the given input stream.
- 2) Same as fgetc, except that if getc is implemented as a macro, it may evaluate stream more than once, so the corresponding argument should never be an expression with side effects.

### **Parameters**

stream - to read the character from

#### Return value

On success, returns the obtained character as an unsigned char converted to an int. On failure, returns EOF.

If the failure has been caused by end-of-file condition, additionally sets the *eof* indicator (see feof()) on stream. If the failure has been caused by some other error, sets the *error* indicator (see ferror()) on stream.

## Example

```
Run this code
#include <stdio.h>
#include <stdlib.h>
int main(void)
    int is_ok = EXIT_FAILURE;
    const char* fname = "/tmp/unique name.txt"; // or tmpnam(NULL);
    FILE* fp = fopen(fname, "w+");
    if(!fp) {
        perror("File opening failed");
        return is_ok;
    fputs("Hello, world!\n", fp);
    rewind(fp);
    int c; // note: int, not char, required to handle EOF
    while ((c = fgetc(fp)) != EOF) { // standard C I/O file reading loop
       putchar(c);
    if (ferror(fp)) {
        puts("I/O error when reading");
    } else if (feof(fp)) {
        puts("End of file reached successfully");
        is_ok = EXIT_SUCCESS;
    fclose(fp);
    remove(fname);
    return is ok;
}
```

Possible output:

```
Hello, world!
End of file reached successfully
```

# References

• C17 standard (ISO/IEC 9899:2018):

- 7.21.7.1 The fgetc function (p: 240-241)
- 7.21.7.5 The getc function (p: 242)
- C11 standard (ISO/IEC 9899:2011):
  - 7.21.7.1 The fgetc function (p: 330)
  - 7.21.7.5 The getc function (p: 332)
- C99 standard (ISO/IEC 9899:1999):
  - 7.19.7.1 The fgetc function (p: 296)
  - 7.19.7.5 The getc function (p: 297-298)
- C89/C90 standard (ISO/IEC 9899:1990):
  - 4.9.7.1 The fgetc function
  - 4.9.7.5 The getc function

# See also

getchar	reads a character from stdin (function)
<pre>gets (removed in C11) gets_s (C11)</pre>	reads a character string from stdin (function)
fputc putc	writes a character to a file stream (function)
ungetc	<pre>puts a character back into a file stream (function)</pre>

C++ documentation for fgetc, getc

Retrieved from "https://en.cppreference.com/mwiki/index.php?title=c/io/fgetc&oldid=128882"