Amazon EKS User Guide

nEKS

Amazon EKS: User Guide

Copyright © 2020 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon. All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

Table of Contents

What is Amazon EKS?	
Amazon EKS control plane architecture	
How does Amazon EKS work?	2
Pricing	2
Aligning with Amazon EKS for your self-managed Kubernetes clusters	2
Getting started with Amazon EKS	4
Getting started with eksctl	
Prerequisites	
Create your Amazon EKS cluster and compute	
Next steps	
Getting started with the console	
Prerequisites	
Step 1: Create your Amazon EKS cluster	
Step 2: Create a kubeconfig file	
Step 3: Create a kubeconing me	
Clusters	
Creating a cluster	
[Create a cluster with eksctl]	
[Create a cluster with the AWS Management Console]	
[Create a cluster with the AWS CLI]	
Updating a cluster	
Updating Kubernetes version	
Configure an Amazon EKS add-on	
Deleting a cluster	
Cluster endpoint access	
Modifying cluster endpoint access	
Accessing a private only API server	
Cluster Autoscaler	
Create an Amazon EKS cluster	
Cluster Autoscaler node group considerations	63
Deploy the Cluster Autoscaler	64
View your Cluster Autoscaler logs	. 65
Control plane logging	
Enabling and disabling control plane logs	
Viewing cluster control plane logs	
Kubernetes versions	
Available Amazon EKS Kubernetes versions	
Kubernetes 1.18	
Kubernetes 1.17	
Kubernetes 1.16	
Kubernetes 1.15	
Amazon EKS Kubernetes release calendar	
Amazon EKS version support and FAQ	
Platform versions	
Kubernetes version 1.18	
Kubernetes version 1.17	
Kubernetes version 1.17	
Kubernetes version 1.15	
Windows support	
Considerations	
Enabling Windows support	
Deploy a Windows sample application	
Inferentia support	
Considerations	86

Prerequisites	86
Create a cluster	87
(Optional) Create a Neuron TensorFlow Serving application image	87
(Optional) Deploy a TensorFlow Serving application image	
(Optional) Make predictions against your TensorFlow Serving service	91
Viewing API server flags	92
Private clusters	
Requirements	92
Considerations	
Creating local copies of container images	93
VPC endpoints for private clusters	94
Nodes	95
View nodes	98
Managed node groups	. 100
Managed node groups concepts	100
Managed node group capacity types	101
Creating a managed node group	103
Updating a managed node group	108
Launch template support	. 111
Deleting a managed node group	115
Self-managed nodes	116
Amazon Linux	116
Bottlerocket	121
Windows	. 124
Updates	128
AWS Fargate	136
Fargate considerations	. 137
Getting started with Fargate	138
Fargate profile	. 142
Fargate pod configuration	. 145
Usage metrics	146
Fargate logging	147
Amazon EKS optimized AMIs	. 152
Amazon Linux	152
Ubuntu Linux	166
Bottlerocket	166
Windows	. 169
Storage	180
Storage classes	180
Amazon EBS CSI driver	181
Amazon EFS CSI driver	185
Amazon FSx for Lustre CSI driver	. 190
Networking	196
Creating a VPC for Amazon EKS	197
Creating a VPC for Amazon EKS	199
Next steps	202
Cluster VPC considerations	. 202
VPC IP addressing	202
VPC tagging requirement	
Subnet tagging requirement	
Amazon EKS security group considerations	
Cluster security group	
Control plane and node security groups	
Pod networking (CNI)	
External SNAT	
Configure plugin for IAM account	
Security groups for pods	213

CNI custom networking	224
CNI metrics helper	
CNI configuration variables	229
CNI upgrades	235
Alternate compatible CNI plugins	
Installing or upgrading CoreDNS	
Upgrading CoreDNS	
Installing Calico on Amazon EKS	
Stars policy demo	
Workloads	
View workloads	
Sample workload deployment	
Vertical Pod Autoscaler	
Install the metrics server	
Deploy the Vertical Pod Autoscaler	
Test your Vertical Pod Autoscaler installation	254
Horizontal Pod Autoscaler	257
Install the metrics server	257
Run a Horizontal Pod Autoscaler test application	258
Network load balancing	
Load balancer – Instance targets	
Load balancer – IP targets	
Application load balancing	
Restrict service external IP address assignment	
Cluster authentication	
Installing aws-iam-authenticator	
Create a kubeconfig for Amazon EKS	
Create kubeconfig automatically	
Create kubeconfig manually	
Managing users or IAM roles for your cluster	
Cluster management	
Installing kubect1	289
All Regions except China (Ningxia) and China (Beijing)	289
China Regions	
Installing eksct1	
Installing or upgrading eksctl	
Tutorial: Deploy Kubernetes Dashboard	
Prerequisites	
Step 1: Deploy the Kubernetes Metrics Server	
Step 1: Deploy the Rubernetes Metrics Server	ZO1
Step 3: Create an eks-admin service account and cluster role binding	
Step 4: Connect to the dashboard	
Step 5: Next steps	
Metrics server	
Prometheus metrics	
Viewing the raw metrics	305
Deploying Prometheus	306
Using Helm	308
Tagging your resources	309
Tag basics	
Tagging your resources	
Tag restrictions	
Working with tags using the console	
Working with tags using the CLI, API, or eksct1	
Service quotas	
Cocurity	515

Identity and access management	. 315
Audience	316
Authenticating with identities	316
Managing access using policies	. 318
How Amazon EKS works with IAM	
Identity-based policy examples	
Using Service-Linked Roles	
Cluster IAM role	
Node IAM role	
Pod execution role	
IAM roles for service accounts	
Troubleshooting	
Logging and monitoring	
Compliance validation	
Resilience	
Infrastructure security	
Configuration and vulnerability analysis	
Best practices	
Restricting access to the instance profile	
Pod security policy	
Amazon EKS default pod security policy	
Working with other services	
Creating Amazon EKS resources with AWS CloudFormation	
Amazon EKS and AWS CloudFormation templates	
Learn more about AWS CloudFormation	
Use App Mesh with Kubernetes	
Logging Amazon EKS API calls with AWS CloudTrail	
Amazon EKS information in CloudTrail	
Understanding Amazon EKS log file entries	
Amazon EKS on AWS Outposts	
Prerequisites	361
Considerations	
Network connectivity considerations	361
Creating Amazon EKS nodes on an Outpost	. 361
Use App Mesh with Kubernetes	. 358
Amazon EKS on AWS Local Zones	363
Deep Learning Containers	. 364
Troubleshooting	365
Insufficient capacity	365
Nodes fail to join cluster	365
Unauthorized or access denied (kubectl)	366
aws-iam-authenticator Not found	
hostname doesn't match	
getsockopt: no route to host	
Managed node group errors	
CNI log collection tool	
Container runtime network not ready	
TLS handshake timeout	
InvalidClientTokenId	
IAM	
AccessDeniedException	
Can't see workloads or nodes and receive an error in the AWS Management Console	
aws-auth ConfigMap does not grant access to the cluster	
I Am not authorized to perform iam:PassRole	
·	
I want to view my access keys	
I want to allow people outside of my AWS account to access my Amazon EKS resources	
	7//

Amazon EKS User Guide

Amazon EKS Distro	2
Related projects	
Management tools	
eksctl	376
AWS controllers for Kubernetes	376
Flux CD	376
CDK for Kubernetes	376
Networking	377
Amazon VPC CNI plugin for Kubernetes	377
AWS Application Load Balancer (ALB) ingress controller for Kubernetes	377
ExternalDNS	377
App Mesh Controller	
Security	377
AWS IAM authenticator	378
Machine learning	378
Kubeflow	378
Auto Scaling	378
Cluster autoscaler	378
Escalator	
Monitoring	378
Prometheus	
Continuous integration / continuous deployment	379
Jenkins X	379
Document history	380

What is Amazon EKS?

Amazon EKS is a managed service that you can use to run Kubernetes on AWS without needing to install, operate, and maintain your own Kubernetes control plane or nodes. Kubernetes is an open-source system for automating the deployment, scaling, and management of containerized applications.

Amazon EKS runs Kubernetes control plane instances across multiple Availability Zones to ensure high availability. Amazon EKS automatically detects and replaces unhealthy control plane instances, and it provides automated version upgrades and patching for them.

Amazon EKS is integrated with many AWS services to provide scalability and security for your applications, including the following capabilities:

- · Amazon ECR for container images
- Elastic Load Balancing for load distribution
- · IAM for authentication
- · Amazon VPC for isolation

Amazon EKS runs up-to-date versions of the open-source Kubernetes software, so you can use all of the existing plugins and tooling from the Kubernetes community. Applications that are running on Amazon EKS are fully compatible with applications running on any standard Kubernetes environment, no matter whether they're running in on-premises data centers or public clouds. This means that you can easily migrate any standard Kubernetes application to Amazon EKS without any code modification.

Amazon EKS control plane architecture


Amazon EKS runs a single tenant Kubernetes control plane for each cluster, and control plane infrastructure is not shared across clusters or AWS accounts.

This control plane consists of at least two API server nodes and three etcd nodes that run across three Availability Zones within a Region. Amazon EKS automatically detects and replaces unhealthy control plane instances, restarting them across the Availability Zones within the Region as needed. Amazon EKS leverages the architecture of AWS Regions in order to maintain high availability. Because of this, Amazon EKS is able to offer an SLA for API server endpoint availability.

Amazon EKS uses Amazon VPC network policies to restrict traffic between control plane components to within a single cluster. Control plane components for a cluster can't view or receive communication from other clusters or other AWS accounts, except as authorized with Kubernetes RBAC policies.

This secure and highly available configuration makes Amazon EKS reliable and recommended for production workloads.

How does Amazon EKS work?



Getting started with Amazon EKS is easy:

- Create an Amazon EKS cluster in the AWS Management Console or with the AWS CLI or one of the AWS SDKs.
- 2. Launch managed or self-managed Amazon EC2 nodes, or deploy your workloads to AWS Fargate.
- 3. When your cluster is ready, you can configure your favorite Kubernetes tools, such as kubectl, to communicate with your cluster.
- 4. Deploy and manage workloads on your Amazon EKS cluster the same way that you would with any other Kubernetes environment. You can also view information about your workloads using the AWS Management Console.

To create your first cluster and its associated resources, see Getting started with Amazon EKS (p. 4).

Pricing

An Amazon EKS cluster consists of a control plane and the Amazon EC2 or AWS Fargate compute that you run pods on. For more information about pricing for the control plane, see Amazon EKS pricing. Both Amazon EC2 and Fargate provide:

- On-Demand Instances Pay for the instances that you use by the second, with no long-term commitments or upfront payments. For more information, see Amazon EC2 On-Demand Pricing and AWS Fargate Pricing.
- Savings Plans You can reduce your costs by making a commitment to a consistent amount of usage, in USD per hour, for a term of 1 or 3 years. For more information, see Pricing with Savings Plans.

Aligning with Amazon EKS for your self-managed Kubernetes clusters

Amazon EKS Distro is a distribution of the same open-source Kubernetes software and dependencies deployed by Amazon EKS in the cloud. With Amazon EKS Distro, you can create reliable and secure clusters wherever your applications are deployed. You can rely on the same versions of Kubernetes deployed by Amazon EKS, etcd, CoreDNS, upstream CNI, and CSI sidecars with the latest updates, and extended security patching support. Amazon EKS Distro follows the same Kubernetes version release cycle as Amazon EKS and is provided as an open-source project.

Amazon EKS User Guide Aligning with Amazon EKS for your self-managed Kubernetes clusters

Note

The source code for the Amazon EKS Distro is available on GitHub. The latest documentation is available on the Amazon EKS Distro website. If you find any issues, you can report them with Amazon EKS Distro by connecting with us on GitHub. There you can open issues, provide feedback, and report bugs.

Getting started with Amazon EKS

There are two getting started guides available for creating a new Kubernetes cluster with nodes in Amazon EKS:

- Getting started with eksctl (p. 4) This getting started guide helps you to install all of the
 required resources to get started with Amazon EKS using eksctl, a simple command line utility for
 creating and managing Kubernetes clusters on Amazon EKS. At the end of the tutorial, you will have a
 running Amazon EKS cluster that you can deploy applications to. This is the fastest and simplest way
 to get started with Amazon EKS.
- Getting started with the AWS Management Console (p. 15) This getting started guide helps you
 to create all of the required resources to get started with Amazon EKS using the AWS Management
 Console. At the end of the tutorial, you will have a running Amazon EKS cluster that you can
 deploy applications to. In this guide, you manually create each resource in the Amazon EKS or AWS
 CloudFormation consoles. The procedures give you complete visibility into how each resource is
 created and how they interact with each other.

Getting started with eksctl

This getting started guide helps you to create all of the required resources to get started with Amazon EKS using eksctl, a simple command line utility for creating and managing Kubernetes clusters on Amazon EKS. At the end of this tutorial, you will have a running Amazon EKS cluster that you can deploy applications to.

The procedures in this guide create several resources for you automatically, that you have to create manually when you create your cluster using the AWS Management Console. If you'd rather manually create most of the resources to better understand how they interact with each other, then use the AWS Management Console to create your cluster and compute. For more information, see Getting started with the AWS Management Console (p. 15).

Prerequisites

This section helps you to install and configure the following tools that you need to create and manage an Amazon EKS cluster.

- AWS CLI (p. 4) Command line tools for working with AWS services, including Amazon EKS.
- eksct1 (p. 6) A command line tool for working with EKS clusters that automates many individual tasks.
- kubectl (p. 7) A command line tool for working with Kubernetes clusters.

Install the AWS CLI

You can install the latest version of the AWS CLI for macOS (p. 4), Linux (p. 5), or Windows (p. 5).

[To install the AWS CLI for macOS]

1. If you currently have the AWS CLI installed, determine which version that you have installed.

```
aws --version
```

 If you don't have version 1.18.190 or later, or version 2.1.7 or later installed, then install the AWS CLI version 2. For other installation options, or to upgrade your currently installed version 2, see Upgrading the AWS CLI version 2 on macOS.

```
curl "https://awscli.amazonaws.com/AWSCLIV2.pkg" -o "AWSCLIV2.pkg" sudo installer -pkg AWSCLIV2.pkg -target /
```

If you're unable to use the AWS CLI version 2, then ensure that you have the latest version of the AWS CLI version 1 installed using the following command.

```
pip3 install awscli --upgrade --user
```

[To install the AWS CLI for Linux]

1. If you currently have the AWS CLI installed, determine which version that you have installed.

```
aws --version
```

 If you don't have version 1.18.190 or later, or version 2.1.7 or later installed, then install the AWS CLI version 2. For other installation options, or to upgrade your currently installed version 2, see Upgrading the AWS CLI version 2 on Linux.

```
curl "https://awscli.amazonaws.com/awscli-exe-linux-x86_64.zip" -o "awscliv2.zip" unzip awscliv2.zip sudo ./aws/install
```

If you're unable to use the AWS CLI version 2, then ensure that you have the latest version of the AWS CLI version 1 installed using the following command.

```
pip3 install --upgrade --user awscli
```

[To install the AWS CLI for Windows]

1. If you currently have the AWS CLI installed, determine which version that you have installed.

```
aws --version
```

- 2. If you don't have either version 1.18.190 or later, or version 2.1.7 or later installed, then install the AWS CLI version 2 using the following steps. For other installation options, or to upgrade your currently installed version 2, see Upgrading the AWS CLI version 2 on Windows.
 - Download the AWS CLI MSI installer for Windows (64-bit) at https://awscli.amazonaws.com/ AWSCLIV2.msi
 - b. Run the downloaded MSI installer and follow the onscreen instructions. By default, the AWS CLI installs to C:\Program Files\Amazon\AWSCLIV2.
- 3. (Optional) If you're unable to use the AWS CLI version 2, then ensure that you have the latest version of the AWS CLI version 1 installed using the following command.

```
pip3 install --user --upgrade awscli
```

Configure your AWS CLI credentials

Both eksctl and the AWS CLI require that you have AWS credentials configured in your environment. The aws configure command is the fastest way to set up your AWS CLI installation for general use.

```
$ aws configure
AWS Access Key ID [None]: <AKIAIOSFODNN7EXAMPLE>
AWS Secret Access Key [None]: <wJalrxUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY>
Default region name [None]: <region-code>
Default output format [None]: <json>
```

When you type this command, the AWS CLI prompts you for four pieces of information: access key, secret access key, AWS Region, and output format. This information is stored in a profile (a collection of settings) named default. This profile is used when you run commands, unless you specify another one.

For more information, see Configuring the AWS CLI in the AWS Command Line Interface User Guide.

Install eksct1

You can install 0.33.0 version or later of the eksctl command line utility on macOS (p. 6), Linux (p. 7), or Windows (p. 7). For more information, see https://eksctl.io/.

[To install or upgrade eksctl on macOS using Homebrew]

The easiest way to get started with Amazon EKS and macOS is by installing eksctl with Homebrew. The eksctl Homebrew recipe installs eksctl and any other dependencies that are required for Amazon EKS, such as kubectl. The recipe also installs the aws-iam-authenticator (p. 277), which is required if you don't have the AWS CLI version 1.16.156 or higher installed.

1. If you do not already have Homebrew installed on macOS, install it with the following command.

```
/bin/bash -c "$(curl -fsSL https://raw.githubusercontent.com/Homebrew/install/master/install.sh)"
```

2. Install the Weaveworks Homebrew tap.

```
brew tap weaveworks/tap
```

- Install or upgrade eksctl.
 - Install eksctl with the following command:

```
brew install weaveworks/tap/eksctl
```

If eksctl is already installed, run the following command to upgrade:

```
brew upgrade eksctl && brew link --overwrite eksctl
```

4. Test that your installation was successful with the following command.

```
eksctl version
```

Note

The GitTag version should be at least 0.33.0. If not, check your terminal output for any installation or upgrade errors, or manually download an archive of the release from https://github.com/weaveworks/eksctl/releases/download/0.33.0/eksctl_Darwin_amd64.tar.gz, extract eksctl, and then execute it.

[To install or upgrade eksctl on Linux using curl]

1. Download and extract the latest release of eksctl with the following command.

```
curl --silent --location "https://github.com/weaveworks/eksctl/releases/latest/download/eksctl_$(uname -s)_amd64.tar.gz" | tar xz -C /tmp
```

Move the extracted binary to /usr/local/bin.

```
sudo mv /tmp/eksctl /usr/local/bin
```

3. Test that your installation was successful with the following command.

```
eksctl version
```

Note

The GitTag version should be at least 0.33.0. If not, check your terminal output for any installation or upgrade errors, or replace the address in step 1 with https://github.com/weaveworks/eksctl/releases/download/0.33.0/eksctl_Linux_amd64.tar.gz and complete steps 1-3 again.

[To install or upgrade eksctl on Windows using Chocolatey]

- 1. If you do not already have Chocolatey installed on your Windows system, see Installing Chocolatey.
- 2. Install or upgrade eksctl.
 - Install the binaries with the following command:

```
choco install -y eksctl
```

• If they are already installed, run the following command to upgrade:

```
choco upgrade -y eksctl
```

3. Test that your installation was successful with the following command.

```
eksctl version
```

Note

The GitTag version should be at least 0.33.0. If not, check your terminal output for any installation or upgrade errors, or manually download an archive of the release from https://github.com/weaveworks/eksctl/releases/download/0.33.0/eksctl_Windows_amd64.zip, extract eksctl, and then execute it.

Install and configure kubect1

Kubernetes uses the kubectl command-line utility for communicating with the cluster API server.

Note

If you used the preceding Homebrew instructions to install eksctl on macOS, then kubectl has already been installed on your system. You can skip to Create your Amazon EKS cluster and compute (p. 11).

You can install version 1.18 of the kubectl command line utility for macOS (p. 8), Linux (p. 9), or Windows (p. 10). If you need to install a different version to use with a different cluster version, then see Installing kubectl (p. 289).

[To install kubectl on macOS]

- Download the Amazon EKS vended kubectl binary that corresponds to the Region that your cluster is in.
 - · All Regions other than China Regions.

```
curl -o kubectl https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/
darwin/amd64/kubectl
```

· Beijing and Ningxia China Regions.

```
curl -o kubectl https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/
bin/darwin/amd64/kubectl
```

- 2. (Optional) Verify the downloaded binary with the SHA-256 sum.
 - a. Download the SHA-256 sum that corresponds to the Region that your cluster is in.
 - All Regions other than China Regions.

```
curl -o kubectl.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.18.9/2020-11-02/bin/darwin/amd64/kubectl.sha256
```

· Beijing and Ningxia China Regions.

```
curl -o kubectl.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/darwin/amd64/kubectl.sha256
```

b. Check the SHA-256 sum.

```
openssl sha1 -sha256 kubectl
```

- c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match.
- 3. Apply execute permissions to the binary.

```
chmod +x ./kubectl
```

- 4. Move kubectl to a folder that is in your path.
 - If you don't already have a version of kubectl installed, then move the binary to a folder that's
 already in your PATH.

```
sudo mv ./kubectl /usr/local/bin
```

If you already have a version of kubectl installed, then we recommend creating a \$HOME/bin/kubectl folder, moving the binary to that folder, and ensuring that \$HOME/bin comes first in your \$PATH.

```
mkdir -p $HOME/bin && mv ./kubectl $HOME/bin/kubectl && export PATH=$PATH:$HOME/bin
```

(Optional) Add the \$HOME/bin path to your shell initialization file so that it is configured when you open a shell.

```
echo 'export PATH=$PATH:$HOME/bin' >> ~/.bash_profile
```

5. After you install kubect1, you can verify its version with the following command:

```
kubectl version --short --client
```

[To install kubect1 on Linux]

- Download the Amazon EKS vended kubectl binary that corresponds to the Region that your cluster is in.
 - · All Regions other than China Regions.

```
\verb|curl -o| kubectl https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/linux/amd64/kubectl|
```

Beijing and Ningxia China Regions.

```
curl -o kubectl https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/linux/amd64/kubectl
```

- 2. (Optional) Verify the downloaded binary with the SHA-256 sum.
 - a. Download the SHA-256 sum that corresponds to the Region that your cluster is in.
 - All Regions other than China Regions.

```
curl -o kubectl.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.18.9/2020-11-02/bin/linux/amd64/kubectl.sha256
```

· Beijing and Ningxia China Regions.

```
curl -o kubectl.sha256 https://amazon-eks.s3.cn-
north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/linux/amd64/kubectl.sha256
```

b. Check the SHA-256 sum.

```
openssl sha1 -sha256 kubectl
```

- c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match.
- 3. Apply execute permissions to the binary.

```
chmod +x ./kubectl
```

- 4. Move kubectl to a folder that is in your path.
 - If you don't already have a version of kubectl installed, then move the binary to a folder in your PATH.

```
sudo mv ./kubectl /usr/local/bin
```

If you already have a version of kubectl installed, then we recommend creating a \$HOME/bin/kubectl folder, moving the binary to that folder, and ensuring that \$HOME/bin comes first in your \$PATH.

```
mkdir -p $HOME/bin && mv ./kubectl $HOME/bin/kubectl && export PATH=$PATH:$HOME/bin
```

(Optional) Add the \$HOME/bin path to your shell initialization file so that it is configured when you open a shell.

```
echo 'export PATH=$PATH:$HOME/bin' >> ~/.bash_profile
```

Note

This step assumes you are using the Bash shell; if you are using another shell, change the command to use your specific shell initialization file.

5. After you install kubect1, you can verify its version with the following command:

```
kubectl version --short --client
```

[To install kubectl on Windows]

- 1. Open a PowerShell terminal.
- Download the Amazon EKS vended kubect1 binary that corresponds to the region that your cluster is in.
 - All Regions other than China Regions.

```
curl -o kubectl.exe https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/windows/amd64/kubectl.exe
```

Beijing and Ningxia China Regions.

```
curl -o kubectl.exe https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/windows/amd64/kubectl.exe
```

- 3. (Optional) Verify the downloaded binary with the SHA-256 sum.
 - a. Download the SHA-256 sum that corresponds to the region that your cluster is in.
 - · All Regions other than China Regions.

```
curl -o kubectl.exe.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.18.9/2020-11-02/bin/windows/amd64/kubectl.exe.sha256
```

Beijing and Ningxia China Regions.

```
curl -o kubectl.exe.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/windows/amd64/kubectl.exe.sha256
```

b. Check the SHA-256 sum.

```
Get-FileHash kubectl.exe
```

c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match, although the PowerShell output will be uppercase.

Amazon EKS User Guide Create your Amazon EKS cluster and compute

- 4. Copy the binary to a folder in your PATH. If you have an existing directory in your PATH that you use for command line utilities, copy the binary to that directory. Otherwise, complete the following steps.
 - a. Create a new directory for your command line binaries, such as C:\bin.
 - b. Copy the kubectl.exe binary to your new directory.
 - c. Edit your user or system PATH environment variable to add the new directory to your PATH.
 - d. Close your PowerShell terminal and open a new one to pick up the new PATH variable.
- 5. After you install kubect1, you can verify its version with the following command:

kubectl version --short --client

Create your Amazon EKS cluster and compute

This section helps you to create an Amazon EKS cluster with a compute option to run your applications. The latest Kubernetes version available in Amazon EKS is installed so that you can take advantage of the latest Kubernetes and Amazon EKS features. Some features are not available on older versions of Kubernetes.

Important

Make sure that the AWS Security Token Service (STS) endpoint for the Region that your cluster is in is enabled for your account. If the endpoint is not enabled, then nodes will fail to join the cluster during cluster creation. For more information, see Activating and deactivating AWS STS in an AWS Region.

Select one of the following compute options. To learn more about each option, see Amazon EKS nodes (p. 95). After your cluster is deployed, you can add other options, if you choose.

- Fargate Linux (p. 11) Select this option if you want to run Linux applications on AWS Fargate.
- Managed nodes Linux (p. 12) Select this option if you want to run Amazon Linux applications on Amazon EC2 instances
- Self-managed nodes Windows (p. 13) Select this option if you want to run Windows applications on Amazon EC2 instances. You can also run Linux applications using this option because even if you only need to run Windows applications, your cluster must still have at least one Linux node.

Though not covered in this guide, you can also add Bottlerocket nodes to your cluster. For more information, see Launching self-managed Bottlerocket nodes (p. 121).

[Fargate – Linux]

Note

- You can only use AWS Fargate with Amazon EKS in some Regions. Before using Fargate with Amazon EKS, ensure that the Region that you want to use is supported. For more information, see Getting started with AWS Fargate using Amazon EKS (p. 138).
- Do not use eksctl to create a cluster or nodes in an AWS Region where you have AWS
 Outposts, AWS Wavelength, or AWS Local Zones enabled. Create a cluster and self-managed
 nodes using the Amazon EC2 API or AWS CloudFormation instead. For more information, see
 To launch self-managed Linux nodes using the AWS Management Console (p. 118) and To
 launch self-managed Windows nodes using the AWS Management Console (p. 125).

Create your Amazon EKS cluster with Fargate support with the following command. Replace the <example values> (including <>) with your own values. You can replace <us-west-2> with any Amazon EKS supported Region. You can replace <us-west-2> with any Amazon EKS Fargate supported

Amazon EKS User Guide Create your Amazon EKS cluster and compute

Region (p. 136). We recommend that you deploy version 1.18, but if you replace it with an earlier version, then read the important Amazon EKS release notes (p. 68) for the version and install the corresponding version of kubect1 (p. 289).

```
eksctl create cluster \
--name <my-cluster> \
--version <1.18> \
--region <us-west-2> \
--fargate
```

Your new Amazon EKS cluster is created without a node group. Eksctl creates a pod execution role, a Fargate profile (p. 142) for the default and kube-system namespaces, and it patches the coredns deployment so that it can run on Fargate. For more information see AWS Fargate (p. 136).

[Managed nodes – Linux]

 You can create the nodes with or without a launch template. A launch template allows for greater customization, to include the ability to deploy a custom AMI. For either option, replace the <example values> (including <>) with your own values.

You can replace <us-west-2> with any Amazon EKS supported Region. We recommend that you deploy version 1.18, but if you replace it with an earlier version, then read the important Amazon EKS release notes (p. 68) for the version and install the corresponding version of kubect1 (p. 289).

Though --ssh-public-key is optional, we highly recommend that you specify it when you create your node group with a cluster. This option enables SSH access to the nodes in your managed node group. Enabling SSH access allows you to connect to your instances and gather diagnostic information if there are issues. You cannot enable remote access after the node group is created. If you don't have a public key, then you can create a key pair for Amazon EC2 to specify for --ssh-public-key. Ensure that you create the key in the same Region that you create the cluster in.

Important

Do not use eksctl to create a cluster or nodes in an AWS Region where you have AWS Outposts, AWS Wavelength, or AWS Local Zones enabled. Create a cluster and self-managed nodes using the Amazon EC2 API or AWS CloudFormation instead. For more information, see To launch self-managed Linux nodes using the AWS Management Console (p. 118) and To launch self-managed Windows nodes using the AWS Management Console (p. 125).

Important

Amazon EKS nodes are standard Amazon EC2 instances, and you are billed for them based on normal Amazon EC2 instance prices. For more information, see Amazon EC2 pricing.

• Without a launch template.

Note

Even when you don't specify your own launch template, the Amazon EKS API creates a default launch template and deploys the nodes using the launch template.

```
eksctl create cluster \
--name <my-cluster> \
--version <1.18> \
--region <us-west-2> \
--nodegroup-name <linux-nodes> \
--nodes <3> \
--nodes-min <1> \
--nodes-max <4> \
--with-oidc \
--ssh-access \
```

Amazon EKS User Guide Create your Amazon EKS cluster and compute

```
--ssh-public-key <name-of-ec2-keypair> \
--managed
```

With a launch template – Create your Amazon EKS cluster and Amazon Linux nodes with a launch template. The launch template must already exist and must meet the requirements specified in Launch template configuration basics (p. 112). Create a file with the following contents, replacing the <example values> (including <>) with your own values. Several settings that you specify when deploying without a launch template are moved into the launch template. If you don't specify a version, the template's default version is used.

```
apiVersion: eksctl.io/v1alpha5
kind: ClusterConfig

metadata:
   name: <my-cluster>
   region: <us-west-2>
   version: '<1.18>'
   iam:
   withOIDC: true
managedNodeGroups:
- name: <ng-linux>
   launchTemplate:
   id: lt-<id>
   version: "<1>"
```

2. Create the cluster and node group with the following command.

```
eksctl create cluster --config-file <filename-you-used-in-previous-step.yaml>
```

Output:

You'll see several lines of output as the cluster and nodes are created. The last line of output is similar to the following example line.

```
[#] EKS cluster "<my-cluster>" in "<us-west-2>" region is ready
```

If nodes fail to join the cluster, then see Nodes fail to join cluster (p. 365) in the Troubleshooting guide.

[Self-managed nodes – Windows]

Familiarize yourself with the Windows support considerations (p. 79), which include supported values for instanceType in the example text below. Replace the example <values> with your own values.

We recommend that you deploy version 1.18. If you must deploy an earlier version, then you can only replace it with version 1.16 or later. If you change 1.18, then read the important Amazon EKS release notes (p. 68) for the version and install the corresponding version of kubect1 (p. 289).

Important

Do not use eksctl to create a cluster or nodes in an AWS Region where you have AWS Outposts, AWS Wavelength, or AWS Local Zones enabled. Create a cluster and self-managed nodes using the Amazon EC2 API or AWS CloudFormation instead. For more information, see To launch self-managed Linux nodes using the AWS Management Console (p. 118) and To launch self-managed Windows nodes using the AWS Management Console (p. 125).

Important

Amazon EKS nodes are standard Amazon EC2 instances, and you are billed for them based on normal Amazon EC2 instance prices. For more information, see Amazon EC2 pricing.

1. Create a file with the following contents, replacing the <example values> (including <>) with your own values. The file will be used to create a cluster with a self-managed Windows node group and a managed Linux node group. Even if you only want to run Windows applications in your cluster, all Amazon EKS clusters must contain at least one Linux node, though we recommend that you create at least two Linux nodes for availability purposes. For more information about using a config file with eksctl, the config file schema, and config file samples, see the eksctl documentation. We recommend that you deploy version 1.18 (but first remove the <>). If you replace 1.18, then read the important Amazon EKS release notes (p. 68) for the version and install the corresponding version of kubectl (p. 289).

```
apiVersion: eksctl.io/v1alpha5
kind: ClusterConfig
metadata:
  name: <my-cluster>
 region: <us-west-2>
 version: '<1.18>'
iam:
  withOIDC: true
managedNodeGroups:
  - name: nux-ng>
    instanceType: <m5.large>
    minSize: <2>
nodeGroups:
  - name: <windows-ng>
    instanceType: <m5.large>
    minSize: <2>
    volumeSize: <100>
    amiFamily: <WindowsServer2019FullContainer>
```

2. Create your Amazon EKS cluster and Windows and Linux nodes with the following command.

```
eksctl create cluster -f <filename-you-used-in-previous-step.yaml> --install-vpc-
controllers
```

Note

For more information about the available options for eksctl create cluster, see the project README on GitHub or view the help page with the following command.

```
eksctl create cluster --help
```

Output:

You'll see several lines of output as the cluster and nodes are created. The last line of output is similar to the following example line.

```
[#] EKS cluster "<my-cluster>" in "<us-west-2>" region is ready
```

If nodes fail to join the cluster, then see Nodes fail to join cluster (p. 365) in the Troubleshooting quide.

Cluster provisioning usually takes between 10 and 15 minutes.

3. When your cluster is ready, test that your kubectl configuration is correct.

Amazon EKS User Guide Next steps

```
kubectl get svc
```

Note

If you receive any authorization or resource type errors, see Unauthorized or access denied (kubectl) (p. 366) in the troubleshooting section.

Output:

NAME	TYPE	CLUSTER-IP	EXTERNAL-IP	PORT(S)	AGE
svc/kubernetes	ClusterIP	10.100.0.1	<none></none>	443/TCP	1m

4. (Linux accelerated AMI nodes only) If you chose an accelerated AMI instance type and the Amazon EKS optimized accelerated AMI, then you must apply the NVIDIA device plugin for Kubernetes as a DaemonSet on your cluster with the following command.

```
kubectl apply -f https://raw.githubusercontent.com/NVIDIA/k8s-device-plugin/v0.6.0/
nvidia-device-plugin.yml
```

Next steps

Now that you have a working Amazon EKS cluster with nodes, you are ready to start installing Kubernetes add-ons and deploying applications to your cluster. The following documentation topics help you to extend the functionality of your cluster.

- Restrict access to IMDS (p. 349) If you plan to assign IAM roles to all of your Kubernetes service
 accounts so that pods only have the minimum permissions that they need, and no pods in the
 cluster require access to the Amazon EC2 instance metadata service (IMDS) for other reasons, such as
 retrieving the current Region, then we recommend blocking pod access to IMDS. For more information,
 see the section called "IAM roles for service accounts" (p. 336) and the section called "Restricting
 access to the instance profile" (p. 349).
- Cluster Autoscaler (p. 61) Configure the Kubernetes Cluster Autoscaler to automatically adjust the number of nodes in your node groups.
- Deploy a sample Linux workload (p. 248) Deploy a sample application to test your cluster and Linux nodes.
- Deploy a Windows sample application (p. 85) Deploy a sample application to test your cluster and Windows nodes.
- Cluster management (p. 289) Learn how to use important tools for managing your cluster.

Getting started with the AWS Management Console

This getting started guide helps you to create all of the required resources to get started with Amazon EKS using the AWS Management Console. In this guide, you manually create each resource in the Amazon EKS or AWS CloudFormation consoles. At the end of this tutorial, you will have a running Amazon EKS cluster that you can deploy applications to.

The procedures in this guide give you complete visibility into how each resource is created and how the resources interact with each other. If you'd rather have most of the resources created for you automatically, use the <code>eksctl</code> CLI to create your cluster and nodes. For more information, see Getting started with <code>eksctl</code> (p. 4).

Prerequisites

This section helps you to install and configure the following tools and resources that you need to create and manage an Amazon EKS cluster.

- The AWS CLI (p. 16) A command line tools for working with AWS services, including Amazon EKS.
- kubect1 (p. 17) A command line tool for working with Kubernetes clusters.
- Cluster IAM role (p. 21) A role allows Kubernetes clusters managed by Amazon EKS to make calls to other AWS services on your behalf to manage the resources that you use with the service.

Install the AWS CLI

You can install the latest version of the AWS CLI, for macOS (p. 16), Linux (p. 16), or Windows (p. 17).

[To install the AWS CLI for macOS]

1. If you currently have the AWS CLI installed, determine which version that you have installed.

```
aws --version
```

2. If you don't have version 1.18.190 or later, or version 2.1.7 or later installed, then install the AWS CLI version 2. For other installation options, or to upgrade your currently installed version 2, see Upgrading the AWS CLI version 2 on macOS.

```
curl "https://awscli.amazonaws.com/AWSCLIV2.pkg" -o "AWSCLIV2.pkg" sudo installer -pkg AWSCLIV2.pkg -target /
```

If you're unable to use the AWS CLI version 2, then ensure that you have the latest version of the AWS CLI version 1 installed using the following command.

```
pip3 install awscli --upgrade --user
```

[To install the AWS CLI for Linux]

1. If you currently have the AWS CLI installed, determine which version that you have installed.

```
aws --version
```

 If you don't have version 1.18.190 or later, or version 2.1.7 or later installed, then install the AWS CLI version 2. For other installation options, or to upgrade your currently installed version 2, see Upgrading the AWS CLI version 2 on Linux.

```
curl "https://awscli.amazonaws.com/awscli-exe-linux-x86_64.zip" -o "awscliv2.zip" unzip awscliv2.zip sudo ./aws/install
```

If you're unable to use the AWS CLI version 2, then ensure that you have the latest version of the AWS CLI version 1 installed using the following command.

```
pip3 install --upgrade --user awscli
```

[To install the AWS CLI for Windows]

1. If you currently have the AWS CLI installed, determine which version that you have installed.

```
aws --version
```

- 2. If you don't have either version 1.18.190 or later, or version 2.1.7 or later installed, then install the AWS CLI version 2 using the following steps. For other installation options, or to upgrade your currently installed version 2, see Upgrading the AWS CLI version 2 on Windows.
 - a. Download the AWS CLI MSI installer for Windows (64-bit) at https://awscli.amazonaws.com/ AWSCLIV2.msi
 - b. Run the downloaded MSI installer and follow the onscreen instructions. By default, the AWS CLI installs to C:\Program Files\Amazon\AWSCLIV2.
- 3. (Optional) If you're unable to use the AWS CLI version 2, then ensure that you have the latest version of the AWS CLI version 1 installed using the following command.

```
pip3 install --user --upgrade awscli
```

Configure your AWS CLI credentials

The AWS CLI requires that you have AWS credentials configured in your environment. The aws configure command is the fastest way to set up your AWS CLI installation for general use.

```
$ aws configure
AWS Access Key ID [None]: <AKIAIOSFODNN7EXAMPLE>
AWS Secret Access Key [None]: <wJalrxUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY>
Default region name [None]: <region-code>
Default output format [None]: <json>
```

When you type this command, the AWS CLI prompts you for four pieces of information: access key, secret access key, AWS Region, and output format. This information is stored in a profile (a collection of settings) named default. This profile is used when you run commands, unless you specify another one.

For more information, see Configuring the AWS CLI in the AWS Command Line Interface User Guide.

Install and configure kubect1

Kubernetes uses the kubect1 command-line utility for communicating with the cluster API server.

You can install version 1.18 of the kubectl command line utility for macOS (p. 17), Linux (p. 18), or Windows (p. 20).

[To install kubect1 on macOS]

- Download the Amazon EKS vended kubect1 binary that corresponds to the Region that your cluster is in.
 - All Regions other than China Regions.

```
curl -o kubectl https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/darwin/amd64/kubectl
```

· Beijing and Ningxia China Regions.

curl -o kubectl https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/ bin/darwin/amd64/kubectl

- 2. (Optional) Verify the downloaded binary with the SHA-256 sum.
 - a. Download the SHA-256 sum that corresponds to the Region that your cluster is in.
 - · All Regions other than China Regions.

```
curl -o kubectl.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.18.9/2020-11-02/bin/darwin/amd64/kubectl.sha256
```

· Beijing and Ningxia China Regions.

```
curl -o kubectl.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/darwin/amd64/kubectl.sha256
```

b. Check the SHA-256 sum.

```
openssl sha1 -sha256 kubectl
```

- c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match.
- Apply execute permissions to the binary.

```
chmod +x ./kubectl
```

- 4. Move kubectl to a folder that is in your path.
 - If you don't already have a version of kubect1 installed, then move the binary to a folder that's already in your PATH.

```
sudo mv ./kubectl /usr/local/bin
```

If you already have a version of kubectl installed, then we recommend creating a \$HOME/bin/kubectl folder, moving the binary to that folder, and ensuring that \$HOME/bin comes first in your \$PATH.

```
\verb|mkdir -p $HOME/bin \&\& mv ./kubectl $HOME/bin/kubectl \&\& export PATH=$PATH:$HOME/bin | line of the context o
```

(Optional) Add the \$HOME/bin path to your shell initialization file so that it is configured when you open a shell.

```
echo 'export PATH=$PATH:$HOME/bin' >> ~/.bash_profile
```

5. After you install kubect1, you can verify its version with the following command:

```
kubectl version --short --client
```

[To install kubect1 on Linux]

- Download the Amazon EKS vended kubectl binary that corresponds to the Region that your cluster is in.
 - All Regions other than China Regions.

curl -o kubectl https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/ linux/amd64/kubectl

Beijing and Ningxia China Regions.

curl -o kubectl https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/ bin/linux/amd64/kubectl

- 2. (Optional) Verify the downloaded binary with the SHA-256 sum.
 - a. Download the SHA-256 sum that corresponds to the Region that your cluster is in.
 - All Regions other than China Regions.

```
curl -o kubectl.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.18.9/2020-11-02/bin/linux/amd64/kubectl.sha256
```

· Beijing and Ningxia China Regions.

```
curl -o kubectl.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/linux/amd64/kubectl.sha256
```

b. Check the SHA-256 sum.

```
openssl sha1 -sha256 kubectl
```

- c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match.
- Apply execute permissions to the binary.

```
chmod +x ./kubectl
```

- 4. Move kubectl to a folder that is in your path.
 - If you don't already have a version of kubectl installed, then move the binary to a folder in your PATH.

```
sudo mv ./kubectl /usr/local/bin
```

• If you already have a version of kubectl installed, then we recommend creating a \$HOME/bin/kubectl folder, moving the binary to that folder, and ensuring that \$HOME/bin comes first in your \$PATH.

```
mkdir -p $HOME/bin && mv ./kubectl $HOME/bin/kubectl && export PATH=$PATH:$HOME/bin
```

(Optional) Add the \$HOME/bin path to your shell initialization file so that it is configured when you open a shell.

```
echo 'export PATH=$PATH:$HOME/bin' >> ~/.bash_profile
```

Note

This step assumes you are using the Bash shell; if you are using another shell, change the command to use your specific shell initialization file.

5. After you install kubectl, you can verify its version with the following command:

```
kubectl version --short --client
```

[To install kubectl on Windows]

- 1. Open a PowerShell terminal.
- 2. Download the Amazon EKS vended kubectl binary that corresponds to the Region that your cluster is in.
 - All Regions other than China Regions.

```
\verb|curl -o kubectl.exe https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/windows/amd64/kubectl.exe|
```

Beijing and Ningxia China Regions.

```
curl -o kubectl.exe https://amazon-eks.s3.cn-
north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/windows/amd64/kubectl.exe
```

- 3. (Optional) Verify the downloaded binary with the SHA-256 sum.
 - a. Download the SHA-256 sum that corresponds to the Region that your cluster is in.
 - All Regions other than China Regions.

```
curl -o kubectl.exe.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.18.9/2020-11-02/bin/windows/amd64/kubectl.exe.sha256
```

· Beijing and Ningxia China Regions.

```
curl -o kubectl.exe.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/windows/amd64/kubectl.exe.sha256
```

b. Check the SHA-256 sum.

```
Get-FileHash kubectl.exe
```

- c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match, although the PowerShell output will be uppercase.
- 4. Copy the binary to a folder in your PATH. If you have an existing directory in your PATH that you use for command line utilities, copy the binary to that directory. Otherwise, complete the following steps.
 - a. Create a new directory for your command line binaries, such as C:\bin.
 - b. Copy the kubectl.exe binary to your new directory.
 - c. Edit your user or system PATH environment variable to add the new directory to your PATH.
 - d. Close your PowerShell terminal and open a new one to pick up the new PATH variable.
- 5. After you install kubect1, you can verify its version with the following command:

```
kubectl version --short --client
```

Create your Amazon EKS cluster IAM role

You can create the role using the AWS Management Console (p. 21) or AWS CloudFormation (p. 21).

[To create your Amazon EKS cluster role in the IAM console]

- 1. Open the IAM console at https://console.aws.amazon.com/iam/.
- 2. Choose Roles, then Create role.
- Choose EKS from the list of services, then EKS Cluster for your use case, and then Next: Permissions.
- 4. Choose Next: Tags.
- 5. (Optional) Add metadata to the role by attaching tags as key–value pairs. For more information about using tags in IAM, see Tagging IAM Entities in the IAM User Guide.
- 6. Choose Next: Review.
- For Role name, enter a unique name for your role, such as eksClusterRole, then choose Create role.

[To create your Amazon EKS cluster role with AWS CloudFormation]

1. Save the following AWS CloudFormation template to a text file on your local system.

```
AWSTemplateFormatVersion: '2010-09-09'
Description: 'Amazon EKS Cluster Role'
Resources:
  eksClusterRole:
    Type: AWS::IAM::Role
    Properties:
      AssumeRolePolicyDocument:
        Version: '2012-10-17'
        Statement:
         - Effect: Allow
          Principal:
            Service:
            - eks.amazonaws.com
          Action:
          - sts:AssumeRole
      ManagedPolicyArns:
        - arn:aws:iam::aws:policy/AmazonEKSClusterPolicy
Outputs:
    Description: The role that Amazon EKS will use to create AWS resources for
 Kubernetes clusters
    Value: !GetAtt eksClusterRole.Arn
    Export:
      Name: !Sub "${AWS::StackName}-RoleArn"
```

Note

Prior to April 16, 2020, ManagedPolicyArns had an entry for arn:aws:iam::aws:policy/AmazonEKSServicePolicy. With the AWSServiceRoleForAmazonEKS service-linked role, that policy is no longer required.

2. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.

- 3. Choose Create stack.
- 4. For Specify template, select Upload a template file, and then choose Choose file.
- 5. Choose the file you created earlier, and then choose Next.
- 6. For Stack name, enter a name for your role, such as eksClusterRole, and then choose Next.
- 7. On the **Configure stack options** page, choose **Next**.
- 8. On the **Review** page, review your information, acknowledge that the stack might create IAM resources, and then choose **Create stack**.

Create your Amazon EKS cluster VPC

This section guides you through creating a VPC with either:

- Two public subnets and two private subnets (p. 22)
- Three public subnets (p. 23)
- Three private subnets (p. 24)

When you create an Amazon EKS cluster, you specify the VPC subnets for your cluster to use. Amazon EKS requires subnets in at least two Availability Zones. We recommend a VPC with public and private subnets so that Kubernetes can create public load balancers in the public subnets that load balance traffic to pods running on nodes that are in private subnets.

For more information about the VPC types, see Creating a VPC for your Amazon EKS cluster (p. 197).

To create your cluster VPC with public and private subnets

- 1. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
- 2. From the navigation bar, select a Region that supports Amazon EKS.
- 3. Choose Create stack, With new resources (standard).
- 4. For Choose a template, select Specify an Amazon S3 template URL.
- Paste the URL that corresponds to the Region that your cluster is in into the text area and choose Next:
 - All Regions other than China Regions.

https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/amazon-eks-vpc-private-subnets.yaml

· Beijing and Ningxia China Regions.

 $\label{lem:https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/amazon-eks-vpc-private-subnets.yaml$

- 6. On the Specify Details page, fill out the parameters accordingly, and then choose Next.
 - Stack name: Choose a stack name for your AWS CloudFormation stack. For example, you can call
 it eks-vpc.
 - VpcBlock: Choose a CIDR range for your VPC. Each worker node, pod, and load balancer that you
 deploy is assigned an IP address from this block. The default value provides enough IP addresses
 for most implementations, but if it doesn't, then you can change it. For more information, see VPC
 and subnet sizing in the Amazon VPC User Guide. You can also add additional CIDR blocks to the
 VPC once it's created.
 - PublicSubnet01Block: Specify a CIDR block for public subnet 1. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it

- PublicSubnet02Block: Specify a CIDR block for public subnet 2. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
- **PrivateSubnet01Block**: Specify a CIDR block for private subnet 1. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
- **PrivateSubnet02Block**: Specify a CIDR block for private subnet 2. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
- 7. (Optional) On the Options page, tag your stack resources. Choose Next.
- 8. On the Review page, choose Create.
- 9. When your stack is created, select it in the console and choose **Outputs**.
- 10. Record the **SecurityGroups** value for the security group that was created. When you add nodes to your cluster, you must specify the ID of the security group. The security group is applied to the elastic network interfaces that are created by Amazon EKS in your subnets that allows the control plane to communicate with your nodes. These network interfaces have Amazon EKS <cluster name> in their description.
- 11. Record the **VpcId** for the VPC that was created. You need this when you launch your node group template.
- 12. Record the **SubnetIds** for the subnets that were created and whether you created them as public or private subnets. When you add nodes to your cluster, you must specify the IDs of the subnets that you want to launch the nodes into.

To create your cluster VPC with only public subnets

- 1. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
- 2. From the navigation bar, select a Region that supports Amazon EKS.
- 3. Choose Create stack, With new resources (standard).
- 4. For Choose a template, select Specify an Amazon S3 template URL.
- Paste the URL that corresponds to the Region that your cluster is in into the text area and choose Next:
 - · All Regions other than China Regions.

https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/amazon-eks-vpc-sample.yaml

Beijing and Ningxia China Regions.

https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/amazon-eks-vpc-sample.yaml

- 6. On the **Specify Details** page, fill out the parameters accordingly, and then choose **Next**.
 - Stack name: Choose a stack name for your AWS CloudFormation stack. For example, you can call
 it eks-vpc.
 - VpcBlock: Choose a CIDR block for your VPC. Each worker node, pod, and load balancer that you
 deploy is assigned an IP address from this block. The default value provides enough IP addresses
 for most implementations, but if it doesn't, then you can change it. For more information, see VPC
 and subnet sizing in the Amazon VPC User Guide. You can also add additional CIDR blocks to the
 VPC once it's created.
 - **SubnetO1Block**: Specify a CIDR block for subnet 1. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
 - **Subnet02Block**: Specify a CIDR block for subnet 2. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it

- **Subnet03Block**: Specify a CIDR block for subnet 3. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
- 7. (Optional) On the Options page, tag your stack resources. Choose Next.
- On the Review page, choose Create.
- 9. When your stack is created, select it in the console and choose **Outputs**.
- 10. Record the **SecurityGroups** value for the security group that was created. When you add nodes to your cluster, you must specify the ID of the security group. The security group is applied to the elastic network interfaces that are created by Amazon EKS in your subnets that allows the control plane to communicate with your nodes. These network interfaces have Amazon EKS <cluster name> in their description.
- 11. Record the **VpcId** for the VPC that was created. You need this when you launch your node group template.
- 12. Record the **SubnetIds** for the subnets that were created. When you add nodes to your cluster, you must specify the IDs of the subnets that you want to launch the nodes into.

To create your cluster VPC with only private subnets

- 1. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
- 2. From the navigation bar, select a Region that supports Amazon EKS.
- 3. Choose Create stack, With new resources (standard).
- 4. For Choose a template, select Specify an Amazon S3 template URL.
- Paste the URL that corresponds to the Region that your cluster is in into the text area and choose Next:
 - · All Regions other than China Regions.

 $\label{lem:https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/amazon-eks-fully-private-vpc.yaml$

Beijing and Ningxia China Regions.

 $\label{lem:https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/amazon-eks-fully-private-vpc.yaml$

- 6. On the Specify Details page, fill out the parameters accordingly, and then choose Next.
 - Stack name: Choose a stack name for your AWS CloudFormation stack. For example, you can call
 it eks-vpc.
 - VpcBlock: Choose a CIDR block for your VPC. Each worker node, pod, and load balancer that you
 deploy is assigned an IP address from this block. The default value provides enough IP addresses
 for most implementations, but if it doesn't, then you can change it. For more information, see VPC
 and subnet sizing in the Amazon VPC User Guide. You can also add additional CIDR blocks to the
 VPC once it's created.
 - **PrivateSubnet01Block**: Specify a CIDR block for subnet 1. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
 - **PrivateSubnet02Block**: Specify a CIDR block for subnet 2. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
 - PrivateSubnet03Block: Specify a CIDR block for subnet 3. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
- 7. (Optional) On the **Options** page, tag your stack resources. Choose **Next**.
- 8. On the Review page, choose Create.
- 9. When your stack is created, select it in the console and choose **Outputs**.

- 10. Record the **SecurityGroups** value for the security group that was created. When you add nodes to your cluster, you must specify the ID of the security group. The security group is applied to the elastic network interfaces that are created by Amazon EKS in your subnets that allow the control plane to communicate with your nodes. These network interfaces have Amazon EKS <cluster name> in their description.
- 11. Record the **VpcId** for the VPC that was created. You need this when you launch your node group template.
- 12. Record the **SubnetIds** for the subnets that were created. When you add nodes to your cluster, you must specify the IDs of the subnets that you want to launch the nodes into.

Step 1: Create your Amazon EKS cluster

This section helps you to create an Amazon EKS cluster. The latest Kubernetes version available in Amazon EKS is installed so that you can take advantage of the latest Kubernetes and Amazon EKS features. Some features are not available on older versions of Kubernetes.

Important

When an Amazon EKS cluster is created, the IAM entity (user or role) that creates the cluster is added to the Kubernetes RBAC authorization table as the administrator (with system:masters permissions). Initially, only that IAM user can make calls to the Kubernetes API server using kubectl. For more information, see Managing users or IAM roles for your cluster (p. 285). If you use the console to create the cluster, you must ensure that the same IAM user credentials are in the AWS SDK credential chain when you are running kubectl commands on your cluster. If you install and configure the AWS CLI, you can configure the IAM credentials for your user. If the AWS CLI version 1.16.156 or later is configured properly for your user, then eksctl can find those credentials. For more information, see Configuring the AWS CLI in the AWS Command Line Interface User Guide. If you can't install the AWS CLI version 1.16.156 or later, then you must install the aws-iam-authenticator.

To create your cluster with the console

- Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. Choose Create cluster.

Note

If your IAM user doesn't have administrative privileges, you must explicitly add permissions for that user to call the Amazon EKS API operations. For more information, see Amazon EKS identity-based policy examples (p. 322).

- 3. On the **Configure cluster** page, fill in the following fields:
 - Name A unique name for your cluster.
 - Kubernetes version The version of Kubernetes to use for your cluster.
 - Cluster service role Select the IAM role that you created with Create your Amazon EKS cluster IAM role (p. 21).
 - Secrets encryption (Optional) Choose to enable envelope encryption of Kubernetes secrets using the AWS Key Management Service (AWS KMS). If you enable envelope encryption, the Kubernetes secrets are encrypted using the customer master key (CMK) that you select. The CMK must be symmetric, created in the same region as the cluster, and if the CMK was created in a different account, the user must have access to the CMK. For more information, see Allowing users in other accounts to use a CMK in the AWS Key Management Service Developer Guide.

Kubernetes secrets encryption with an AWS KMS CMK requires Kubernetes version 1.13 or later. If no keys are listed, you must create one first. For more information, see Creating keys.

 Tags – (Optional) Add any tags to your cluster. For more information, see Tagging your Amazon EKS resources (p. 309).

- 4. Select Next.
- 5. On the **Specify networking** page, select values for the following fields:
 - VPC The VPC that you created previously in Create your Amazon EKS cluster VPC (p. 22). You
 can find the name of your VPC in the drop-down list.
 - Subnets By default, the available subnets in the VPC specified in the previous field are
 preselected. Unselect any subnet that you don't want to host cluster resources, such as worker
 nodes or load balancers.

Important

Do not select a subnet in AWS Outposts, AWS Wavelength or an AWS Local Zone when creating your cluster. After cluster creation, you can tag the AWS Outposts AWS Wavelength or AWS Local Zone subnets with the cluster name, which will then enable you to deploy self-managed nodes to the subnet. For more information, see Subnet tagging requirement (p. 204).

• Security groups – The SecurityGroups value from the AWS CloudFormation output that you generated with Create your Amazon EKS cluster VPC (p. 22). This security group has ControlPlaneSecurityGroup in the drop-down name.

Important

The node AWS CloudFormation template modifies the security group that you specify here, so **Amazon EKS strongly recommends that you use a dedicated security group for each cluster control plane (one per cluster)**. If this security group is shared with other resources, you might block or disrupt connections to those resources.

- (Optional) Choose **Configure Kubernetes Service IP address range** and specify a **Service IPv4 range** if you want to specify which CIDR block Kubernetes assigns service IP addresses from. The CIDR block must meet the following requirements:
 - Within one of the following ranges: 10.0.0.0/8, 172.16.0.0/12, or 192.168.0.0/16.
 - Between /24 and /12.
 - Doesn't overlap with any CIDR block specified in your VPC.

We recommend specifying a CIDR block that doesn't overlap with any other networks that are peered or connected to your VPC. If you don't enable this, Kubernetes assigns service IP addresses from either the 10.100.0.0/16 or 172.20.0.0/16 CIDR blocks.

Important

You can only specify a custom CIDR block when you create a cluster and can't change this value once the cluster is created.

- For **Cluster endpoint access** Choose one of the following options:
 - Public Enables only public access to your cluster's Kubernetes API server endpoint. Kubernetes
 API requests that originate from outside of your cluster's VPC use the public endpoint. By
 default, access is allowed from any source IP address. You can optionally restrict access to one
 or more CIDR ranges such as 192.168.0.0/16, for example, by selecting Advanced settings and
 then selecting Add source.
 - Private Enables only private access to your cluster's Kubernetes API server endpoint.
 Kubernetes API requests that originate from within your cluster's VPC use the private VPC endpoint.

Important

If you created a VPC without outbound internet access, then you must enable private access.

• Public and private – Enables public and private access.

For more information about the previous options, see Modifying cluster endpoint access (p. 57).

6. If you selected Kubernetes version 1.17 or earlier on the previous page, skip to the next step. If you selected version 1.18, accept the defaults in the **Networking add-ons** section to install the latest

Amazon EKS User Guide Step 2: Create a kubeconfig file

version of the AWS VPC CNI (p. 208) Amazon EKS add-on. You can only use Amazon EKS add-ons with 1.18 clusters because Amazon EKS add-ons require the Server-side Apply Kubernetes feature, which wasn't available until Kubernetes 1.18. If you selected a different Kubernetes version for your cluster, then this option isn't shown.

Important

The AWS VPC CNI add-on is configured to use the IAM permissions assigned to the Amazon EKS node IAM role (p. 332). After the cluster is created, but before you deploy any Amazon EC2 nodes to your cluster, you must ensure that the Amazoneks_CNI_Policy IAM policy is attached to either the node IAM role, or to a different role associated to the Kubernetes service account that the add-on runs as. We recommend that you assign the policy to a different IAM role than the node IAM role by completing the instructions in Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210). Once your cluster and IAM role are created, you can update the add-on (p. 52) to use the IAM role that you create.

- 7. Select Next.
- 8. On the **Configure logging** page, you can optionally choose which log types that you want to enable. By default, each log type is **Disabled**. For more information, see Amazon EKS control plane logging (p. 66).
- 9. Select Next.
- 10. On the Review and create page, review the information that you entered or selected on the previous pages. Select Edit if you need to make changes to any of your selections. Once you're satisfied with your settings, select Create. The Status field shows CREATING until the cluster provisioning process completes.

Note

You might receive an error that one of the Availability Zones in your request doesn't have sufficient capacity to create an Amazon EKS cluster. If this happens, the error output contains the Availability Zones that can support a new cluster. Retry creating your cluster with at least two subnets that are located in the supported Availability Zones for your account. For more information, see Insufficient capacity (p. 365).

When your cluster provisioning is complete (usually between 10 and 15 minutes), note the API server endpoint and Certificate authority values. These are used in your kubectl configuration.

11. (Optional) To use Amazon EKS add-ons, or to enable individual Kubernetes workloads to have specific IAM permissions, you need to enable an OpenID Connect (OIDC) provider for your cluster. To configure an OIDC provider for your cluster, see the section called "Enabling" (p. 341). You only need to enable an OIDC provider for your cluster once. To learn more about Amazon EKS addons, see Configure an Amazon EKS add-on (p. 52). To learn more about assigning specific IAM permissions to your workloads, see IAM roles for service accounts technical overview (p. 336).

Step 2: Create a kubeconfig file

In this section, you create a kubeconfig file for your cluster with the AWS CLI update-kubeconfig command.

To create your kubeconfig file with the AWS CLI

- Use the AWS CLI update-kubeconfig command to create or update a kubeconfig for your cluster.
 - By default, the resulting configuration file is created at the default kubeconfig path (.kube/config) in your home directory or merged with an existing kubeconfig at that location. You can specify another path with the --kubeconfig option.
 - You can specify an IAM role ARN with the --role-arn option to use for authentication when you issue kubectl commands. Otherwise, the IAM entity in your default AWS CLI or SDK credential

chain is used. You can view your default AWS CLI or SDK identity by running the aws sts get-caller-identity command.

• For more information, see the help page with the aws eks update-kubeconfig help command or see update-kubeconfig in the AWS CLI Command Reference.

Note

To run the following command, you must have permission to the use the eks:DescribeCluster API action with the cluster that you specify. For more information, see Amazon EKS identity-based policy examples (p. 322).

```
aws eks --region <us-west-2> update-kubeconfig --name <cluster_name>
```

2. Test your configuration.

```
kubectl get svc
```

Note

If you receive any authorization or resource type errors, see Unauthorized or access denied (kubectl) (p. 366) in the troubleshooting section.

Output:

NAME	TYPE	CLUSTER-IP	EXTERNAL-IP	PORT(S)	AGE
svc/kubernetes	ClusterIP	10.100.0.1	<none></none>	443/TCP	1m

Step 3: Create compute

Select one of the following compute options. To learn more about each option, see Amazon EKS nodes (p. 95). After your cluster is deployed, you can add other options, if you choose.

- Fargate Linux (p. 28) Select this option if you want to run Linux applications on AWS Fargate.
- Managed nodes Linux (p. 29) Select this option if you want to run Amazon Linux or Windows
 applications on Amazon EC2 instances.

Though not covered in this guide, you can also add Bottlerocket nodes to your cluster. For more information, see Launching self-managed Bottlerocket nodes (p. 121).

[Fargate – Linux]

Note

You can only use AWS Fargate with Amazon EKS in some Regions. Before using Fargate with Amazon EKS, ensure that the Region that you want to use is supported. For more information, see Getting started with AWS Fargate using Amazon EKS (p. 138).

Before creating an AWS Fargate profile, you must create a Fargate pod execution role to use with your profile.

To create an AWS Fargate pod execution role with the AWS Management Console

- Open the IAM console at https://console.aws.amazon.com/iam/.
- 2. Choose Roles, then Create role.
- Choose EKS from the list of services, EKS Fargate pod for your use case, and then Next: Permissions.

- 4. Choose Next: Tags.
- 5. (Optional) Add metadata to the role by attaching tags as key–value pairs. For more information about using tags in IAM, see Tagging IAM Entities in the IAM User Guide.
- 6. Choose Next: Review.
- For Role name, enter a unique name for your role, such as AmazonEKSFargatePodExecutionRole, then choose Create role.

You can now create the Fargate profile, specifying the IAM role that you created.

To create a Fargate profile for a cluster with the AWS Management Console

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. Choose the cluster to create a Fargate profile for.
- 3. Under Fargate profiles, choose Add Fargate profile.
- 4. On the Configure Fargate profile page, enter the following information and choose Next.
 - a. For Name, enter a unique name for your Fargate profile.
 - b. For **Pod execution role**, choose the pod execution role to use with your Fargate profile. Only IAM roles with the eks-fargate-pods.amazonaws.com service principal are shown. If you do not see any roles listed here, you must create one. For more information, see Pod execution role (p. 334).
 - c. For **Subnets**, choose the subnets to use for your pods. By default, all subnets in your cluster's VPC are selected. Only private subnets are supported for pods running on Fargate; you must deselect any public subnets.
 - d. For **Tags**, you can optionally tag your Fargate profile. These tags do not propagate to other resources associated with the profile, such as its pods.
- 5. On the Configure pods selection page, enter the following information and choose Next.
 - a. For Namespace, enter a namespace to match for pods, such as kube-system or default.
 - b. (Optional) Add Kubernetes labels to the selector that pods in the specified namespace must have to match the selector. For example, you could add the label infrastructure: fargate to the selector so that only pods in the specified namespace that also have the infrastructure: fargate Kubernetes label match the selector.
- 6. On the **Review and create** page, review the information for your Fargate profile and choose **Create**.

[Managed nodes – Linux]

The Amazon EKS node kubelet daemon makes calls to AWS APIs on your behalf. Nodes receive permissions for these API calls through an IAM instance profile and associated policies. You must create an IAM role before you can launch the nodes. You can create the role using the AWS Management Console (p. 29) or AWS CloudFormation (p. 30).

Note

We recommend that you create a new node IAM role for each cluster. Otherwise, a node from one cluster could authenticate with another cluster that it does not belong to.

To create your Amazon EKS node role in the IAM console

- 1. Open the IAM console at https://console.aws.amazon.com/iam/.
- Choose Roles, then Create role.
- Choose EC2 from the list of Common use cases under Choose a use case, then choose Next: Permissions.

- In the Filter policies box, enter AmazonEKSWorkerNodePolicy. Check the box to the left of AmazonEKSWorkerNodePolicy.
- 5. In the **Filter policies** box, enter AmazonEC2ContainerRegistryReadOnly. Check the box to the left of **AmazonEC2ContainerRegistryReadOnly**.
- 6. The AmazonEKS_CNI_Policy policy must be attached to either this role or to a different role that is mapped to the aws-node Kubernetes service account. We recommend assigning the policy to the role associated to the Kubernetes service account instead of assigning it to this role. For more information, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).
- 7. Choose **Next: Tags**.
- 8. (Optional) Add metadata to the role by attaching tags as key–value pairs. For more information about using tags in IAM, see Tagging IAM Entities in the IAM User Guide.
- Choose Next: Review.
- For Role name, enter a unique name for your role, such as NodeInstanceRole. For Role description, replace the current text with descriptive text such as Amazon EKS - Node Group Role, then choose Create role.

To create your Amazon EKS node role using AWS CloudFormation

- Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
- 2. Choose Create stack and then choose With new resources (standard).
- 3. For Specify template, select Amazon S3 URL.
- 4. Paste the URL that corresponds to the Region that your cluster is in into the **Amazon S3 URL** text area and choose **Next** twice:
 - All Regions other than China Regions.

 $\verb|https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/amazon-eks-nodegroup-role.yaml|$

· Beijing and Ningxia China Regions.

https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/amazon-eks-nodegroup-role.yaml

- On the Specify stack details page, for Stack name enter a name such as eks-node-group-instancerole and choose Next.
- 6. (Optional) On the **Configure stack options** page, you can choose to tag your stack resources. Choose **Next**.
- 7. On the **Review** page, check the box in the **Capabilities** section and choose **Create stack**.
- 8. When your stack is created, select it in the console and choose **Outputs**.
- 9. Record the **NodeInstanceRole** value for the IAM role that was created. You need this when you create your node group.
- 10. (Optional, but recommended) One of the IAM policies attached to the role by the AWS CloudFormation template in a previous step is the AmazonEKS_CNI_Policy managed policy. The policy must be attached to this role or to a role associated to the Kubernetes aws-node service account that is used for the Amazon EKS VPC CNI plugin. We recommend assigning the policy to the role associated to the Kubernetes service account. For more information, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).

You can now create a managed node group.

Important

Amazon EKS nodes are standard Amazon EC2 instances, and you are billed for them based on normal Amazon EC2 instance prices. For more information, see Amazon EC2 pricing.

To create your managed node group using the AWS Management Console

- 1. Wait for your cluster status to show as ACTIVE. You cannot create a managed node group for a cluster that is not yet ACTIVE.
- 2. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 3. Choose the name of the cluster that you want to create your managed node group in.
- 4. Select the **Configuration** tab.
- 5. On the Configuration tab, select the Compute tab, and then choose Add Node Group.
- On the Configure node group page, fill out the parameters accordingly, and then choose Next.
 - Name Enter a unique name for your managed node group.
 - Node IAM role name Choose the node instance role to use with your node group. For more information, see Amazon EKS node IAM role (p. 332).

Important

We recommend using a role that is not currently in use by any self-managed node group, or that you plan to use with a new self-managed node group. For more information, see Deleting a managed node group (p. 115).

- Use launch template (Optional) Choose if you want to use an existing launch template and then select a Launch template version (Optional). If you don't select a version, then Amazon EKS uses the template's default version. Launch templates allow for more customization of your node group, including allowing you to deploy a custom AMI. The launch template must meet the requirements in Launch template support (p. 111). If you don't use your own launch template, the Amazon EKS API creates a default Amazon EC2 launch template in your account and deploys the node group using the default launch template. If you implement IAM roles for service accounts (p. 336), assign necessary permissions directly to all pods that require access to AWS services, and no pods in your cluster require access to IMDS for other reasons, such as retrieving the current Region, then you can also disable access to IMDS for pods that don't use host networking in a launch template. For more information, see the section called "Restricting access to the instance profile" (p. 349).
- Kubernetes labels (Optional) You can choose to apply Kubernetes labels to the nodes in your managed node group.
- **Tags** (Optional) You can choose to tag your Amazon EKS managed node group. These tags do not propagate to other resources in the node group, such as Auto Scaling groups or instances. For more information, see Tagging your Amazon EKS resources (p. 309).
- 7. On the **Set compute and scaling configuration** page, fill out the parameters accordingly, and then choose **Next**.

Node group compute configuration

• AMI type – Choose Amazon Linux 2 (AL2_x86_64) for non-GPU instances, Amazon Linux 2 GPU Enabled (AL2_x86_64_GPU) for GPU instances, or Amazon Linux 2 (AL2_ARM_64) for Arm.

If you are deploying Arm instances, be sure to review the considerations in the section called "Arm" (p. 160) before deploying.

If you specified a launch template on the previous page, and specified an AMI in the launch template, then you cannot select a value. The value from the template is displayed. The AMI specified in the template must meet the requirements in Using a custom AMI (p. 114).

• Capacity type – Select a capacity type. For more information about choosing a capacity type, see the section called "Managed node group capacity types" (p. 101). You cannot mix different

capacity types within the same node group. If you want to use both capacity types, create separate node groups, each with their own capacity and instance types.

• Instance type – One or more instance type is specified by default. To remove a default instance type, select the X on the right side of the instance type. Choose the instance types to use in your managed node group. The console displays a set of commonly used instance types. If you need to create a managed node group with an instance type that is not displayed, then use eksctl, the AWS CLI, AWS CloudFormation, or an SDK to create the node group. If you specified a launch template on the previous page, then you cannot select a value because it must be specified in the launch template. The value from the launch template is displayed. If you selected **Spot** for **Capacity type**, then we recommend specifying multiple instance types to enhance availability. For more information about selecting instance types, see **Considerations** in the section called "Managed node group capacity types" (p. 101).

Each Amazon EC2 instance type supports a maximum number of elastic network interfaces (ENIs) and each ENI supports a maximum number of IP addresses. Since each worker node and pod is assigned its own IP address it's important to choose an instance type that will support the maximum number of pods that you want to run on each worker node. For a list of the number of ENIs and IP addresses supported by instance types, see IP addresses per network interface per instance type. For example, the m5.large instance type supports a maximum of 30 IP addresses for the worker node and pods. Some instance types might not be available in all Regions.

If you plan to use Security groups for pods (p. 213), then make sure to specify a supported Amazon EC2 instance type. For more information, see Amazon EC2 supported instances and branch network interfaces (p. 217). If specifying an Arm Amazon EC2 instance type, then review the considerations in Amazon EKS optimized Arm Amazon Linux AMIs (p. 160) before deploying.

• Disk size – Enter the disk size (in GiB) to use for your node's root volume.

If you specified a launch template on the previous page, then you cannot select a value because it must be specified in the launch template.

Node group scaling configuration

Note

Amazon EKS does not automatically scale your node group in or out. However, you can configure the Kubernetes Cluster Autoscaler (p. 61) to do this for you.

- **Minimum size** Specify the minimum number of nodes that the managed node group can scale in to.
- Maximum size Specify the maximum number of nodes that the managed node group can scale out to.
- **Desired size** Specify the current number of nodes that the managed node group should maintain at launch.
- 8. On the Specify networking page, fill out the parameters accordingly, and then choose Next.
 - **Subnets** Choose the subnets to launch your managed nodes into.

Important

If you are running a stateful application across multiple Availability Zones that is backed by Amazon EBS volumes and using the Kubernetes Cluster Autoscaler (p. 61), you should configure multiple node groups, each scoped to a single Availability Zone. In addition, you should enable the --balance-similar-node-groups feature.

Important

• If you choose a public subnet, then the subnet must have MapPublicIpOnLaunch set to true for the instances to be able to successfully join a cluster. If the subnet was created using eksctl or the Amazon EKS vended AWS CloudFormation templates (p. 197) on or after March 26, 2020, then this setting is already set to true.

If the subnets were created with eksctl or the AWS CloudFormation templates before March 26, 2020, then you need to change the setting manually. For more information, see Modifying the public IPv4 addressing attribute for your subnet.

- Do not select a subnet in AWS Outposts, AWS Wavelength, or an AWS Local Zone. You
 can't deploy managed nodes to a subnet in AWS Outposts, AWS Wavelength, or an
 AWS Local Zone. You can only deploy self-managed nodes (p. 116) to AWS Outposts,
 AWS Wavelength, or AWS Local Zone subnets.
- Allow remote access to nodes (Optional, but default). Enabling SSH allows you to connect to your instances and gather diagnostic information if there are issues. Complete the following steps to enable remote access. We highly recommend enabling remote access when you create your node group. You cannot enable remote access after the node group is created.

If you chose to use a launch template, then this option isn't shown. To enable remote access to your nodes, specify a key pair in the launch template and ensure that the proper port is open to the nodes in the security groups that you specify in the launch template. For more information, see Using custom security groups (p. 113).

- For SSH key pair (Optional), choose an Amazon EC2 SSH key to use. For more information, see Amazon EC2 key pairs in the Amazon EC2 User Guide for Linux Instances. If you chose to use a launch template, then you can't select one.
- For **Allow remote access from**, if you want to limit access to specific instances, then select the security groups that are associated to those instances. If you don't select specific security groups, then SSH access is allowed from anywhere on the internet (0.0.0.0/0).
- 9. On the Review and create page, review your managed node group configuration and choose Create.

If nodes fail to join the cluster, then see Nodes fail to join cluster (p. 365) in the Troubleshooting quide.

10. Watch the status of your nodes and wait for them to reach the Ready status.

```
kubectl get nodes --watch
```

11. (GPU nodes only) If you chose a GPU instance type and the Amazon EKS optimized accelerated AMI, then you must apply the NVIDIA device plugin for Kubernetes as a DaemonSet on your cluster with the following command.

- 12. (Optional) Deploy a sample Linux workload (p. 248) Deploy a sample application to test your cluster and Linux nodes.
- 13. (Optional) After you add Linux worker nodes to your cluster, follow the procedures in Windows support (p. 79) to add Windows support to your cluster and to add Windows worker nodes. All Amazon EKS clusters must contain at least one Linux worker node, even if you only want to run Windows workloads in your cluster.

Next steps

Now that you have a working Amazon EKS cluster with nodes, you are ready to start installing Kubernetes add-ons and deploying applications to your cluster. The following documentation topics help you to extend the functionality of your cluster.

• Restrict access to IMDS (p. 349) – If you plan to assign IAM roles to all of your Kubernetes service accounts so that pods only have the minimum permissions that they need, and no pods in the cluster require access to the Amazon EC2 instance metadata service (IMDS) for other reasons, such as retrieving the current Region, then we recommend blocking pod access to IMDS. For more information,

Amazon EKS User Guide Step 3: Create compute

see the section called "IAM roles for service accounts" (p. 336) and the section called "Restricting access to the instance profile" (p. 349).

- Cluster Autoscaler (p. 61) Configure the Kubernetes Cluster Autoscaler to automatically adjust the number of nodes in your node groups.
- Deploy a sample Linux workload (p. 248) Deploy a sample application to test your cluster and Linux nodes.
- Deploy a Windows sample application (p. 85) Deploy a sample application to test your cluster and Windows nodes.
- Cluster management (p. 289) Learn how to use important tools for managing your cluster.

Amazon EKS clusters

An Amazon EKS cluster consists of two primary components:

- · The Amazon EKS control plane
- Amazon EKS nodes that are registered with the control plane

The Amazon EKS control plane consists of control plane nodes that run the Kubernetes software, such as etcd and the Kubernetes API server. The control plane runs in an account managed by AWS, and the Kubernetes API is exposed via the Amazon EKS endpoint associated with your cluster. Each Amazon EKS cluster control plane is single-tenant and unique, and runs on its own set of Amazon EC2 instances.

All of the data stored by the etcd nodes and associated Amazon EBS volumes is encrypted using AWS KMS. The cluster control plane is provisioned across multiple Availability Zones and fronted by an Elastic Load Balancing Network Load Balancer. Amazon EKS also provisions elastic network interfaces in your VPC subnets to provide connectivity from the control plane instances to the nodes (for example, to support kubectl exec, logs, and proxy data flows).

Amazon EKS nodes run in your AWS account and connect to your cluster's control plane via the API server endpoint and a certificate file that is created for your cluster.

Creating an Amazon EKS cluster

This topic walks you through creating an Amazon EKS cluster. If this is your first time creating an Amazon EKS cluster, then we recommend that you follow one of our Getting started with Amazon EKS (p. 4) guides instead. They provide complete end-to-end walkthroughs for creating an Amazon EKS cluster with nodes.

Important

When an Amazon EKS cluster is created, the IAM entity (user or role) that creates the cluster is added to the Kubernetes RBAC authorization table as the administrator (with system:masters permissions). Initially, only that IAM user can make calls to the Kubernetes API server using kubect1. For more information, see Managing users or IAM roles for your cluster (p. 285). If you use the console to create the cluster, you must ensure that the same IAM user credentials are in the AWS SDK credential chain when you are running kubect1 commands on your cluster. If you install and configure the AWS CLI, you can configure the IAM credentials for your user. If the AWS CLI version 1.16.156 or later is configured properly for your user, then eksct1 can find those credentials. For more information, see Configuring the AWS CLI in the AWS Command Line Interface User Guide. If you can't install the AWS CLI version 1.16.156 or later, then you must install the aws-iam-authenticator.

Prerequisites

You must have the AWS CLI version 1.16.156 or later or the aws-iam-authenticator installed. For more information, see Install the AWS CLI (p. 16) or Installing aws-iam-authenticator (p. 277).

You can create a cluster with eksctl (p. 36), the AWS Management Console (p. 37), or the AWS CLI (p. 40).

[Create a cluster with eksctl]

This procedure requires eksctl version 0.33.0 or later. You can check your version with the following command:

```
eksctl version
```

For more information on installing or upgrading eksct1, see Installing or upgrading eksct1 (p. 298).

To create your cluster with eksctl

1. Create a cluster with the Amazon EKS latest Kubernetes version in your default Region. Replace the <example-values> (including <>) with your own values. You can replace <1.18> with any supported version (p. 68).

```
eksctl create cluster \
--name <my-cluster> \
--version <1.18> \
--with-oidc \
--without-nodegroup
```

Note

To see most options that can be specified when creating a cluster with eksctl, use the eksctl create cluster --help command. To see all options, you can use a config file. For more information, see Using config files and the config file schema in the eksctl documentation. You can find config file examples on GitHub.

Important

Do not use eksctl to create a cluster or nodes in an AWS Region where you have AWS Outposts, AWS Wavelength, or AWS Local Zones enabled. Create a cluster and self-managed nodes using the Amazon EC2 API or AWS CloudFormation instead. For more information, see To launch self-managed Linux nodes using the AWS Management Console (p. 118) and To launch self-managed Windows nodes using the AWS Management Console (p. 125).

Warning

If you create a cluster using a config file with the secretsEncryption option, which
requires an existing AWS Key Management Service key, and the key that you use is ever
deleted, then there is no path to recovery for the cluster. If you enable envelope encryption,
the Kubernetes secrets are encrypted using the customer master key (CMK) that you select.
The CMK must be symmetric, created in the same Region as the cluster, and if the CMK was
created in a different account, the user must have access to the CMK. For more information,
see Allowing users in other accounts to use a CMK in the AWS Key Management Service
Developer Guide. Kubernetes secrets encryption with an AWS KMS CMK requires Kubernetes
version 1.13 or later.

By default, the create-key command creates a symmetric key with a key policy that gives the account's root user admin access on AWS KMS actions and resources. For more information, see Creating keys. If you want to scope down the permissions, make sure that the kms:DescribeKey and kms:CreateGrant actions are permitted on the key policy for the principal that will be calling the create-cluster API. Amazon EKS does not support the key policy condition kms:GrantIsForAWSResource. Creating a cluster will not work if this action is in the key policy statement.

Cluster provisioning takes several minutes. During cluster creation, you'll see several lines of output. The last line of output is similar to the following example line.

```
[#] EKS cluster "<my-cluster>" in "<region-code>" region is ready
```

2. When your cluster is ready, test that your kubectl configuration is correct.

```
kubectl get svc
```

Note

If you receive any authorization or resource type errors, see Unauthorized or access denied (kubectl) (p. 366) in the troubleshooting section.

Output:

NAME	TYPE	CLUSTER-IP	EXTERNAL-IP	PORT(S)	AGE
svc/kubernetes	ClusterIP	10.100.0.1	<none></none>	443/TCP	1m

- 3. (Optional) If you want to run pods on AWS Fargate in your cluster, then you must Create a Fargate pod execution role (p. 139) and Create a Fargate profile for your cluster (p. 140).
- 4. Follow the procedures in Launching self-managed Amazon Linux nodes (p. 116) to add Linux nodes to your cluster to support your workloads.
- 5. (Optional) After you add Linux nodes to your cluster, follow the procedures in Windows support (p. 79) to add Windows support to your cluster and to add Windows nodes. All Amazon EKS clusters must contain at least one Linux node, even if you only want to run Windows workloads in your cluster.

[Create a cluster with the AWS Management Console]

Prerequisites

- You have created a VPC and a dedicated security group that meet the requirements for an Amazon EKS cluster. For more information, see Cluster VPC considerations (p. 202) and Amazon EKS security group considerations (p. 204). The Getting started with the AWS Management Console (p. 15) guide creates a VPC that meets the requirements, or you can also follow Creating a VPC for your Amazon EKS cluster (p. 197) to create one.
- You have created an Amazon EKS cluster IAM role to apply to your cluster. The Getting started with Amazon EKS (p. 4) guide creates a service role for you, or you can also follow Amazon EKS IAM roles (p. 322) to create one manually.

To create your cluster with the console

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. Choose Create cluster.

Note

If your IAM user doesn't have administrative privileges, you must explicitly add permissions for that user to call the Amazon EKS API operations. For more information, see Amazon EKS identity-based policy examples (p. 322).

- 3. On the Configure cluster page, fill in the following fields:
 - Name A unique name for your cluster.
 - **Kubernetes version** The version of Kubernetes to use for your cluster.
 - Cluster service role Choose the Amazon EKS cluster role to allow the Kubernetes control plane to manage AWS resources on your behalf. For more information, see Amazon EKS cluster IAM role (p. 330).

• Secrets encryption – (Optional) Choose to enable envelope encryption of Kubernetes secrets using the AWS Key Management Service (AWS KMS). If you enable envelope encryption, the Kubernetes secrets are encrypted using the customer master key (CMK) that you select. The CMK must be symmetric, created in the same region as the cluster, and if the CMK was created in a different account, the user must have access to the CMK. For more information, see Allowing users in other accounts to use a CMK in the AWS Key Management Service Developer Guide.

Kubernetes secrets encryption with an AWS KMS CMK requires Kubernetes version 1.13 or later. If no keys are listed, you must create one first. For more information, see Creating keys.

Note

By default, the create-key command creates a symmetric key with a key policy that gives the account's root user admin access on AWS KMS actions and resources. If you want to scope down the permissions, make sure that the kms:DescribeKey and kms:CreateGrant actions are permitted on the key policy for the principal that will be calling the create-cluster API.

Amazon EKS does not support the key policy condition kms: GrantIsForAWSResource. Creating a cluster will not work if this action is in the key policy statement.

Warning

Deletion of the CMK will permanently put the cluster in a degraded state. If any CMKs used for cluster creation are scheduled for deletion, verify that this is the intended action before deletion. Once the key is deleted, there is no path to recovery for the cluster.

- Tags (Optional) Add any tags to your cluster. For more information, see Tagging your Amazon EKS resources (p. 309).
- 4. Select Next.
- 5. On the **Specify networking** page, select values for the following fields:
 - **VPC** Select an existing VPC to use for your cluster. If none are listed, then you need to create one first. For more information, see Creating a VPC for your Amazon EKS cluster (p. 197).
 - **Subnets** By default, the available subnets in the VPC specified in the previous field are preselected. Unselect any subnet that you don't want to host cluster resources, such as worker nodes or load balancers. The subnets must meet the requirements for an Amazon EKS cluster. For more information, see Cluster VPC considerations (p. 202).

Important

If you select subnets that were created before March 26, 2020 using one of the Amazon EKS AWS CloudFormation VPC templates, be aware of a default setting change that was introduced on March 26, 2020. For more information, see Creating a VPC for your Amazon EKS cluster (p. 197).

Important

Do not select a subnet in AWS Outposts, AWS Wavelength or an AWS Local Zone when creating your cluster. After cluster creation, you can tag the AWS Outposts AWS Wavelength or AWS Local Zone subnets with the cluster name, which will then enable you to deploy self-managed nodes to the subnet. For more information, see Subnet tagging requirement (p. 204).

• Security groups – The SecurityGroups value from the AWS CloudFormation output that you generated with Create your Amazon EKS cluster VPC (p. 22). This security group has ControlPlaneSecurityGroup in the drop-down name.

Important

The node AWS CloudFormation template modifies the security group that you specify here, so Amazon EKS strongly recommends that you use a dedicated security group for each cluster control plane (one per cluster). If this security group is shared with other resources, you might block or disrupt connections to those resources.

- (Optional) Choose Configure Kubernetes Service IP address range and specify a Service IPv4
 range if you want to specify which CIDR block Kubernetes assigns service IP addresses from. The
 CIDR block must meet the following requirements:
 - Within one of the following ranges: 10.0.0.0/8, 172.16.0.0/12, or 192.168.0.0/16.
 - Between /24 and /12.
 - Doesn't overlap with any CIDR block specified in your VPC.

We recommend specifying a CIDR block that doesn't overlap with any other networks that are peered or connected to your VPC. If you don't enable this, Kubernetes assigns service IP addresses from either the 10.100.0.0/16 or 172.20.0.0/16 CIDR blocks.

Important

You can only specify a custom CIDR block when you create a cluster and can't change this value once the cluster is created.

- For Cluster endpoint access Choose one of the following options:
 - Public Enables only public access to your cluster's Kubernetes API server endpoint. Kubernetes
 API requests that originate from outside of your cluster's VPC use the public endpoint. By
 default, access is allowed from any source IP address. You can optionally restrict access to one
 or more CIDR ranges such as 192.168.0.0/16, for example, by selecting Advanced settings and
 then selecting Add source.
 - Private Enables only private access to your cluster's Kubernetes API server endpoint.
 Kubernetes API requests that originate from within your cluster's VPC use the private VPC endpoint.

Important

If you created a VPC without outbound internet access, then you must enable private access.

• Public and private – Enables public and private access.

For more information about the previous options, see Modifying cluster endpoint access (p. 57).

6. If you selected Kubernetes version 1.17 or earlier on the previous page, skip to the next step. If you selected version 1.18, accept the defaults in the **Networking add-ons** section to install the latest version of the AWS VPC CNI (p. 208) Amazon EKS add-on. You can only use Amazon EKS add-ons with 1.18 clusters because Amazon EKS add-ons require the Server-side Apply Kubernetes feature, which wasn't available until Kubernetes 1.18. If you selected a different Kubernetes version for your cluster, then this option isn't shown.

Important

The AWS VPC CNI add-on is configured to use the IAM permissions assigned to the Amazon EKS node IAM role (p. 332). After the cluster is created, but before you deploy any Amazon EC2 nodes to your cluster, you must ensure that the AmazonEKS_CNI_Policy IAM policy is attached to either the node IAM role, or to a different role associated to the Kubernetes service account that the add-on runs as. We recommend that you assign the policy to a different IAM role than the node IAM role by completing the instructions in Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210). Once your cluster and IAM role are created, you can update the add-on (p. 52) to use the IAM role that you create.

- 7. Select Next.
- 8. On the **Configure logging** page, you can optionally choose which log types that you want to enable. By default, each log type is **Disabled**. For more information, see Amazon EKS control plane logging (p. 66).
- 9. Select Next.
- 10. On the Review and create page, review the information that you entered or selected on the previous pages. Select Edit if you need to make changes to any of your selections. Once you're satisfied with your settings, select Create. The Status field shows CREATING until the cluster provisioning process completes.

Amazon EKS User Guide [Create a cluster with the AWS CLI]

Note

You might receive an error that one of the Availability Zones in your request doesn't have sufficient capacity to create an Amazon EKS cluster. If this happens, the error output contains the Availability Zones that can support a new cluster. Retry creating your cluster with at least two subnets that are located in the supported Availability Zones for your account. For more information, see Insufficient capacity (p. 365).

Cluster provisioning usually takes between 10 and 15 minutes.

- 11. (Optional) To use Amazon EKS add-ons, or to enable individual Kubernetes workloads to have specific IAM permissions, you need to enable an OpenID Connect (OIDC) provider for your cluster. To configure an OIDC provider for your cluster, see the section called "Enabling" (p. 341). You only need to enable an OIDC provider for your cluster once. To learn more about Amazon EKS addons, see Configure an Amazon EKS add-on (p. 52). To learn more about assigning specific IAM permissions to your workloads, see IAM roles for service accounts technical overview (p. 336).
- 12. Now that you have created your cluster, follow the procedures in Installing aws-iam-authenticator (p. 277) and Create a kubeconfig for Amazon EKS (p. 281) to enable communication with your new cluster.
- 13. (Optional) If you want to run pods on AWS Fargate in your cluster, see Getting started with AWS Fargate using Amazon EKS (p. 138).
- 14. After you enable communication, follow the procedures in Launching self-managed Amazon Linux nodes (p. 116) to add Linux worker nodes to your cluster to support your workloads.
- 15. (Optional) After you add Linux worker nodes to your cluster, follow the procedures in Windows support (p. 79) to add Windows support to your cluster and to add Windows worker nodes. All Amazon EKS clusters must contain at least one Linux worker node, even if you only want to run Windows workloads in your cluster.

Before deploying nodes to your cluster, we recommend configuring the AWS VPC CNI plugin that was deployed with the cluster to use IAM roles for service accounts (p. 336). For more information, see the section called "Configure plugin for IAM account" (p. 210).

[Create a cluster with the AWS CLI]

This procedure has the following prerequisites:

- You have created a VPC and a dedicated security group that meets the requirements for an Amazon EKS cluster. For more information, see Cluster VPC considerations (p. 202) and Amazon EKS security group considerations (p. 204). The Getting started with the AWS Management Console (p. 15) guide creates a VPC that meets the requirements, or you can also follow Creating a VPC for your Amazon EKS cluster (p. 197) to create one.
- You have created an Amazon EKS cluster IAM role to apply to your cluster. The Getting started with Amazon EKS (p. 4) guide creates a service role for you, or you can also follow Amazon EKS IAM roles (p. 322) to create one manually.

To create your cluster with the AWS CLI

Create your cluster with the following command. Replace the Amazon Resource Name (ARN) of your Amazon EKS cluster IAM role that you created in Create your Amazon EKS cluster IAM role (p. 21), and the subnet and security group IDs for the VPC that you created in Create your Amazon EKS cluster VPC (p. 22). Replace <my-cluster> with your cluster name and <region-code> with a supported Region. You can replace <1.18> with any supported version (p. 68).

```
aws eks create-cluster \
   --region <region-code> \
   --name <my-cluster> \
```

Amazon EKS User Guide [Create a cluster with the AWS CLI]

```
--kubernetes-version <1.18> \
--role-arn <arn:aws:iam::111122223333:role/eks-service-role-
AWSServiceRoleForAmazonEKS-EXAMPLEBKZRQR> \
--resources-vpc-config subnetIds=<subnet-
a9189fe2>,<subnet-50432629>,securityGroupIds=<sg-f5c54184>
```

Important

Do not specify subnets in AWS Outposts, AWS Wavelength, or an AWS Local Zone. Specify only subnets in the Region. After the cluster is deployed, tag the AWS Outposts, AWS Wavelength, or AWS Local Zones, subnets that you want to deploy self-managed nodes to with the cluster name. For more information, see Subnet tagging requirement (p. 204).

Note

If your IAM user doesn't have administrative privileges, you must explicitly add permissions for that user to call the Amazon EKS API operations. For more information, see Amazon EKS identity-based policy examples (p. 322).

Output:

```
{
    "cluster": {
        "name": "<my-cluster>",
        "arn": "arn:aws:eks:<reqion-code>:<111122223333>:cluster/<my-cluster>",
        "createdAt": <1527785885.159>,
        "version": "<1.18>",
        "roleArn": "arn:aws:iam::<111122223333>:role/eks-service-role-
AWSServiceRoleForAmazonEKS-<AFNL4H8HB71F>",
        "resourcesVpcConfig": {
            "subnetIds": [
                "<subnet-a9189fe2>",
                "<subnet-50432629>"
            1,
            "securityGroupIds": [
                "<sg-f5c54184>"
            "vpcId": "<vpc-a54041dc>",
            "endpointPublicAccess": true,
            "endpointPrivateAccess": false
        "status": "CREATING",
        "certificateAuthority": {}
    }
}
```

Note

You might receive an error that one of the Availability Zones in your request doesn't have sufficient capacity to create an Amazon EKS cluster. If this happens, the error output contains the Availability Zones that can support a new cluster. Retry creating your cluster with at least two subnets that are located in the supported Availability Zones for your account. For more information, see Insufficient capacity (p. 365).

To encrypt the Kubernetes secrets with a customer master key (CMK) from AWS Key Management Service (AWS KMS), first create a CMK using the create-key operation.

```
MY_KEY_ARN=$(aws kms create-key --query KeyMetadata.Arn --output text)
```

Note

By default, the create-key command creates a symmetric key with a key policy that gives the account's root user admin access on AWS KMS actions and resources. If you want to scope down the permissions, make sure that the kms:DescribeKey and

Amazon EKS User Guide [Create a cluster with the AWS CLI]

kms:CreateGrant actions are permitted on the key policy for the principal that will be calling the create-cluster API.

Amazon EKS does not support the key policy condition kms:GrantIsForAWSResource. Creating a cluster will not work if this action is in the key policy statement.

Add the --encryption-config parameter to the aws eks create-cluster command. Encryption of Kubernetes secrets can only be enabled when the cluster is created.

```
--encryption-config '[{"resources":["secrets"],"provider":{"keyArn":"<$MY_KEY_ARN>"}}]'
```

The keyArn member can contain either the alias or ARN of your CMK. The CMK must be symmetric, created in the same Region as the cluster, and if the CMK was created in a different account, the user must have access to the CMK. For more information, see Allowing users in other accounts to use a CMK in the AWS Key Management Service Developer Guide. Kubernetes secrets encryption with an AWS KMS CMK requires Kubernetes version 1.13 or later.

Warning

Deletion of the CMK will permanently put the cluster in a degraded state. If any CMKs used for cluster creation are scheduled for deletion, verify that this is the intended action before deletion. Once the key is deleted, there is no path to recovery for the cluster.

2. Cluster provisioning usually takes between 10 and 15 minutes. You can query the status of your cluster with the following command. When your cluster status is ACTIVE, you can proceed.

```
aws eks --region <region-code> describe-cluster --name <my-cluster> --query "cluster.status"
```

- 3. When your cluster provisioning is complete, retrieve the endpoint and certificateAuthority.data values with the following commands. You must add these values to your kubectl configuration so that you can communicate with your cluster.
 - a. Retrieve the endpoint.

```
aws eks --region <region-code> describe-cluster --name <my-cluster> --query "cluster.endpoint" --output text
```

b. Retrieve the certificateAuthority.data.

```
aws eks --region <region-code> describe-cluster --name <my-cluster> --query
"cluster.certificateAuthority.data" --output text
```

- 4. Now that you have created your cluster, follow the procedures in Create a kubeconfig for Amazon EKS (p. 281) to enable communication with your new cluster.
- 5. (Optional) If you want to run pods on AWS Fargate in your cluster, see Getting started with AWS Fargate using Amazon EKS (p. 138).
- 6. After you enable communication, follow the procedures in Launching self-managed Amazon Linux nodes (p. 116) to add nodes to your cluster to support your workloads.
- (Optional) After you add Linux nodes to your cluster, follow the procedures in Windows support (p. 79) to add Windows support to your cluster and to add Windows nodes. All Amazon EKS clusters must contain at least one Linux node, even if you only want to run Windows workloads in your cluster.
- 8. (Optional) If the AmazonEKS_CNI_Policy managed IAM policy is attached to your node IAM role, we recommend assigning it to an IAM role that you associate to the Kubernetes aws-node service account instead. For more information, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).

Updating a Cluster

You can update an existing cluster to a new Kubernetes version or configure managed add-ons for your cluster.

Updating an Amazon EKS cluster Kubernetes version

When a new Kubernetes version is available in Amazon EKS, you can update your cluster to the latest version.

Important

We recommend that before updating to a new Kubernetes version that you review the information in Amazon EKS Kubernetes versions (p. 68) and in the update steps in this topic.

New Kubernetes versions have introduced significant changes. Therefore, we recommend that you test the behavior of your applications against a new Kubernetes version before you update your production clusters. You can achieve this by building a continuous integration workflow to test your application behavior before moving to a new Kubernetes version.

The update process consists of Amazon EKS launching new API server nodes with the updated Kubernetes version to replace the existing ones. Amazon EKS performs standard infrastructure and readiness health checks for network traffic on these new nodes to verify that they're working as expected. If any of these checks fail, Amazon EKS reverts the infrastructure deployment, and your cluster remains on the prior Kubernetes version. Running applications aren't affected, and your cluster is never left in a non-deterministic or unrecoverable state. Amazon EKS regularly backs up all managed clusters, and mechanisms exist to recover clusters if necessary. We're constantly evaluating and improving our Kubernetes infrastructure management processes.

To upgrade the cluster, Amazon EKS requires 2 to 3 free IP addresses from the subnets that were provided when you created the cluster. If these subnets don't have available IP addresses, then the upgrade can fail. Additionally, if any of the subnets or security groups that were provided during cluster creation have been deleted, the cluster upgrade process can fail.

Note

Even though Amazon EKS runs a highly available control plane, you might experience minor service interruptions during an update. For example, if you attempt to connect to an API server just before or just after it's terminated and replaced by a new API server running the new version of Kubernetes, you might experience API call errors or connectivity issues. If this happens, retry your API operations until they succeed.

Amazon EKS doesn't modify any of your Kubernetes add-ons when you update a cluster. After updating your cluster, we recommend that you update your add-ons to the versions listed in the following table for the new Kubernetes version that you're updating to. Steps to accomplish this are included in the update procedures.

Kubernetes version	1.18	1.17	1.16	1.15
Amazon VPC CNI plug-in	1.7.5	1.7.5	1.7.5	1.7.5
DNS (CoreDNS)	1.7.0	1.6.6	1.6.6	1.6.6
KubeProxy	1.18.9	1.17.12	1.16.15	1.15.12

If you're using additional add-ons for your cluster that aren't listed in the previous table, update them to the latest compatible versions after updating your cluster.

Update an existing cluster

Update the cluster and Kubernetes add-ons.

To update an existing cluster

- Compare the Kubernetes version of your cluster control plane to the Kubernetes version of your nodes.
 - Get the Kubernetes version of your cluster control plane with the following command.

```
kubectl version --short
```

• Get the Kubernetes version of your nodes with the following command.

```
kubectl get nodes
```

If your nodes are more than one Kubernetes minor version older than your control plane, then you must upgrade your nodes to a newer Kubernetes minor version before you update your cluster's Kubernetes version. For more information, see Kubernetes version and version skew support policy in the Kubernetes documentation.

We recommend that you update your nodes to your cluster's current pre-update Kubernetes minor version prior to your cluster update. Your nodes must not run a newer Kubernetes version than your control plane. For example, if your control plane is running version 1.17 and your nodes are running version 1.15, update your nodes to version 1.16 or 1.17 (recommended) before you update your cluster's Kubernetes version to 1.18. For more information, see Self-managed node updates (p. 128).

2. The pod security policy admission controller is enabled on Amazon EKS clusters running Kubernetes version 1.13 or later. If you're upgrading your cluster to Kubernetes version 1.13 or later, ensure that the proper pod security policies are in place before you update to avoid any issues. You can check for the default policy with the following command:

```
kubectl get psp eks.privileged
```

If you receive the following error, see To install or restore the default pod security policy (p. 355) before proceeding.

```
{\tt Error \ from \ server \ (NotFound): \ podsecurity policies. extensions \ "eks.privileged" \ not \ found}
```

- 3. If you originally deployed your cluster on Kubernetes 1.17 or earlier, then you may need to remove a deprecated term from your CoreDNS manifest.
 - a. Check to see if your CoreDNS manifest has the line.

```
kubectl get configmap coredns -n kube-system -o yaml |grep upstream
```

If no output is returned, your manifest doesn't have the line and you can skip to the next step to update your cluster. If output is returned, then you need to remove the line.

b. Edit the configmap, removing the line in the file that has the word upstream in it. Don't change anything else in the file. After the line is removed, save the changes.

```
kubectl edit configmap coredns -n kube-system -o yaml
```

- 4. Update your cluster using eksct1, the AWS Management Console, or the AWS CLI.
 - eksctl This procedure requires eksctl version 0.33.0 or later. You can check your version with the following command:

eksctl version

For more information about installing or upgrading eksctl, see Installing or upgrading eksctl (p. 298).

Note

This procedure only works for clusters that were created with eksctl.

Update your Amazon EKS cluster Kubernetes version one minor version later than its current version with the following command. Replace <dev> with your cluster name. Because Amazon EKS runs a highly available control plane, you can update only one minor version at a time. See Kubernetes Version and Version Skew Support Policy for the rationale behind this requirement.

Important

You may need to update some of your deployed resources before you can update to 1.16. For more information, see Kubernetes 1.16 upgrade prerequisites (p. 50). Upgrading a cluster from 1.16 to 1.17 will fail if any of your AWS Fargate pods have a kubelet minor version earlier than 1.16. Before upgrading your cluster from 1.16 to 1.17, you need to recycle your Fargate pods so that their kubelet is 1.16 before attempting to upgrade the cluster to 1.17.

eksctl upgrade cluster --name <dev> --approve

This process takes several minutes to complete.

- AWS Management Console
 - a. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
 - b. Choose the name of the cluster to update and choose **Update cluster version**.
 - c. For Kubernetes version, select the version to update your cluster to and choose Update.

Important

- Upgrading a cluster from 1.16 to 1.17 will fail if any of your AWS Fargate pods have a kubelet minor version earlier than 1.16. Before upgrading your cluster from 1.16 to 1.17, you need to recycle your Fargate pods so that their kubelet is 1.16 before attempting to upgrade the cluster to 1.17.
- You may need to update some of your deployed resources before you can update to 1.16. For more information, see Kubernetes 1.16 upgrade prerequisites (p. 50).

Important

Because Amazon EKS runs a highly available control plane, you can update only one minor version at a time. See Kubernetes Version and Version Skew Support Policy for the rationale behind this requirement. Therefore, if your current version is 1.16 and you want to upgrade to 1.18, then you must first upgrade your cluster to 1.17 and then upgrade it from 1.17 to 1.18. If you try to update directly from 1.16 to 1.18, then the update version command throws an error.

d. For Cluster name, type the name of your cluster and choose Confirm.

Note

The cluster update should finish in a few minutes.

- AWS CLI
 - a. Update your cluster with the following AWS CLI command. Substitute your cluster name and desired Kubernetes minor version.

Important

You may need to update some of your deployed resources before you can update to 1.16. For more information, see Kubernetes 1.16 upgrade prerequisites (p. 50). Upgrading a cluster from 1.16 to 1.17 will fail if any of your AWS Fargate pods have a kubelet minor version earlier than 1.16. Before upgrading your cluster from 1.16 to 1.17, you need to recycle your Fargate pods so that their kubelet is 1.16 before attempting to upgrade the cluster to 1.17.

Important

Because Amazon EKS runs a highly available control plane, you can update only one minor version at a time. See Kubernetes Version and Version Skew Support Policy for the rationale behind this requirement. Therefore, if your current version is 1.16 and you want to upgrade to 1.18, then you must first upgrade your cluster to 1.17 and then upgrade it from 1.17 to 1.18. If you try to update directly from 1.16 to 1.18, then the update version command throws an error.

```
aws eks --region <region-code> update-cluster-version --name <my-cluster> -- kubernetes-version <1.18>
```

The output is as follows:

```
"update": {
        "id": "<b5f0ba18-9a87-4450-b5a0-825e6e84496f>",
        "status": "InProgress",
        "type": "VersionUpdate",
        "params": [
            {
                 "type": "Version",
                 "value": "1.18"
            },
            {
                 "type": "PlatformVersion",
                 "value": "eks.1"
            }
        ],
. . .
        "errors": []
    }
}
```

b. Monitor the status of your cluster update with the following command. Use the cluster name and update ID that the previous command returned. Your update is complete when the status appears as Successful.

Note

The cluster update should finish in a few minutes.

```
aws eks --region <region-code> describe-update --name <my-cluster> --update-id <b5f0ba18-9a87-4450-b5a0-825e6e84496f>
```

Output:

```
{
    "update": {
        "id": "b5f0ba18-9a87-4450-b5a0-825e6e84496f",
        "status": "<Successful>",
        "type": "VersionUpdate",
        "params": [
```

```
{
    "type": "Version",
    "value": "1.18"
    },
    {
        "type": "PlatformVersion",
        "value": "eks.1"
     }
    ],
    ...
    "errors": []
    }
}
```

5. Patch the kube-proxy daemonset to use the image that corresponds to your cluster's Region and current Kubernetes version (in this example, 1.18.9).

Kubernetes version	1.18	1.17	1.16	1.15
KubeProxy	1.18.9	1.17.12	1.16.15	1.15.12

a. First, retrieve your current kube-proxy image:

```
kubectl get daemonset kube-proxy --namespace kube-system -
o=jsonpath='{$.spec.template.spec.containers[:1].image}'
```

b. Update kube-proxy to the recommended version by taking the output from the previous step and replacing the version tag with your cluster's recommended kube-proxy version:

```
kubectl set image daemonset.apps/kube-proxy \
    -n kube-system \
    kube-proxy=<602401143452.dkr.ecr.us-west-2.amazonaws.com>/eks/kube-
proxy:v<1.18.9>-eksbuild.1
```

Your account ID and Region may differ from the example above.

c. (Optional) If you're using x86 and Arm nodes in the same cluster and your cluster was deployed before August 17,2020. Then, edit your kube-proxy manifest to include a node selector for multiple hardware architectures with the following command. This is a one-time operation. After you've added the selector to your manifest, you don't need to do it each time you upgrade. If your cluster was deployed on or after August 17, 2020, then kube-proxy is already multi-architecture capable.

```
kubectl edit -n kube-system daemonset/kube-proxy
```

Add the following node selector to the file in the editor and then save the file. For an example of where to include this text in the editor, see the CNI manifest file on GitHub. This enables Kubernetes to pull the correct hardware image based on the node's hardware architecture.

6. Check your cluster's DNS provider. Clusters that were created with Kubernetes version 1.10 shipped with kube-dns as the default DNS and service discovery provider. If you have updated a 1.10 cluster

to a newer version and you want to use CoreDNS for DNS and service discovery, then you must install CoreDNS and remove kube-dns.

To check if your cluster is already running CoreDNS, use the following command.

```
kubectl get pod -n kube-system -l k8s-app=kube-dns
```

If the output shows coredns in the pod names, you're already running CoreDNS in your cluster. If not, see Installing or upgrading CoreDNS (p. 237) to install CoreDNS on your cluster, update it to the recommended version, return here, and skip steps 7-8.

7. Check the current version of your cluster's coredns deployment.

```
kubectl describe deployment coredns --namespace kube-system | grep Image | cut -d "/" - f 3
```

Output:

```
coredns:v<1.1.3>
```

The recommended coredns versions for the corresponding Kubernetes versions are as follows:

Kubernetes version	1.18	1.17	1.16	1.15
CoreDNS	1.7.0	1.6.6	1.6.6	1.6.6

- 8. If your current coredns version is 1.5.0 or later, but earlier than the recommended version, then skip this step. If your current version is earlier than 1.5.0, then you need to modify the config map for coredns to use the forward plug-in, rather than the proxy plug-in.
 - a. Open the configmap with the following command.

```
kubectl edit configmap coredns -n kube-system
```

b. Replace proxy in the following line with forward. Save the file and exit the editor.

```
proxy . /etc/resolv.conf
```

9. Retrieve your current coredns image:

```
kubectl get deployment coredns --namespace kube-system -
o=jsonpath='{$.spec.template.spec.containers[:1].image}'
```

10. Update coredns to the recommended version by taking the output from the previous step and replacing <1.7.0> (including <>) with your cluster's recommended coredns version:

11. (Optional) If you're using x86 and Arm nodes in the same cluster and your cluster was deployed before August 17,2020, then edit your coredns manifest to include a node selector for multiple hardware architectures with the following command. This is a one-time operation. After you've added the selector to your manifest, you don't need to do it each time you upgrade. If you cluster was deployed on or after August 17, 2020, then coredns is already multi-architecture capable.

```
kubectl edit -n kube-system deployment/coredns
```

Add the following node selector to the file in the editor and then save the file. For an example of where to include this text in the editor, see the CNI manifest file on GitHub.

```
- key: "beta.kubernetes.io/arch"
operator: In
values:
- amd64
- arm64
```

12. Check the version of your cluster's Amazon VPC CNI Plugin for Kubernetes. Use the following command to print your cluster's CNI version.

```
kubectl describe daemonset aws-node --namespace kube-system | grep Image | cut -d "/" - f \mathbf{2}
```

The output is as follows:

```
amazon-k8s-cni:<1.6.3>
```

If your CNI version is earlier than 1.7.5, then use the appropriate command below to update your CNI version to the latest recommended version:

• US West (Oregon) (us-west-2)

```
kubectl apply -f https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/v1.7.5/
config/v1.7/aws-k8s-cni.yaml
```

China (Beijing) (cn-north-1) or China (Ningxia) (cn-northwest-1)

```
\label{local_complex} $$ kubectl apply -f https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/v1.7.5/config/v1.7/aws-k8s-cni-cn.yaml
```

AWS GovCloud (US-East) (us-gov-east-1)

```
kubectl apply -f https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/v1.7.5/
config/v1.7/aws-k8s-cni-us-gov-east-1.yaml
```

AWS GovCloud (US-West) (us-gov-west-1)

```
\label{local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_loc
```

- · For all other Regions
 - Download the manifest file.

```
curl -o aws-k8s-cni.yaml https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/
v1.7.5/config/v1.7/aws-k8s-cni.yaml
```

• Replace <region-code> in the following command with the Region that your cluster is in.
Then, run the modified command to replace the Region code in the file (currently us-west-2).

```
sed -i -e 's/us-west-2/<region-code>/' aws-k8s-cni.yaml
```

· Apply the modified manifest file to your cluster.

```
kubectl apply -f aws-k8s-cni.yaml
```

13. (Optional) If you deployed the Kubernetes Cluster Autoscaler to your cluster before upgrading the cluster, update the Cluster Autoscaler to the latest version that matches the Kubernetes major and minor version that you upgraded to.

Important

You can't use the Kubernetes Cluster Autoscaler with Arm.

- a. Open the Cluster Autoscaler releases page in a web browser and find the latest Cluster Autoscaler version that matches your cluster's Kubernetes major and minor version. For example, if your cluster's Kubernetes version is 1.18 find the latest Cluster Autoscaler release that begins with 1.18. Record the semantic version number (<1.18.n>) for that release to use in the next step.
- b. Set the Cluster Autoscaler image tag to the version that you recorded in the previous step with the following command. Replace <1.18.n> with your own value. You can replace us with <asia> or <eu>.

```
kubectl -n kube-system set image deployment.apps/cluster-autoscaler cluster-
autoscaler=<us>.gcr.io/k8s-artifacts-prod/autoscaling/cluster-autoscaler:v<1.18.n>
```

Note

Depending on the version that you need, you may need to change the previous address to gcr.io/google-containers/cluster-autoscaler:v1.<n.n>. The image address is listed on the releases page.

14. (Clusters with GPU nodes only) If your cluster has node groups with GPU support (for example, p3.2xlarge), you must update the NVIDIA device plugin for Kubernetes DaemonSet on your cluster with the following command.

```
\label{local_poly} $$ kubectl apply -f https://raw.githubusercontent.com/NVIDIA/k8s-device-plugin/v0.6.0/nvidia-device-plugin.yml
```

15. After your cluster update is complete, update your nodes to the same Kubernetes version of your updated cluster. For more information, see Self-managed node updates (p. 128) or Updating a managed node group (p. 108). Any new pods launched on Fargate will have a kubelet version that matches your cluster version. Existing Fargate pods won't be changed.

Kubernetes 1.16 upgrade prerequisites

As noted in the Kubernetes 1.15 changelog and Deprecated APIs Removed In 1.16: Here's What You Need To Know documents, if you have an existing cluster, API changes are required for the following deployed resources before upgrading a cluster to 1.16.

Warning

If you don't change these APIs before upgrading to 1.16, workloads fail after the upgrade is complete.

- NetworkPolicy resources will no longer be served from extensions/v1beta1 in v1.16. Migrate use to the networking.k8s.io/v1 API, available since v1.8. Existing persisted data can be retrieved through the networking.k8s.io/v1 API.
- PodSecurityPolicy resources will no longer be served from extensions/v1beta1 in v1.16. Migrate to the policy/v1beta1 API, available since v1.10. Existing persisted data can be retrieved through the policy/v1beta1 API.

• DaemonSet, Deployment, StatefulSet, and ReplicaSet resources will no longer be served from extensions/v1beta1, apps/v1beta1, or apps/v1beta2 in v1.16. Migrate to the apps/v1 API, available since v1.9. Existing persisted data can be retrieved through the apps/v1 API. For example, to convert a Deployment that currently uses apps/v1beta1, enter the following command.

```
kubectl convert -f ./<my-deployment.yaml> --output-version apps/v1
```

Note

The previous command may use different default values from what is set in your current manifest file. To learn more about a specific resource, see the Kubernetes API reference.

If you originally created an Amazon EKS cluster with Kubernetes version 1.11 or earlier and haven't removed the --resource-container flag from the kube-proxy DaemonSet, then updating to Kubernetes 1.16 will cause kube-proxy failures. This flag is deprecated in Kubernetes 1.16. For more information, see kube-proxy in Kubernetes 1.16 Deprecations and removals. You must remove this flag before updating to Kubernetes 1.16.

What you need to do before upgrading to 1.16

- · Change your YAML files to reference the new APIs.
- Update custom integrations and controllers to call the new APIs.
- Ensure that you use an updated version of any third party tools, such as ingress controllers, continuous delivery systems, and other tools that call the new APIs.

To easily check for deprecated API usage in your cluster, make sure that the audit control plane log (p. 66) is enabled, and specify v1beta as a filter for the events. All of the replacement APIs are in Kubernetes versions later than 1.10. Applications on any supported version of Amazon EKS can begin using the updated APIs now.

Remove the --resource-container="" flag from your kube-proxy DaemonSet, if your cluster
was originally deployed with Kubernetes 1.11 or earlier or use a kube-proxy configuration file
(recommended). To determine whether your current version of kube-proxy has the flag, enter the
following command.

```
kubectl get daemonset kube-proxy --namespace kube-system -o yaml | grep 'resource-container='
```

If you receive no output, then you don't need to remove anything. If you receive output similar to --resource-container="", then you need to remove the flag. Enter the following command to edit your current kube-proxy config.

```
kubectl edit daemonset kube-proxy --namespace kube-system
```

With the editor open, remove the --resource-container="" line, and save the file. We recommend that you instead, start using a kube-proxy configuration file. To do so, download the following manifest.

```
curl -o kube-proxy-daemonset.yaml https://amazon-eks.s3-us-west-2.amazonaws.com/cloudformation/2020-06-10/kube-proxy-daemonset.yaml
```

Determine your cluster's endpoint with the following command.

```
aws eks describe-cluster \
   --name <cluster-name> \
   --region <region-code> \
```

Amazon EKS User Guide Configure an Amazon EKS add-on

```
--query 'cluster.endpoint' \
--output text
```

The ouput is as follows:

```
https://<A89DBB2140C8AC0C2F920A36CCC6E18C>.sk1.<region-code>.eks.amazonaws.com
```

Edit the kube-proxy-daemonset.yaml file that you downloaded. In your editor, replace <MASTER_ENDPOINT> (including <>) with the output from the previous command. Replace <REGION> with your cluster's Region. On the same line, replace the version with the version of your cluster if necessary. Apply the file with the following command.

```
kubectl apply -f kube-proxy-daemonset.yaml
```

Configure an Amazon EKS add-on

An add-on is Kubernetes operational software that provides capabilities like observability, scaling, networking, and AWS cloud resource integrations for your Amazon EKS cluster. You can manage add-ons yourself, or let Amazon EKS control the launch and version of the add-on through the Amazon EKS API for clusters running Kubernetes version 1.18 with platform version eks. 3 or later. Amazon EKS add-ons use the Kubernetes Server-Side Apply feature, which is only available with Kubernetes version 1.18 or later. For more information, see Server-Side Apply in the Kubernetes documentation.

To configure an Amazon EKS add-on using the AWS Management Console

- Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. In the left navigation, select **Clusters**, and then select the name of the cluster that you want to configure an Amazon EKS add-on for.
- 3. Choose the **Configuration** tab and then choose the **Add-ons** tab.
- 4. Configure the add-on. To add a new Amazon EKS add-on, select Add new. To change an existing Amazon EKS add-on, select the add-on and choose Edit. To remove an add-on, select the add-on and select Remove. Removing the add-on also removes it from your cluster. You can always manually add the add-on back to your cluster, but be aware that its removal and addition could cause service disruption to your cluster.
 - a. Select the Name of the Amazon EKS add-on that you want to add or edit.
 - b. Select the **Version** of the Amazon EKS add-on that you want to use.
 - c. Select the Service account role that you want the add-on to run as. If you don't select an existing IAM role, then the the section called "Node IAM role" (p. 332) is used. However, we recommend specifying your own role so that the node IAM role isn't assigned more than the minimum permissions that it requires.

Whichever role you choose must be assigned the permissions required by the add-on. For example, the role that you specify for the **vpc-cni** add-on must have the Amazoneks_CNI_Policy IAM policy assigned to it, and the role must have unique settings in its trust relationship. For more information, see To create your CNI plugin IAM role with the AWS Management Console (p. 211). If the Kubernetes service account used by the add-on isn't currently annotated with the IAM role that you specify, then the API will annotate the service account with the IAM role for you.

Important

To specify an IAM role, you must have an IAM OpenID Connect (OIDC) provider for your cluster. To create an OIDC provider, see the section called "Enabling" (p. 341).

Amazon EKS User Guide Configure an Amazon EKS add-on

- d. If you currently have the add-on deployed to your cluster, are managing it yourself, and want Amazon EKS to manage the add-on you can **Enable Override existing configuration for this add-on on the cluster**. If you enable this option, then any setting for the existing add-on can be overwritten with the Amazon EKS add-on's settings. If you currently have the add-on deployed to your cluster and don't enable this option and any of the Amazon EKS add-on settings conflict with your existing settings, then migrating the add-on to an Amazon EKS add-on will fail, and you'll receive an error message to help you resolve the conflict.
- e. Select Add or Update.

To configure an Amazon EKS add-on using eksctl

Replace the <example values> (including <>) with your own values.

- 1. Add an Amazon EKS add-on to your cluster.
 - a. Determine which Amazon EKS add-ons are available for your cluster.

```
eksctl utils describe-addon-versions --cluster <name-of-your-cluster>
```

b. Add an Amazon EKS add-on to your cluster. When specifying <name-of-addon>, specify a name returned from the previous command. The --force option overwrites any existing configuration if the add-on is already installed on your cluster, but you're managing it yourself. You can specify the ARN of an IAM role, policy, or both. The add-on's Kubernetes service account is then annotated with the role. If you don't specify an existing role or policy, eksctl creates a default role and attaches the necessary policy to it for you.

```
{\tt eksctl \ create \ addon \ --name \ < name--of-addon-from-previous-command > \ --cluster \ < name-of-your-cluster > \ --force}
```

- 2. You can update an add-on to a newer version. See other update options with eksctl update addon -h.
 - a. Determine which versions are available for an add-on.

```
eksctl utils describe-addon-versions --name <name-of-addon> --cluster <name-of-
your-cluster>
```

b. Update the add-on to a newer version.

```
eksctl update addon --name <name-from-previous-command> --version <version-from-
previous-command> --cluster <name-of-your-cluster>
```

- 3. Delete an Amazon EKS add-on from your cluster.
 - a. See which add-ons are currently enabled for your cluster.

```
eksctl get addons --cluster <name-of-your-cluster>
```

b. Delete an Amazon EKS add-on from your cluster. Deleting the add-on also deletes any IAM roles associated to it.

```
eksctl delete addon --cluster <name-of-your-cluster> --name <addon-name-from-
previous-command>
```

Deleting a cluster

When you're done using an Amazon EKS cluster, you should delete the resources associated with it so that you don't incur any unnecessary costs.

Important

If you have active services in your cluster that are associated with a load balancer, you must delete those services before deleting the cluster so that the load balancers are deleted properly. Otherwise, you can have orphaned resources in your VPC that prevent you from being able to delete the VPC.

You can delete a cluster with eksct1 (p. 54), the AWS Management Console (p. 54), or the AWS CLI (p. 55).

[To delete an Amazon EKS cluster and nodes with eksctl]

This procedure requires eksctl version 0.33.0 or later. You can check your version with the following command:

```
eksctl version
```

For more information on installing or upgrading eksct1, see Installing or upgrading eksct1 (p. 298).

Note

This procedure only works for clusters that were created with eksctl.

1. List all services running in your cluster.

```
kubectl get svc --all-namespaces
```

2. Delete any services that have an associated EXTERNAL-IP value. These services are fronted by an Elastic Load Balancing load balancer, and you must delete them in Kubernetes to allow the load balancer and associated resources to be properly released.

```
kubectl delete svc <service-name>
```

3. Delete the cluster and its associated nodes with the following command, replacing prod> with your cluster name.

```
eksctl delete cluster --name <prod>
```

Output:

```
[#] using region <region-code>
[#] deleting EKS cluster "prod"
[#] will delete stack "eksctl-prod-nodegroup-standard-nodes"
[#] waiting for stack "eksctl-prod-nodegroup-standard-nodes" to get deleted
[#] will delete stack "eksctl-prod-cluster"
[#] the following EKS cluster resource(s) for "prod" will be deleted: cluster. If in doubt, check CloudFormation console
```

[To delete an Amazon EKS cluster with the AWS Management Console]

1. List all services running in your cluster.

```
kubectl get svc --all-namespaces
```

Amazon EKS User Guide Deleting a cluster

 Delete any services that have an associated EXTERNAL-IP value. These services are fronted by an Elastic Load Balancing load balancer, and you must delete them in Kubernetes to allow the load balancer and associated resources to be properly released.

kubectl delete svc <service-name>

- 3. Delete all node groups and Fargate profiles.
 - a. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
 - b. In the left navigation, select **Clusters**, and then in the tabbed list of clusters, select the name of the cluster that you want to delete.
 - c. Select the **Configuration** tab. On the **Compute** tab, select a node group to delete, select **Delete**, enter the name of the node group, and then select **Delete**. Delete all node groups in the cluster.

Note

The node groups listed are managed node groups (p. 100) only.

- d. Select a **Fargate Profile** to delete, select **Delete**, enter the name of the profile, and then select **Delete**. Delete all Fargate profiles in the cluster.
- 4. Delete all self-managed node AWS CloudFormation stacks.
 - a. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
 - b. Select the node stack to delete and then choose **Actions**, **Delete Stack**.
 - On the **Delete Stack** confirmation screen, choose **Yes, Delete**. Delete all self-managed node stacks in the cluster.
- 5. Delete the cluster.
 - a. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
 - b. Select the cluster to delete and choose **Delete**.
 - c. On the delete cluster confirmation screen, choose **Delete**.
- (Optional) Delete the VPC AWS CloudFormation stack.
 - a. Select the VPC stack to delete and choose Actions and then Delete Stack.
 - b. On the **Delete Stack** confirmation screen, choose **Yes, Delete**.

[To delete an Amazon EKS cluster with the AWS CLI]

1. List all services running in your cluster.

```
kubectl get svc --all-namespaces
```

 Delete any services that have an associated EXTERNAL-IP value. These services are fronted by an Elastic Load Balancing load balancer, and you must delete them in Kubernetes to allow the load balancer and associated resources to be properly released.

kubectl delete svc <service-name>

- 3. Delete all node groups and Fargate profiles.
 - a. List the node groups in your cluster with the following command.

```
aws eks list-nodegroups --cluster-name <my-cluster>
```

Note

The node groups listed are managed node groups (p. 100) only.

b. Delete each node group with the following command. Delete all node groups in the cluster.

```
aws eks delete-nodegroup --nodegroup-name <my-nodegroup> --cluster-name <my-
cluster>
```

c. List the Fargate profiles in your cluster with the following command.

```
aws eks list-fargate-profiles --cluster-name <my-cluster>
```

 Delete each Fargate profile with the following command. Delete all Fargate profiles in the cluster.

```
aws eks delete-fargate-profile --fargate-profile-name <my-fargate-profile> --
cluster-name <my-cluster>
```

- 4. Delete all self-managed node AWS CloudFormation stacks.
 - a. List your available AWS CloudFormation stacks with the following command. Find the node template name in the resulting output.

```
aws cloudformation list-stacks --query "StackSummaries[].StackName"
```

b. Delete each node stack with the following command, replacing <node-stack> with your node stack name. Delete all self-managed node stacks in the cluster.

```
aws cloudformation delete-stack --stack-name <node-stack>
```

5. Delete the cluster with the following command, replacing <my-cluster> with your cluster name.

```
aws eks delete-cluster --name <my-cluster>
```

- 6. (Optional) Delete the VPC AWS CloudFormation stack.
 - List your available AWS CloudFormation stacks with the following command. Find the VPC template name in the resulting output.

```
aws cloudformation list-stacks --query "StackSummaries[].StackName"
```

b. Delete the VPC stack with the following command, replacing <my-vpc-stack> with your VPC stack name.

```
aws cloudformation delete-stack --stack-name <my-vpc-stack>
```

Amazon EKS cluster endpoint access control

This topic helps you to enable private access for your Amazon EKS cluster's Kubernetes API server endpoint and limit, or completely disable, public access from the internet.

When you create a new cluster, Amazon EKS creates an endpoint for the managed Kubernetes API server that you use to communicate with your cluster (using Kubernetes management tools such as kubectl). By default, this API server endpoint is public to the internet, and access to the API server is secured using a combination of AWS Identity and Access Management (IAM) and native Kubernetes Role Based Access Control (RBAC).

Amazon EKS User Guide Modifying cluster endpoint access

You can enable private access to the Kubernetes API server so that all communication between your nodes and the API server stays within your VPC. You can limit the IP addresses that can access your API server from the internet, or completely disable internet access to the API server.

Note

Because this endpoint is for the Kubernetes API server and not a traditional AWS PrivateLink endpoint for communicating with an AWS API, it doesn't appear as an endpoint in the Amazon VPC console.

When you enable endpoint private access for your cluster, Amazon EKS creates a Route 53 private hosted zone on your behalf and associates it with your cluster's VPC. This private hosted zone is managed by Amazon EKS, and it doesn't appear in your account's Route 53 resources. In order for the private hosted zone to properly route traffic to your API server, your VPC must have enableDnsHostnames and enableDnsSupport set to true, and the DHCP options set for your VPC must include AmazonProvidedDNS in its domain name servers list. For more information, see Updating DNS support for your VPC in the Amazon VPC User Guide.

Note

In addition to standard Amazon EKS permissions, your IAM user or role must have route53:AssociateVPCWithHostedZone permissions to enable the cluster's endpoint private access.

You can define your API server endpoint access requirements when you create a new cluster, and you can update the API server endpoint access for a cluster at any time.

Modifying cluster endpoint access

Use the procedures in this section to modify the endpoint access for an existing cluster. The following table shows the supported API server endpoint access combinations and their associated behavior.

API server endpoint access options

Endpoint public access	Endpoint private access	Behavior
Enabled	Disabled	 This is the default behavior for new Amazon EKS clusters. Kubernetes API requests that originate from within your cluster's VPC (such as node to control plane communication) leave the VPC but not Amazon's network. Your cluster API server is accessible from the internet. You can, optionally, limit the CIDR blocks that can access the public endpoint. If you limit access to specific CIDR blocks, then it is recommended that you also enable the private endpoint, or ensure that the CIDR blocks that you specify include the addresses that nodes and Fargate pods (if you use them) access the public endpoint from.

Amazon EKS User Guide Modifying cluster endpoint access

Endpoint public access	Endpoint private access	Behavior
Enabled	Enabled	 Kubernetes API requests within your cluster's VPC (such as node to control plane communication) use the private VPC endpoint. Your cluster API server is accessible from the internet. You can, optionally, limit the CIDR blocks that can access the public endpoint.
Disabled	Enabled	 All traffic to your cluster API server must come from within your cluster's VPC or a connected network. There is no public access to your API server from the internet. Any kubectl commands must come from within the VPC or a connected network. For connectivity options, see Accessing a private only API server (p. 61). The cluster's API server endpoint is resolved by public DNS servers to a private IP address from the VPC. In the past, the endpoint could only be resolved from within the VPC. If your endpoint does not resolve to a private IP address within the VPC for an existing cluster, you can: Enable public access and then disable it again. You only need to do so once for a cluster and the endpoint will resolve to a private IP address from that point forward. Update (p. 43) your cluster.

You can modify your cluster API server endpoint access using the AWS Management Console (p. 58) or AWS CLI (p. 59).

[To modify your cluster API server endpoint access using the AWS Management Console]

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. Choose the name of the cluster to display your cluster information.

- 3. Choose the Configuration tab. On the Networking tab, choose Update.
- 4. For **Private access**, choose whether to enable or disable private access for your cluster's Kubernetes API server endpoint. If you enable private access, Kubernetes API requests that originate from within your cluster's VPC use the private VPC endpoint. You must enable private access to disable public access.
- 5. For **Public access**, choose whether to enable or disable public access for your cluster's Kubernetes API server endpoint. If you disable public access, your cluster's Kubernetes API server can only receive requests from within the cluster VPC.
- 6. (Optional) If you've enabled **Public access**, you can specify which addresses from the Internet can communicate to the public endpoint. Select **Advanced Settings**. Enter a CIDR block, such as <203.0.113.5/32>. The block cannot include reserved addresses. You can enter additional blocks by selecting **Add Source**. There is a maximum number of CIDR blocks that you can specify. For more information, see Amazon EKS service quotas (p. 312). If you specify no blocks, then the public API server endpoint receives requests from all (0.0.0.0/0) IP addresses. If you restrict access to your public endpoint using CIDR blocks, it is recommended that you also enable private endpoint access so that nodes and Fargate pods (if you use them) can communicate with the cluster. Without the private endpoint enabled, your public access endpoint CIDR sources must include the egress sources from your VPC. For example, if you have a node in a private subnet that communicates to the internet through a NAT Gateway, you will need to add the outbound IP address of the NAT gateway as part of an allowed CIDR block on your public endpoint.
- 7. Choose **Update** to finish.

[To modify your cluster API server endpoint access using the AWS CLI]

Complete the following steps using the AWS CLI version 1.18.190 or later. You can check your current version with aws --version. To install or upgrade the AWS CLI, see Installing the AWS CLI.

1. Update your cluster API server endpoint access with the following AWS CLI command. Substitute your cluster name and desired endpoint access values. If you set endpointPublicAccess=true, then you can (optionally) enter single CIDR block, or a comma-separated list of CIDR blocks for publicAccessCidrs. The blocks cannot include reserved addresses. If you specify CIDR blocks, then the public API server endpoint will only receive requests from the listed blocks. There is a maximum number of CIDR blocks that you can specify. For more information, see Amazon EKS service quotas (p. 312). If you restrict access to your public endpoint using CIDR blocks, it is recommended that you also enable private endpoint access so that nodes and Fargate pods (if you use them) can communicate with the cluster. Without the private endpoint enabled, your public access endpoint CIDR sources must include the egress sources from your VPC. For example, if you have a node in a private subnet that communicates to the internet through a NAT Gateway, you will need to add the outbound IP address of the NAT gateway as part of an allowed CIDR block on your public endpoint. If you specify no CIDR blocks, then the public API server endpoint receives requests from all (0.0.0.0/0) IP addresses.

Note

The following command enables private access and public access from a single IP address for the API server endpoint. Replace <203.0.113.5/32> with a single CIDR block, or a comma-separated list of CIDR blocks that you want to restrict network access to.

```
aws eks update-cluster-config \
    --region <region-code> \
    --name <my-cluster> \
    --resources-vpc-config
endpointPublicAccess=<true>, publicAccessCidrs="<203.0.113.5/32>", endpointPrivateAccess=<true>
```

Output:

```
{
```

Amazon EKS User Guide Modifying cluster endpoint access

```
"update": {
        "id": "<e6f0905f-a5d4-4a2a-8c49-EXAMPLE00000>",
        "status": "InProgress",
        "type": "EndpointAccessUpdate",
        "params": [
            {
                "type": "EndpointPublicAccess",
                "value": "<true>"
            },
            {
                "type": "EndpointPrivateAccess",
                "value": "<true>"
            },
            {
                "type": "publicAccessCidrs",
                "value": "[\<203.0.113.5/32>\"]"
        ],
        "createdAt": <1576874258.137>,
        "errors": []
    }
}
```

2. Monitor the status of your endpoint access update with the following command, using the cluster name and update ID that was returned by the previous command. Your update is complete when the status is shown as Successful.

```
aws eks describe-update \
--region <region-code> \
--name <my-cluster> \
--update-id <e6f0905f-a5d4-4a2a-8c49-EXAMPLE00000>
```

Output:

```
"update": {
        "id": "<e6f0905f-a5d4-4a2a-8c49-EXAMPLE00000>",
        "status": "Successful",
        "type": "EndpointAccessUpdate",
        "params": [
                "type": "EndpointPublicAccess",
                "value": "<true>"
            },
                "type": "EndpointPrivateAccess",
                "value": "<true">
            },
                "type": "publicAccessCidrs",
                "value": "[\<203.0.113.5/32>\"]"
        ],
        "createdAt": <1576874258.137>,
        "errors": []
    }
}
```

Accessing a private only API server

If you have disabled public access for your cluster's Kubernetes API server endpoint, you can only access the API server from within your VPC or a connected network. Here are a few possible ways to access the Kubernetes API server endpoint:

- Connected network Connect your network to the VPC with an AWS transit gateway or other
 connectivity option and then use a computer in the connected network. You must ensure that your
 Amazon EKS control plane security group contains rules to allow ingress traffic on port 443 from your
 connected network.
- Amazon EC2 bastion host You can launch an Amazon EC2 instance into a public subnet in your
 cluster's VPC and then log in via SSH into that instance to run kubectl commands. For more
 information, see Linux bastion hosts on AWS. You must ensure that your Amazon EKS control plane
 security group contains rules to allow ingress traffic on port 443 from your bastion host. For more
 information, see Amazon EKS security group considerations (p. 204).

When you configure kubectl for your bastion host, be sure to use AWS credentials that are already mapped to your cluster's RBAC configuration, or add the IAM user or role that your bastion will use to the RBAC configuration before you remove endpoint public access. For more information, see Managing users or IAM roles for your cluster (p. 285) and Unauthorized or access denied (kubectl) (p. 366).

AWS Cloud9 IDE – AWS Cloud9 is a cloud-based integrated development environment (IDE) that lets
you write, run, and debug your code with just a browser. You can create an AWS Cloud9 IDE in your
cluster's VPC and use the IDE to communicate with your cluster. For more information, see Creating
an environment in AWS Cloud9. You must ensure that your Amazon EKS control plane security group
contains rules to allow ingress traffic on port 443 from your IDE security group. For more information,
see Amazon EKS security group considerations (p. 204).

When you configure kubectl for your AWS Cloud9 IDE, be sure to use AWS credentials that are already mapped to your cluster's RBAC configuration, or add the IAM user or role that your IDE will use to the RBAC configuration before you remove endpoint public access. For more information, see Managing users or IAM roles for your cluster (p. 285) and Unauthorized or access denied (kubectl) (p. 366).

Cluster Autoscaler

The Kubernetes Cluster Autoscaler automatically adjusts the number of nodes in your cluster when pods fail to launch due to lack of resources or when nodes in the cluster are underutilized and their pods can be rescheduled onto other nodes in the cluster.

This topic shows you how to deploy the Cluster Autoscaler to your Amazon EKS cluster and how to configure it to modify your Amazon EC2 Auto Scaling groups. The Cluster Autoscaler modifies your node groups so that they scale out when you need more resources and scale in when you have underutilized resources.

Create an Amazon EKS cluster

This section helps you to create a cluster and node group or groups. If you already have a cluster, you can skip ahead to Cluster Autoscaler node group considerations (p. 63).

If you are running a stateful application across multiple Availability Zones that is backed by Amazon EBS volumes and using the Kubernetes Cluster Autoscaler (p. 61), you should configure multiple node groups, each scoped to a single Availability Zone. In addition, you should enable the --balance-

Amazon EKS User Guide Create an Amazon EKS cluster

similar-node-groups feature. Otherwise, you can create a single node group that spans multiple Availability Zones.

Complete the steps in one of the following cluster creation procedures.

[To create a cluster with a single managed group that spans multiple Availability Zones]

• Create an Amazon EKS cluster with a single managed node group with the following eksctl command. For more information, see Creating an Amazon EKS cluster (p. 35). Substitute the <variable text> with your own values.

```
eksctl create cluster --name <my-cluster> --version <1.18> --managed --asg-access
```

Portions of the output showing the Availability Zones:

```
[#] using region <region-code>
[#] setting availability zones to [<region-code>a <region-code>b <region-code>c]
[#] subnets for <region-code>a - public:192.168.0.0/19 private:192.168.96.0/19
[#] subnets for <region-code>b - public:192.168.32.0/19 private:192.168.128.0/19
[#] subnets for <region-code>c - public:192.168.64.0/19 private:192.168.160.0/19
...
[#] nodegroup "ng-6bcca56a" has 2 node(s)
[#] node "ip-192-168-28-68.<region-code>.compute.internal" is ready
[#] node "ip-192-168-61-153.<region-code>.compute.internal" is ready
[#] waiting for at least 2 node(s) to become ready in "ng-6bcca56a"
[#] nodegroup "ng-6bcca56a" has 2 node(s)
[#] node "ip-192-168-28-68.<region-code>.compute.internal" is ready
[#] node "ip-192-168-61-153.
region-code>.compute.internal" is ready
[#] node "ip-192-168-61-153.
**Region-code>.compute.internal" is ready
**Region-code is ready
**
```

[To create a cluster with a dedicated managed node group for each Availability Zone]

Create an Amazon EKS cluster with no node groups with the following eksctl command. For
more information, see Creating an Amazon EKS cluster (p. 35). Note the Availability Zones that
the cluster is created in. You will use these Availability Zones when you create your node groups.
Substitute the red variable text with your own values.

```
eksctl create cluster --name <my-cluster> --version <1.18> --without-nodegroup
```

Portions of the output showing the Availability Zones:

```
...
[#] using region <region-code>
[#] setting availability zones to [<region-code>a <region-code>c <region-code>b]
[#] subnets for <region-code>a - public:192.168.0.0/19 private:192.168.96.0/19
[#] subnets for <region-code>c - public:192.168.32.0/19 private:192.168.128.0/19
[#] subnets for <region-code>b - public:192.168.64.0/19 private:192.168.160.0/19
...
[#] EKS cluster "my-cluster" in "<region-code>" region is ready
```

This cluster was created in the following Availability Zones: <region-code>a, <region-code>c, and <region-code>b.

2. For each Availability Zone in your cluster, use the following eksctl command to create a node group. Substitute the <variable text> with your own values. This command creates an Auto Scaling group with a minimum count of one and a maximum count of ten.

Amazon EKS User Guide Cluster Autoscaler node group considerations

```
eksctl create nodegroup --cluster <my-cluster> --node-zones <<region-code>a> --name <<region-code>a> --asg-access --nodes-min <1> --nodes <5> --nodes-max <10> --managed
```

Cluster Autoscaler node group considerations

The Cluster Autoscaler requires additional IAM and resource tagging considerations that are explained in this section.

Node group IAM policy

The Cluster Autoscaler requires the following IAM permissions to make calls to AWS APIs on your behalf.

If you used the previous <code>eksctl</code> commands to create your node groups, these permissions are automatically provided and attached to your node IAM roles. If you did not use <code>eksctl</code>, you must create an IAM policy with the following document and attach it to your node IAM roles. For more information, see <code>Modifying</code> a role in the <code>IAM User Guide</code>.

Auto Scaling group tags

The Cluster Autoscaler requires the following tags on your node group Auto Scaling groups so that they can be auto-discovered.

If you used the previous eksctl commands to create your node groups, these tags are automatically applied. If not, you must manually tag your Auto Scaling groups with the following tags. For more information, see Tagging your Amazon EC2 resources in the Amazon EC2 User Guide for Linux Instances.

Key	Value
k8s.io/cluster-autoscaler/ <cluster-name></cluster-name>	owned
k8s.io/cluster-autoscaler/enabled	true

Deploy the Cluster Autoscaler

To deploy the Cluster Autoscaler

- 1. Apply the manifest to your cluster by completing the option that corresponds to the region that your cluster is in.
 - All regions other than China (Ningxia) or China (Beijing)

kubectl apply -f https://raw.githubusercontent.com/kubernetes/autoscaler/master/
cluster-autoscaler/cloudprovider/aws/examples/cluster-autoscaler-autodiscover.yaml

- · China (Ningxia) or China (Beijing)
 - 1. Download the manifest with the following command.

curl -o cluster-autoscaler-autodiscover.yaml https://raw.githubusercontent.com/ kubernetes/autoscaler/master/cluster-autoscaler/cloudprovider/aws/examples/clusterautoscaler-autodiscover.yaml

- 2. Modify the manifest.
 - a. View the manifest file or files that you downloaded and note the name of the image. Download the image locally with the following command.

```
docker pull image:<tag>
```

b. Tag the image to be pushed to an Amazon Elastic Container Registry repository in China with the following command.

```
docker tag image:<tag> <aws_account_id>.dkr.ecr.<cn-north-1>.amazonaws.com/
image:<tag>
```

c. Push the image to a China Amazon ECR repository with the following command.

```
docker push image:<tag> <aws_account_id>.dkr.ecr.<cn-north-1>.amazonaws.com/
image:<tag>
```

- d. Update the Kubernetes manifest file or files to reference the Amazon ECR image URL in your region.
- 3. Apply the manifest.

```
kubectl apply -f cluster-autoscaler-autodiscover.yaml
```

Add the cluster-autoscaler.kubernetes.io/safe-to-evict annotation to the deployment with the following command.

```
kubectl -n kube-system annotate deployment.apps/cluster-autoscaler cluster-
autoscaler.kubernetes.io/safe-to-evict="false"
```

3. Edit the Cluster Autoscaler deployment with the following command.

```
kubectl -n kube-system edit deployment.apps/cluster-autoscaler
```

Edit the cluster-autoscaler container command to replace <YOUR CLUSTER NAME> with your cluster's name, and add the following options.

<--balance-similar-node-groups>

<--skip-nodes-with-system-pods=false>

```
spec:
    containers:
    - command:
        - ./cluster-autoscaler
        - --v=4
        - --stderrthreshold=info
        - --cloud-provider=aws
        - --skip-nodes-with-local-storage=false
        - --expander=least-waste
        - --node-group-auto-discovery=asg:tag=k8s.io/cluster-autoscaler/enabled,k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enabled.k8s.io/cluster-autoscaler/enable
```

Save and close the file to apply the changes.

- 4. Open the Cluster Autoscaler releases page in a web browser and find the latest Cluster Autoscaler version that matches your cluster's Kubernetes major and minor version. For example, if your cluster's Kubernetes version is 1.18 find the latest Cluster Autoscaler release that begins with 1.18. Record the semantic version number (1.18.nexample.com/number-page-10.18.
- 5. Set the Cluster Autoscaler image tag to the version that you recorded in the previous step with the following command. Replace 1.15.n with your own value. You can replace us with asia or eu.

```
kubectl -n kube-system set image deployment.apps/cluster-autoscaler cluster-
autoscaler=<us>.gcr.io/k8s-artifacts-prod/autoscaling/cluster-autoscaler:v<1.15.n>
```

Note

Depending on the version that you need, you may need to change the previous address to gcr.io/google-containers/cluster-autoscaler:v1.<n.n>. The image address is listed on the releases page.

View your Cluster Autoscaler logs

After you have deployed the Cluster Autoscaler, you can view the logs and verify that it is monitoring your cluster load.

View your Cluster Autoscaler logs with the following command.

```
kubectl -n kube-system logs -f deployment.apps/cluster-autoscaler
```

Output:

```
10926 23:15:55.165842
                           1 static_autoscaler.go:138] Starting main loop
I0926 23:15:55.166279
                           1 utils.go:595] No pod using affinity / antiaffinity found in
 cluster, disabling affinity predicate for this loop
I0926 23:15:55.166293 1 static_autoscaler.go:294] Filtering out schedulables
I0926 23:15:55.166330
                           1 static_autoscaler.go:311] No schedulable pods
I0926 23:15:55.166338
                         1 static_autoscaler.go:319] No unschedulable pods
10926 23:15:55.166345
                           1 static_autoscaler.go:366] Calculating unneeded nodes
I0926 23:15:55.166357
                           1 utils.go:552] Skipping ip-192-168-3-111.<region-
code>.compute.internal - node group min size reached
I0926 23:15:55.166365
                        1 utils.go:552] Skipping ip-192-168-71-83.<region-
code>.compute.internal - node group min size reached
10926 23:15:55.166373
                          1 utils.go:552] Skipping ip-192-168-60-191.<region-
code>.compute.internal - node group min size reached
```

Amazon EKS User Guide Control plane logging

```
      I0926 23:15:55.166435
      1 static_autoscaler.go:393] Scale down status:

      unneededOnly=false lastScaleUpTime=2019-09-26 21:42:40.908059094 ...

      I0926 23:15:55.166458
      1 static_autoscaler.go:403] Starting scale down

      I0926 23:15:55.166488
      1 scale_down.go:706] No candidates for scale down
```

Amazon EKS control plane logging

Amazon EKS control plane logging provides audit and diagnostic logs directly from the Amazon EKS control plane to CloudWatch Logs in your account. These logs make it easy for you to secure and run your clusters. You can select the exact log types you need, and logs are sent as log streams to a group for each Amazon EKS cluster in CloudWatch.

You can start using Amazon EKS control plane logging by choosing which log types you want to enable for each new or existing Amazon EKS cluster. You can enable or disable each log type on a per-cluster basis using the AWS Management Console, AWS CLI (version 1.16.139 or higher), or through the Amazon EKS API. When enabled, logs are automatically sent from the Amazon EKS cluster to CloudWatch Logs in the same account.

When you use Amazon EKS control plane logging, you're charged standard Amazon EKS pricing for each cluster that you run. You are charged the standard CloudWatch Logs data ingestion and storage costs for any logs sent to CloudWatch Logs from your clusters. You are also charged for any AWS resources, such as Amazon EC2 instances or Amazon EBS volumes, that you provision as part of your cluster.

The following cluster control plane log types are available. Each log type corresponds to a component of the Kubernetes control plane. To learn more about these components, see Kubernetes Components in the Kubernetes documentation.

- Kubernetes API server component logs (api) Your cluster's API server is the control plane
 component that exposes the Kubernetes API. For more information, see kube-apiserver in the
 Kubernetes documentation.
- Audit (audit) Kubernetes audit logs provide a record of the individual users, administrators, or system components that have affected your cluster. For more information, see Auditing in the Kubernetes documentation.
- Authenticator (authenticator) Authenticator logs are unique to Amazon EKS. These logs represent the control plane component that Amazon EKS uses for Kubernetes Role Based Access Control (RBAC) authentication using IAM credentials. For more information, see Cluster authentication (p. 277).
- Controller manager (controllerManager) The controller manager manages the core control
 loops that are shipped with Kubernetes. For more information, see kube-controller-manager in the
 Kubernetes documentation.
- Scheduler (scheduler) The scheduler component manages when and where to run pods in your cluster. For more information, see kube-scheduler in the Kubernetes documentation.

Enabling and disabling control plane logs

By default, cluster control plane logs aren't sent to CloudWatch Logs. You must enable each log type individually to send logs for your cluster. CloudWatch Logs ingestion, archive storage, and data scanning rates apply to enabled control plane logs. For more information, see CloudWatch pricing.

When you enable a log type, the logs are sent with a log verbosity level of 2.

To enable or disable control plane logs with the console

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. Choose the name of the cluster to display your cluster information.

- 3. Select the Configuration tab.
- 4. Under Logging, choose Update.
- 5. For each individual log type, choose whether the log type should be **Enabled** or **Disabled**. By default, each log type is **Disabled**.
- 6. Choose **Update** to finish.

To enable or disable control plane logs with the AWS CLI

1. Check your AWS CLI version with the following command.

```
aws --version
```

If your AWS CLI version is below 1.16.139, you must first update to the latest version. To install or upgrade the AWS CLI, see Installing the AWS command line interface in the AWS Command Line Interface User Guide.

2. Update your cluster's control plane log export configuration with the following AWS CLI command. Substitute your cluster name and desired endpoint access values.

Note

The following command sends all available log types to CloudWatch Logs.

Output:

3. Monitor the status of your log configuration update with the following command, using the cluster name and the update ID that were returned by the previous command. Your update is complete when the status appears as Successful.

Output:

```
{
    "update": {
        "id": "<883405c8-65c6-4758-8cee-2a7c1340a6d9>",
        "status": "Successful",
```

Amazon EKS User Guide Viewing cluster control plane logs

Viewing cluster control plane logs

After you have enabled any of the control plane log types for your Amazon EKS cluster, you can view them on the CloudWatch console.

To learn more about viewing, analyzing, and managing logs in CloudWatch, see the Amazon CloudWatch Logs User Guide.

To view your cluster control plane logs on the CloudWatch console

- Open the CloudWatch console at https://console.aws.amazon.com/cloudwatch/home#logs:prefix=/ aws/eks. This URL displays your current available log groups and filters them with the /aws/eks prefix.
- 2. Choose the cluster that you want to view logs for. The log group name format is /aws/eks/ <cluster-name>/cluster.
- Choose the log stream to view. The following list describes the log stream name format for each log type.

Note

As log stream data grows, the log stream names are rotated. When multiple log streams exist for a particular log type, you can view the latest log stream by looking for the log stream name with the latest **Last Event Time**.

- Kubernetes API server component logs (api) kube-apiserver-<nnn...>
- Audit (audit) kube-apiserver-audit-<nnn...>
- Authenticator (authenticator) authenticator < nnn...>
- Controller manager (controllerManager) kube-controller-manager-<nnn...>
- Scheduler (scheduler) kube-scheduler-<nnn...>

Amazon EKS Kubernetes versions

The Kubernetes project is rapidly evolving with new features, design updates, and bug fixes. The community releases new Kubernetes minor versions, such as 1.18, as generally available approximately every three months, and each minor version is supported for approximately twelve months after it is first released.

Available Amazon EKS Kubernetes versions

The following Kubernetes versions are currently available for new clusters in Amazon EKS:

1.18.9

- 1.17.12
- 1.16.15
- 1.15.12

Unless your application requires a specific version of Kubernetes, we recommend that you choose the latest available Kubernetes version supported by Amazon EKS for your clusters. As new Kubernetes versions become available in Amazon EKS, we recommend that you proactively update your clusters to use the latest available version. For more information, see Updating a Cluster (p. 43). For more information, see Amazon EKS Kubernetes release calendar (p. 72) and Amazon EKS version support and FAQ (p. 72).

Kubernetes 1.18

Kubernetes 1.18 is now available in Amazon EKS. For more information about Kubernetes 1.18, see the official release announcement.

The following Kubernetes features are now supported in Kubernetes 1.18 Amazon EKS clusters:

- Topology Manager has reached beta status. This feature allows the CPU and Device Manager to coordinate resource allocation decisions, optimizing for low latency with machine learning and analytics workloads. For more information, see Control Topology Management Policies on a node in the Kubernetes documentation.
- Server-side Apply is updated with a new beta version. This feature tracks and manages changes to fields of all new Kubernetes objects, allowing you to know what changed your resources and when. For more information, see What is Server-side Apply? in the Kubernetes documentation.
- A new pathType field and a new IngressClass resource has been added to the Ingress specification.
 These features make it simpler to customize Ingress configuration, and are supported by the AWS Load
 Balancer Controller (p. 267) (formerly called the ALB Ingress Controller). For more information, see
 Improvements to the Ingress API in Kubernetes 1.18 in the Kubernetes documentation.
- Configurable horizontal pod autoscaling behavior. For more information, see Support for configurable scaling behavior in the Kubernetes documentation.
- In 1.18 clusters, you no longer need to include the AWS_DEFAULT_REGION=<region-code> environment variable to pods when using IAM roles for service accounts in China regions, whether you use the mutating web hook or configure the environment variables manually. You still need to include the variable for all pods in earlier versions.

For the complete Kubernetes 1.18 changelog, see https://github.com/kubernetes/kubernetes/blob/master/CHANGELOG/CHANGELOG-1.18.md.

Kubernetes 1.17

Kubernetes 1.17 is now available in Amazon EKS. For more information about Kubernetes 1.17, see the official release announcement.

Important

- EKS has not enabled the CSIMigrationAWS feature flag. This will be enabled in a future release, along with detailed migration instructions. For more info on CSI migration, see the Kubernetes blog.
- Upgrading a cluster from 1.16 to 1.17 will fail if any of your AWS Fargate pods have a
 kubelet minor version earlier than 1.16. Before upgrading your cluster from 1.16 to 1.17,
 you need to recycle your Fargate pods so that their kubelet is 1.16 before attempting to
 upgrade the cluster to 1.17. To recycle a Kubernetes deployment on a 1.15 or later cluster, use
 the following command.

Amazon EKS User Guide Kubernetes 1.16

kubectl rollout restart deployment <deployment-name>

The following Kubernetes features are now supported in Kubernetes 1.17 Amazon EKS clusters:

- Cloud Provider Labels have reached general availability. If you are using the beta labels in your pod specs for features such as node affinity, or in any custom controllers, then we recommend that you start migrating them to the new GA labels. For information about the new labels, see the following Kubernetes documentation:
 - node.kubernetes.io/instance-type
 - · topology.kubernetes.io/region
 - topology.kubernetes.io/zone
- The ResourceQuotaScopeSelectors feature has graduated to generally available. This feature allows you to limit the number of resources a quota supports to only those that pertain to the scope.
- The TaintNodesByCondition feature has graduated to generally available. This feature allows you to taint nodes that have conditions such as high disk or memory pressure.
- The CSI Topology feature has graduated to generally available, and is fully supported by the EBS CSI driver. You can use topology to restrict the Availability Zone where a volume is provisioned.
- Finalizer protection for services of type LoadBalancer has graduated to generally available. This
 feature ensures that a service resource is not fully deleted until the correlating load balancer is also
 deleted.
- Custom resources now support default values. You specify values in an OpenAPI v3 validation schema.
- The Windows containers RunAsUsername feature is now in beta, allowing you to run Windows
 applications in a container as a different username than the default.

For the complete Kubernetes 1.17 changelog, see https://github.com/kubernetes/kubernetes/blob/master/CHANGELOG/CHANGELOG-1.17.md.

Kubernetes 1.16

Kubernetes 1.16 is now available in Amazon EKS. For more information about Kubernetes 1.16, see the official release announcement.

Important

- Kubernetes 1.16 removes a number of deprecated APIs. Changes to your applications
 may be required before upgrading your cluster to 1.16. Carefully follow the 1.16 upgrade
 prerequisites (p. 50) before upgrading.
- Starting with 1.16, the Amazon EKS certificate authority will honor certificate signing requests with SAN X.509 extensions, which resolves the EKS CA should honor SAN x509 extension feature request from GitHub.

The following Kubernetes features are now supported in Kubernetes 1.16 Amazon EKS clusters:

- Volume expansion in the CSI specification has moved to beta, which allows for any CSI spec
 volume plugin to be resizeable. For more information, see Volume Expansion in the Kubernetes CSI
 documentation. The latest version of the EBS CSI driver supports volume expansion when running on
 an Amazon EKS 1.16 cluster.
- Windows GMSA support has graduated from alpha to beta, and is now supported by Amazon EKS.
 For more information, see Configure GMSA for Windows Pods and containers in the Kubernetes documentation.

Amazon EKS User Guide Kubernetes 1.15

- A new annotation: service.beta.kubernetes.io/aws-load-balancer-eip-allocations is available on service type LoadBalancer to assign an elastic IP address to Network Load Balancers.
 For more information, see the Support EIP Allocations with AWS NLB GitHub issue.
- Finalizer protection for service load balancers is now in beta and enabled by default. Service load balancer finalizer protection ensures that any load balancer resources allocated for a Kubernetes Service object, such as the AWS Network Load Balancer, will be destroyed or released when the service is deleted. For more information, see Garbage Collecting Load Balancers in the Kubernetes documentation.
- The Kubernetes custom resource definitions and admission webhooks extensibility mechanisms have both reached general availability. For more information, see Custom Resources and Dynamic Admission Control in the Kubernetes documentation.
- The server-side apply feature has reached beta status and is enabled by default. For more information, see Server Side Apply in the Kubernetes documentation.
- The CustomResourceDefaulting feature is promoted to beta and enabled by default. Defaults may be specified in structural schemas through the apiextensions.k8s.io/v1 API. For more information, see Specifying a structural schema in the Kubernetes documentation.

For the complete Kubernetes 1.16 changelog, see https://github.com/kubernetes/kubernetes/blob/master/CHANGELOG/CHANGELOG-1.16.md.

Kubernetes 1.15

Kubernetes 1.15 is now available in Amazon EKS. For more information about Kubernetes 1.15, see the official release announcement.

Important

Starting with 1.15, Amazon EKS no longer tags the VPC containing your cluster.

- Subnets within the VPC of your cluster are still tagged.
- VPC tags will not be modified on existing cluster upgrades to 1.15.
- For more information about VPC tagging, see VPC tagging requirement (p. 203).

Important

Amazon EKS has set the re-invocation policy for the Pod Identity Webhook to IfNeeded. This allows the webhook to be re-invoked if objects are changed by other mutating admission webhooks like the App Mesh sidecar injector. For more information about the App Mesh sidecar injector, see Install the sidecar injector.

The following features are now supported in Kubernetes 1.15 Amazon EKS clusters:

- EKS now supports configuring transport layer security (TLS) termination, access logs, and source ranges for network load balancers. For more information, see Network Load Balancer support on AWS on GitHub.
- Improved flexibility of Custom Resource Definitions (CRD), including the ability to convert between versions on the fly. For more information, see Extend the Kubernetes API with CustomResourceDefinitions on GitHub.
- NodeLocal DNSCache is in beta for Kubernetes version 1.15 clusters. This feature can help improve cluster DNS performance by running a DNS caching agent on cluster nodes as a DaemonSet. For more information, see Using NodeLocal DNSCache in Kubernetes clusters on GitHub.

Note

When running CoreDNS on Amazon EC2, we recommend not using force_tcp in the configuration and ensuring that options use-vc is not set in /etc/resolv.conf.

For the complete Kubernetes 1.15 changelog, see https://github.com/kubernetes/kubernetes/blob/master/CHANGELOG/CHANGELOG-1.15.md.

Amazon EKS Kubernetes release calendar

Note

Dates with only a month and a year are approximate and are updated with an exact date when it is known.

Kubernetes version	Upstream release	Amazon EKS release	Amazon EKS end of support
1.15	June 19, 2019	March 10, 2020	May, 2021
1.16	September 8, 2019	April 30, 2020	July, 2021
1.17	December 9, 2019	July 10, 2020	September, 2021
1.18	March 23, 2020	October 13, 2020	November, 2021
1.19	August 26, 2020	January, 2021	February, 2022

Amazon EKS version support and FAQ

In line with the Kubernetes community support for Kubernetes versions, Amazon EKS is committed to supporting at least four production-ready versions of Kubernetes at any given time. We will announce the end of support date of a given Kubernetes minor version at least 60 days before the end of support date. Because of the Amazon EKS qualification and release process for new Kubernetes versions, the end of support date of a Kubernetes version on Amazon EKS will be on or after the date that the Kubernetes project stops supporting the version upstream.

Kubernetes supports compatibility between the control plane and nodes for up to two minor versions. For example, 1.16 nodes will continue to operate when orchestrated by a 1.18 control plane. For more information, see Kubernetes version and version skew support policy in the Kubernetes documentation.

Frequently asked questions

Q: How long is a Kubernetes version supported by Amazon EKS?

A: A Kubernetes version is fully supported for 14 months after first being available on Amazon EKS. This is true even if upstream Kubernetes is no longer supporting a version available on Amazon EKS. We backport security patches that are applicable to the Kubernetes versions supported on Amazon EKS.

Q: When does support end for a Kubernetes version on Amazon EKS?

A: Approximately 12 months after a version is released on Amazon EKS (usually with the release of a new version) Amazon EKS will send out a notice through the AWS Personal Health Dashboard if any clusters in your account are running the version nearing end of support. The notice will include the end of support date, which will be at least 60 days from the date of the notice.

Q: What happens on the end of support date?

A: On the end of support date, you will no longer be able to create new Amazon EKS clusters with the unsupported version. Existing clusters will be automatically upgraded to the oldest supported version through a gradual deployment process after the end of support date.

Q: When exactly will my cluster be automatically upgraded after the end of support date?

A: Amazon EKS is unable to provide specific timeframes. Automatic upgrades can happen at any time after the end of support date. We recommend that you take proactive action and upgrade your clusters without relying on the Amazon EKS automatic upgrade process.

Q: Can I leave my cluster on a Kubernetes version indefinitely?

A: No. In the interest of security, Amazon EKS does not allow clusters to stay on a version that has reached end of support.

Amazon EKS platform versions

Amazon EKS platform versions represent the capabilities of the cluster control plane, such as which Kubernetes API server flags are enabled, as well as the current Kubernetes patch version. Each Kubernetes minor version has one or more associated Amazon EKS platform versions. The platform versions for different Kubernetes minor versions are independent.

When a new Kubernetes minor version is available in Amazon EKS, such as 1.18, the initial Amazon EKS platform version for that Kubernetes minor version starts at eks.1. However, Amazon EKS releases new platform versions periodically to enable new Kubernetes control plane settings and to provide security fixes

When new Amazon EKS platform versions become available for a minor version:

- The Amazon EKS platform version number is incremented (eks.<n+1>).
- Amazon EKS automatically upgrades all existing clusters to the latest Amazon EKS platform version for their corresponding Kubernetes minor version.
- Amazon EKS might publish a new node AMI with a corresponding patch version. However, all patch
 versions are compatible between the EKS control plane and node AMIs for a given Kubernetes minor
 version.

New Amazon EKS platform versions don't introduce breaking changes or cause service interruptions.

Note

Automatic upgrades of existing Amazon EKS platform versions are rolled out incrementally. The roll-out process might take some time. If you need the latest Amazon EKS platform version features immediately, you should create a new Amazon EKS cluster.

Clusters are always created with the latest available Amazon EKS platform version (eks.<n>) for the specified Kubernetes version. If you update your cluster to a new Kubernetes minor version, your cluster receives the current Amazon EKS platform version for the Kubernetes minor version that you updated to.

The current and recent Amazon EKS platform versions are described in the following tables.

Kubernetes version	Amazon EKS platform version	Enabled admission controllers	Release notes
1.18.9	eks.3	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota,	Includes support for Amazon EKS add-ons (p. 52) , and Fargate logging (p. 147).

Kubernetes version	Amazon EKS platform version	Enabled admission controllers	Release notes
		DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	bhook, Webhook, on, rotection,
1.18.9	eks.2	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	with security fixes and enhancements. conds, bhook, webhook, on,
1.18.8	eks.1	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	Kubernetes 1.18 for Amazon EKS. For , more information, see Kubernetes conds(p. 69). Chook, webhook, on,

Kubernetes version	Amazon EKS platform version	Enabled admission controllers	Release notes
1.17.12	eks.5	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction,	

Kubernetes version	Amazon EKS platform version	Enabled admission controllers	Release notes
		MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	Webhook, on, rotection,
1.17.12	eks.4	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	with security fixes and enhancements. conds, bhook, Webhook, on, rotection,
1.17.9	eks.3	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	with support for Security groups for , pods (p. 213). This release creates a copdsresource-controller service baccolunt that is required webstably PC resource controller. on,
1.17.9	eks.2	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	with security fixes and enhancements, including UDP support for services of type cbaddpalancer when using NLB and support bfordsing Amazon WEES wolumes with Fargate pods. For more oimformation, see the Allow UDP for AWS NLB rissue on of the supposition of the

Kubernetes version	Amazon EKS platform version	Enabled admission controllers	Release notes
1.17.6	eks.1	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	see Kubernetes conds(p. 69). bhook, Webhook, on, rotection,

Kubernetes version	Amazon EKS platform version	Enabled admission controllers	Release notes
1.16.15	eks.5	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	for Fargate logging (p. 147). conds, bhook, Webhook, on, rotection,
1.16.15	eks.4	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	with security fixes and enhancements. conds, bhook, Webhook, on, rotection,
1.16.13	eks.3	NamespaceLifecycle, LimitRanger,	New platform version with security fixes

Kubernetes version	Amazon EKS platform version	Enabled admission controllers	Release notes
		ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	for services of type cbnadpalancer when using NLB. For more bimformation, see the WabbrodkDP for AWS NLB issue on GitHub. on, rotection,
1.16.8	eks.2	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	with security fixes. conds, bhook, webhook, on, rotection,
1.16.8	eks.1	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	Kubernetes 1.16 for Amazon EKS. For , more information, see Kubernetes conds(p. 70). bhook, Webhook, on, rotection,

Kubernetes version	Amazon EKS platform version	Enabled admission controllers	Release notes
1.15.12	eks.6	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass	Includes support for Fargate logging (p. 147).

Kubernetes version	Amazon EKS platform version	Enabled admission controllers	Release notes
		ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	bhook, Webhook, on, rotection,
1.15.12	eks.5	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmissionPodSecurityPolicy, TaintNodesByConditiPriority, StorageObjectInUsePPersistentVolumeClass	conds, bhook, Webhook, on, rotection,
1.15.11	eks.4	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	with security fixes and enhancements, including UDP support for services of type cbadBalancer when using NLB. For more bimformation, see the WabbodkDP for AWS NLB issue on GitHub. on,

Kubernetes version	Amazon EKS platform version	Enabled admission controllers	Release notes
1.15.11	eks.3	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	with security fixes. conds, bhook, Webhook, on, rotection,
1.15.11	eks.2	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	with bug fixes and enhancements, including an update to the server side AWS cland Authenticator, with IAM role traceability bimopicy ements. Webhook, on, rotection,
1.15.10	eks.1	NamespaceLifecycle, LimitRanger, ServiceAccount, DefaultStorageClass ResourceQuota, DefaultTolerationSe NodeRestriction, MutatingAdmissionWe ValidatingAdmission PodSecurityPolicy, TaintNodesByConditi Priority, StorageObjectInUseP PersistentVolumeCla	Kubernetes 1.15 for Amazon EKS. For , more information, see Kubernetes conds(p. 71). bhook, Webhook, on, rotection,

Windows support

This topic describes how to add Windows support to Amazon EKS clusters.

Considerations

Before deploying Windows nodes, be aware of the following considerations.

- Amazon EC2 instance types C3, C4, D2, I2, M4 (excluding m4.16xlarge), and R3 instances are not supported for Windows workloads.
- Host networking mode is not supported for Windows workloads.
- Amazon EKS clusters must contain one or more Linux nodes to run core system pods that only run on Linux, such as coredns and the VPC resource controller.
- The kubelet and kube-proxy event logs are redirected to the EKS Windows Event Log and are set to a 200 MB limit.
- · You cannot use Security groups for pods (p. 213) with pods running on Windows nodes.
- Windows nodes support one elastic network interface per node. The number of pods that you can run
 per Windows node is equal to the number of IP addresses available per elastic network interface for
 the node's instance type, minus one. For more information, see IP addresses per network interface per
 instance type in the Amazon EC2 User Guide for Linux Instances.
- Group Managed Service Accounts (GMSA) for Windows pods and containers is not supported by Amazon EKS versions earlier than 1.16. You can follow the instructions in the Kubernetes documentation to enable and test this alpha feature on clusters that are earlier than 1.16.

Enabling Windows support

The following steps help you to enable Windows support for your Amazon EKS cluster. You can use eksct1 (p. 80), a Windows client (p. 81), or a macOS or Linux client (p. 82) to enable Windows support for your cluster.

To enable Windows support for your cluster with eksctl

This procedure only works for clusters that were created with eksctl and assumes that your eksctl version is 0.33.0 or later. You can check your version with the following command.

```
eksctl version
```

For more information about installing or upgrading eksctl, see Installing or upgrading eksctl (p. 298).

Enable Windows support for your Amazon EKS cluster with the following eksctl command. This
command deploys the VPC resource controller and VPC admission controller webhook that are
required on Amazon EKS clusters to run Windows workloads.

```
eksctl utils install-vpc-controllers --cluster <cluster_name> --approve
```

2. After you have enabled Windows support, you can launch a Windows node group into your cluster. For more information, see Launching self-managed Windows nodes (p. 124).

After you add Windows support to your cluster, you must specify node selectors on your applications so that the pods land on a node with the appropriate operating system. For Linux pods, use the following node selector text in your manifests.

```
nodeSelector:
    kubernetes.io/os: linux
    kubernetes.io/arch: amd64
```

For Windows pods, use the following node selector text in your manifests.

```
nodeSelector:
```

kubernetes.io/os: windows
kubernetes.io/arch: amd64

To enable Windows support for your cluster with a Windows client

In the following steps, replace the <region-code> with the Region that your cluster resides in.

- Deploy the VPC resource controller to your cluster using the command that corresponds to the Region that your cluster is in.
 - All Regions other than China (Beijing) and China (Ningxia)

kubectl apply -f https://s3.us-west-2.amazonaws.com/amazon-eks/manifests/<regioncode>/vpc-resource-controller/latest/vpc-resource-controller.yaml

China (Beijing) and China (Ningxia)

kubectl apply -f https://s3.cn-north-1.amazonaws.com.cn/amazon-eks/manifests/<regioncode>/vpc-resource-controller/latest/vpc-resource-controller.yaml

- 2. Deploy the VPC admission controller webhook to your cluster.
 - Download the required scripts and deployment files that correspond to the Region that your cluster is in.
 - All Regions other than China (Beijing) and China (Ningxia)

curl -o vpc-admission-webhook-deployment.yaml https://s3.us-west-2.amazonaws.com/
amazon-eks/manifests/<region-code>/vpc-admission-webhook/latest/vpc-admissionwebhook-deployment.yaml;
curl -o Setup-VPCAdmissionWebhook.ps1 https://s3.us-west-2.amazonaws.com/
amazon-eks/manifests/<region-code>/vpc-admission-webhook/latest/SetupVPCAdmissionWebhook.ps1;
curl -o webhook-create-signed-cert.ps1 https://s3.us-west-2.amazonaws.com/amazoneks/manifests/<region-code>/vpc-admission-webhook/latest/webhook-create-signedcert.ps1;
curl -o webhook-patch-ca-bundle.ps1 https://s3.us-west-2.amazonaws.com/amazoneks/manifests/<region-code>/vpc-admission-webhook/latest/webhook-patch-cabundle.ps1;

China (Beijing) and China (Ningxia)

```
curl -o vpc-admission-webhook-deployment.yaml https://s3.cn-
north-1.amazonaws.com.cn/amazon-eks/manifests/<region-code>/vpc-admission-
webhook/latest/vpc-admission-webhook-deployment.yaml;
curl -o Setup-VPCAdmissionWebhook.ps1 https://s3.cn-north-1.amazonaws.com.cn/
amazon-eks/manifests/<region-code>/vpc-admission-webhook/latest/Setup-
VPCAdmissionWebhook.ps1;
curl -o webhook-create-signed-cert.ps1 https://s3.cn-north-1.amazonaws.com.cn/
amazon-eks/manifests/<region-code>/vpc-admission-webhook/latest/webhook-create-
signed-cert.ps1;
curl -o webhook-patch-ca-bundle.ps1 https://s3.cn-north-1.amazonaws.com.cn/
amazon-eks/manifests/<region-code>/vpc-admission-webhook/latest/webhook-patch-ca-
bundle.ps1;
```

- b. Install OpenSSL and jq.
- c. Set up and deploy the VPC admission webhook.

./Setup-VPCAdmissionWebhook.ps1 -DeploymentTemplate ".\vpc-admission-webhook-deployment.yaml"

3. Determine if your cluster has the required cluster role binding.

```
kubectl get clusterrolebinding eks:kube-proxy-windows
```

If output similar to the following example output is returned, then the cluster has the necessary role binding.

```
NAME AGE
eks:kube-proxy-windows 10d
```

If the output includes Error from server (NotFound), then the cluster does not have the necessary cluster role binding. Add the binding by creating a file named eks-kube-proxywindows-crb.yaml with the following content.

```
kind: ClusterRoleBinding
apiVersion: rbac.authorization.k8s.io/v1beta1
metadata:
name: eks:kube-proxy-windows
labels:
    k8s-app: kube-proxy
    eks.amazonaws.com/component: kube-proxy
subjects:
    - kind: Group
    name: "eks:kube-proxy-windows"
roleRef:
    kind: ClusterRole
    name: system:node-proxier
    apiGroup: rbac.authorization.k8s.io
```

Apply the configuration to the cluster.

```
kubectl apply -f eks-kube-proxy-windows-crb.yaml
```

4. After you have enabled Windows support, you can launch a Windows node group into your cluster. For more information, see Launching self-managed Windows nodes (p. 124).

After you add Windows support to your cluster, you must specify node selectors on your applications so that the pods land on a node with the appropriate operating system. For Linux pods, use the following node selector text in your manifests.

```
nodeSelector:
    kubernetes.io/os: linux
    kubernetes.io/arch: amd64
```

For Windows pods, use the following node selector text in your manifests.

```
nodeSelector:
    kubernetes.io/os: windows
    kubernetes.io/arch: amd64
```

To enable Windows support for your cluster with a macOS or Linux client

This procedure requires that the openss1 library and jq JSON processor are installed on your client system.

In the following steps, replace < region-code > with the Region that your cluster resides in.

- 1. Deploy the VPC resource controller to your cluster using the command that corresponds to the Region that your cluster is in.
 - All Regions other than China (Beijing) and China (Ningxia)

kubectl apply -f https://s3.us-west-2.amazonaws.com/amazon-eks/manifests/<regioncode>/vpc-resource-controller/latest/vpc-resource-controller.yaml

China (Beijing) and China (Ningxia)

kubectl apply -f https://s3.cn-north-1.amazonaws.com.cn/amazon-eks/manifests/<regioncode>/vpc-resource-controller/latest/vpc-resource-controller.yaml

- 2. Create the VPC admission controller webhook manifest for your cluster.
 - a. Download the required scripts and deployment files for the Region that your cluster is in.
 - All Regions other than China (Beijing) and China (Ningxia)

curl -o webhook-create-signed-cert.sh https://s3.us-west-2.amazonaws.com/amazoneks/manifests/<region-code>/vpc-admission-webhook/latest/webhook-create-signedcert.sh curl -o webhook-patch-ca-bundle.sh https://s3.us-west-2.amazonaws.com/amazon-eks/

curl -o webhook-patch-ca-bundle.sh https://s3.us-west-2.amazonaws.com/amazon-eks/manifests/<region-code>/vpc-admission-webhook/latest/webhook-patch-ca-bundle.sh curl -o vpc-admission-webhook-deployment.yaml https://s3.us-west-2.amazonaws.com/amazon-eks/manifests/<region-code>/vpc-admission-webhook/latest/vpc-admission-webhook-deployment.yaml

· China (Beijing) and China (Ningxia)

curl -o webhook-create-signed-cert.sh https://s3.cn-north-1.amazonaws.com.cn/amazon-eks/manifests/<region-code>/vpc-admission-webhook/latest/webhook-create-signed-cert.sh
curl -o webhook-patch-ca-bundle.sh https://s3.cn-north-1.amazonaws.com.cn/amazon-eks/manifests/<region-code>/vpc-admission-webhook/latest/webhook-patch-ca-bundle.sh
curl -o vpc-admission-webhook-deployment.yaml https://s3.cnnorth-1.amazonaws.com.cn/amazon-eks/manifests/<region-code>/vpc-admission-webhook/latest/vpc-admission-webhook-deployment.yaml

b. Add permissions to the shell scripts so that they can be executed.

chmod +x webhook-create-signed-cert.sh webhook-patch-ca-bundle.sh

c. Create a secret for secure communication.

./webhook-create-signed-cert.sh

d. Verify the secret.

kubectl get secret -n kube-system vpc-admission-webhook-certs

e. Configure the webhook and create a deployment file.

cat ./vpc-admission-webhook-deployment.yaml | ./webhook-patch-ca-bundle.sh > vpcadmission-webhook.yaml

Deploy the VPC admission webhook.

```
kubectl apply -f vpc-admission-webhook.yaml
```

4. Determine if your cluster has the required cluster role binding.

```
kubectl get clusterrolebinding eks:kube-proxy-windows
```

If output similar to the following example output is returned, then the cluster has the necessary role binding.

```
NAME AGE
eks:kube-proxy-windows 10d
```

If the output includes Error from server (NotFound), then the cluster does not have the necessary cluster role binding. Add the binding by creating a file named eks-kube-proxy-windows-crb.yaml with the following content.

```
kind: ClusterRoleBinding
apiVersion: rbac.authorization.k8s.io/v1beta1
metadata:
name: eks:kube-proxy-windows
labels:
k8s-app: kube-proxy
eks.amazonaws.com/component: kube-proxy
subjects:
- kind: Group
name: "eks:kube-proxy-windows"
roleRef:
kind: ClusterRole
name: system:node-proxier
apiGroup: rbac.authorization.k8s.io
```

Apply the configuration to the cluster.

```
kubectl apply -f eks-kube-proxy-windows-crb.yaml
```

5. After you have enabled Windows support, you can launch a Windows node group into your cluster. For more information, see Launching self-managed Windows nodes (p. 124).

After you add Windows support to your cluster, you must specify node selectors on your applications so that the pods land on a node with the appropriate operating system. For Linux pods, use the following node selector text in your manifests.

```
nodeSelector:
    kubernetes.io/os: linux
    kubernetes.io/arch: amd64
```

For Windows pods, use the following node selector text in your manifests.

```
nodeSelector:
    kubernetes.io/os: windows
    kubernetes.io/arch: amd64
```

Deploy a Windows sample application

To deploy a Windows sample application

1. Create a file named windows-server-iis.yaml with the following content.

```
apiVersion: apps/v1
kind: Deployment
metadata:
 name: windows-server-iis
spec:
  selector:
   matchLabels:
     app: windows-server-iis
      tier: backend
     track: stable
  replicas: 1
  template:
   metadata:
      labels:
        app: windows-server-iis
        tier: backend
        track: stable
    spec:
      containers:
      - name: windows-server-iis
        image: mcr.microsoft.com/windows/servercore:1809
        ports:
        - name: http
         containerPort: 80
        imagePullPolicy: IfNotPresent
        command:
        - powershell.exe
        - -command
        - "Add-WindowsFeature Web-Server; Invoke-WebRequest -UseBasicParsing
 -Uri 'https://dotnetbinaries.blob.core.windows.net/servicemonitor/2.0.1.6/
ServiceMonitor.exe' -OutFile 'C:\\ServiceMonitor.exe'; echo '<html><body><br/>><br/>
><br/><marquee><H1>Hello EKS!!!<H1><marquee></body><html>' > C:\\inetpub\\wwwroot\
\default.html; C:\\ServiceMonitor.exe 'w3svc'; "
     nodeSelector:
        kubernetes.io/os: windows
apiVersion: v1
kind: Service
metadata:
 name: windows-server-iis-service
 namespace: default
spec:
 ports:
  - port: 80
   protocol: TCP
    targetPort: 80
   app: windows-server-iis
   tier: backend
   track: stable
  sessionAffinity: None
  type: LoadBalancer
```

2. Deploy the application to the cluster.

```
kubectl apply -f windows-server-iis.yaml
```

3. Get the status of the pod.

```
kubectl get pods -o wide --watch
```

Wait for the pod to transition to the Running state.

4. Query the services in your cluster and wait until the **External IP** column for the windows-server-iis-service service is populated.

Note

It might take several minutes for the IP address to become available.

```
kubectl get services -o wide
```

5. After your external IP address is available, point a web browser to that address to view the IIS home page.

Note

It might take several minutes for DNS to propagate and for your sample application to load in your web browser.

Inferentia support

This topic describes how to create an Amazon EKS cluster with nodes running Amazon EC2 Inf1 instances and (optionally) deploy a sample application. Amazon EC2 Inf1 instances are powered by AWS Inferentia chips, which are custom built by AWS to provide high performance and lowest cost inference in the cloud. Machine learning models are deployed to containers using AWS Neuron, a specialized software development kit (SDK) consisting of a compiler, run-time, and profiling tools that optimize the machine learning inference performance of Inferentia chips. AWS Neuron supports popular machine learning frameworks such as TensorFlow, PyTorch, and MXNet.

Considerations

- Neuron device logical IDs must be contiguous. If a pod requesting multiple Neuron devices is scheduled on an inf1.6xlarge or inf1.24xlarge instance type (which have more than one Neuron device), that pod will fail to start if the Kubernetes scheduler selects non-contiguous device IDs. For more information, see Device logical IDs must be contiguous on GitHub.
- Amazon EC2 Inf1 instances are not currently supported with managed node groups.

Prerequisites

- Have eksctl installed on your computer. If you don't have it installed, see Install eksctl (p. 6) for installation instructions.
- Have kubect1 installed on your computer. For more information, see Installing kubect1 (p. 289).
- (Optional) Have python3 installed on your computer. If you don't have it installed, then see Python downloads for installation instructions.

Create a cluster

To create a cluster with Inf1 Amazon EC2 instance nodes

Create a cluster with Inf1 Amazon EC2 instance nodes. You can replace <inf1.2xlarge> with any Inf1 instance type. eksctl detects that you are launching a node group with an Inf1 instance type and will start your nodes using the EKS-optimized accelerated AMI (p. 162).

Note

You can't use IAM roles for service accounts (p. 336) with TensorFlow Serving.

```
eksctl create cluster \
    --name <inferentia> \
    --version <1.16> \
    --region <region-code> \
    --nodegroup-name <ng-inf1> \
    --node-type <inf1.2xlarge> \
    --nodes <2> \
    --nodes-min <1> \
    --nodes-max <4>
```

Note

Note the value of the following line of the output. It's used in a later (optional) step.

```
[#] adding identity "arn:aws:iam::<111122223333>:role/eksctl-<inferentia>-
<nodegroup-ng-in>-NodeInstanceRole-<FI7HIYS3BS09>" to auth ConfigMap
```

When launching a node group with Inf1 instances, eksctl automatically installs the AWS Neuron Kubernetes device plugin. This plugin advertises Neuron devices as a system resource to the Kubernetes scheduler, which can be requested by a container. In addition to the default Amazon EKS node IAM policies, the Amazon S3 read only access policy is added so that the sample application, covered in a later step, can load a trained model from Amazon S3.

2. Make sure that all pods have started correctly.

```
kubectl get pods -n kube-system
```

Output

```
STATUS
                                     READY
                                                      RESTARTS
                                                                 AGE
aws-node-kx2m8
                                     1/1
                                            Running
                                                     0
                                                                 5m
aws-node-q57pf
                                     1/1
                                            Running 0
                                                                 5m
coredns-86d5cbb4bd-56dz2
                                     1/1
                                            Running 0
                                                                 5m
coredns-86d5cbb4bd-d6n4z
                                     1/1
                                            Running 0
                                                                 5m
                                                     0
                                            Running
kube-proxy-75zx6
                                     1/1
                                                                 5m
kube-proxy-plkfq
                                     1/1
                                            Running
                                                     0
                                                                 5m
                                                     0
neuron-device-plugin-daemonset-6djhp
                                     1/1
                                            Running
                                                                 5m
neuron-device-plugin-daemonset-hwjsj
                                     1/1
                                            Running
                                                                 5m
```

(Optional) Create a Neuron TensorFlow Serving application image

Note

Neuron will soon be available pre-installed in AWS Deep Learning Containers. For updates, check AWS Neuron.

1. Create an Amazon ECR repository to store your application image.

```
aws ecr create-repository --repository-name tensorflow-model-server-neuron
```

Note the repositoryUri returned in the output for use in a later step.

Create a Dockerfile named Dockerfile.tf-serving with the following contents. The Dockerfile
contains the commands to build a Neuron optimized TensorFlow Serving application image. Neuron
TensorFlow Serving uses the same API as normal TensorFlow Serving. The only differences are that
the saved model must be compiled for Inferentia and the entry point is a different binary.

```
FROM amazonlinux:2

RUN yum install -y awscli

RUN echo $'[neuron] \n\
name=Neuron YUM Repository \n\
baseurl=https://yum.repos.neuron.amazonaws.com \n\
enabled=1' > /etc/yum.repos.d/neuron.repo

RUN rpm --import https://yum.repos.neuron.amazonaws.com/GPG-PUB-KEY-AMAZON-AWS-NEURON.PUB

RUN yum install -y tensorflow-model-server-neuron
```

3. Log your Docker client into your ECR repository.

```
aws ecr get-login-password \
--region <region-code> \
| docker login \
--username AWS \
--password-stdin <111122223333>.dkr.ecr.<region-code>.amazonaws.com
```

4. Build the Docker image and upload it to the Amazon ECR repository created in a previous step.

```
docker build . -f Dockerfile.tf-serving -t tensorflow-model-server-neuron docker tag tensorflow-model-server-neuron:latest <111122223333>.dkr.ecr.<region-code>.amazonaws.com/tensorflow-model-server-neuron:1.15.0 docker push <111122223333>.dkr.ecr.<region-code>.amazonaws.com/tensorflow-model-server-neuron:1.15.0
```

Note

If you receive permission related issues from Docker, then you may need to configure Docker for non-root user use. For more information, see Manage Docker as a non-root user in the Docker documentation.

(Optional) Deploy a TensorFlow Serving application image

A trained model must be compiled to an Inferentia target before it can be deployed on Inferentia instances. To continue, you will need a Neuron optimized TensorFlow model saved in Amazon S3. If you don't already have a saved model, then you can follow the tutorial in the AWS Neuron documentation to create a Neuron compatible BERT-Large model and upload it to S3. BERT is a popular machine learning technique used for understanding natural language tasks. For more information about compiling Neuron models, see The AWS Inferentia Chip With DLAMI in the AWS Deep Learning AMI Developer Guide.

The sample deployment manifest manages two containers: The Neuron runtime container image and the TensorFlow Serving application. For more information about the Neuron container image, see Tutorial: Neuron container tools on GitHub. The Neuron runtime runs as a sidecar container image and is used to interact with the Inferentia chips on your nodes. The two containers communicate over a Unix domain socket placed in a shared mounted volume. At start-up, the application image will fetch your model from Amazon S3, launch Neuron TensorFlow Serving with the saved model, and wait for prediction requests.

The number of Inferentia devices can be adjusted using the aws.amazon.com/neuron resource in the Neuron runtime container specification. The runtime expects 128 2-MB pages per Inferentia device, therefore, hugepages-2Mi has to be set to 256 $\, x$ the number of Inferentia devices. In order to access Inferentia devices, the Neuron runtime requires SYS_ADMIN and IPC_LOCK capabilities, however, the runtime drops these capabilities at initialization, before opening a gRPC socket.

Add the AmazonS3ReadOnlyAccess IAM policy to the node instance role that was created in step
1 of Create a cluster (p. 87). This is necessary so that the sample application can load a trained
model from Amazon S3.

```
aws iam attach-role-policy \
    --policy-arn arn:aws:iam::aws:policy/AmazonS3ReadOnlyAccess \
    --role-name eksctl-<inferentia>-<nodegroup-ng-in>-NodeInstanceRole-<FI7HIYS3BS09>
```

2. Create a file named bert_deployment.yaml with the contents below. Update <111122223333>, <region-code>, and <bert/saved_model> with your account ID, Region code, and saved model name and location. The model name is for identification purposes when a client makes a request to the TensorFlow server. This example uses a model name to match a sample BERT client script that will be used in a later step for sending prediction requests. You can also replace <1.0.7865.0> with a later version. For the latest version, see Neuron Runtime Release Notes on GitHub or enter the following command.

```
aws ecr list-images --repository-name neuron-rtd --registry-id 790709498068 --region us-west-2
```

```
kind: Deployment
apiVersion: apps/v1
metadata:
  name: <eks-neuron-test>
  labels:
    app: <eks-neuron-test>
    role: master
spec:
 replicas: <2>
  selector:
   matchLabels:
     app: <eks-neuron-test>
     role: master
  template:
    metadata:
      labels:
        app: <eks-neuron-test>
        role: master
    spec:
      volumes:
        - name: sock
          emptyDir: {}
      containers:
         name: <eks-neuron-test>
          image: <111122223333>.dkr.ecr.<region-code>.amazonaws.com/tensorflow-model-
server-neuron:1.15.0
          command:
            - /usr/local/bin/tensorflow_model_server_neuron
```

```
args:
           - --port=9000
            - --rest_api_port=8500
            - --model_name=bert_mrpc_hc_gelus_b4_124_0926_02
            - --model_base_path=s3://<bert/saved_model>
          ports:
            - containerPort: 8500
            - containerPort: 9000
          imagePullPolicy: IfNotPresent
          env:
            - name: AWS_REGION
             value: "<region-code>"
            - name: S3_USE_HTTPS
             value: "1"
            - name: S3_VERIFY_SSL
             value: "0"
            - name: AWS_LOG_LEVEL
             value: "3"
            - name: NEURON RTD ADDRESS
             value: unix:/sock/neuron.sock
          resources:
            limits:
             cpu: 4
             memory: 4Gi
            requests:
             cpu: "1"
             memory: 1Gi
          volumeMounts:
            - name: sock
             mountPath: /sock
        - name: neuron-rtd
          image: 790709498068.dkr.ecr.<region-code>.amazonaws.com/neuron-
rtd:<1.0.7865.0>
          securityContext:
            capabilities:
              add:
                - SYS_ADMIN
                - IPC LOCK
          volumeMounts:
            - name: sock
             mountPath: /sock
          resources:
            limits:
             hugepages-2Mi: 256Mi
              aws.amazon.com/neuron: 1
            requests:
             memory: 1024Mi
```

3. Deploy the model.

```
kubectl apply -f bert_deployment.yaml
```

4. Create a file named bert_service.yaml with the following contents. The HTTP and gRPC ports are opened for accepting prediction requests.

```
kind: Service
apiVersion: v1
metadata:
  name: <eks-neuron-test>
  labels:
    app: <eks-neuron-test>
spec:
  type: ClusterIP
  ports:
```

Amazon EKS User Guide (Optional) Make predictions against your TensorFlow Serving service

```
- name: http-tf-serving
  port: 8500
  targetPort: 8500
- name: grpc-tf-serving
  port: 9000
  targetPort: 9000
selector:
  app: <eks-neuron-test>
  role: master
```

5. Create a Kubernetes service for your TensorFlow model Serving application.

```
kubectl apply -f bert_service.yaml
```

(Optional) Make predictions against your TensorFlow Serving service

1. To test locally, forward the gRPC port to the eks-neuron-test service.

```
kubectl port-forward svc/eks-neuron-test 9000:9000 &
```

2. Download the sample BERT client from the Neuron GitHub repository.

```
curl https://raw.githubusercontent.com/aws/aws-neuron-sdk/master/src/examples/
tensorflow/k8s_bert_demo/bert_client.py > bert_client.py
```

3. Run the script to submit predictions to your service.

```
python3 bert_client.py
```

Output

```
Inference successful: 0
Inference successful: 1
Inference successful: 2
Inference successful: 3
Inference successful: 4
Inference successful: 5
Inference successful: 6
Inference successful: 7
Inference successful: 8
Inference successful: 9
Inference successful: 91
Inference successful: 92
Inference successful: 93
Inference successful: 94
Inference successful: 95
Inference successful: 96
Inference successful: 97
Inference successful: 98
Inference successful: 99
Ran 100 inferences successfully. Latency
```

Viewing API server flags

You can use the control plane logging feature for Amazon EKS clusters to view the API server flags that were enabled when a cluster was created. For more information, see Amazon EKS control plane logging (p. 66). This topic shows you how to view the API server flags for an Amazon EKS cluster in the Amazon CloudWatch console.

When a cluster is first created, the initial API server logs include the flags that were used to start the API server. If you enable API server logs when you launch the cluster, or shortly thereafter, these logs are sent to CloudWatch Logs and you can view them there.

To view API server flags for a cluster

- 1. If you have not already done so, enable API server logs for your Amazon EKS cluster.
 - a. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
 - b. Choose the name of the cluster to display your cluster information.
 - c. Select the Configuration tab. On the Logging tab, choose Update.
 - d. For API server, make sure that the log type is Enabled.
 - e. Choose Update to finish.
- 2. In the Amazon EKS console, scroll down to the **Logging** section of the cluster detail page. Choose the link under **CloudWatch** to open the CloudWatch console page for your cluster's logs.
- In the list of log streams, find the earliest version of the kube-apiserver-<example-ID-288ec988b77a59d70ec77> log stream. Use the Last Event Time column to determine the log stream ages.
- 4. Scroll up to the earliest events (the beginning of the log stream). You should see the initial API server flags for the cluster.

Note

If you don't see the API server logs at the beginning of the log stream, then it is likely that the API server log file was rotated on the server before you enabled API server logging on the server. Any log files that are rotated before API server logging is enabled cannot be exported to CloudWatch.

However, you can create a new cluster with the same Kubernetes version and enable the API server logging when you create the cluster. Clusters with the same platform version have the same flags enabled, so your flags should match the new cluster's flags. When you finish viewing the flags for the new cluster in CloudWatch, you can delete the new cluster.

Private clusters

This topic describes how to deploy a private cluster without outbound internet access. If you're not familiar with Amazon EKS networking, see De-mystifying cluster networking for Amazon EKS worker nodes.

Requirements

The following requirements must be met to run Amazon EKS in a private cluster without outbound internet access.

 A container image must be in or copied to Amazon Elastic Container Registry (Amazon ECR) or to a registry inside the VPC to be pulled. For more information, see Creating local copies of container images (p. 93).

Amazon EKS User Guide Considerations

- Endpoint private access is required for nodes to register with the cluster endpoint. Endpoint public access is optional. For more information, see Amazon EKS cluster endpoint access control (p. 56).
- You may need to include the VPC endpoints found at VPC endpoints for private clusters (p. 94).
- You must include the following text to the bootstrap arguments when launching self-managed nodes.
 This text bypasses the Amazon EKS introspection and does not require access to the Amazon EKS API
 from within the VPC. Replace <cluster-endpoint> and <cluster-certificate-authority> with the values
 from your Amazon EKS cluster.

```
--apiserver-endpoint <cluster-endpoint> --b64-cluster-ca <cluster-certificate-authority>
```

• The aws-auth ConfigMap must be created from within the VPC. For more information about create the aws-auth ConfigMap, see Managing users or IAM roles for your cluster (p. 285).

Considerations

Here are some things to consider when running Amazon EKS in a private cluster without outbound internet access.

- AWS X-Ray is not supported with private clusters.
- Amazon CloudWatch Logs is supported with private clusters, but you must use an Amazon CloudWatch Logs VPC endpoint. For more information, see VPC endpoints for private clusters (p. 94).
- Self-managed and managed nodes (p. 116) are supported. The instances for nodes must have access to the VPC endpoints. If you create a managed node group, the VPC endpoint security group must allow the CIDR for the subnets, or you must add the created node security group to the VPC endpoint security group.
- IAM roles for service accounts (p. 336) is supported. You must include the STS VPC endpoint. For more information, see VPC endpoints for private clusters (p. 94).
- The Amazon EBS CSI driver (p. 181) is supported. Before deploying, the kustomization.yaml file must be changed to set the container images to use the same Region as the Amazon EKS cluster.
- The Amazon EFS CSI driver (p. 185) is supported. Before deploying, the kustomization.yaml file must be changed to set the container images to use the same Region as the Amazon EKS cluster.
- The Amazon FSx for Lustre CSI driver (p. 190) is not supported.
- AWS Fargate (p. 136) is supported with private clusters. You must include the STS VPC endpoint. For
 more information, see VPC endpoints for private clusters (p. 94). You can use the AWS load balancer
 controller to deploy AWS Application Load Balancers and Network Load Balancers with. The controller
 supports network load balancers with IP targets, which are required for use with Fargate. For more
 information, see the section called "Application load balancing" (p. 267) and the section called "Load
 balancer IP targets" (p. 262).
- App Mesh is supported with private clusters when you use the App Mesh Envoy VPC endpoint. For more information, see VPC endpoints for private clusters (p. 94).
 - The App Mesh sidecar injector for Kubernetes is supported. For more information, see App Mesh sidecar injector on GitHub.
 - The App Mesh controller for Kubernetes is not supported. For more information, see App Mesh controller on GitHub.

Creating local copies of container images

Because a private cluster has no outbound internet access, container images cannot be pulled from external sources such as Docker Hub. Instead, container images must be copied locally to Amazon ECR or to an alternative registry accessible in the VPC. A container image can be copied to Amazon ECR from outside the private VPC. The private cluster accesses the Amazon ECR repository using the Amazon ECR

Amazon EKS User Guide VPC endpoints for private clusters

VPC endpoints. You must have Docker and the AWS CLI installed on the workstation that you use to create the local copy.

To create a local copy of a container image

- 1. Create an Amazon ECR repository. For more information, see Creating a repository.
- 2. Pull the container image from the external registry using docker pull.
- 3. Tag your image with the Amazon ECR registry, repository, and optional image tag name combination using docker tag.
- 4. Authenticate to the registry. For more information, see Registry authentication.
- 5. Push the image to Amazon ECR using docker push.

Note

Be sure to update your resource configuration to use the new image location.

The following example pulls the amazon/aws-node-termination-handler image, using tag v1.3.1-linux-amd64, from Docker Hub and creates a local copy in Amazon ECR.

aws ecr create-repository --repository-name amazon/aws-node-termination-handler docker pull amazon/aws-node-termination-handler:v1.3.1-linux-amd64 docker tag amazon/aws-node-termination-handler <111122223333>.dkr.ecr.<region-code>.amazonaws.com/amazon/aws-node-termination-handler:v1.3.1-linux-amd64 aws ecr get-login-password --region <region-code> | docker login --username AWS --password-stdin <111122223333>.dkr.ecr.<region-code>.amazonaws.com docker push <111122223333>.dkr.ecr.<region-code>.amazonaws.com/amazon/aws-node-termination-handler:v1.3.1-linux-amd64

VPC endpoints for private clusters

The following VPC endpoints may be required.

- com.amazonaws.<region>.ec2
- com.amazonaws.<region>.ecr.api
- com.amazonaws.<region>.ecr.dkr
- com.amazonaws.<region>.s3 For pulling container images
- com.amazonaws.<region>.logs For CloudWatch Logs
- com.amazonaws.<region>.sts If using AWS Fargate or IAM roles for service accounts
- com.amazonaws.<region>.elasticloadbalancing If using Application Load Balancers
- com.amazonaws.<region>.autoscaling If using Cluster Autoscaler
- com.amazonaws.<region>.appmesh-envoy-management If using App Mesh

Amazon EKS nodes

Your Amazon EKS cluster can schedule pods on any combination of Self-managed nodes (p. 116), Amazon EKS Managed node groups (p. 100), and AWS Fargate (p. 136). The following table provides several criteria to evaluate when deciding which options best meets your requirements. We recommend reviewing this page often because the data in this table changes frequently as new capabilities are introduced to Amazon EKS. To view details about any existing nodes deployed in your cluster, see View nodes (p. 98).

Criteria	EKS managed node groups	Self-managed nodes	AWS Fargate
Can be deployed to AWS Outposts	No	Yes – For more information, see Amazon EKS on AWS Outposts (p. 361).	No
Can be deployed to AWS Local Zones	No	Yes – For more information, see Amazon EKS on AWS Local Zones (p. 363).	No
Can run containers that require Windows	No	Yes (p. 79) – Your cluster still requires at least one (two recommended for availability) Linux node though.	No
Can run containers that require Linux	Yes	Yes	Yes
Can run workloads that require the Inferentia chip	No	Yes (p. 86) – Amazon Linux only	No
Can run workloads that require a GPU	Yes (p. 158) – Amazon Linux nodes only	Yes (p. 158) – Amazon Linux only	No
Can run workloads that require Arm processors	Yes (p. 160)	Yes (p. 160)	No
Can run AWS Bottlerocket	No	Yes (p. 121)	No – There is no node.
Pods share a kernel runtime environment with other pods	Yes – All of your pods on each of your nodes	Yes – All of your pods on each of your nodes	No – Each pod has a dedicated kernel
Pods share CPU, memory, storage, and network resources with other pods.	Yes – Can result in unused resources on each node	Yes – Can result in unused resources on each node	No – Each pod has dedicated resources and can be sized

Criteria	EKS managed node groups	Self-managed nodes	AWS Fargate
			independently to maximize resource utilization.
Pods can use more hardware and memory than requested in pod specs	Yes – If the pod requires more resources than requested, and resources are available on the node, the pod can use additional resources.	Yes – If the pod requires more resources than requested, and resources are available on the node, the pod can use additional resources.	No – The pod can be re-deployed using a larger vCPU and memory configuration though.
Must deploy and manage Amazon EC2 instances	Yes (p. 103) – automated through Amazon EKS if you deployed an Amazon EKS optimized AMI. If you deployed a custom AMI, then you must update the instance manually.	Yes – Manual configuration or using Amazon EKS provided AWS CloudFormation templates to deploy Linux (x86) (p. 116), Linux (Arm) (p. 160), or Windows (p. 79) nodes.	No
Must secure, maintain, and patch the operating system of Amazon EC2 instances	Yes	Yes	No
Can provide bootstrap arguments at deployment of a node, such as extra kubelet arguments.	Yes – Using a launch template (p. 111) with a custom AMI	Yes – For more information, view the bootstrap script usage information on GitHub.	No – There is no node.
Can assign IP addresses to pods from a different CIDR block than the IP address assigned to the node.	Yes – Using a launch template (p. 111) with a custom AMI	Yes, using CNI custom networking (p. 224)	No – There is no node.
Can SSH into node	Yes	Yes	No – There is no node host operating system to SSH to.
Can deploy your own custom AMI to nodes	Yes – Using a launch template (p. 111)	Yes	No – You don't manage nodes.
Can deploy your own custom CNI to nodes	Yes – Using a launch template (p. 111) with a custom AMI	Yes	No – You don't manage nodes.

Criteria	EKS managed node groups	Self-managed nodes	AWS Fargate
Must update node AMI yourself	Yes – If you deployed an Amazon EKS optimized AMI, then you're notified in the Amazon EKS console when updates are available and can perform the update with one click in the console. If you deployed a custom AMI, then you're not notified in the Amazon EKS console when updates are available and must perform the update yourself.	Yes - Using tools other than the Amazon EKS console, because self-managed nodes can't be managed with the Amazon EKS console.	No – You don't manage nodes.
Must update node Kubernetes version yourself	Yes – If you deployed an Amazon EKS optimized AMI, then you're notified in the Amazon EKS console when updates are available and can perform the update with one click in the console. If you deployed a custom AMI, then you're not notified in the Amazon EKS console when updates are available and must perform the update yourself.	Yes – Using tools other than the Amazon EKS console, because self-managed nodes can't be managed with the Amazon EKS console.	No – You don't manage nodes.
Can use Amazon EBS storage with pods	Yes (p. 181)	Yes (p. 181)	No
Can use Amazon EFS storage with pods	Yes (p. 185)	Yes (p. 185)	Yes (p. 185)
Can use Amazon FSx for Lustre storage with pods	Yes (p. 190)	Yes (p. 190)	No

Amazon EKS User Guide View nodes

Criteria	EKS managed node groups	Self-managed nodes	AWS Fargate
Can use Network Load Balancer for services	Yes (p. 260)	Yes (p. 260)	Yes, when using the the section called "Load balancer – IP targets" (p. 262)
Pods can run in a public subnet	Yes	Yes	No
Can assign different VPC security groups to individual pods	Yes (p. 213) – Linux nodes only	Yes (p. 213) – Linux nodes only	No
Can run Kubernetes DaemonSets	Yes	Yes	No
Support HostPort and HostNetwork in the pod manifest	Yes	Yes	No
Region availability	All Amazon EKS supported regions	All Amazon EKS supported regions	Some Amazon EKS supported regions (p. 136)
Pricing	Cost of Amazon EC2 instance that runs multiple pods. For more information, see Amazon EC2 pricing.	Cost of Amazon EC2 instance that runs multiple pods. For more information, see Amazon EC2 pricing.	Cost of an individual Fargate memory and CPU configuration. Each pod has its own cost. For more information, see AWS Fargate pricing.

View nodes

The Amazon EKS console shows information about all of your cluster's nodes, including Amazon EKS managed nodes, self-managed nodes, and Fargate. Nodes represent the compute resources provisioned for your cluster from the perspective of the Kubernetes API. For more information, see Nodes in the Kubernetes documentation. To learn more about the different types of Amazon EKS nodes that you can deploy your workloads (p. 246) to, see *Nodes* (p. 95).

Prerequisites

The IAM user or IAM role that you sign into the AWS Management Console with must meet the following requirements.

- Have the eks: AccessKubernetesApi and other necessary IAM permissions to view nodes attached
 to it. For an example IAM policy, see the section called "View nodes and workloads for all clusters in
 the AWS Management Console" (p. 324).
- Is mapped to Kubernetes user or group in the aws-auth configmap. For more information, see the section called "Managing users or IAM roles for your cluster" (p. 285).
- The Kubernetes user or group that the IAM user or role is mapped to in the configmap must be bound to a Kubernetes role or clusterrole that has permissions to view the resources in the namespaces that you want to view. For more information, see Using RBAC Authorization in the Kubernetes documentation. You can download the following example manifests that create a clusterrole and clusterrolebinding or a role and rolebinding:

Amazon EKS User Guide View nodes

- View Kubernetes resources in all namespaces The group name in the file is eks-console-dashboard-full-access-group, which is the group that your IAM user or role needs to be mapped to in the aws-auth configmap. You can change the name of the group before applying it to your cluster, if desired, and then map your IAM user or role to that group in the configmap. To download the file, select the appropriate link for the Region that your cluster is in.
 - · All Regions other than Beijing and Ningxia China
 - · Beijing and Ningxia China Regions
- View Kubernetes resources in a specific namespace The namespace in this file is default, so if you want to specify a different namespace, edit the file before applying it to your cluster. The group name in the file is eks-console-dashboard-restricted-access-group, which is the group that your IAM user or role needs to be mapped to in the aws-auth configmap. You can change the name of the group before applying it to your cluster, if desired, and then map your IAM user or role to that group in the configmap. To download the file, select the appropriate link for the Region that your cluster is in.
 - · All Regions other than Beijing and Ningxia China
 - · Beijing and Ningxia China Regions

To view nodes using the AWS Management Console

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. In the left navigation panel, select **Clusters**, and then in the **Clusters** list, select the cluster that you want to view compute resources for.
- 3. On the **Overview** tab, you see a list of all compute **Nodes** for your cluster and the nodes' status.

Important

If you can't see any **Nodes** on the **Overview** tab, or you see a **Your current user or role does not have access to Kubernetes objects on this EKS cluster** error, see the prerequisites for this topic. If you don't resolve the issue, you can still view and manage your Amazon EKS cluster on the **Configuration** tab, but you won't see self-managed nodes or some of the information that you see for managed nodes and Fargate under **Nodes**.

Note

Each pod that runs on Fargate is registered as a separate Kubernetes node within the cluster. This is because Fargate runs each pod in an isolated compute environment and independently connects to the cluster control plane. For more information, see the section called "AWS Fargate" (p. 136).

- 4. In the **Nodes** list, you see a list of all of the managed, self-managed, and Fargate nodes for your cluster. Selecting the link for one of the nodes provides the following information about the node:
 - The Amazon EC2 Instance type, Kernel version, Kubelet version, Container runtime, OS and OS image for managed and self-managed nodes.
 - Deep links to the Amazon EC2 console and the Amazon EKS managed node group (if applicable) for the node.
 - The **Resource** allocation, which shows baseline and allocatable capacity for the node.
 - **Conditions** describe the current operational status of the node. This is useful information for troubleshooting issues on the node.

Conditions are reported back to the Kubernetes control plane by the Kubernetes agent kubelet that runs locally on each node. For more information, see kubelet in the Kubernetes documentation. Conditions on the node are always reported as part of the node detail and the **Status** of each condition along with its **Message** indicates the health of the node for that condition. The following common conditions are reported for a node:

• Ready – This condition is TRUE if the node is healthy and can accept pods. The condition is FALSE if the node is not ready and will not accept pods. UNKNOWN indicates that the

Kubernetes control plane has not recently received a heartbeat signal from the node. The heartbeat timeout period is set to the Kubernetes default of 40 seconds for Amazon EKS clusters.

- Memory pressure This condition is FALSE under normal operation and TRUE if node memory is low.
- **Disk pressure** This condition is **FALSE** under normal operation and **TRUE** if disk capacity for the node is low.
- PID pressure This condition is FALSE under normal operation and TRUE if there are too many
 processes running on the node. On the node, each container runs as a process with a unique
 Process ID, or PID.
- NetworkUnavailable This condition is FALSE, or not present, under normal operation. If TRUE, the network for the node is not properly configured.
- The Kubernetes **Labels** and **Annotations** assigned to the node. These could have been assigned by you, by Kubernetes, or by the Amazon EKS API when the node was created. These values can be used by your workloads for scheduling pods.

Managed node groups

Amazon EKS managed node groups automate the provisioning and lifecycle management of nodes (Amazon EC2 instances) for Amazon EKS Kubernetes clusters.

With Amazon EKS managed node groups, you don't need to separately provision or register the Amazon EC2 instances that provide compute capacity to run your Kubernetes applications. You can create, update, or terminate nodes for your cluster with a single operation. Nodes run using the latest Amazon EKS optimized AMIs in your AWS account. Node updates and terminations gracefully drain nodes to ensure that your applications stay available.

All managed nodes are provisioned as part of an Amazon EC2 Auto Scaling group that's managed for you by Amazon EKS. All resources including the instances and Auto Scaling groups run within your AWS account. Each node group uses the Amazon EKS optimized Amazon Linux 2 AMI and can run across multiple Availability Zones that you define.

You can add a managed node group to new or existing clusters using the Amazon EKS console, eksctl, AWS CLI; AWS API, or infrastructure as code tools including AWS CloudFormation. Nodes launched as part of a managed node group are automatically tagged for auto-discovery by the Kubernetes cluster autoscaler. You can use the node group to apply Kubernetes labels to nodes and update them at any time.

There are no additional costs to use Amazon EKS managed node groups, you only pay for the AWS resources you provision. These include Amazon EC2 instances, Amazon EBS volumes, Amazon EKS cluster hours, and any other AWS infrastructure. There are no minimum fees and no upfront commitments.

To get started with a new Amazon EKS cluster and managed node group, see Getting started with the AWS Management Console (p. 15).

To add a managed node group to an existing cluster, see Creating a managed node group (p. 103).

Managed node groups concepts

- Amazon EKS managed node groups create and manage Amazon EC2 instances for you.
- All managed nodes are provisioned as part of an Amazon EC2 Auto Scaling group that's managed for you by Amazon EKS. Moreover, all resources including Amazon EC2 instances and Auto Scaling groups run within your AWS account.

Amazon EKS User Guide Managed node group capacity types

- A managed node group's Auto Scaling group spans all of the subnets that you specify when you create the group.
- Amazon EKS tags managed node group resources so that they are configured to use the Kubernetes Cluster Autoscaler (p. 61).

Important

If you are running a stateful application across multiple Availability Zones that is backed by Amazon EBS volumes and using the Kubernetes Cluster Autoscaler (p. 61), you should configure multiple node groups, each scoped to a single Availability Zone. In addition, you should enable the --balance-similar-node-groups feature.

- By default, instances in a managed node group use the latest version of the Amazon EKS optimized Amazon Linux 2 AMI for its cluster's Kubernetes version. You can choose between standard and GPU variants of the Amazon EKS optimized Amazon Linux 2 AMI. If you deploy using a launch template, you can also use a custom AMI. For more information, see Launch template support (p. 111).
- Amazon EKS follows the shared responsibility model for CVEs and security patches on managed node groups. When managed nodes run an Amazon EKS optimized AMI, Amazon EKS is responsible for building patched versions of the AMI when bugs or issues are reported. We can publish a fix. However, you're responsible for deploying these patched AMI versions to your managed node groups. When managed nodes run a custom AMI, you're responsible for building patched versions of the AMI when bugs or issues are reported and then deploying the AMI. For more information, see Updating a managed node group (p. 108).
- Amazon EKS managed node groups can be launched in both public and private subnets. If you launch a managed node group in a public subnet on or after April 22, 2020, the subnet must have MapPublicIpOnLaunch set to true for the instances to successfully join a cluster. If the public subnet was created using eksctl or the Amazon EKS vended AWS CloudFormation templates (p. 197) on or after March 26, 2020, then this setting is already set to true. If the public subnets were created before March 26, 2020, then you need to change the setting manually. For more information, see Modifying the public IPv4 addressing attribute for your subnet.
- When using VPC endpoints in private subnets, you must create endpoints for com.amazonaws.region.ecr.api, com.amazonaws.region.ecr.dkr, and a gateway endpoint for Amazon S3. For more information, see Amazon ECR interface VPC endpoints (AWS PrivateLink).
- Managed node groups can't be deployed to nodes on AWS Outposts (p. 361) or to nodes deployed in AWS Wavelength or AWS Local Zones.
- You can create multiple managed node groups within a single cluster. For example, you can create one node group with the standard Amazon EKS optimized Amazon Linux 2 AMI for some workloads and another with the GPU variant for workloads that require GPU support.
- If your managed node group encounters a health issue, Amazon EKS returns an error message to help you to diagnose the issue. For more information, see Managed node group errors (p. 367).
- Amazon EKS adds Kubernetes labels to managed node group instances. These Amazon EKS provided labels are prefixed with eks.amazonaws.com.
- Amazon EKS automatically drains nodes using the Kubernetes API during terminations or updates.
 Updates respect the pod disruption budgets that you set for your pods.
- There are no additional costs to use Amazon EKS managed node groups. You only pay for the AWS resources that you provision.

Managed node group capacity types

When creating a managed node group, you can choose either the On-Demand or Spot capacity type. Amazon EKS deploys a managed node group with an Amazon EC2 Auto Scaling Group that either contains only On-Demand or only Amazon EC2 Spot Instances. You can schedule pods for fault tolerant applications to Spot managed node groups, and fault intolerant applications to On-Demand node groups within a single Kubernetes cluster. By default, a managed node group deploys On-Demand Amazon EC2 instances.

Amazon EKS User Guide Managed node group capacity types

On-Demand

With On-Demand Instances, you pay for compute capacity by the second, with no long-term commitments.

How it works

By default, if you don't specify a **Capacity Type**, the managed node group is provisioned with On-Demand Instances. A managed node group configures an Amazon EC2 Auto Scaling group on your behalf with the following settings applied:

- The allocation strategy to provision On-Demand capacity is set to prioritized. Managed node groups use the order of instance types passed in the API to determine which instance type to use first when fulfilling On-Demand capacity. For example, you might specify three instance types in the following order: c5.large, c4.large, and c3.large. When your On-Demand Instances are launched, the managed node group fulfills On-Demand capacity by starting with c5.large, then c4.large, and then c3.large. For more information, see Amazon EC2 Auto Scaling group in the Amazon EC2 Auto Scaling User Guide.
- Amazon EKS adds the following Kubernetes label to all nodes in your managed node group that specifies the capacity type: eks.amazonaws.com/capacityType: ON_DEMAND. You can use this label to schedule stateful or fault intolerant applications on On-Demand nodes.

Spot

Amazon EC2 Spot Instances are spare Amazon EC2 capacity that offers steep discounts off of On-Demand prices. Amazon EC2 Spot Instances can be interrupted with a two-minute interruption notice when EC2 needs the capacity back. For more information, see Spot Instances in the Amazon EC2 User Guide for Linux Instances. You can configure a managed node group with Amazon EC2 Spot Instances to optimize costs for the compute nodes running in your Amazon EKS cluster.

How it works

To use Spot Instances inside a managed node group, you need to create a managed node group by setting the capacity type as spot. A managed node group configures an Amazon EC2 Auto Scaling group on your behalf with the following Spot best practices applied:

- The allocation strategy to provision Spot capacity is set to capacity-optimized to ensure that your Spot nodes are provisioned in the optimal Spot capacity pools. To increase the number of Spot capacity pools available for allocating capacity from, we recommend that you configure a managed node group to use multiple instance types.
- Amazon EC2 Spot Capacity Rebalancing is enabled so that Amazon EKS can gracefully drain and rebalance your Spot nodes to minimize application disruption when a Spot node is at elevated risk of interruption. For more information, see Amazon EC2 Auto Scaling Capacity Rebalancing in the Amazon EC2 Auto Scaling User Guide.
 - When a Spot node receives a rebalance recommendation, Amazon EKS automatically attempts to launch a new replacement Spot node and waits until it successfully joins the cluster.
 - When a replacement Spot node is bootstrapped and in the Ready state on Kubernetes, Amazon EKS
 cordons and drains the Spot node that received the rebalance recommendation. Cordoning the Spot
 node ensures that the service controller doesn't send any new requests to this Spot node. It also
 removes it from its list of healthy, active Spot nodes. Draining the Spot node ensures that running
 pods are evicted gracefully.
 - If a Spot two-minute interruption notice arrives before the replacement Spot node is in a Ready state, Amazon EKS starts draining the Spot node that received the rebalance recommendation.
- Amazon EKS adds the following Kubernetes label to all nodes in your managed node group that specifies the capacity type: eks.amazonaws.com/capacityType: SPOT. You can use this label to schedule fault tolerant applications on Spot nodes.

Considerations for selecting a capacity type

When deciding whether to deploy a node group with On-Demand or Spot capacity, you should consider the following conditions:

- Spot Instances are a good fit for stateless, fault-tolerant, flexible applications such as batch and machine learning training workloads, big data ETLs such as Apache Spark, queue processing applications, and stateless API endpoints. Because Spot is spare Amazon EC2 capacity, which can change over time, we recommend that you use Spot capacity for interruption-tolerant workloads that can tolerate periods where the required capacity is not available.
- We recommend that you use On-Demand for applications that are fault intolerant, including cluster management tools such as monitoring and operational tools, deployments that require StatefulSets, and stateful applications, such as databases.
- To maximize the availability of your applications while using Spot Instances, we recommend that you configure a Spot managed node group to use multiple instance types. We recommend applying the following rules when using multiple instance types:
 - Within a managed node group, if you're using the the section called "Cluster Autoscaler" (p. 61), we recommend using a flexible set of instance types with the same amount of vCPU and memory resources to ensure that the nodes in your cluster scale as expected. For example, if you need four vCPUs and eight GiB memory, we recommend that you use c3.xlarge, c4.xlarge, c5.xlarge, c5d.xlarge, c5n.xlarge, or other similar instance types.
 - To enhance application availability, we recommend deploying multiple Spot managed node groups, each using a flexible set of instance types that have the same vCPU and memory resources. For example, if you need 4 vCPUs and 8 GiB memory, we recommend that you create one managed node group with c3.xlarge, c4.xlarge, c5.xlarge, c5d.xlarge, c5a.xlarge, c5n.xlarge, or other similar instance types, and a second managed node group with m3.xlarge, m4.xlarge, m5.xlarge, m5d.xlarge, m5a.xlarge, m5n.xlarge or other similar instance types.
 - When deploying your node group with the Spot capacity type that's using a custom launch template, use the API to pass multiple instance types instead of passing a single instance type through the launch template. For more information about deploying a node group using a launch template, see the section called "Launch template support" (p. 111).

Creating a managed node group

This topic describes how you can launch an Amazon EKS managed node group of Linux nodes that register with your Amazon EKS cluster. After the nodes join the cluster, you can deploy Kubernetes applications to them.

If this is your first time launching an Amazon EKS managed node group, we recommend that you follow one of our Getting started with Amazon EKS (p. 4) guides instead. The guides provide walkthroughs for creating an Amazon EKS cluster with nodes.

Important

Amazon EKS nodes are standard Amazon EC2 instances. You're billed based on the normal Amazon EC2 prices. For more information, see Amazon EC2 Pricing.

You can create a managed node group with eksctl (p. 103) or the AWS Management Console (p. 105).

To create a managed node group with eksctl

This procedure requires eksctl version 0.33.0 or later. You can check your version with the following command:

eksctl version

Amazon EKS User Guide Creating a managed node group

For more information on installing or upgrading eksct1, see Installing or upgrading eksct1 (p. 298).

Do not use eksctl to create a cluster or nodes in an AWS Region where you have AWS Outposts, AWS Wavelength, or AWS Local Zones enabled. Create a cluster and self-managed nodes using the Amazon EC2 API or AWS CloudFormation instead. For more information, see To launch self-managed Linux nodes using the AWS Management Console (p. 118) and To launch self-managed Windows nodes using the AWS Management Console (p. 125).

You can create your node group with or without a launch template. A launch template allows for greater customization of a node group, to include deploying a custom AMI. Complete one of the following steps. If you plan to use Security groups for pods (p. 213), then make sure to specify a supported Amazon EC2 instance type. For more information, see Amazon EC2 supported instances and branch network interfaces (p. 217). If specifying an Arm Amazon EC2 instance type, then review the considerations in Amazon EKS optimized Arm Amazon Linux AMIs (p. 160) before deploying.

- 1. (Optional) If the AmazonEKS_CNI_Policy managed IAM policy is attached to your the section called "Node IAM role" (p. 332), we recommend assigning it to an IAM role that you associate to the Kubernetes aws-node service account instead. For more information, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).
- Create your managed node group without a launch template with the following eksctl command, replacing the <example values> (including the <>) with your own values. When you don't specify your own launch template, eksctl creates a default Amazon EC2 launch template in your account and deploys the node group using a launch template that it creates based on options you specify.

If you plan to assign IAM roles to all of your Kubernetes service accounts so that pods only have the minimum permissions that they need, and no pods in the cluster require access to the Amazon EC2 instance metadata service (IMDS) for other reasons, such as retrieving the current Region, then we recommend blocking pod access to IMDS. For more information, see the section called "IAM roles for service accounts" (p. 336) and the section called "Restricting access to the instance profile" (p. 349). If you want to block pod access to IMDS, then add the --disable-pod-imds option to the following command.

```
eksctl create nodegroup \
    --cluster <my-cluster> \
    --region <us-west-2> \
    --name <my-mng> \
    --node-type <m5.large> \
    --nodes <3> \
    --nodes-min <2> \
    --nodes-max <4> \
    --ssh-access \
    --ssh-public-key <my-public-key.pub> \
    --managed
```

- 3. Create your managed node group with a launch template. The launch template must already exist and must meet the requirements specified in Launch template configuration basics (p. 112). If you plan to assign IAM roles to all of your Kubernetes service accounts so that pods only have the minimum permissions that they need, and no pods in the cluster require access to the Amazon EC2 instance metadata service (IMDS) for other reasons, such as retrieving the current Region, then we recommend blocking pod access to IMDS. For more information, see the section called "IAM roles for service accounts" (p. 336) and the section called "Restricting access to the instance profile" (p. 349). If you want to block pod access to IMDS, then specify the necessary settings in the launch template.
 - a. Create a file with the following contents, replacing the <example values> (including <>) with your own values. Several settings that you specify when deploying without a launch template are moved into the launch template. If you don't specify a version, the template's default version is used.

Amazon EKS User Guide Creating a managed node group

```
apiVersion: eksctl.io/v1alpha5
kind: ClusterConfig
metadata:
  name: <my-cluster>
  region: <region-code>
managedNodeGroups:
  - name: <node-group-lt>
  launchTemplate:
    id: lt-<id>
      version: "<1>"
```

b. Deploy the nodegroup with the following command.

```
eksctl create nodegroup --config-file <filename-you-used-in-previous-step>
```

To create your managed node group using the AWS Management Console

- Wait for your cluster status to show as ACTIVE. You cannot create a managed node group for a cluster that is not yet ACTIVE.
- 2. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- Choose the name of the cluster that you want to create your managed node group in.
- 4. Select the Configuration tab.
- 5. On the Configuration tab, select the Compute tab, and then choose Add Node Group.
- 6. On the Configure node group page, fill out the parameters accordingly, and then choose Next.
 - Name Enter a unique name for your managed node group.
 - Node IAM role name Choose the node instance role to use with your node group. For more
 information, see Amazon EKS node IAM role (p. 332).

Important

We recommend using a role that is not currently in use by any self-managed node group, or that you plan to use with a new self-managed node group. For more information, see Deleting a managed node group (p. 115).

- Use launch template (Optional) Choose if you want to use an existing launch template and then select a Launch template version (Optional). If you don't select a version, then Amazon EKS uses the template's default version. Launch templates allow for more customization of your node group, including allowing you to deploy a custom AMI. The launch template must meet the requirements in Launch template support (p. 111). If you don't use your own launch template, the Amazon EKS API creates a default Amazon EC2 launch template in your account and deploys the node group using the default launch template. If you implement IAM roles for service accounts (p. 336), assign necessary permissions directly to all pods that require access to AWS services, and no pods in your cluster require access to IMDS for other reasons, such as retrieving the current Region, then you can also disable access to IMDS for pods that don't use host networking in a launch template. For more information, see the section called "Restricting access to the instance profile" (p. 349).
- **Kubernetes labels** (Optional) You can choose to apply Kubernetes labels to the nodes in your managed node group.
- Tags (Optional) You can choose to tag your Amazon EKS managed node group. These tags do
 not propagate to other resources in the node group, such as Auto Scaling groups or instances. For
 more information, see Tagging your Amazon EKS resources (p. 309).
- On the Set compute and scaling configuration page, fill out the parameters accordingly, and then choose Next.

Amazon EKS User Guide Creating a managed node group

Node group compute configuration

• AMI type – Choose Amazon Linux 2 (AL2_x86_64) for non-GPU instances, Amazon Linux 2 GPU Enabled (AL2_x86_64_GPU) for GPU instances, or Amazon Linux 2 (AL2_ARM_64) for Arm.

If you are deploying Arm instances, be sure to review the considerations in the section called "Arm" (p. 160) before deploying.

If you specified a launch template on the previous page, and specified an AMI in the launch template, then you cannot select a value. The value from the template is displayed. The AMI specified in the template must meet the requirements in Using a custom AMI (p. 114).

- Capacity type Select a capacity type. For more information about choosing a capacity type, see the section called "Managed node group capacity types" (p. 101). You cannot mix different capacity types within the same node group. If you want to use both capacity types, create separate node groups, each with their own capacity and instance types.
- Instance type One or more instance type is specified by default. To remove a default instance type, select the X on the right side of the instance type. Choose the instance types to use in your managed node group. The console displays a set of commonly used instance types. If you need to create a managed node group with an instance type that is not displayed, then use eksctl, the AWS CLI, AWS CloudFormation, or an SDK to create the node group. If you specified a launch template on the previous page, then you cannot select a value because it must be specified in the launch template. The value from the launch template is displayed. If you selected **Spot** for **Capacity type**, then we recommend specifying multiple instance types to enhance availability. For more information about selecting instance types, see **Considerations** in the section called "Managed node group capacity types" (p. 101).

Each Amazon EC2 instance type supports a maximum number of elastic network interfaces (ENIs) and each ENI supports a maximum number of IP addresses. Since each worker node and pod is assigned its own IP address it's important to choose an instance type that will support the maximum number of pods that you want to run on each worker node. For a list of the number of ENIs and IP addresses supported by instance types, see IP addresses per network interface per instance type. For example, the m5.large instance type supports a maximum of 30 IP addresses for the worker node and pods. Some instance types might not be available in all Regions.

If you plan to use Security groups for pods (p. 213), then make sure to specify a supported Amazon EC2 instance type. For more information, see Amazon EC2 supported instances and branch network interfaces (p. 217). If specifying an Arm Amazon EC2 instance type, then review the considerations in Amazon EKS optimized Arm Amazon Linux AMIs (p. 160) before deploying.

• Disk size - Enter the disk size (in GiB) to use for your node's root volume.

If you specified a launch template on the previous page, then you cannot select a value because it must be specified in the launch template.

Node group scaling configuration

Note

Amazon EKS does not automatically scale your node group in or out. However, you can configure the Kubernetes Cluster Autoscaler (p. 61) to do this for you.

- Minimum size Specify the minimum number of nodes that the managed node group can scale in to.
- Maximum size Specify the maximum number of nodes that the managed node group can scale out to.
- **Desired size** Specify the current number of nodes that the managed node group should maintain at launch.

- 8. On the Specify networking page, fill out the parameters accordingly, and then choose Next.
 - Subnets Choose the subnets to launch your managed nodes into.

Important

If you are running a stateful application across multiple Availability Zones that is backed by Amazon EBS volumes and using the Kubernetes Cluster Autoscaler (p. 61), you should configure multiple node groups, each scoped to a single Availability Zone. In addition, you should enable the --balance-similar-node-groups feature.

Important

- If you choose a public subnet, then the subnet must have MapPublicIpOnLaunch set to true for the instances to be able to successfully join a cluster. If the subnet was created using eksctl or the Amazon EKS vended AWS CloudFormation templates (p. 197) on or after March 26, 2020, then this setting is already set to true. If the subnets were created with eksctl or the AWS CloudFormation templates before March 26, 2020, then you need to change the setting manually. For more information, see Modifying the public IPv4 addressing attribute for your subnet.
- Do not select a subnet in AWS Outposts, AWS Wavelength, or an AWS Local Zone. You
 can't deploy managed nodes to a subnet in AWS Outposts, AWS Wavelength, or an
 AWS Local Zone. You can only deploy self-managed nodes (p. 116) to AWS Outposts,
 AWS Wavelength, or AWS Local Zone subnets.
- Allow remote access to nodes (Optional, but default). Enabling SSH allows you to connect to your instances and gather diagnostic information if there are issues. Complete the following steps to enable remote access. We highly recommend enabling remote access when you create your node group. You cannot enable remote access after the node group is created.

If you chose to use a launch template, then this option isn't shown. To enable remote access to your nodes, specify a key pair in the launch template and ensure that the proper port is open to the nodes in the security groups that you specify in the launch template. For more information, see Using custom security groups (p. 113).

- For **SSH** key pair (Optional), choose an Amazon EC2 SSH key to use. For more information, see Amazon EC2 key pairs in the Amazon EC2 User Guide for Linux Instances. If you chose to use a launch template, then you can't select one.
- For **Allow remote access from**, if you want to limit access to specific instances, then select the security groups that are associated to those instances. If you don't select specific security groups, then SSH access is allowed from anywhere on the internet (0.0.0.0/0).
- 9. On the Review and create page, review your managed node group configuration and choose Create.

If nodes fail to join the cluster, then see Nodes fail to join cluster (p. 365) in the Troubleshooting quide.

10. Watch the status of your nodes and wait for them to reach the Ready status.

```
kubectl get nodes --watch
```

11. (GPU nodes only) If you chose a GPU instance type and the Amazon EKS optimized accelerated AMI, then you must apply the NVIDIA device plugin for Kubernetes as a DaemonSet on your cluster with the following command.

```
kubectl apply -f https://raw.githubusercontent.com/NVIDIA/k8s-device-plugin/v0.6.0/
nvidia-device-plugin.yml
```

- 12. (Optional) Deploy a sample Linux workload (p. 248) Deploy a sample application to test your cluster and Linux nodes.
- 13. (Optional) After you add Linux worker nodes to your cluster, follow the procedures in Windows support (p. 79) to add Windows support to your cluster and to add Windows worker nodes. All

Amazon EKS User Guide Updating a managed node group

Amazon EKS clusters must contain at least one Linux worker node, even if you only want to run Windows workloads in your cluster.

Now that you have a working Amazon EKS cluster with nodes, you're ready to start installing Kubernetes add-ons and deploying applications to your cluster. The following documentation topics help you to extend the functionality of your cluster.

- Restrict access to IMDS (p. 349) If you plan to assign IAM roles to all of your Kubernetes service accounts so that pods only have the minimum permissions that they need, and no pods in the cluster require access to the Amazon EC2 instance metadata service (IMDS) for other reasons, such as retrieving the current Region, then we recommend blocking pod access to IMDS. For more information, see the section called "IAM roles for service accounts" (p. 336) and the section called "Restricting access to the instance profile" (p. 349).
- Cluster Autoscaler (p. 61) Configure the Kubernetes Cluster Autoscaler to automatically adjust the number of nodes in your node groups.
- Deploy a sample Linux workload (p. 248) Deploy a sample application to test your cluster and Linux nodes
- Deploy a Windows sample application (p. 85) Deploy a sample application to test your cluster and Windows nodes.
- Cluster management (p. 289) Learn how to use important tools for managing your cluster.

Updating a managed node group

There are several scenarios where it's useful to update your Amazon EKS managed node group's version or configuration:

- You have updated the Kubernetes version for your Amazon EKS cluster and want to update your nodes to use the same Kubernetes version.
- A new AMI release version is available for your managed node group. For more information about AMI versions, see Amazon EKS optimized Amazon Linux AMI versions (p. 160).
- You want to adjust the minimum, maximum, or desired count of the instances in your managed node group.
- You want to add or remove Kubernetes labels from the instances in your managed node group.
- You want to add or remove AWS tags from your managed node group.
- You need to deploy a new version of a launch template with configuration changes, such as an updated custom AMI.

If there's a newer AMI release version for your managed node group's Kubernetes version, you can update your node group's version to use the newer AMI version. Similarly, if your cluster is running a Kubernetes version that's newer than your node group, you can update the node group to use the latest AMI release version to match your cluster's Kubernetes version.

Note

You can't roll back a node group to an earlier Kubernetes version or AMI version.

When a node in a managed node group is terminated due to a scaling action or update, the pods in that node are drained first. For more information, see Managed node update behavior (p. 111).

Update a node group version

You can update a node group version with the AWS Management Console (p. 109) or eksctl (p. 109).

Amazon EKS User Guide Updating a managed node group

To update a node group version with the AWS Management Console

1. (Optional) If you're using the Kubernetes Cluster Autoscaler, scale the deployment down to zero replicas to avoid conflicting scaling actions.

kubectl scale deployments/cluster-autoscaler --replicas=0 -n kube-system

- 2. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 3. Choose the cluster that contains the node group to update.
- 4. If at least one of your node groups that was deployed with an Amazon EKS optimized AMI has an update available, you'll see a notification under the cluster name. The notification lets you know how many of your node groups have an update available. In the **Node Groups** table on the **Compute** tab of the **Configuration** tab, you will see **Update now** to the right of these values:
 - The value in the AMI release version column for each node group that has an Amazon EKS optimized AMI update available. If a node group is deployed with a custom AMI, this option won't appear. If your nodes are deployed with a custom AMI, you should follow these steps to deploy a new updated custom AMI. First, create a new version of your AMI, then create a new launch template version with the new AMI ID, and last upgrade the nodes to the new version of the launch template. To do this, select **Update now** for a node group that you want to update.
 - The value in the Launch template column for each node group that's deployed with a launch template. Select Update now for a node group that you want to update the launch template version for.

If you select a node group from the table and an update is available for it, you'll receive a notification on the **Node Group configuration** page. On this page, you can choose **Update now**.

- 5. On the **Update Node Group version** page, select:
 - **Update Node Group version** This option is unavailable if you deployed a custom AMI or your EKS optimized AMI is already currently on the latest version for your cluster.
 - Launch template version This option is unavailable if the node group is deployed without a custom launch template. You can only update the launch template version for a node group that has been deployed with a custom launch template. Select the version that you want to update the node group to. If your node group is configured with a custom AMI, then the version that you select must also specify an AMI. When you upgrade to a newer version of your launch template, all of your nodes are recycled to match the new configuration of the launch template version specified.
- 6. For **Update strategy**, select one of the following options and then choose **Update**.
 - Rolling update This option respects the pod disruption budgets for your cluster. Updates fail if there is a pod disruption budget issue that causes Amazon EKS to be unable to gracefully drain the pods that are running on this node group.
 - Force update This option doesn't respect pod disruption budgets. Updates occur regardless of pod disruption budget issues by forcing node restarts to occur.
- (Optional) If you use the Kubernetes Cluster Autoscaler, scale the deployment back to your desired number of replicas.

kubectl scale deployments/cluster-autoscaler --replicas=<1> -n kube-system

To update a node group version with eksctl

1. (Optional) If you're using the Kubernetes Cluster Autoscaler, scale the deployment down to zero replicas to avoid conflicting scaling actions.

Amazon EKS User Guide Updating a managed node group

```
kubectl scale deployments/cluster-autoscaler --replicas=0 -n kube-system
```

Upgrade a managed node group to the latest AMI release of the same Kubernetes version that's currently deployed on the nodes with the following command.

```
eksctl upgrade nodegroup --name=<node-group-name> --cluster=<cluster-name>
```

Note

If you're upgrading a node group that's deployed with a launch template to a new launch template version, add --launch-template-<version> to the preceding command. The launch template must meet the requirements described in Launch template support (p. 111). If the launch template includes a custom AMI, the AMI must meet the requirements in Using a custom AMI (p. 114). When you upgrade your node group to a newer version of your launch template, all of your nodes are recycled to match the new configuration of the launch template version that's specified.

You can't directly upgrade a node group that's deployed without a launch template to a new launch template version. Instead, you must deploy a new node group using the launch template to update the node group to a new launch template version.

You can upgrade a node group to a version that's one minor release later than the node group's current Kubernetes version, but the version can't be later than the cluster's Kubernetes version. For example, if you have a cluster running Kubernetes 1.18, you can upgrade nodes currently running Kubernetes 1.17 to version 1.18 with the following command.

```
eksctl upgrade nodegroup --name=<node-group-name> --cluster=<cluster-name> --
kubernetes-version=<1.18>
```

3. (Optional) If you use the Kubernetes Cluster Autoscaler, scale the deployment back to your desired number of replicas.

```
kubectl scale deployments/cluster-autoscaler --replicas=<1> -n kube-system
```

Edit a node group configuration

You can modify some of the configurations of a managed node group.

To edit a node group configuration

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- Choose the cluster that contains the node group to edit.
- 3. Select the Configuration tab. On the Compute tab, select the node group to edit, and choose Edit.
- 4. (Optional) On the Edit node group page, edit the Group configuration.
 - **Tags** Add tags to or remove tags from your node group resource. These tags are only applied to the Amazon EKS node group. They do not propagate to other resources, such as subnets or Amazon EC2 instances in the node group.
 - **Kubernetes labels** Add or remove Kubernetes labels to the nodes in your node group. The labels shown here are only the labels that you have applied with Amazon EKS. Other labels may exist on your nodes that aren't shown here.
- 5. (Optional) On the **Edit node group** page, edit the **Group size**.
 - Minimum size Specify the minimum number of nodes that the managed node group can scale in to.

- Maximum size Specify the maximum number of nodes that the managed node group can scale out to. Managed node groups can support up to 100 nodes by default.
- **Desired size** Specify the current number of nodes that the managed node group should maintain.
- 6. When you're finished editing, choose Save changes.

Managed node update behavior

When you update a managed node group version to the latest AMI release version for your node group's Kubernetes version or to a newer Kubernetes version to match your cluster, Amazon EKS triggers the following logic:

- 1. Amazon EKS creates a new Amazon EC2 launch template version for the Auto Scaling group associated with your node group. The new template uses the target AMI for the update.
- 2. The Auto Scaling group is updated to use the latest launch template with the new AMI.
- 3. The Auto Scaling group maximum size and desired size are incremented by one up to twice the number of Availability Zones in the Region that the Auto Scaling group is deployed in. This is to ensure that at least one new instance comes up in every Availability Zone in the Region that your node group is deployed in.
- 4. Amazon EKS checks the nodes in the node group for the eks.amazonaws.com/nodegroup-image label, and applies a eks.amazonaws.com/nodegroup=unschedulable:NoSchedule taint on all of the nodes in the node group that aren't labeled with the latest AMI ID. This prevents nodes that have already been updated from a previous failed update from being tainted.
- 5. Amazon EKS randomly selects a node in the node group and evicts all pods from it.
- After all of the pods are evicted, Amazon EKS cordons the node. This is done so that the service controller doesn't send any new request to this node and removes this node from its list of healthy, active nodes.
- 7. Amazon EKS sends a termination request to the Auto Scaling group for the cordoned node.
- 8. Steps 5-7 are repeated until there are no nodes in the node group that are deployed with the earlier version of the launch template.
- 9. The Auto Scaling group maximum size and desired size are decremented by 1 to return to your preupdate values.

Launch template support

Managed node groups are always deployed with an Amazon EC2 Auto Scaling Group launch template. If you don't specify your own launch template to use when creating a managed node group, the Amazon EKS API creates a launch template with default values in your account. Creating your own launch template and a managed node group from that template has the benefit of providing you with a greater level of flexibility and customization when deploying managed nodes than is provided by the default launch template. For the highest level of customization, you can deploy managed nodes using your own launch template and a custom AMI.

After you've deployed a managed node group with your own launch template, you can then update it with a different version of the same launch template. When you update your node group to a different version of your launch template, all of the nodes in the group are recycled to match the new configuration of the specified launch template version. Existing node groups that do not use a custom launch template can't be updated directly. Rather, you must create a new node group with a custom launch template to do so.

Launch template configuration basics

You can create an Amazon EC2 Auto Scaling launch template with the AWS Management Console, AWS CLI, or an AWS SDK. For more information, see Creating a Launch Template for an Auto Scaling Group in the Amazon EC2 User Guide. Some of the settings in a launch template are similar to the settings used for managed node configuration. When deploying or updating a node group with a launch template, some settings must be specified in the node group configuration or the launch template, but not both. If a setting exists where it shouldn't, then operations such as creating or updating a node group fail.

The following table lists the settings that are prohibited in a launch template and which similar settings (if any) are required in the managed node group configuration. The listed settings are the settings that appear in the console. They might have similar but different names in the AWS CLI and SDK.

Launch template – Prohibited	Amazon EKS node group configuration
IAM instance profile under Advanced details	Node IAM Role under Node Group configuration on the Configure Node Group page
Subnet under Network interfaces (Add network interface)	Subnets under Node Group network configuration on the Specify networking page
Shutdown behavior and Stop - Hibernate behavior under Advanced details. Retain default Don't include in launch template setting in launch template for both settings.	No equivalent. Amazon EKS must control the instance lifecycle, not the Auto Scaling group.

The following table lists the settings that are prohibited in a managed node group configuration and which similar settings (if any) are required in a launch template. The listed settings are the settings that appear in the console. They might have similar names in the AWS CLI and SDK.

Amazon EKS node group configuration – Prohibited	Launch template
(Only if you specified a custom AMI in a launch template) AMI type under Node Group compute configuration on Set compute and scaling configuration page – Console displays Specified in launch template and the AMI ID that was specified.	AMI under Launch template contents – You must specify if you're using a custom AMI. If you specify an AMI that doesn't meet the requirements listed in Using a custom AMI (p. 114), the node group deployment will fail.
If an AMI type was not specified in the launch template, then you can select an AMI in the node group configuration.	
Disk size under Node Group compute configuration on Set compute and scaling configuration page – Console displays Specified in launch template.	Size under Storage (Volumes) (Add new volume). You must specify this in the launch template.
SSH key pair under Node Group configuration on the Specify Networking page – The console displays the key that was specified in the launch template or displays Not specified in launch template.	Key pair name under Key pair (login).

Amazon EKS node group configuration – Prohibited	Launch template
You can't specify source security groups that are allowed remote access when using a launch template.	Security groups under Network settings for the instance or Security groups under Network interfaces (Add network interface), but not both. For more information, see Using custom security groups (p. 113).

Note

- If you deploy a node group using a launch template, then you can specify zero or one Instance type under Launch template contents in a launch template or you can specify 0-20 instance types for Instance types on the Set compute and scaling configuration page in the console, or using other tools that use the Amazon EKS API. If you specify an instance type in a launch template, and use that launch template to deploy your node group, then you can't specify any instance types in the console or using other tools that use the Amazon EKS API. If you don't specify an instance type in a launch template, in the console, or using other tools that use the Amazon EKS API, then the t3.medium instance type is used, by default. If your node group is using the Spot capacity type, then we recommend specifying multiple instance types using the console. For more information, see the section called "Managed node group capacity types" (p. 101).
- If any containers that you deploy to the node group use the Instance Metadata Service Version 2, then make sure to set the **Metadata response hop limit** to 2 in your launch template. For more information, see Instance metadata and user data in the Amazon EC2 User Guide. If you deploy a managed node group without using a custom launch template, this value is automatically set for the node group in the default launch template.

Tagging Amazon EC2 instances

You can use the TagSpecification parameter of a launch template to specify which tags to apply to Amazon EC2 instances in your node group. The IAM entity calling the CreateNodegroup or UpdateNodegroupVersion APIs must have permissions for ec2:RunInstances and ec2:CreateTags, and the tags must be added to the launch template.

Using custom security groups

You can use a launch template to specify custom Amazon EC2 security groups to apply to instances in your node group. This can be either in the instance level security groups parameter or as part of the network interface configuration parameters. However, you can't create a launch template that specifies both instance level and network interface security groups. Consider the following conditions that apply to using custom security groups with managed node groups:

- Amazon EKS only allows launch templates with a single network interface specification.
- By default, Amazon EKS applies the cluster security group to the instances in your node group to facilitate communication between nodes and the control plane. If you specify custom security groups in the launch template using either option mentioned earlier, Amazon EKS doesn't add the cluster security group. Therefore, you must ensure that the inbound and outbound rules of your security groups enable communication with your cluster's endpoint. Incorrect security group rules result in worker nodes being unable to join the cluster. To learn about the security group rules that you should need to apply, see Amazon EKS security group considerations (p. 204).
- If you need SSH access to the instances in your node group, be sure to include a security group that allows that access.

Amazon EC2 user data

You can supply Amazon EC2 user data in your launch template using cloud-init when launching your instances. For more information, see the cloud-init documentation. Your user data can be used to perform common configuration operations. This includes the following operations:

- · Including users or groups
- Installing packages

Amazon EC2 user data in launch templates that are used with managed node groups must be in the MIME multi-part archive format. This is because your user data is merged with Amazon EKS user data required for nodes to join the cluster. Do not specify any commands in your user data that starts or modifies kubelet, as this will be performed as part of the user data merged by Amazon EKS. Certain kubelet parameters, such as setting labels on nodes, can be configured directly through the managed node groups API.

Note

If you have a need for advanced kubelet customization, including manually starting it or passing in custom configuration parameters, see Using a custom AMI (p. 114) for more information. Amazon EKS doesn't merge user data when a custom AMI ID is specified in a launch template.

You can combine multiple user data blocks together into a single MIME multi-part file. For example, you can combine a cloud boothook that configures the Docker daemon with a user data shell script that installs a custom package. A MIME multi-part file consists of the following components:

- The content type and part boundary declaration Content-Type: multipart/mixed; boundary="==BOUNDARY=="
- The MIME version declaration MIME-Version: 1.0
- One or more user data blocks, which contain the following components:
 - The opening boundary, which signals the beginning of a user data block ——==BOUNDARY==
 - The content type declaration for the block: Content-Type: text/cloud-config; charset="us-ascii". For more information about content types, see the cloud-init documentation.
 - The content of the user data, for example, a list of shell commands or cloud-init directives.
 - The closing boundary, which signals the end of the MIME multi-part file: --==BOUNDARY==--

The following is an example of a MIME multi-part file that you can use to create your own.

```
MIME-Version: 1.0
Content-Type: multipart/mixed; boundary="==MYBOUNDARY=="

--==MYBOUNDARY==
Content-Type: text/x-shellscript; charset="us-ascii"

#!/bin/bash
echo "Running custom user data script"

--==MYBOUNDARY==--\
```

Using a custom AMI

If your organization needs to run a custom AMI due to specific security, compliance, or internal policy requirements, you can deploy such AMIs to managed node groups by using a launch template. For more

Amazon EKS User Guide Deleting a managed node group

information, see Amazon Machine Images (AMI) in the Amazon EC2 User Guide for Linux Instances. The Amazon EKS AMI build specification contains resources and configuration scripts for building a custom Amazon EKS AMI based on Amazon Linux 2. For more information, see Amazon EKS AMI Build Specification on GitHub. To build custom AMIs installed with other operating systems, see Amazon EKS Sample Custom AMIs on GitHub.

Note

When using a custom AMI, Amazon EKS doesn't merge any user data. Rather, you're responsible for supplying the required bootstrap commands for nodes to join the cluster. If your nodes fail to join the cluster, the Amazon EKS CreateNodegroup and UpdateNodegroupVersion actions also fail.

To use a custom AMI with managed node groups, specify an AMI ID in the imageId field of the launch template. To update your node group to a newer version of a custom AMI, create a new version of the launch template with an updated AMI ID, and update the node group with the new launch template version.

Limitations of using custom AMIs with managed node groups

- You must create a new node group to switch between using custom AMIs and Amazon EKS optimized AMIs.
- The following fields can't be set in the API if you're using a custom AMI
 - amiType
 - releaseVersion
 - version
- The custom AMI can't be Windows because Windows can't be used in managed node groups.

Deleting a managed node group

This topic describes how you can delete an Amazon EKS managed node group.

When you delete a managed node group, Amazon EKS will first set the minimum, maximum, and desired size of your Auto Scaling group to zero, which will trigger a scale down of your node group. Before each instance is terminated, Amazon EKS will send a signal to drain the pods from that node and wait a few minutes. If the pods haven't drained after a few minutes, Amazon EKS will let Auto Scaling continue the termination of the instance. Once all instances are terminated, the Auto Scaling group is deleted.

Important

If you delete a managed node group that uses a node IAM role that isn't used by any other managed node group in the cluster, the role is removed from the aws-auth
ConfigMap (p. 285). If any self-managed node groups in the cluster are using the same node IAM role, the self-managed nodes move to the NotReady status, and the cluster operation are also disrupted. You can add the mapping back to the ConfigMap to minimize disruption.

To delete a managed node group

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. Choose the cluster that contains the node group to delete.
- 3. Select the **Configuration** tab. On the **Compute** tab, select the node group to delete, and choose **Delete**.
- 4. On the **Delete Node group: <node group name>** page, type the name of the node group in the text field and choose **Delete**.

Self-managed nodes

A cluster contains one or more Amazon EC2 nodes that pods are scheduled on. Amazon EKS nodes run in your AWS account and connect to your cluster's control plane via the cluster API server endpoint. You deploy one or more nodes into a node group. A node group is one or more Amazon EC2 instances that are deployed in an Amazon EC2 Auto Scaling group. All instances in a node group must:

- · Be the same instance type
- · Be running the same Amazon Machine Image (AMI)
- Use the same Amazon EKS node IAM role (p. 332)

A cluster can contain several node groups. As long as each node group meets the previous requirements, the cluster can contain node groups that contain different instance types and host operating systems. Each node group can contain several nodes.

Amazon EKS nodes are standard Amazon EC2 instances, and you are billed for them based on normal EC2 prices. For more information, see Amazon EC2 pricing.

Amazon EKS provides specialized Amazon Machine Images (AMI) called Amazon EKS optimized AMIs. The AMIs are configured to work with Amazon EKS and include Docker, kubelet, and the AWS IAM Authenticator. The AMIs also contain a specialized bootstrap script that allows it to discover and connect to your cluster's control plane automatically.

If you restrict access to your cluster's public endpoint using CIDR blocks, it is recommended that you also enable private endpoint access so that nodes can communicate with the cluster. Without the private endpoint enabled, the CIDR blocks that you specify for public access must include the egress sources from your VPC. For more information, see Amazon EKS cluster endpoint access control (p. 56).

To add self-managed nodes to your Amazon EKS cluster, see the topics that follow. If you launch self-managed nodes manually, then you must add the following tag to each node. For more information, see Adding and deleting tags on an individual resource. If you follow the steps in the guides that follow, then the required tag is automatically added to nodes for you.

Key	Value
kubernetes.io/cluster/ <cluster-name></cluster-name>	owned

For more information about nodes from a general Kubernetes perspective, see Nodes in the Kubernetes documentation.

Topics

- Launching self-managed Amazon Linux nodes (p. 116)
- Launching self-managed Bottlerocket nodes (p. 121)
- Launching self-managed Windows nodes (p. 124)
- Self-managed node updates (p. 128)

Launching self-managed Amazon Linux nodes

This topic helps you to launch an Auto Scaling group of Linux nodes that register with your Amazon EKS cluster. After the nodes join the cluster, you can deploy Kubernetes applications to them. You can launch self-managed Amazon Linux 2 nodes with eksctl (p. 117) or the AWS Management Console (p. 118).

To launch self-managed Linux nodes using eksctl

This procedure only works for clusters that were created with eksctl.

Note

This procedure requires eksctl version 0.33.0 or later. You can check your version with the following command:

```
eksctl version
```

For more information on installing or upgrading eksctl, see Installing or upgrading eksctl (p. 298).

Important

Do not use eksctl to create a cluster or nodes in an AWS Region where you have AWS Outposts, AWS Wavelength, or AWS Local Zones enabled. Create a cluster and self-managed nodes using the Amazon EC2 API or AWS CloudFormation instead. For more information, see To launch self-managed Linux nodes using the AWS Management Console (p. 118) and To launch self-managed Windows nodes using the AWS Management Console (p. 125).

- 1. (Optional) If the AmazonEKS_CNI_Policy managed IAM policy is attached to your the section called "Node IAM role" (p. 332), we recommend assigning it to an IAM role that you associate to the Kubernetes aws-node service account instead. For more information, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).
- 2. The following command assumes that you have an existing cluster named my-cluster in the us-west-2 Region. For a different existing cluster, change the values. If you don't have an existing cluster then you must first create a cluster (p. 35). If you want to deploy on Amazon EC2 Arm instances, then replace t3.medium with an Arm instance type. If specifying an Arm Amazon EC2 instance type, then review the considerations in Amazon EKS optimized Arm Amazon Linux AMIs (p. 160) before deploying.

Create your node group with the following command. Replace the <example values> with your own values.

```
eksctl create nodegroup \
    --cluster <my-cluster> \
    --version auto \
    --name <al-nodes> \
    --node-type <t3.medium> \
    --node-ami auto \
    --nodes <3> \
    --nodes-min <1> \
    --nodes-max <4>
```

If nodes fail to join the cluster, then see Nodes fail to join cluster (p. 365) in the Troubleshooting guide.

Output:

You'll see several lines of output as the nodes are created. One of the last lines of output is the following example line.

```
[#] created 1 nodegroup(s) in cluster "<my-cluster>"
```

- 3. (Optional) Deploy a sample application (p. 248) to test your cluster and Linux nodes.
- 4. (Optiona) If you plan to assign IAM roles to all of your Kubernetes service accounts so that pods only have the minimum permissions that they need, and no pods in the cluster require access to the Amazon EC2 instance metadata service (IMDS) for other reasons, such as retrieving the current Region, then we recommend blocking pod access to IMDS. For more information, see the section

called "IAM roles for service accounts" (p. 336) and the section called "Restricting access to the instance profile" (p. 349).

To launch self-managed Linux nodes using the AWS Management Console

This procedure has the following prerequisites:

- An existing VPC and security group that meet the requirements for an Amazon EKS cluster. For
 more information, see Cluster VPC considerations (p. 202) and Amazon EKS security group
 considerations (p. 204). The Getting started with Amazon EKS (p. 4) guide creates a VPC that meets
 the requirements, or you can also follow Creating a VPC for your Amazon EKS cluster (p. 197) to
 create one manually.
- An existing Amazon EKS cluster that uses a VPC and security group that meet the requirements of an Amazon EKS cluster. For more information, see Creating an Amazon EKS cluster (p. 35).
- 1. Wait for your cluster status to show as ACTIVE. If you launch your nodes before the cluster is active, the nodes will fail to register with the cluster and you will have to relaunch them.
- 2. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
- 3. Choose Create stack.
- 4. For **Specify template**, select **Amazon S3 URL**, copy the URL that corresponds to the Region that your cluster is in, paste it into **Amazon S3 URL**, and then select **Next** twice.
 - All Regions other than China (Beijing) and China (Ningxia)

https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/amazon-eks-nodegroup.yaml

China (Beijing) and China (Ningxia)

 $\label{lem:https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/amazon-eks-nodegroup.yaml$

- 5. On the **Quick create stack** page, fill out the following parameters accordingly:
 - Stack name: Choose a stack name for your AWS CloudFormation stack. For example, you can call
 it cluster-name-nodes.
 - ClusterName: Enter the name that you used when you created your Amazon EKS cluster.

Important

This name must exactly match the name you used in Step 1: Create your Amazon EKS cluster (p. 25); otherwise, your nodes cannot join the cluster.

- ClusterControlPlaneSecurityGroup: Choose the SecurityGroups value from the AWS CloudFormation output that you generated with Create your Amazon EKS cluster VPC (p. 22).
- **NodeGroupName**: Enter a name for your node group. This name can be used later to identify the Auto Scaling node group that is created for your nodes.
- **NodeAutoScalingGroupMinSize**: Enter the minimum number of nodes that your node Auto Scaling group can scale in to.
- **NodeAutoScalingGroupDesiredCapacity**: Enter the desired number of nodes to scale to when your stack is created.
- NodeAutoScalingGroupMaxSize: Enter the maximum number of nodes that your node Auto Scaling group can scale out to.
- NodeInstanceType: Choose an instance type for your nodes. Before choosing an Arm instance type, make sure to review the considerations in Amazon EKS optimized Arm Amazon Linux AMIs (p. 160).

Note

The supported instance types for the latest version of the Amazon VPC CNI plugin for Kubernetes are shown here. You may need to update your CNI version to take advantage of the latest supported instance types. For more information, see Amazon VPC CNI plugin for Kubernetes upgrades (p. 235).

Important

Some instance types might not be available in all Regions.

• NodeImageIdSSMParam: Pre-populated with the Amazon EC2 Systems Manager parameter of the current recommended Amazon EKS optimized Amazon Linux AMI ID for a Kubernetes version. If you want to use the Amazon EKS optimized accelerated AMI, then replace amazon-linux-2 with amazon-linux-2-gpu. If you want to use the Amazon EKS optimized Arm AMI, then replace amazon-linux-2 with amazon-linux-2-arm64. If you want to use a different Kubernetes minor version supported with Amazon EKS, then you can replace 1.x with a different supported version (p. 68). We recommend specifying the same Kubernetes version as your cluster.

Note

The Amazon EKS node AMI is based on Amazon Linux 2. You can track security or privacy events for Amazon Linux 2 at the Amazon Linux Security Center or subscribe to the associated RSS feed. Security and privacy events include an overview of the issue, what packages are affected, and how to update your instances to correct the issue.

- **NodeImageId**: (Optional) If you are using your own custom AMI (instead of the Amazon EKS optimized AMI), enter a node AMI ID for your Region. If you specify a value here, it overrides any values in the **NodeImageIdSSMParam** field.
- NodeVolumeSize: Specify a root volume size for your nodes, in GiB.
- **KeyName**: Enter the name of an Amazon EC2 SSH key pair that you can use to connect using SSH into your nodes with after they launch. If you don't already have an Amazon EC2 keypair, you can create one in the AWS Management Console. For more information, see Amazon EC2 key pairs in the Amazon EC2 User Guide for Linux Instances.

Note

If you do not provide a keypair here, the AWS CloudFormation stack creation fails.

• **BootstrapArguments**: Specify any optional arguments to pass to the node bootstrap script, such as extra kubelet arguments. For more information, view the bootstrap script usage information on GitHub.

Note

• If you are launching nodes into a private VPC without outbound internet access, then you need to include the following arguments.

```
--apiserver-endpoint <cluster-endpoint> --b64-cluster-ca <cluster-certificate-authority>
```

- If you want to assign IP addresses to pods that are from a different CIDR block than the block that includes the IP address for the node, then you may need to add a CIDR block to your VPC and specify an argument to support the capability. For more information, see CNI custom networking (p. 224).
- **DisableIMDSv1**: Each node supports the Instance Metadata Service Version 1 (IMDSv1) and IMDSv2 by default, but you can disable IMDSv1. Select **true** if you don't want any nodes in the node group, or any pods scheduled on the nodes in the node group to use IMDSv1. For more information about IMDS, see Configuring the instance metadata service. For more information about restricting access to it on your nodes, see the section called "Restricting access to the instance profile" (p. 349).
- VpcId: Enter the ID for the VPC that you created in Create your Amazon EKS cluster VPC (p. 22).
- **Subnets**: Choose the subnets that you created in Create your Amazon EKS cluster VPC (p. 22). If you created your VPC using the steps described at Creating a VPC for your Amazon EKS

cluster (p. 197), then specify only the private subnets within the VPC for your nodes to launch into

Important

If any of the subnets are public subnets, then they must have the automatic public IP address assignment setting enabled. If the setting is not enabled for the public subnet, then any nodes that you deploy to that public subnet will not be assigned a public IP address and will not be able to communicate with the cluster or other AWS services. If the subnet was deployed before March 26, 2020 using either of the Amazon EKS AWS CloudFormation VPC templates (p. 197), or by using eksctl, then automatic public IP address assignment is disabled for public subnets. For information about how to enable public IP address assignment for a subnet, see Modifying the Public IPv4 Addressing Attribute for Your Subnet. If the node is deployed to a private subnet, then it is able to communicate with the cluster and other AWS services through a NAT gateway.

Important

- If the subnets do not have internet access, then make sure that you're aware of the considerations and extra steps in Private clusters (p. 92).
- Ensure that the subnets you select are tagged with the cluster name. For more
 information, see Subnet tagging requirement (p. 204). If you have subnets in AWS
 Outposts, AWS Wavelength, or an AWS Local Zone, they likely are not currently tagged.
- 6. Acknowledge that the stack might create IAM resources, and then choose Create stack.
- 7. When your stack has finished creating, select it in the console and choose **Outputs**.
- 8. Record the **NodeInstanceRole** for the node group that was created. You need this when you configure your Amazon EKS nodes.

To enable nodes to join your cluster

Note

If you launched nodes inside a private VPC without outbound internet access, then you must enable nodes to join your cluster from within the VPC.

- 1. Download, edit, and apply the AWS IAM Authenticator configuration map.
 - a. Use the command that corresponds to the Region that your cluster is in to download the configuration map:
 - All Regions other than China (Beijing) and China (Ningxia)

```
curl -o aws-auth-cm.yaml https://s3.us-west-2.amazonaws.com/amazon-eks/
cloudformation/2020-10-29/aws-auth-cm.yaml
```

China (Beijing) and China (Ningxia)

```
curl -o aws-auth-cm.yaml https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/aws-auth-cm.yaml
```

b. Open the file with your text editor. Replace the <ARN of instance role (not instance profile)> snippet with the NodeInstanceRole value that you recorded in the previous procedure, and save the file.

Important

Do not modify any other lines in this file.

```
apiVersion: v1
kind: ConfigMap
metadata:
name: aws-auth
```

Amazon EKS User Guide Bottlerocket

c. Apply the configuration. This command may take a few minutes to finish.

```
kubectl apply -f aws-auth-cm.yaml
```

Note

If you receive any authorization or resource type errors, see Unauthorized or access denied (kubect1) (p. 366) in the troubleshooting section.

If nodes fail to join the cluster, then see Nodes fail to join cluster (p. 365) in the Troubleshooting guide.

2. Watch the status of your nodes and wait for them to reach the Ready status.

```
kubectl get nodes --watch
```

(GPU nodes only) If you chose a GPU instance type and the Amazon EKS optimized accelerated AMI, you must apply the NVIDIA device plugin for Kubernetes as a DaemonSet on your cluster with the following command.

```
kubectl apply -f https://raw.githubusercontent.com/NVIDIA/k8s-device-plugin/v0.6.0/
nvidia-device-plugin.yml
```

- 4. (Optional) Deploy a sample application (p. 248) to test your cluster and Linux nodes.
- 5. (Optional) If the AmazonEKS_CNI_Policy managed IAM policy is attached to your the section called "Node IAM role" (p. 332), we recommend assigning it to an IAM role that you associate to the Kubernetes aws-node service account instead. For more information, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).
- 6. (Optional) If you plan to assign IAM roles to all of your Kubernetes service accounts so that pods only have the minimum permissions that they need, and no pods in the cluster require access to the Amazon EC2 instance metadata service (IMDS) for other reasons, such as retrieving the current Region, then we recommend blocking pod access to IMDS. For more information, see the section called "IAM roles for service accounts" (p. 336) and the section called "Restricting access to the instance profile" (p. 349).

Launching self-managed Bottlerocket nodes

This topic helps you to launch an Auto Scaling group of Bottlerocket nodes that register with your Amazon EKS cluster. Bottlerocket is a Linux-based open-source operating system that is purpose-built by AWS for running containers on virtual machines or bare metal hosts. After the nodes join the cluster, you can deploy Kubernetes applications to them. For more information about Bottlerocket, see the documentation on GitHub.

Important

Amazon EKS nodes are standard Amazon EC2 instances, and you are billed for them based on normal Amazon EC2 instance prices. For more information, see Amazon EC2 pricing.

Important

Considerations

Amazon EKS User Guide Bottlerocket

- You can deploy to Amazon EC2 instances with x86 or Arm processors, but not to instances that have GPUs or Inferentia chips.
- You cannot deploy to the following regions: China (Beijing) (cn-north-1), China (Ningxia) (cn-northwest-1), AWS GovCloud (US-East) (us-gov-east-1), or AWS GovCloud (US-West) (us-gov-west-1).
- There is no AWS CloudFormation template to deploy nodes with.

Important

Do not use eksctl to create a cluster or nodes in an AWS Region where you have AWS Outposts, AWS Wavelength, or AWS Local Zones enabled. Create a cluster and self-managed nodes using the Amazon EC2 API or AWS CloudFormation instead. For more information, see To launch self-managed Linux nodes using the AWS Management Console (p. 118) and To launch self-managed Windows nodes using the AWS Management Console (p. 125).

To launch Bottlerocket nodes using eksctl

This procedure requires eksctl version 0.33.0 or later. You can check your version with the following command:

```
eksctl version
```

For more information on installing or upgrading eksct1, see Installing or upgrading eksct1 (p. 298).

Note

This procedure only works for clusters that were created with eksctl.

- (Optional) If the AmazonEKS_CNI_Policy managed IAM policy is attached to your the section called "Node IAM role" (p. 332), we recommend assigning it to an IAM role that you associate to the Kubernetes aws-node service account instead. For more information, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).
- 2. This procedure assumes that you have an existing cluster named my-cluster in the us-west-2 Region. For a different existing cluster, change the values. If you don't have an existing cluster then you must first create a cluster (p. 35).

Create a file with the following contents. Replace the <example values> (including <>) with your own values. If you change 1.18, then it can only be changed to 1.15 or later. If you want to deploy on Arm instances, then replace m5.large with an Arm instance type. If specifying an Arm Amazon EC2 instance type, then review the considerations in Amazon EKS optimized Arm Amazon Linux AMIs (p. 160) before deploying. If you want to deploy using a custom AMI, then see Building Bottlerocket on GitHub and Custom AMI support in the eksctl documentation. If you want to deploy a managed node group then you must deploy a custom AMI using a launch template. For more information, see the section called "Launch template support" (p. 111).

For more information about using a config file with eksctl, the config file schema, and config file samples, see the eksctl documentation.

```
apiVersion: eksctl.io/v1alpha5
kind: ClusterConfig

metadata:
   name: <my-cluster>
   region: <us-west-2>
   version: <'1.18'>

nodeGroups:
   - name: <ng-bottlerocket>
   instanceType: <m5.large>
```

Amazon EKS User Guide Bottlerocket

```
desiredCapacity: <3>
amiFamily: <Bottlerocket>
iam:
   attachPolicyARNs:
        - arn:aws:iam::aws:policy/AmazonEKSWorkerNodePolicy
        - arn:aws:iam::aws:policy/AmazonEKS_CNI_Policy
        - arn:aws:iam::aws:policy/AmazonEC2ContainerRegistryReadOnly
        - arn:aws:iam::aws:policy/AmazonSSMManagedInstanceCore
ssh:
    allow: true
   publicKeyName: <YOUR_EC2_KEYPAIR_NAME>
```

3. Deploy your nodes with the following command.

```
eksctl create nodegroup --config-file=<filename-you-used-in-previous-step.yaml>
```

If nodes fail to join the cluster, then see Nodes fail to join cluster (p. 365) in the Troubleshooting quide.

Output:

You'll see several lines of output as the nodes are created. One of the last lines of output is the following example line.

```
[#] created 1 nodegroup(s) in cluster "<my-cluster>"
```

- 4. (Optional) Create a Kubernetes persistent volume on a Bottlerocket node using the Amazon EBS CSI Plugin. The default Amazon EBS driver relies on file system tools that are not included with Bottlerocket. For more information about creating a storage class using the driver, see Amazon EBS CSI driver (p. 181).
- 5. (Optional) By default kube-proxy will set the nf_conntrack_max kernel parameter to a default value that may differ from what Bottlerocket originally sets at boot. If you prefer to keep Bottlerocket's default setting, then edit the kube-proxy configuration with the following command.

```
kubectl edit -n kube-system daemonset kube-proxy
```

Add --conntrack-max-per-core and --conntrack-min to the kube-proxy arguments as shown in the following example. A setting of 0 implies no change.

```
containers:
    - command:
    - kube-proxy
    - -v=2
    - -config=/var/lib/kube-proxy-config/config
    - -conntrack-max-per-core=0
    - -conntrack-min=0
```

- 6. (Optional) Deploy a sample application (p. 248) to test your Bottlerocket nodes.
- 7. (Optional) If the AmazonEKS_CNI_Policy managed IAM policy is attached to your the section called "Node IAM role" (p. 332), we recommend assigning it to an IAM role that you associate to the Kubernetes aws-node service account instead. For more information, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).
- 8. (Optional) If you plan to assign IAM roles to all of your Kubernetes service accounts so that pods only have the minimum permissions that they need, and no pods in the cluster require access to the Amazon EC2 instance metadata service (IMDS) for other reasons, such as retrieving the current Region, then we recommend blocking pod access to IMDS. For more information, see the section called "IAM roles for service accounts" (p. 336) and the section called "Restricting access to the instance profile" (p. 349).

Launching self-managed Windows nodes

This topic helps you to launch an Auto Scaling group of Windows nodes that register with your Amazon EKS cluster. After the nodes join the cluster, you can deploy Kubernetes applications to them.

Important

Amazon EKS nodes are standard Amazon EC2 instances, and you are billed for them based on normal Amazon EC2 instance prices. For more information, see Amazon EC2 pricing.

Important

Do not use eksctl to create a cluster or nodes in an AWS Region where you have AWS Outposts, AWS Wavelength, or AWS Local Zones enabled. Create a cluster and self-managed nodes using the Amazon EC2 API or AWS CloudFormation instead. For more information, see To launch self-managed Linux nodes using the AWS Management Console (p. 118) and To launch self-managed Windows nodes using the AWS Management Console (p. 125).

You must enable Windows support for your cluster and we recommend that you review important considerations before you launch a Windows node group. For more information, see Enabling Windows support (p. 80).

You can launch self-managed Windows nodes with eksctl (p. 124) or the AWS Management Console (p. 125).

To launch self-managed Windows nodes using eksctl

This procedure assumes that you have installed eksctl, and that your eksctl version is at least 0.33.0. You can check your version with the following command:

```
eksctl version
```

For more information on installing or upgrading eksct1, see Installing or upgrading eksct1 (p. 298).

Note

This procedure only works for clusters that were created with eksctl.

- (Optional) If the AmazonEKS_CNI_Policy managed IAM policy is attached to your the section called "Node IAM role" (p. 332), we recommend assigning it to an IAM role that you associate to the Kubernetes aws-node service account instead. For more information, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).
- 2. This procedure assumes that you have an existing cluster named my-cluster in the us-west-2 Region. For a different existing cluster, change the values. If you don't already have an Amazon EKS cluster and an Amazon Linux 2 node group to add a Windows node group to, then we recommend that you follow the Getting started with eksctl (p. 4) guide instead. The guide provides a complete end-to-end walkthrough for creating an Amazon EKS cluster with Amazon Linux and Windows nodes.

Create your node group with the following command. Replace the <example values> with your own values.

```
eksctl create nodegroup \
--region <us-west-2> \
--cluster <my-cluster> \
--name <ng-windows> \
--node-type <t2.large> \
--nodes <3> \
--nodes-min <1> \
--nodes-max <4> \
```

Amazon EKS User Guide Windows

--node-ami-family <WindowsServer2019FullContainer>

Note

- If nodes fail to join the cluster, see Nodes fail to join cluster (p. 365) in the Troubleshooting guide.
- For more information on the available options for eksctl commands, enter the following command.

```
eksctl <command> -help
```

Output:

You'll see several lines of output as the nodes are created. One of the last lines of output is the following example line.

```
[#] created 1 nodegroup(s) in cluster "<my-cluster>"
```

- 3. (Optional) Deploy a sample application (p. 85) to test your cluster and Windows nodes.
- 4. (Optional) If you plan to assign IAM roles to all of your Kubernetes service accounts so that pods only have the minimum permissions that they need, and no pods in the cluster require access to the Amazon EC2 instance metadata service (IMDS) for other reasons, such as retrieving the current Region, then we recommend blocking pod access to IMDS. For more information, see the section called "IAM roles for service accounts" (p. 336) and the section called "Restricting access to the instance profile" (p. 349).

To launch self-managed Windows nodes using the AWS Management Console

These procedures have the following prerequisites:

- You have an existing Amazon EKS cluster and a Linux node group. If you don't have these resources, we
 recommend that you follow one of our Getting started with Amazon EKS (p. 4) guides to create them.
 The guides provide a complete end-to-end walkthrough for creating an Amazon EKS cluster with Linux
 nodes.
- You have created a VPC and security group that meet the requirements for an Amazon EKS cluster.
 For more information, see Cluster VPC considerations (p. 202) and Amazon EKS security group
 considerations (p. 204). The Getting started with Amazon EKS (p. 4) guide creates a VPC that meets
 the requirements, or you can also follow Creating a VPC for your Amazon EKS cluster (p. 197) to
 create one manually.
- 1. Wait for your cluster status to show as ACTIVE. If you launch your nodes before the cluster is active, the nodes will fail to register with the cluster and you will have to relaunch them.
- 2. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation
- 3. Choose Create stack.
- 4. For **Specify template**, select **Amazon S3 URL**, copy the URL that corresponds to the Region that your cluster is in, paste it into **Amazon S3 URL**, and select **Next** twice.
 - All Regions other than China (Beijing) and China (Ningxia)

https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/amazon-eks-windows-nodegroup.yaml

• China (Beijing) and China (Ningxia)

Amazon EKS User Guide Windows

https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/amazon-eks-windows-nodegroup.yaml

- 5. On the Quick create stack page, fill out the following parameters accordingly:
 - Stack name: Choose a stack name for your AWS CloudFormation stack. For example, you can call
 it <cluster-name>-nodes.
 - ClusterName: Enter the name that you used when you created your Amazon EKS cluster.

Important

This name must exactly match the name you used in Step 1: Create your Amazon EKS cluster (p. 25); otherwise, your nodes cannot join the cluster.

- ClusterControlPlaneSecurityGroup: Choose the SecurityGroups value from the AWS CloudFormation output that you generated with Create your Amazon EKS cluster VPC (p. 22).
- **NodeGroupName**: Enter a name for your node group. This name can be used later to identify the Auto Scaling node group that is created for your nodes.
- **NodeAutoScalingGroupMinSize**: Enter the minimum number of nodes that your node Auto Scaling group can scale in to.
- NodeAutoScalingGroupDesiredCapacity: Enter the desired number of nodes to scale to when your stack is created.
- NodeAutoScalingGroupMaxSize: Enter the maximum number of nodes that your node Auto Scaling group can scale out to.
- NodeInstanceType: Choose an instance type for your nodes.

Note

The supported instance types for the latest version of the Amazon VPC CNI plugin for Kubernetes are shown here. You may need to update your CNI version to take advantage of the latest supported instance types. For more information, see Amazon VPC CNI plugin for Kubernetes upgrades (p. 235).

- NodelmageIdSSMParam: Pre-populated with the Amazon EC2 Systems Manager parameter of the current recommended Amazon EKS optimized Windows Core AMI ID. If you want to use the full version of Windows, then replace <Core> with Full.
- **NodeImageId**: (Optional) If you are using your own custom AMI (instead of the Amazon EKS optimized AMI), enter a node AMI ID for your Region. If you specify a value here, it overrides any values in the **NodeImageIdSSMParam** field.
- NodeVolumeSize: Specify a root volume size for your nodes, in GiB.
- **KeyName**: Enter the name of an Amazon EC2 SSH key pair that you can use to connect using SSH into your nodes with after they launch. If you don't already have an Amazon EC2 keypair, you can create one in the AWS Management Console. For more information, see Amazon EC2 key pairs in the *Amazon EC2 User Guide for Windows Instances*.

Note

If you do not provide a keypair here, the AWS CloudFormation stack creation fails.

- **BootstrapArguments**: Specify any optional arguments to pass to the node bootstrap script, such as extra kubelet arguments using -KubeletExtraArgs.
- **DisableIMDSv1**: Each node supports the Instance Metadata Service Version 1 (IMDSv1) and IMDSv2 by default, but you can disable IMDSv1. Select **true** if you don't want any nodes in the node group, or any pods scheduled on the nodes in the node group to use IMDSv1. For more information about IMDS, see Configuring the instance metadata service.
- VpcId: Select the ID for the VPC that you created in Create your Amazon EKS cluster VPC (p. 22).
- NodeSecurityGroups: Select the security group that was created for your Linux node group in Create your Amazon EKS cluster VPC (p. 22). If your Linux nodes have more than one security group attached to them (for example, if the Linux node group was created with eksctl), specify all of them here.

Amazon EKS User Guide Windows

• Subnets: Choose the subnets that you created in Create your Amazon EKS cluster VPC (p. 22). If you created your VPC using the steps described at Creating a VPC for your Amazon EKS cluster (p. 197), then specify only the private subnets within the VPC for your nodes to launch into.

Important

If any of the subnets are public subnets, then they must have the automatic public IP address assignment setting enabled. If the setting is not enabled for the public subnet, then any nodes that you deploy to that public subnet will not be assigned a public IP address and will not be able to communicate with the cluster or other AWS services. If the subnet was deployed before March 26, 2020 using either of the Amazon EKS AWS CloudFormation VPC templates (p. 197), or by using eksctl, then automatic public IP address assignment is disabled for public subnets. For information about how to enable public IP address assignment for a subnet, see Modifying the Public IPv4 Addressing Attribute for Your Subnet. If the node is deployed to a private subnet, then it is able to communicate with the cluster and other AWS services through a NAT gateway.

Important

Ensure that the subnets you select are tagged with the cluster name. For more information, see Subnet tagging requirement (p. 204). If you have subnets in AWS Outposts, AWS Wavelength, or an AWS Local Zone, they likely are not currently tagged.

- 6. Acknowledge that the stack might create IAM resources, and then choose Create stack.
- 7. When your stack has finished creating, select it in the console and choose **Outputs**.
- 8. Record the **NodeInstanceRole** for the node group that was created. You need this when you configure your Amazon EKS Windows nodes.

To enable nodes to join your cluster

- 1. Download, edit, and apply the AWS IAM Authenticator configuration map.
 - a. Use the command that corresponds to the Region that your cluster is deployed in to download the configuration map:
 - All Regions other than China (Beijing) and China (Ningxia)

```
curl -o aws-auth-cm-windows.yaml https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/aws-auth-cm-windows.yaml
```

China (Beijing) and China (Ningxia)

```
curl -o aws-auth-cm-windows.yaml https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/aws-auth-cm-windows.yaml
```

b. Open the file with your favorite text editor. Replace the <ARN of instance role (not instance profile) of **Linux** node> and <ARN of instance role (not instance profile) of **Windows** node> snippets with the NodeInstanceRole values that you recorded for your Linux and Windows nodes, and save the file.

Important

Do not modify any other lines in this file.

```
apiVersion: v1
kind: ConfigMap
metadata:
  name: aws-auth
  namespace: kube-system
data:
  mapRoles: |
```

```
- rolearn: <ARN of instance role (not instance profile) of **Linux** node>
username: system:node:{{EC2PrivateDNSName}}
groups:
    - system:bootstrappers
    - system:nodes
- rolearn: <ARN of instance role (not instance profile) of **Windows** node>
username: system:node:{{EC2PrivateDNSName}}
groups:
    - system:bootstrappers
    - system:nodes
    - eks:kube-proxy-windows
```

c. Apply the configuration. This command may take a few minutes to finish.

```
kubectl apply -f aws-auth-cm-windows.yaml
```

Note

If you receive any authorization or resource type errors, see Unauthorized or access denied (kubectl) (p. 366) in the troubleshooting section.

If nodes fail to join the cluster, then see Nodes fail to join cluster (p. 365) in the Troubleshooting guide.

2. Watch the status of your nodes and wait for them to reach the Ready status.

```
kubectl get nodes --watch
```

- 3. (Optional) Deploy a sample application (p. 85) to test your cluster and Windows nodes.
- 4. (Optional) If the AmazonEKS_CNI_Policy managed IAM policy is attached to your the section called "Node IAM role" (p. 332), we recommend assigning it to an IAM role that you associate to the Kubernetes aws-node service account instead. For more information, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).
- 5. (Optional) If you plan to assign IAM roles to all of your Kubernetes service accounts so that pods only have the minimum permissions that they need, and no pods in the cluster require access to the Amazon EC2 instance metadata service (IMDS) for other reasons, such as retrieving the current Region, then we recommend blocking pod access to IMDS. For more information, see the section called "IAM roles for service accounts" (p. 336) and the section called "Restricting access to the instance profile" (p. 349).

Self-managed node updates

When a new Amazon EKS optimized AMI is released, you should consider replacing the nodes in your self-managed node group with the new AMI. Likewise, if you have updated the Kubernetes version for your Amazon EKS cluster, you should also update the nodes to use nodes with the same Kubernetes version.

Important

This topic covers node updates for self-managed nodes. If you are using Managed node groups (p. 100), see Updating a managed node group (p. 108).

There are two basic ways to update self-managed node groups in your clusters to use a new AMI:

Migrating to a new node group (p. 129) – Create a new node group and migrate your pods to that
group. Migrating to a new node group is more graceful than simply updating the AMI ID in an existing
AWS CloudFormation stack, because the migration process taints the old node group as NoSchedule
and drains the nodes after a new stack is ready to accept the existing pod workload.

 Updating an existing self-managed node group (p. 133) – Update the AWS CloudFormation stack for an existing node group to use the new AMI. This method is not supported for node groups that were created with eksct1.

Migrating to a new node group

This topic helps you to create a new node group, gracefully migrate your existing applications to the new group, and then remove the old node group from your cluster. You can migrate to a new node group using eksctl (p. 129) or the AWS Management Console (p. 130).

To migrate your applications to a new node group with eksctl

This procedure requires eksctl version 0.33.0 or later. You can check your version with the following command:

```
eksctl version
```

For more information on installing or upgrading eksct1, see Installing or upgrading eksct1 (p. 298).

Note

This procedure only works for clusters and node groups that were created with eksctl.

 Retrieve the name of your existing node groups, replacing <my-cluster> (including <>) with your cluster name.

```
eksctl get nodegroups --cluster=<my-cluster>
```

Output:

```
CLUSTER NODEGROUP CREATED MIN SIZE MAX SIZE

DESIRED CAPACITY INSTANCE TYPE IMAGE ID

default standard-nodes 2019-05-01T22:26:58Z 1 4 3

t3.medium ami-05a71d034119ffc12
```

2. Launch a new node group with eksctl with the following command, substituting the <example values> (including <>) with your own values. If you plan to assign IAM roles to all of your Kubernetes service accounts so that pods only have the minimum permissions that they need, and no pods in the cluster require access to the Amazon EC2 instance metadata service (IMDS) for other reasons, such as retrieving the current Region, then we recommend blocking pod access to IMDS. For more information, see the section called "IAM roles for service accounts" (p. 336) and the section called "Restricting access to the instance profile" (p. 349). If you want to block pod access to IMDS, then add the --disable-pod-imds option to the following command.

Note

For more available flags and their descriptions, see https://eksctl.io/.

```
eksctl create nodegroup \
--cluster <my-cluster> \
--version <1.18> \
--name <standard-nodes-new> \
--node-type <t3.medium> \
--nodes <3> \
--nodes-min <1> \
--nodes-max <4> \
--node-ami auto
```

3. When the previous command completes, verify that all of your nodes have reached the Ready state with the following command:

```
kubectl get nodes
```

4. Delete the original node group with the following command, replacing the <example values> (including <>) with your cluster and node group names:

```
eksctl delete nodegroup --cluster <my-cluster> --name <standard-nodes>
```

To migrate your applications to a new node group with the AWS Management Console

- 1. Launch a new node group by following the steps outlined in Launching self-managed Amazon Linux nodes (p. 116).
- 2. When your stack has finished creating, select it in the console and choose Outputs.
- 3. Record the **NodeInstanceRole** for the node group that was created. You need this to add the new Amazon EKS nodes to your cluster.

Note

If you have attached any additional IAM policies to your old node group IAM role, such as adding permissions for the Kubernetes Cluster Autoscaler, you should attach those same policies to your new node group IAM role to maintain that functionality on the new group.

- 4. Update the security groups for both node groups so that they can communicate with each other. For more information, see Amazon EKS security group considerations (p. 204).
 - a. Record the security group IDs for both node groups. This is shown as the **NodeSecurityGroup** value in the AWS CloudFormation stack outputs.

You can use the following AWS CLI commands to get the security group IDs from the stack names. In these commands, oldNodes is the AWS CloudFormation stack name for your older node stack, and newNodes is the name of the stack that you are migrating to.

```
oldNodes="<old_node_CFN_stack_name>"
newNodes="<new_node_CFN_stack_name>"

oldSecGroup=$(aws cloudformation describe-stack-resources --stack-name $oldNodes \
    --query 'StackResources[?
ResourceType==`AWS::EC2::SecurityGroup`].PhysicalResourceId' \
    --output text)
newSecGroup=$(aws cloudformation describe-stack-resources --stack-name $newNodes \
    --query 'StackResources[?
ResourceType==`AWS::EC2::SecurityGroup`].PhysicalResourceId' \
    --output text)
```

b. Add ingress rules to each node security group so that they accept traffic from each other.

The following AWS CLI commands add ingress rules to each security group that allow all traffic on all protocols from the other security group. This configuration allows pods in each node group to communicate with each other while you are migrating your workload to the new group.

```
aws ec2 authorize-security-group-ingress --group-id $oldSecGroup \
   --source-group $newSecGroup --protocol -1
aws ec2 authorize-security-group-ingress --group-id $newSecGroup \
   --source-group $oldSecGroup --protocol -1
```

5. Edit the aws-auth configmap to map the new node instance role in RBAC.

```
kubectl edit configmap -n kube-system aws-auth
```

Add a new mapRoles entry for the new node group.

Replace the <ARN of instance role (not instance profile)> snippet with the **NodeInstanceRole** value that you recorded in a previous step (p. 130), then save and close the file to apply the updated configmap.

6. Watch the status of your nodes and wait for your new nodes to join your cluster and reach the Ready status.

```
kubectl get nodes --watch
```

(Optional) If you are using the Kubernetes Cluster Autoscaler, scale the deployment down to 0 replicas to avoid conflicting scaling actions.

```
kubectl scale deployments/cluster-autoscaler --replicas=0 -n kube-system
```

8. Use the following command to taint each of the nodes that you want to remove with NoSchedule so that new pods are not scheduled or rescheduled on the nodes you are replacing:

```
kubectl taint nodes <node_name> key=value:NoSchedule
```

If you are upgrading your nodes to a new Kubernetes version, you can identify and taint all of the nodes of a particular Kubernetes version (in this case, 1.16) with the following code snippet.

```
K8S_VERSION=<1.16>
nodes=$(kubectl get nodes -o jsonpath="{.items[?(@.status.nodeInfo.kubeletVersion==\"v
$K8S_VERSION\")].metadata.name}")
for node in ${nodes[@]}
do
    echo "Tainting $node"
    kubectl taint nodes $node key=value:NoSchedule
done
```

9. Determine your cluster's DNS provider.

```
kubectl get deployments -1 k8s-app=kube-dns -n kube-system
```

Output (this cluster is using kube-dns for DNS resolution, but your cluster may return coredns instead):

```
NAME DESIRED CURRENT UP-TO-DATE AVAILABLE AGE <kube-dns> 1 1 1 1 31m
```

10. If your current deployment is running fewer than two replicas, scale out the deployment to two replicas. Replace <kube-dns> with coredns if your previous command output returned that instead.

```
kubectl scale deployments/<kube-dns> --replicas=2 -n kube-system
```

11. Drain each of the nodes that you want to remove from your cluster with the following command:

```
kubectl drain <node_name> --ignore-daemonsets --delete-local-data
```

If you are upgrading your nodes to a new Kubernetes version, you can identify and drain all of the nodes of a particular Kubernetes version (in this case, 1.16) with the following code snippet.

```
K8S_VERSION=<1.16>
nodes=$(kubectl get nodes -o jsonpath="{.items[?(@.status.nodeInfo.kubeletVersion==\"v
$K8S_VERSION\")].metadata.name}")
for node in ${nodes[@]}
do
    echo "Draining $node"
    kubectl drain $node --ignore-daemonsets --delete-local-data
done
```

12. After your old nodes have finished draining, revoke the security group ingress rules you authorized earlier, and then delete the AWS CloudFormation stack to terminate the instances.

Note

If you have attached any additional IAM policies to your old node group IAM role, such as adding permissions for the Kubernetes Cluster Autoscaler), you must detach those additional policies from the role before you can delete your AWS CloudFormation stack.

a. Revoke the ingress rules that you created for your node security groups earlier. In these commands, oldNodes is the AWS CloudFormation stack name for your older node stack, and newNodes is the name of the stack that you are migrating to.

```
oldNodes="<old_node_CFN_stack_name>"
newNodes="<new_node_CFN_stack_name>"

oldSecGroup=$(aws cloudformation describe-stack-resources --stack-name $oldNodes \
    --query 'StackResources[?
ResourceType==`AWS::EC2::SecurityGroup`].PhysicalResourceId' \
    --output text)
newSecGroup=$(aws cloudformation describe-stack-resources --stack-name $newNodes \
    --query 'StackResources[?
ResourceType==`AWS::EC2::SecurityGroup`].PhysicalResourceId' \
    --output text)
aws ec2 revoke-security-group-ingress --group-id $oldSecGroup \
    --source-group $newSecGroup --protocol -1
aws ec2 revoke-security-group-ingress --group-id $newSecGroup \
    --source-group $oldSecGroup --protocol -1
```

- b. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
- c. Select your old node stack.
- d. Choose **Actions**, then **Delete stack**.
- Edit the aws-auth configmap to remove the old node instance role from RBAC.

```
kubectl edit configmap -n kube-system aws-auth
```

Delete the mapRoles entry for the old node group.

Save and close the file to apply the updated configmap.

14. (Optional) If you are using the Kubernetes Cluster Autoscaler, scale the deployment back to one replica.

Note

You must also tag your new Auto Scaling group appropriately (for example, k8s.io/cluster-autoscaler/enabled, k8s.io/cluster-autoscaler/<YOUR CLUSTER NAME>) and update your Cluster Autoscaler deployment's command to point to the newly tagged Auto Scaling group. For more information, see Cluster Autoscaler on AWS.

```
kubectl scale deployments/cluster-autoscaler --replicas=1 -n kube-system
```

- 15. (Optional) Verify that you are using the latest version of the Amazon VPC CNI plugin for Kubernetes. You may need to update your CNI version to take advantage of the latest supported instance types. For more information, see Amazon VPC CNI plugin for Kubernetes upgrades (p. 235).
- 16. If your cluster is using kube-dns for DNS resolution (see previous step (p. 131)), scale in the kube-dns deployment to one replica.

```
kubectl scale deployments/kube-dns --replicas=1 -n kube-system
```

Updating an existing self-managed node group

This topic helps you to update an existing AWS CloudFormation self-managed node stack with a new AMI. You can use this procedure to update your nodes to a new version of Kubernetes following a cluster update, or you can update to the latest Amazon EKS optimized AMI for an existing Kubernetes version.

Important

This topic covers node updates for self-managed nodes. If you are using Managed node groups (p. 100), see Updating a managed node group (p. 108).

The latest default Amazon EKS node AWS CloudFormation template is configured to launch an instance with the new AMI into your cluster before removing an old one, one at a time. This configuration ensures that you always have your Auto Scaling group's desired count of active instances in your cluster during the rolling update.

Note

This method is not supported for node groups that were created with eksctl. If you created your cluster or node group with eksctl, see Migrating to a new node group (p. 129).

To update an existing node group

1. Determine your cluster's DNS provider.

kubectl get deployments -1 k8s-app=kube-dns -n kube-system

Output (this cluster is using kube-dns for DNS resolution, but your cluster may return coredns instead):

```
NAME DESIRED CURRENT UP-TO-DATE AVAILABLE AGE <kube-dns> 1 1 1 1 31m
```

2. If your current deployment is running fewer than two replicas, scale out the deployment to two replicas. Substitute coredns for kube-dns if your previous command output returned that instead.

```
kubectl scale deployments/<kube-dns> --replicas=2 -n kube-system
```

3. (Optional) If you are using the Kubernetes Cluster Autoscaler, scale the deployment down to zero replicas to avoid conflicting scaling actions.

```
kubectl scale deployments/cluster-autoscaler --replicas=0 -n kube-system
```

- 4. Determine the instance type and desired instance count of your current node group. You will enter these values later when you update the AWS CloudFormation template for the group.
 - a. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
 - b. Choose **Launch Configurations** in the left navigation, and note the instance type for your existing node launch configuration.
 - c. Choose **Auto Scaling Groups** in the left navigation and note the **Desired** instance count for your existing node Auto Scaling group.
- 5. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
- 6. Select your node group stack, and then choose **Update**.
- 7. Select Replace current template and select Amazon S3 URL.
- 8. For **Amazon S3 URL**, paste the URL that corresponds to the Region that your cluster is in into the text area to ensure that you are using the latest version of the node AWS CloudFormation template, and then choose **Next**:
 - All Regions other than China (Beijing) and China (Ningxia)

```
https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/amazon-eks-nodegroup.yaml
```

China (Beijing) and China (Ningxia)

 $\verb|https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/amazon-eks-nodegroup.yaml|$

- 9. On the Specify stack details page, fill out the following parameters, and choose Next:
 - NodeAutoScalingGroupDesiredCapacity Enter the desired instance count that you recorded in a previous step (p. 134), or enter a new desired number of nodes to scale to when your stack is updated.
 - NodeAutoScalingGroupMaxSize Enter the maximum number of nodes to which your node Auto
 Scaling group can scale out. This value must be at least one node greater than your desired
 capacity so that you can perform a rolling update of your nodes without reducing your node
 count during the update.
 - NodeInstanceType Choose the instance type your recorded in a previous step (p. 134), or choose a different instance type for your nodes. Each Amazon EC2 instance type supports a

maximum number of elastic network interfaces (ENIs) and each ENI supports a maximum number of IP addresses. Since each worker node and pod is assigned its own IP address it's important to choose an instance type that will support the maximum number of pods that you want to run on each worker node. For a list of the number of ENIs and IP addresses supported by instance types, see IP addresses per network interface per instance type. For example, the m5.large instance type supports a maximum of 30 IP addresses for the worker node and pods. Some instance types might not be available in all Regions.

Note

The supported instance types for the latest version of the Amazon VPC CNI plugin for Kubernetes are shown here. You may need to update your CNI version to take advantage of the latest supported instance types. For more information, see Amazon VPC CNI plugin for Kubernetes upgrades (p. 235).

Important

Some instance types might not be available in all Regions.

NodeImageIdSSMParam – The Amazon EC2 Systems Manager parameter of the AMI ID that you
want to update to. The following value uses the latest Amazon EKS optimized AMI for Kubernetes
version 1.18.

/aws/service/eks/optimized-ami/<1.18>/<amazon-linux-2>/recommended/image_id

You can replace 1.18 with any supported Kubernetes version (p. 73). If you want to use the Amazon EKS optimized accelerated AMI, then replace <amazon-linux-2> with <amazon-linux-2-gpu>.

Note

Using the Amazon EC2 Systems Manager parameter enables you to update your nodes in the future without having to lookup and specify an AMI ID. If your AWS CloudFormation stack is using this value, any stack update will always launch the latest recommended Amazon EKS optimized AMI for your specified Kubernetes version, even if you don't change any values in the template.

• Nodelmageld - To use your own custom AMI, enter the ID for the AMI to use.

Important

This value overrides any value specified for **NodeImageIdSSMParam**. If you want to use the **NodeImageIdSSMParam** value, ensure that the value for **NodeImageId** is blank.

- **DisableIMDSv1** Each node supports the Instance Metadata Service Version 1 (IMDSv1) and IMDSv2 by default, but you can disable IMDSv1. Select **true** if you don't want any nodes in the node group, or any pods scheduled on the nodes in the node group to use IMDSv1. For more information about IMDS, see Configuring the instance metadata service. If you've implemented IAM roles for service accounts, have assigned necessary permissions directly to all pods that require access to AWS services, and no pods in your cluster require access to IMDS for other reasons, such as retrieving the current Region, then you can also disable access to IMDSv2 for pods that don't use host networking. For more information, see the section called "Restricting access to the instance profile" (p. 349).
- 10. (Optional) On the Options page, tag your stack resources. Choose Next.
- 11. On the **Review** page, review your information, acknowledge that the stack might create IAM resources, and then choose **Update stack**.

Note

The update of each node in the cluster takes several minutes. Wait for the update of all nodes to complete before performing the next steps.

12. If your cluster's DNS provider is kube-dns, scale in the kube-dns deployment to one replica.

kubectl scale deployments/kube-dns --replicas=1 -n kube-system

Amazon EKS User Guide AWS Fargate

 (Optional) If you are using the Kubernetes Cluster Autoscaler, scale the deployment back to your desired amount of replicas.

```
kubectl scale deployments/cluster-autoscaler --replicas=<1> -n kube-system
```

14. (Optional) Verify that you are using the latest version of the Amazon VPC CNI plugin for Kubernetes. You may need to update your CNI version to take advantage of the latest supported instance types. For more information, see Amazon VPC CNI plugin for Kubernetes upgrades (p. 235).

AWS Fargate

This topic discusses using Amazon EKS to run Kubernetes pods on AWS Fargate.

AWS Fargate is a technology that provides on-demand, right-sized compute capacity for containers. With AWS Fargate, you no longer have to provision, configure, or scale groups of virtual machines to run containers. This removes the need to choose server types, decide when to scale your node groups, or optimize cluster packing.

You can control which pods start on Fargate and how they run with Fargate profiles (p. 142), which are defined as part of your Amazon EKS cluster.

Amazon EKS integrates Kubernetes with AWS Fargate by using controllers that are built by AWS using the upstream, extensible model provided by Kubernetes. These controllers run as part of the Amazon EKS managed Kubernetes control plane and are responsible for scheduling native Kubernetes pods onto Fargate. The Fargate controllers include a new scheduler that runs alongside the default Kubernetes scheduler in addition to several mutating and validating admission controllers. When you start a pod that meets the criteria for running on Fargate, the Fargate controllers running in the cluster recognize, update, and schedule the pod onto Fargate.

Each pod running on Fargate has its own isolation boundary and does not share the underlying kernel, CPU resources, memory resources, or elastic network interface with another pod.

This topic describes the different components of pods running on Fargate, and calls out special considerations for using Fargate with Amazon EKS.

AWS Fargate with Amazon EKS is currently available in the following Regions:

Region name	Region (Availability Zone constraint)
US East (Ohio)	us-east-2
US East (N. Virginia)	us-east-1
US West (N. California)	us-west-1
US West (Oregon)	us-west-2
Asia Pacific (Hong Kong)	ap-east-1
Asia Pacific (Mumbai)	ap-south-1
Asia Pacific (Seoul)	ap-northeast-2
Asia Pacific (Singapore)	ap-southeast-1
Asia Pacific (Sydney)	ap-southeast-2
Asia Pacific (Tokyo)	ap-northeast-1 (apne1-az1, apne1-az2, and apne1-az4 only)

Region name	Region (Availability Zone constraint)	
Canada (Central)	ca-central-1 (cac1-az1 and cac1-az2 only)	
Europe (Frankfurt)	eu-central-1	
Europe (Ireland)	eu-west-1	
Europe (London)	eu-west-2	
Europe (Paris)	eu-west-3	
Europe (Stockholm)	eu-north-1	
South America (São Paulo)	sa-east-1	
Middle East (Bahrain)	me-south-1	

AWS Fargate considerations

Here's some things to consider about using Fargate on Amazon EKS.

- Classic Load Balancers and Network Load Balancers can be used with IP targets only. You can also use AWS Application Load Balancers with Fargate. For more information, see the section called "Load balancer IP targets" (p. 262) and the section called "Application load balancing" (p. 267).
- Pods must match a Fargate profile at the time that they are scheduled in order to run on Fargate. Pods
 which do not match a Fargate profile may be stuck as Pending. If a matching Fargate profile exists,
 you can delete pending pods that you have created to reschedule them onto Fargate.
- Daemonsets are not supported on Fargate. If your application requires a daemon, you should reconfigure that daemon to run as a sidecar container in your pods.
- Privileged containers are not supported on Fargate.
- · Pods running on Fargate cannot specify HostPort or HostNetwork in the pod manifest.
- · GPUs are currently not available on Fargate.
- You cannot use Security groups for pods (p. 213) with pods running on Fargate.
- Pods running on Fargate are only supported on private subnets (with NAT gateway access to AWS services, but not a direct route to an Internet Gateway), so your cluster's VPC must have private subnets available. For clusters without outbound internet access, see Private clusters (p. 92).
- You can use the Vertical Pod Autoscaler (p. 252) to initially right size the CPU and memory for your
 Fargate pods, and then use the Horizontal Pod Autoscaler (p. 257) to scale those pods. If you want
 the Vertical Pod Autoscaler to automatically re-deploy pods to Fargate with larger CPU and memory
 combinations, then set the Vertical Pod Autoscaler's mode to either Auto or Recreate to ensure
 correct functionality. For more information, see the Vertical Pod Autoscaler documentation on GitHub.
- DNS resolution and DNS hostnames must be enabled for your VPC. For more information, see Viewing and updating DNS support for your VPC.
- Fargate runs each pod in a VM-isolated environment without sharing resources with other pods.
 However, because Kubernetes is a single-tenant orchestrator, Fargate cannot guarantee pod-level
 security isolation. You should run sensitive workloads or untrusted workloads that need complete
 security isolation using separate Amazon EKS clusters.
- Fargate profiles support specifying subnets from VPC secondary CIDR blocks. You may want to specify
 a secondary CIDR block because there are a limited number of IP addresses available in a subnet. As a
 result, there are a limited number of pods that can be created in the cluster. Using different subnets
 for pods allows you to increase the number of available IP addresses. For more information, see
 Adding IPv4 CIDR blocks to a VPC.

Getting started with AWS Fargate using Amazon EKS

This topic helps you to get started running pods on AWS Fargate with your Amazon EKS cluster.

Note

AWS Fargate with Amazon EKS is currently only available in the following Regions:

Region name	Region (Availability Zone constraint)
US East (Ohio)	us-east-2
US East (N. Virginia)	us-east-1
US West (N. California)	us-west-1
US West (Oregon)	us-west-2
Asia Pacific (Hong Kong)	ap-east-1
Asia Pacific (Mumbai)	ap-south-1
Asia Pacific (Seoul)	ap-northeast-2
Asia Pacific (Singapore)	ap-southeast-1
Asia Pacific (Sydney)	ap-southeast-2
Asia Pacific (Tokyo)	ap-northeast-1 (apne1-az1, apne1-az2, and apne1-az4 only)
Canada (Central)	ca-central-1 (cac1-az1 and cac1-az2 only)
Europe (Frankfurt)	eu-central-1
Europe (Ireland)	eu-west-1
Europe (London)	eu-west-2
Europe (Paris)	eu-west-3
Europe (Stockholm)	eu-north-1
South America (São Paulo)	sa-east-1
Middle East (Bahrain)	me-south-1

If you restrict access to your cluster's public endpoint using CIDR blocks, it is recommended that you also enable private endpoint access so that Fargate pods can communicate with the cluster. Without the private endpoint enabled, the CIDR blocks that you specify for public access must include the egress sources from your VPC. For more information, see Amazon EKS cluster endpoint access control (p. 56).

(Optional) Create a cluster

Prerequisite

An existing cluster in a supported Region (p. 138). If you do not already have an Amazon EKS cluster, you can create one with the following eksctl command.

Note

This procedure requires eksctl version 0.33.0 or later. You can check your version with the following command:

Amazon EKS User Guide Getting started with Fargate

eksctl version

For more information on installing or upgrading eksctl, see Installing or upgrading eksctl (p. 298).

```
eksctl create cluster --name <my-cluster> --version <1.18> --fargate
```

Adding the --fargate option in the command above creates a cluster without a node group. However, eksctl creates a pod execution role, a Fargate profile for the default and kube-system namespaces, and it patches the coredns deployment so that it can run on Fargate.

Ensure that existing nodes can communicate with Fargate pods

If you are working with a new cluster with no nodes, or a cluster with only managed node groups (p. 100), you can skip to Create a Fargate pod execution role (p. 139).

If you are working with an existing cluster that already has nodes associated with it, you need to make sure that pods on these nodes can communicate freely with pods running on Fargate. Pods running on Fargate are automatically configured to use the cluster security group for the cluster that they are associated with. You must ensure that any existing nodes in your cluster can send and receive traffic to and from the cluster security group. Managed node groups (p. 100) are automatically configured to use the cluster security group as well, so you do not need to modify or check them for this compatibility.

For existing node groups that were created with <code>eksctl</code> or the Amazon EKS managed AWS CloudFormation templates, you can add the cluster security group to the nodes manually, or you can modify the node group's Auto Scaling group launch template to attach the cluster security group to the instances. For more information, see Changing an instance's security groups in the Amazon VPC User Guide.

You can check for a cluster security group for your cluster in the AWS Management Console under the cluster's **Networking** section, or with the following AWS CLI command:

```
aws eks describe-cluster --name <cluster_name> --query
cluster.resourcesVpcConfig.clusterSecurityGroupId
```

Create a Fargate pod execution role

When your cluster creates pods on AWS Fargate, the components running on the Fargate infrastructure need to make calls to AWS APIs on your behalf to do things like pull container images from Amazon ECR or route logs to other AWS services. The Amazon EKS pod execution role provides the IAM permissions to do this.

Note

If you created your cluster with eksctl using the --fargate option, then your cluster already has a pod execution role and you can skip ahead to Create a Fargate profile for your cluster (p. 140). Similarly, if you use eksctl to create your Fargate profiles, eksctl will create your pod execution role if one does not already exist.

When you create a Fargate profile, you must specify a pod execution role to use with your pods. This role is added to the cluster's Kubernetes Role based access control (RBAC) for authorization. This allows the kubelet that is running on the Fargate infrastructure to register with your Amazon EKS cluster so that it can appear in your cluster as a node. For more information, see Pod execution role (p. 334).

Important

The containers running in the Fargate pod can't assume the IAM permissions associated with a pod execution role. To give the containers in your Fargate pod permissions to access other AWS services, you must use IAM roles for service accounts (p. 336).

Amazon EKS User Guide Getting started with Fargate

To create an AWS Fargate pod execution role with the AWS Management Console

- 1. Open the IAM console at https://console.aws.amazon.com/iam/.
- 2. Choose Roles, then Create role.
- Choose EKS from the list of services, EKS Fargate pod for your use case, and then Next: Permissions.
- Choose Next: Tags.
- 5. (Optional) Add metadata to the role by attaching tags as key–value pairs. For more information about using tags in IAM, see Tagging IAM Entities in the IAM User Guide.
- 6. Choose Next: Review.
- 7. For **Role name**, enter a unique name for your role, such as AmazonEKSFargatePodExecutionRole, then choose **Create role**.

Create a Fargate profile for your cluster

Before you can schedule pods running on Fargate in your cluster, you must define a Fargate profile that specifies which pods should use Fargate when they are launched. For more information, see AWS Fargate profile (p. 142).

Note

If you created your cluster with eksctl using the --fargate option, then a Fargate profile has already been created for your cluster with selectors for all pods in the kube-system and default namespaces. Use the following procedure to create Fargate profiles for any other namespaces you would like to use with Fargate.

You can create a Fargate profile using eksct1 (p. 140) or the AWS Management Console (p. 140).

To create a Fargate profile for a cluster with eksctl

This procedure requires eksctl version 0.33.0 or later. You can check your version with the following command:

eksctl version

For more information on installing or upgrading eksct1, see Installing or upgrading eksct1 (p. 298).

• Create your Fargate profile with the following eksctl command, replacing the <variable text> with your own values. You must specify a namespace, but the labels option is not required.

eksctl create fargateprofile --cluster <cluster_name> --name <fargate_profile_name> -namespace <kubernetes_namespace> --labels <key=value>

To create a Fargate profile for a cluster with the AWS Management Console

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. Choose the cluster to create a Fargate profile for.
- 3. Under Fargate profiles, choose Add Fargate profile.
- 4. On the Configure Fargate profile page, enter the following information and choose Next.
 - a. For **Name**, enter a unique name for your Fargate profile.
 - b. For **Pod execution role**, choose the pod execution role to use with your Fargate profile. Only IAM roles with the eks-fargate-pods.amazonaws.com service principal are shown. If you

Amazon EKS User Guide Getting started with Fargate

do not see any roles listed here, you must create one. For more information, see Pod execution role (p. 334).

- c. For **Subnets**, choose the subnets to use for your pods. By default, all subnets in your cluster's VPC are selected. Only private subnets are supported for pods running on Fargate; you must deselect any public subnets.
- d. For **Tags**, you can optionally tag your Fargate profile. These tags do not propagate to other resources associated with the profile, such as its pods.
- 5. On the Configure pods selection page, enter the following information and choose Next.
 - a. For Namespace, enter a namespace to match for pods, such as kube-system or default.
 - b. (Optional) Add Kubernetes labels to the selector that pods in the specified namespace must have to match the selector. For example, you could add the label infrastructure: fargate to the selector so that only pods in the specified namespace that also have the infrastructure: fargate Kubernetes label match the selector.
- 6. On the **Review and create** page, review the information for your Fargate profile and choose **Create**.

(Optional) Update CoreDNS

By default, CoreDNS is configured to run on Amazon EC2 infrastructure on Amazon EKS clusters. If you want to *only* run your pods on Fargate in your cluster, you need to modify the CoreDNS deployment to remove the eks.amazonaws.com/compute-type: ec2 annotation. You would also need to create a Fargate profile to target the CoreDNS pods. The following Fargate profile JSON file does this.

Note

If you created your cluster with eksctl using the --fargate option, then coredns has already been patched to run on Fargate and you can skip ahead to Next steps (p. 142).

```
{
    "fargateProfileName": "coredns",
    "clusterName": "<dev>",
    "podExecutionRoleArn": "<arn:aws:iam::111122223333:role/
AmazonEKSFargatePodExecutionRole>",
    "subnets": [
        "subnet-<0b64dd020cdff3864>",
        "subnet-<00b03756df55e2b87>",
        "subnet-<0418fcb68ed294abf>"
    ٦,
    "selectors": [
        {
            "namespace": "kube-system",
            "labels": {
                "k8s-app": "kube-dns"
        }
    ]
}
```

You could apply this Fargate profile to your cluster with the following AWS CLI command. First, create a file called coredns.json and paste the JSON file from the previous step into it, replacing the <variable text> with your own cluster values.

```
aws eks create-fargate-profile --cli-input-json file://coredns.json
```

Then, use the following kubectl command to remove the eks.amazonaws.com/compute-type : ec2 annotation from the CoreDNS pods.

```
kubectl patch deployment coredns -n kube-system --type json \
```

Amazon EKS User Guide Fargate profile

```
-p='[{"op": "remove", "path": "/spec/template/metadata/annotations/
eks.amazonaws.com~1compute-type"}]'
```

Next steps

- You can start migrating your existing applications to run on Fargate with the following workflow.
 - 1. Create a Fargate profile (p. 143) that matches your application's Kubernetes namespace and Kubernetes labels.
 - 2. Delete and re-create any existing pods so that they are scheduled on Fargate. For example, the following command triggers a rollout of the coredns Deployment. You can modify the namespace and deployment type to update your specific pods.

```
kubectl rollout restart -n <kube-system> <deployment coredns>
```

- Deploy the Application load balancing on Amazon EKS (p. 267) to allow Ingress objects for your pods running on Fargate.
- You can use the Vertical Pod Autoscaler (p. 252) to initially right size the CPU and memory for your
 Fargate pods, and then use the Horizontal Pod Autoscaler (p. 257) to scale those pods. If you want
 the Vertical Pod Autoscaler to automatically re-deploy pods to Fargate with larger CPU and memory
 combinations, then set the Vertical Pod Autoscaler's mode to either Auto or Recreate to ensure
 correct functionality. For more information, see the Vertical Pod Autoscaler documentation on GitHub.

AWS Fargate profile

Before you can schedule pods on Fargate in your cluster, you must define at least one Fargate profile that specifies which pods should use Fargate when they are launched.

The Fargate profile allows an administrator to declare which pods run on Fargate. This declaration is done through the profile's selectors. Each profile can have up to five selectors that contain a namespace and optional labels. You must define a namespace for every selector. The label field consists of multiple optional key-value pairs. Pods that match a selector (by matching a namespace for the selector and all of the labels specified in the selector) are scheduled on Fargate. If a namespace selector is defined without any labels, Amazon EKS will attempt to schedule all pods that run in that namespace onto Fargate using the profile. If a to-be-scheduled pod matches any of the selectors in the Fargate profile, then that pod is scheduled on Fargate.

When you create a Fargate profile, you must specify a pod execution role for the Amazon EKS components that run on the Fargate infrastructure using the profile. This role is added to the cluster's Kubernetes Role Based Access Control (RBAC) for authorization so that the kubelet that is running on the Fargate infrastructure can register with your Amazon EKS cluster and appear in your cluster as a node. The pod execution role also provides IAM permissions to the Fargate infrastructure to allow read access to Amazon ECR image repositories. For more information, see Pod execution role (p. 334).

Fargate profiles are immutable. However, you can create a new updated profile to replace an existing profile and then delete the original after the updated profile has finished creating.

Note

Any pods that are running using a Fargate profile will be stopped and put into pending when the profile is deleted.

If any Fargate profiles in a cluster are in the DELETING status, you must wait for that Fargate profile to finish deleting before you can create any other profiles in that cluster.

Fargate profile components

The following components are contained in a Fargate profile.

```
{
    "fargateProfileName": "",
    "clusterName": "",
    "podExecutionRoleArn": "",
    "subnets": [
    ٦,
    "selectors": [
        {
            "namespace": "",
            "labels": {
                 "KeyName": ""
        }
    "clientRequestToken": "",
    "tags": {
        "KeyName": ""
}
```

Pod execution role

When your cluster creates pods on AWS Fargate, the kubelet that is running on the Fargate infrastructure needs to make calls to AWS APIs on your behalf, for example, to pull container images from Amazon ECR. The Amazon EKS pod execution role provides the IAM permissions to do this.

When you create a Fargate profile, you must specify a pod execution role to use with your pods. This role is added to the cluster's Kubernetes Role Based Access Control (RBAC) for authorization, so that the kubelet that is running on the Fargate infrastructure can register with your Amazon EKS cluster and appear in your cluster as a node. For more information, see Pod execution role (p. 334).

Subnets

The IDs of subnets to launch pods into that use this profile. At this time, pods running on Fargate are not assigned public IP addresses, so only private subnets (with no direct route to an Internet Gateway) are accepted for this parameter.

Selectors

The selectors to match for pods to use this Fargate profile. Each selector must have an associated namespace. Optionally, you can also specify labels for a namespace. You may specify up to five selectors in a Fargate profile. A pod only needs to match one selector to run using the Fargate profile.

Namespace

You must specify a namespace for a selector. The selector only matches pods that are created in this namespace, but you can create multiple selectors to target multiple namespaces.

Labels

You can optionally specify Kubernetes labels to match for the selector. The selector only matches pods that have all of the labels that are specified in the selector.

Creating a Fargate profile

This topic helps you to create a Fargate profile. Your cluster must be in a supported Region (p. 136). You also must have created a pod execution role to use for your Fargate profile. For more information,

Amazon EKS User Guide Fargate profile

see Pod execution role (p. 334). Pods running on Fargate are only supported on private subnets (with NAT gateway access to AWS services, but not a direct route to an Internet Gateway), so your cluster's VPC must have private subnets available. You can create a profile with eksctl (p. 144) or the AWS Management Console (p. 144).

To create a Fargate profile for a cluster with eksctl

This procedure requires eksctl version 0.33.0 or later. You can check your version with the following command:

eksctl version

For more information on installing or upgrading eksct1, see Installing or upgrading eksct1 (p. 298).

• Create your Fargate profile with the following eksctl command, replacing the <variable text> with your own values. You must specify a namespace, but the labels option is not required.

eksctl create fargateprofile --cluster <cluster_name> --name <fargate_profile_name> -namespace <kubernetes_namespace> --labels <key=value>

To create a Fargate profile for a cluster with the AWS Management Console

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. Choose the cluster to create a Fargate profile for.
- 3. Under Fargate profiles, choose Add Fargate profile.
- 4. On the Configure Fargate profile page, enter the following information and choose Next.
 - a. For **Name**, enter a unique name for your Fargate profile.
 - b. For **Pod execution role**, choose the pod execution role to use with your Fargate profile. Only IAM roles with the eks-fargate-pods.amazonaws.com service principal are shown. If you do not see any roles listed here, you must create one. For more information, see Pod execution role (p. 334).
 - c. For **Subnets**, choose the subnets to use for your pods. By default, all subnets in your cluster's VPC are selected. Only private subnets are supported for pods running on Fargate; you must deselect any public subnets.
 - d. For **Tags**, you can optionally tag your Fargate profile. These tags do not propagate to other resources associated with the profile, such as its pods.
- 5. On the Configure pods selection page, enter the following information and choose Next.
 - a. For Namespace, enter a namespace to match for pods, such as kube-system or default.
 - b. (Optional) Add Kubernetes labels to the selector that pods in the specified namespace must have to match the selector. For example, you could add the label infrastructure: fargate to the selector so that only pods in the specified namespace that also have the infrastructure: fargate Kubernetes label match the selector.
- 6. On the Review and create page, review the information for your Fargate profile and choose Create.

Deleting a Fargate profile

This topic helps you to delete a Fargate profile.

When you delete a Fargate profile, any pods that were scheduled onto Fargate with the profile are deleted. If those pods match another Fargate profile, then they are scheduled on Fargate with that

Amazon EKS User Guide Fargate pod configuration

profile. If they no longer match any Fargate profiles, then they are not scheduled onto Fargate and may remain as pending.

Only one Fargate profile in a cluster can be in the DELETING status at a time. You must wait for a Fargate profile to finish deleting before you can delete any other profiles in that cluster.

To delete a Fargate profile from a cluster

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. Choose the cluster that you want to delete the Fargate profile from.
- 3. Choose the Fargate profile to delete and then **Delete**.
- 4. On the **Delete <cluster_name>** page, type the name of the cluster and choose **Confirm** to delete.

Fargate pod configuration

This section describes some of the unique pod configuration details for running Kubernetes pods on AWS Fargate.

Pod CPU and memory

Kubernetes allows you to define requests, a minimum amount of vCPU and memory resources that are allocated to each container in a pod. Pods are scheduled by Kubernetes to ensure that at least the requested resources for each pod are available on the compute resource. For more information, see Managing compute resources for containers in the Kubernetes documentation.

When pods are scheduled on Fargate, the vCPU and memory reservations within the pod specification determine how much CPU and memory to provision for the pod.

- The maximum request out of any Init containers is used to determine the Init request vCPU and memory requirements.
- Requests for all long-running containers are added up to determine the long-running request vCPU and memory requirements.
- The larger of the above two values is chosen for the vCPU and memory request to use for your pod.
- Fargate adds 256 MB to each pod's memory reservation for the required Kubernetes components (kubelet, kube-proxy, and containerd).

Fargate rounds up to the compute configuration shown below that most closely matches the sum of vCPU and memory requests in order to ensure pods always have the resources that they need to run.

If you do not specify a vCPU and memory combination, then the smallest available combination is used (.25 vCPU and 0.5 GB memory).

The table below shows the vCPU and memory combinations that are available for pods running on Fargate.

vCPU value	Memory value
.25 vCPU	0.5 GB, 1 GB, 2 GB
.5 vCPU	1 GB, 2 GB, 3 GB, 4 GB
1 vCPU	2 GB, 3 GB, 4 GB, 5 GB, 6 GB, 7 GB, 8 GB

Amazon EKS User Guide Usage metrics

vCPU value	Memory value	
2 vCPU	Between 4 GB and 16 GB in 1-GB increments	
4 vCPU	Between 8 GB and 30 GB in 1-GB increments	

For pricing information on these compute configurations, see AWS Fargate pricing.

Fargate storage

When provisioned, each pod running on Fargate receives 20 GB of container image layer storage. Pod storage is ephemeral. After a pod stops, the storage is deleted. New pods launched onto Fargate on or after 5/28/2020, have encryption of the ephemeral storage volume enabled by default. The ephemeral pod storage is encrypted with an AES-256 encryption algorithm using AWS Fargate managed keys.

Note

The usable storage for Amazon EKS pods running on Fargate is less than 20GB because some space is used by the kubelet and other Kubernetes modules that are loaded inside the pod.

AWS Fargate usage metrics

You can use CloudWatch usage metrics to provide visibility into your accounts usage of resources. Use these metrics to visualize your current service usage on CloudWatch graphs and dashboards.

AWS Fargate usage metrics correspond to AWS service quotas. You can configure alarms that alert you when your usage approaches a service quota. For more information about Fargate service quotas, see Amazon EKS service quotas (p. 312).

AWS Fargate publishes the following metrics in the AWS/Usage namespace.

Metric	Description	
ResourceCount	The total number of the specified resource running on your account. The resource is defined by the dimensions associated with the metric.	

The following dimensions are used to refine the usage metrics that are published by AWS Fargate.

Dimension	Description		
Service	The name of the AWS service containing the resource. For AWS Fargate usage metrics, the value for this dimension is Fargate.		
Type	The type of entity that is being reported. Currently, the only valid value for AWS Fargate usage metrics is Resource.		
Resource	The type of resource that is running. Currently, AWS Fargate returns information on your Fargate On-Demand usage. The resource value for Fargate On-Demand usage is OnDemand.		
	Note Fargate On-Demand usage combines Amazon EKS pods using Fargate, Amazon ECS tasks using the Fargate launch		

Dimension	Description	
	type and Amazon ECS tasks using the FARGATE capacity provider.	
Class	The class of resource being tracked. Currently, AWS Fargate does not use the class dimension.	

Creating a CloudWatch alarm to monitor Fargate resource usage metrics

AWS Fargate provides CloudWatch usage metrics that correspond to the AWS service quotas for Fargate On-Demand resource usage. In the Service Quotas console, you can visualize your usage on a graph and configure alarms that alert you when your usage approaches a service quota. For more information, see AWS Fargate usage metrics (p. 146).

Use the following steps to create a CloudWatch alarm based on the Fargate resource usage metrics.

To create an alarm based on your Fargate usage quotas (AWS Management Console)

- 1. Open the Service Quotas console at https://console.aws.amazon.com/servicequotas/.
- In the navigation pane, choose AWS services.
- 3. From the AWS services list, search for and select AWS Fargate.
- 4. In the Service quotas list, select the Fargate usage quota you want to create an alarm for.
- 5. In the Amazon CloudWatch Events alarms section, choose **Create**.
- 6. For **Alarm threshold**, choose the percentage of your applied quota value that you want to set as the alarm value.
- 7. For Alarm name, enter a name for the alarm and then choose Create.

Fargate logging

Amazon EKS with Fargate supports a built-in log router, which means there are no sidecar containers to install or maintain. The log router allows you to use the breadth of services at AWS for log analytics and storage. You can stream logs from Fargate directly to Amazon CloudWatch, Amazon Elasticsearch Service, and Amazon Kinesis Data Firehose destinations such as Amazon S3, Amazon Kinesis Data Streams, and partner tools. Fargate uses a version of AWS for Fluent Bit, an upstream compliant distribution of Fluent Bit managed by AWS. For more information, see AWS for Fluent Bit on GitHub.

Prerequisites

 An existing Amazon EKS cluster. The cluster must be running one of the following (or later) platform versions.

EKS version	Platform version
1.18	eks.3
1.17	eks.5
1.16	eks.5
1.15	eks.6

If you don't have an existing cluster at one of these platform versions, or later, see *Getting started with Amazon EKS* (p. 4) to deploy a cluster.

• An existing Fargate profile that specifies an existing Kubernetes namespace that you deploy Fargate pods to. For more information, see the section called "Create a Fargate profile for your cluster" (p. 140).

To send logs to a destination of your choice

Apply a ConfigMap to your Amazon EKS cluster with a Fluent Conf data value that defines where container logs are shipped to. Fluent Conf is Fluent Bit, which is a fast and lightweight log processor configuration language that is used to route container logs to a log destination of your choice. For more information, see Configuration File in the Fluent Bit documentation.

- 1. Create a Kubernetes namespace.
 - a. Save the following contents to a yaml file on your computer.

```
kind: Namespace
apiVersion: v1
metadata:
name: aws-observability
labels:
aws-observability: enabled
```

b. Create the namespace. Replace the <example values> (including <>) with your own values.

```
kubectl apply -f <name-of-file-from-previous-step>.yaml
```

- 2. Configure Kubernetes to send Fargate logs to one of the following destinations.
 - a. (Optional) Send logs to CloudWatch. You have two output options when using CloudWatch:
 - cloudwatch logs An output plugin written in C.
 - cloudwatch An output plugin written in Golang.

The following example shows you how to use the cloudwatch_logs plugin to send logs to CloudWatch.

i. Create a yaml file with the following contents.

```
kind: ConfigMap
apiVersion: v1
metadata:
  name: aws-logging
  namespace: aws-observability
  labels:
data:
  output.conf: |
   [OUTPUT]
    Name cloudwatch_logs
    Match *
    region <us-east-1>
     log_group_name fluent-bit-cloudwatch
    log_stream_prefix from-fluent-bit-
    auto_create_group On
```

ii. Apply the manifest to your cluster.

```
kubectl apply -f <filename-you-created>.yaml
```

 Download the CloudWatch IAM policy to your computer. You can also view the policy on GitHub.

```
curl -o permissions.json https://raw.githubusercontent.com/aws-samples/
amazon-eks-fluent-logging-examples/mainline/examples/fargate/cloudwatchlogs/
permissions.json
```

- b. (Optional) Send logs to Amazon Elasticsearch Service. You can use es output, which is a plugin written in C. The following example shows you how to use the plugin to send logs to Elasticsearch.
 - i. Create a yaml file with the following contents.

```
kind: ConfigMap
apiVersion: v1
metadata:
 name: aws-logging
 namespace: aws-observability
  labels:
data:
 output.conf: |
    [OUTPUT]
      Name es
      Match *
     Host 192.168.2.3
     Port 9200
      Index my_index
      Type my_type
      AWS_Auth On
      AWS_Region <us-east-1>
```

ii. Apply the manifest to your cluster.

```
kubectl apply -f <filename-you-created>.yaml
```

 Download the Elasticsearch IAM policy to your computer. You can also view the policy on GitHub.

```
curl -o permissions.json https://raw.githubusercontent.com/aws-samples/amazon-eks-fluent-logging-examples/mainline/examples/fargate/amazon-elasticsearch/permissions.json
```

- c. (Optional) Send logs to Kinesis Data Firehose. You have two output options when using Kinesis Data Firehose:
 - kinesis_firehose An output plugin written in C.
 - firehose An output plugin written in Golang.

The following example shows you how to use the kinesis_firehose plugin to send logs to Kinesis Data Firehose.

i. Create a yaml file with the following contents.

```
kind: ConfigMap
apiVersion: v1
metadata:
```

```
name: aws-logging
namespace: aws-observability
labels:
data:
  output.conf: |
    [OUTPUT]
    Name kinesis_firehose
    Match *
    region <us-east-1>
    delivery_stream my-stream-firehose
```

ii. Apply the manifest to your cluster.

```
kubectl apply -f <filename-you-created>.yaml
```

iii. Download the Kinesis Data Firehose IAM policy to your computer. You can also view the policy on GitHub.

```
curl -o permissions.json https://raw.githubusercontent.com/aws-samples/amazon-
eks-fluent-logging-examples/mainline/examples/fargate/kinesis-firehose/
permissions.json
```

3. Create an IAM policy.

```
aws iam create-policy --policy-name <eks-fargate-logging-policy> --policy-document
file://permissions.json
```

4. Attach the IAM policy to the pod execution role specified for your Fargate profile. Replace <111122223333> with your account ID.

```
aws iam attach-role-policy --policy-arn arn:aws:iam::<1111122223333>:policy/<eks-
fargate-logging-policy> --role-name <your-pod-execution-role>
```

- 5. Deploy a sample pod.
 - a. Save the following contents to a yaml file on your computer.

```
apiVersion: apps/v1
kind: Deployment
metadata:
 name: sample-app
  namespace: <same-namespace-as-your-fargate-profile>
spec:
 replicas: 3
  selector:
    matchLabels:
      app: nginx
  template:
    metadata:
      labels:
        app: nginx
    spec:
      containers:
        - name: nginx
          image: nginx:latest
          ports:
            - name: http
              containerPort: 80
```

b. Apply the manifest to the cluster.

```
kubectl apply -f <name-of-file-from-previous-step>.yaml
```

6. View your logs using the tool that you sent your logs to.

Size considerations

We suggest that you plan for up to 50 MB of memory for your logs. If you expect your application to generate logs at very high throughput then you should plan for up to 100 MB.

Troubleshooting

To confirm whether the logging feature is enabled or disabled for some reason, such as an invalid ConfigMap, and why it is invalid, check your pod events with kubectl describe pod <pod_name>. The output might include pod events that clarify whether logging is enabled or not, such as the following example output.

The pod events are ephemeral with a time period depending on the settings. You can also view a pod's annotations using kubectl describe pod <pod-name>. In the pod annotation, there is information about whether the logging feature is enabled or disabled and the reason.

Validation strategy

The main sections included in a typical Fluent Conf are Service, Input, Filter, and Output. Filter, Output, and Parser. Service and Input are generated by Fargate. Fargate only validates the Filter, Output, and Parser specified in the Fluent Conf. Any sections provided other than Filter, Output, and Parser are ignored. The following rules are used to validate the Filter, Output, and Parser fields.

- 1. [FILTER], [OUTPUT], and [PARSER] are supposed to be specified under each corresponding key:filters.conf, output.conf, and parsers.conf. For example, [FILTER] must be under filters.conf. You can have many [FILTER]s under filters.conf. The same is true for [OUTPUT] and [PARSER].
- 2. Fargate validates the required keys for each section. Name and match are required for each [FILTER] and [OUTPUT]. Name and format are required for each [PARSER]. The keys are case-insensitive.
- 3. Environment variables such as \${ENV_VAR} are not allowed in the configmap.
- 4. The indentation has to be the same for either directive or key-value pair within each filters.conf, output.conf, and parsers.conf. Key-value pairs have to be indented more than directives.
- 5. Fargate validates against the following supported filters: grep, kubernetes,parser, record_modifier, rewrite_tag, throttle, nest, and modify.
- 6. Fargate validates against the following supported output: es, firehose, kinesis_firehose, cloudwatch, cloudwatch_logs, and kinesis.
- 7. At least one supported Output plugin has to be provided in the ConfigMap to enable logging. Filter and Parser are not required to enable logging.

For more information about Fluent Conf see Configuration File in the Fluent Bit documentation. You can also run Fluent Bit on Amazon EC2 using the desired configuration to troubleshoot any issues that arise from validation.

Amazon EKS optimized AMIs

You can deploy nodes with pre-built Amazon EKS optimized Amazon Machine Images (AMI), or your own custom AMIs. For more information about each type of Amazon EKS optimized AMI, see one of the following topics. For more information about creating your own custom AMI, see Amazon EKS optimized Amazon Linux AMI build script (p. 165).

Topics

- Amazon EKS optimized Amazon Linux AMIs (p. 152)
- Amazon EKS optimized Ubuntu Linux AMIs (p. 166)
- Amazon EKS optimized Bottlerocket AMIs (p. 166)
- Amazon EKS optimized Windows AMIs (p. 169)

Amazon EKS optimized Amazon Linux AMIs

The Amazon EKS optimized Amazon Linux AMI is built on top of Amazon Linux 2, and is configured to serve as the base image for Amazon EKS nodes. The AMI is configured to work with Amazon EKS and it includes Docker, kubelet, and the AWS IAM Authenticator.

Note

- You can track security or privacy events for Amazon Linux 2 at the Amazon Linux security center or subscribe to the associated RSS feed. Security and privacy events include an overview of the issue, what packages are affected, and how to update your instances to correct the issue.
- Before deploying an accelerated or Arm AMI, review the information in Amazon EKS optimized accelerated Amazon Linux AMIs (p. 158) and Amazon EKS optimized Arm Amazon Linux AMIs (p. 160).

Select a link in one of the following tables to view the latest Amazon EKS optimized Amazon Linux AMI ID for a region and Kubernetes version. You can also retrieve the IDs with an AWS Systems Manager parameter using different tools. For more information, see Retrieving Amazon EKS optimized Amazon Linux AMI IDs (p. 165).

Kubernetes version 1.18.9

Region	x86	x86 accelerated	Arm
US East (Ohio) (us- east-2)	View AMI ID	View AMI ID	View AMI ID
US East (N. Virginia) (us-east-1)	View AMI ID	View AMI ID	View AMI ID
US West (Oregon) (us- west-2)	View AMI ID	View AMI ID	View AMI ID
US West (N. California) (us-west-1)	View AMI ID	View AMI ID	View AMI ID

Region	x86	x86 accelerated	Arm
Africa (Cape Town) (af-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Hong Kong) (ap-east-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Mumbai) (ap-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Tokyo) (ap-northeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Seoul) (ap- northeast-2)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Singapore) (ap-southeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Sydney) (ap-southeast-2)	View AMI ID	View AMI ID	View AMI ID
Canada (Central) (ca- central-1)	View AMI ID	View AMI ID	View AMI ID
China (Beijing) (cn- north-1)	View AMI ID	View AMI ID	View AMI ID
China (Ningxia) (cn- northwest-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Frankfurt) (eu- central-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Ireland) (eu- west-1)	View AMI ID	View AMI ID	View AMI ID
Europe (London) (eu- west-2)	View AMI ID	View AMI ID	View AMI ID
Europe (Milan) (eu- south-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Paris) (eu- west-3)	View AMI ID	View AMI ID	View AMI ID
Europe (Stockholm) (eu-north-1)	View AMI ID	View AMI ID	View AMI ID
Middle East (Bahrain) (me-south-1)	View AMI ID	View AMI ID	View AMI ID
South America (São Paulo) (sa-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- East) (us-gov-east-1)	View AMI ID	View AMI ID	View AMI ID

Region	x86	x86 accelerated	Arm
AWS GovCloud (US- West) (us-gov- west-1)	View AMI ID	View AMI ID	View AMI ID

Kubernetes version 1.17.12

Region	x86	x86 accelerated	Arm
US East (Ohio) (us- east-2)	View AMI ID	View AMI ID	View AMI ID
US East (N. Virginia) (us-east-1)	View AMI ID	View AMI ID	View AMI ID
US West (Oregon) (us- west-2)	View AMI ID	View AMI ID	View AMI ID
US West (N. California) (us-west-1)	View AMI ID	View AMI ID	View AMI ID
Africa (Cape Town) (af-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Hong Kong) (ap-east-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Mumbai) (ap-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Tokyo) (ap-northeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Seoul) (ap- northeast-2)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Singapore) (ap-southeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Sydney) (ap-southeast-2)	View AMI ID	View AMI ID	View AMI ID
Canada (Central) (ca- central-1)	View AMI ID	View AMI ID	View AMI ID
China (Beijing) (cn- north-1)	View AMI ID	View AMI ID	View AMI ID
China (Ningxia) (cn- northwest-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Frankfurt) (eu- central-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Ireland) (eu- west-1)	View AMI ID	View AMI ID	View AMI ID

Region	x86	x86 accelerated	Arm
Europe (London) (eu- west-2)	View AMI ID	View AMI ID	View AMI ID
Europe (Milan) (eu- south-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Paris) (eu- west-3)	View AMI ID	View AMI ID	View AMI ID
Europe (Stockholm) (eu-north-1)	View AMI ID	View AMI ID	View AMI ID
Middle East (Bahrain) (me-south-1)	View AMI ID	View AMI ID	View AMI ID
South America (São Paulo) (sa-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- East) (us-gov-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- West) (us-gov- west-1)	View AMI ID	View AMI ID	View AMI ID

Kubernetes version 1.16.15

Region	x86	x86 accelerated	Arm
US East (Ohio) (us- east-2)	View AMI ID	View AMI ID	View AMI ID
US East (N. Virginia) (us-east-1)	View AMI ID	View AMI ID	View AMI ID
US West (Oregon) (us- west-2)	View AMI ID	View AMI ID	View AMI ID
US West (N. California) (us-west-1)	View AMI ID	View AMI ID	View AMI ID
Africa (Cape Town) (af-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Hong Kong) (ap-east-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Mumbai) (ap-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Tokyo) (ap-northeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Seoul) (ap- northeast-2)	View AMI ID	View AMI ID	View AMI ID

Region	x86	x86 accelerated	Arm
Asia Pacific (Singapore) (ap-southeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Sydney) (ap-southeast-2)	View AMI ID	View AMI ID	View AMI ID
Canada (Central) (ca- central-1)	View AMI ID	View AMI ID	View AMI ID
China (Beijing) (cn- north-1)	View AMI ID	View AMI ID	View AMI ID
China (Ningxia) (cn- northwest-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Frankfurt) (eu- central-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Ireland) (eu- west-1)	View AMI ID	View AMI ID	View AMI ID
Europe (London) (eu- west-2)	View AMI ID	View AMI ID	View AMI ID
Europe (Milan) (eu- south-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Paris) (eu- west-3)	View AMI ID	View AMI ID	View AMI ID
Europe (Stockholm) (eu-north-1)	View AMI ID	View AMI ID	View AMI ID
Middle East (Bahrain) (me-south-1)	View AMI ID	View AMI ID	View AMI ID
South America (São Paulo) (sa-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- East) (us-gov-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- West) (us-gov- west-1)	View AMI ID	View AMI ID	View AMI ID

Kubernetes version 1.15.12

Region	x86	x86 accelerated	Arm
US East (Ohio) (us- east-2)	View AMI ID	View AMI ID	View AMI ID
US East (N. Virginia) (us-east-1)	View AMI ID	View AMI ID	View AMI ID

Region	x86	x86 accelerated	Arm
US West (Oregon) (us- west-2)	View AMI ID	View AMI ID	View AMI ID
US West (N. California) (us-west-1)	View AMI ID	View AMI ID	View AMI ID
Africa (Cape Town) (af- south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Hong Kong) (ap-east-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Mumbai) (ap-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Tokyo) (ap-northeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Seoul) (ap- northeast-2)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Singapore) (ap-southeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Sydney) (ap-southeast-2)	View AMI ID	View AMI ID	View AMI ID
Canada (Central) (ca- central-1)	View AMI ID	View AMI ID	View AMI ID
China (Beijing) (cn- north-1)	View AMI ID	View AMI ID	View AMI ID
China (Ningxia) (cn- northwest-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Frankfurt) (eu- central-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Ireland) (eu- west-1)	View AMI ID	View AMI ID	View AMI ID
Europe (London) (eu- west-2)	View AMI ID	View AMI ID	View AMI ID
Europe (Milan) (eu- south-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Paris) (eu- west-3)	View AMI ID	View AMI ID	View AMI ID
Europe (Stockholm) (eu-north-1)	View AMI ID	View AMI ID	View AMI ID
Middle East (Bahrain) (me-south-1)	View AMI ID	View AMI ID	View AMI ID
South America (São Paulo) (sa-east-1)	View AMI ID	View AMI ID	View AMI ID

Region	x86	x86 accelerated	Arm
AWS GovCloud (US- East) (us-gov-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- West) (us-gov- west-1)	View AMI ID	View AMI ID	View AMI ID

Important

These AMIs require the latest AWS CloudFormation node template. You can't use these AMIs with a previous version of the node template; they will fail to join your cluster. Be sure to upgrade any existing AWS CloudFormation node stacks with the latest template (URL shown below) before you attempt to use these AMIs. Use the URL that corresponds to the Region that your cluster is in.

· All Regions other than China (Beijing) and China (Ningxia)

```
\verb|https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/amazon-eks-nodegroup.yaml|
```

China (Beijing) and China (Ningxia)

```
https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/amazon-eks-nodegroup.yaml
```

The AWS CloudFormation node template launches your nodes with Amazon EC2 user data that triggers a specialized bootstrap script. This script allows your nodes to discover and connect to your cluster's control plane automatically. For more information, see Launching self-managed Amazon Linux nodes (p. 116).

Amazon EKS optimized accelerated Amazon Linux AMIs

The Amazon EKS optimized accelerated Amazon Linux AMI is built on top of the standard Amazon EKS optimized Amazon Linux AMI, and is configured to serve as an optional image for Amazon EKS nodes to support GPU and Inferentia based workloads.

In addition to the standard Amazon EKS optimized AMI configuration, the accelerated AMI includes the following:

- NVIDIA drivers
- The nvidia-container-runtime (as the default runtime)
- · AWS Neuron container runtime

Note

- The Amazon EKS optimized accelerated AMI only supports GPU and Inferentia based instance types. Be sure to specify these instance types in your node AWS CloudFormation template.
 By using the Amazon EKS optimized accelerated AMI, you agree to NVIDIA's end user license agreement (EULA).
- The Amazon EKS optimized accelerated AMI was previously referred to as the Amazon EKS optimized AMI with GPU support.

• Previous versions of the Amazon EKS optimized accelerated AMI installed the nvidia-docker repository. The repository is no longer included in Amazon EKS AMI version v20200529 and later.

To enable GPU based workloads

The following procedure describes how to run a workload on a GPU based instance with the Amazon EKS optimized accelerated AMI. For more information about using Inferentia based workloads, see Inferentia support (p. 86).

1. After your GPU nodes join your cluster, you must apply the NVIDIA device plugin for Kubernetes as a DaemonSet on your cluster with the following command.

```
\label{local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_local_loc
```

2. You can verify that your nodes have allocatable GPUs with the following command:

```
kubectl get nodes "-o=custom-columns=NAME:.metadata.name,GPU:.status.allocatable.nvidia \.com/gpu"
```

To deploy a pod to test that your GPU nodes are configured properly

1. Create a file named nvidia-smi.yaml with the following contents. This manifest launches a Cuda container that runs nvidia-smi on a node.

```
apiVersion: v1
kind: Pod
metadata:
  name: nvidia-smi
spec:
  restartPolicy: OnFailure
  containers:
  - name: nvidia-smi
  image: nvidia/cuda:9.2-devel
  args:
  - "nvidia-smi"
  resources:
    limits:
        nvidia.com/gpu: 1
```

2. Apply the manifest with the following command:

```
kubectl apply -f nvidia-smi.yaml
```

3. After the pod has finished running, view its logs with the following command:

```
kubectl logs nvidia-smi
```

Output:

				00000000:00	•	0
•				OMiB ,	•	Default
				+	 -+	
					 	CDU Mamana
Processes						GPU Memory
GPU	חדם	Type	Process	s name		Usaqe

Amazon EKS optimized Arm Amazon Linux AMIs

Arm instances deliver significant cost savings for scale-out and Arm-based applications such as web servers, containerized microservices, caching fleets, and distributed data stores. When adding Arm nodes to your cluster, review the following considerations.

Considerations

- You can only deploy Arm AMIs in 1.15 or later clusters.
- If your cluster was deployed before August 17, 2020, then you must do a one-time upgrade of critical cluster add-on manifests so that Kubernetes can pull the correct image for each hardware architecture in use in your cluster. For more information about updating cluster add-ons, see Update an existing cluster (p. 44). If you deployed your cluster on or after August 17, 2020, then your coredns, kube-proxy, and Amazon VPC CNI Plugin for Kubernetes add-ons are already multi-architecture capable.
- Applications deployed to Arm nodes must be compiled for Arm.
- You can't use the Amazon FSx for Lustre CSI driver (p. 190) with Arm.
- If you have any DaemonSets deployed in an existing cluster, or you want to deploy them to a new cluster that you also want to deploy Arm nodes in, then ensure that your DaemonSet can run on all hardware architectures in your cluster.
- You can run Arm node groups and x86 node groups in the same cluster. If you do, consider deploying
 multi-architecture container images to a container repository such as Amazon Elastic Container
 Registry and then adding node selectors to your manifests so that Kubernetes knows what hardware
 architecture a pod can be deployed to. For more information, see Pushing a multi-architecture image
 in the Amazon ECR User Guide and the Introducing multi-architecture container images for Amazon
 ECR blog post.

Amazon EKS optimized Amazon Linux AMI versions

This topic lists versions of the Amazon EKS optimized Amazon Linux AMIs and their corresponding versions of kubelet, Docker, the Linux kernel, and the Packer build script (p. 165) configuration.

The Amazon EKS optimized AMI metadata, including the AMI ID, for each variant can be retrieved programmatically. For more information, see Retrieving Amazon EKS optimized Amazon Linux AMI IDs (p. 165).

AMIs are versioned by Kubernetes version and the release date of the AMI in the following format:

```
<k8s_major_version>.<k8s_minor_version>.<k8s_patch_version>-<release_date>
```

Amazon EKS optimized Amazon Linux AMI

The tables below list the current and previous versions of the Amazon EKS optimized Amazon Linux AMI.

Kubernetes version 1.18

AMI version	kubelet version	Docker version	Kernel version	Packer version
1.18.9-20201126	1.18.9	19.03.6-ce-4	4.14.203	v20201126
1.18.9-20201117	1.18.9	19.03.6-ce-4	4.14.203	v20201117
1.18.9-20201112	1.18.9	19.03.6-ce-4	4.14.203	v20201112
1.18.8-20201007	1.18.8	19.03.6-ce-4	4.14.198	v20201007

Kubernetes version 1.17

AMI version	kubelet version	Docker version	Kernel version	Packer version
1.17.12-20201126	1.17.12	19.03.6-ce-4	4.14.203	v20201126
1.17.12-20201117	1.17.12	19.03.6-ce-4	4.14.203	v20201117
1.17.12-20201112	1.17.12	19.03.6-ce-4	4.14.203	v20201112
1.17.11-20201007	1.17.11	19.03.6-ce-4	4.14.198	v20201007
1.17.11-20201002	1.17.11	19.03.6-ce-4	4.14.198	v20201002
1.17.11-20200921	1.17.11	19.03.6-ce-4	4.14.193	v20200921
1.17.9-20200904	1.17.9	19.03.6-ce-4	4.14.193	v20200904
1.17.9-20200814	1.17.9	19.03.6-ce-4	4.14.186	v20200814
1.17.9-20200723	1.17.9	19.03.6-ce	4.14.181	v20200723
1.17.7-20200710	1.17.7	19.03.6-ce	4.14.181	v20200710
1.17.7-20200709	1.17.7	19.03.6-ce	4.14.181	v20200709

Kubernetes version 1.16

AMI version	kubelet version	Docker version	Kernel version	Packer version
1.16.15-20201126	1.16.15	19.03.6-ce-4	4.14.203	v20201126
1.16.15-20201117	1.16.15	19.03.6-ce-4	4.14.203	v20201117
1.16.15-20201112	1.16.15	19.03.6-ce-4	4.14.203	v20201112
1.16.13-20201007	1.16.13	19.03.6-ce-4	4.14.198	v20201007
1.16.13-20201002	1.16.13	19.03.6-ce-4	4.14.198	v20201002
1.16.13-20200921	1.16.13	19.03.6-ce-4	4.14.193	v20200921
1.16.13-20200904	1.16.13	19.03.6-ce-4	4.14.193	v20200904
1.16.13-20200814	1.16.13	19.03.6-ce-4	4.14.186	v20200814
1.16.13-20200723	1.16.13	19.03.6-ce	4.14.181	v20200723
1.16.12-20200710	1.16.12	19.03.6-ce	4.14.181	v20200710

AMI version	kubelet version	Docker version	Kernel version	Packer version
1.16.12-20200709	1.16.12	19.03.6-ce	4.14.181	v20200709
1.16.8-20200615	1.16.8	19.03.6-ce	4.14.181	v20200615
1.16.8-20200609	1.16.8	19.03.6-ce	4.14.181	v20200609
1.16.8-20200531	1.16.8	18.09.9-ce	4.14.177	v20200531
1.16.8-20200507	1.16.8	18.09.9-ce	4.14.177	v20200507
1.16.8-20200423	1.16.8	18.09.9-ce	4.14.173	v20200423

Kubernetes version 1.15

AMI version	kubelet version	Docker version	Kernel version	Packer version
1.15.12-20201126	1.15.12	19.03.6-ce-4	4.14.203	v20201126
1.15.12-20201117	1.15.12	19.03.6-ce-4	4.14.203	v20201117
1.15.12-20201112	1.15.12	19.03.6-ce-4	4.14.203	v20201112
1.15.11-20201007	1.15.11	19.03.6-ce-4	4.14.198	v20201007
1.15.11-20201002	1.15.11	19.03.6-ce-4	4.14.198	v20201002
1.15.11-20200921	1.15.11	19.03.6-ce-4	4.14.193	v20200921
1.15.11-20200904	1.15.11	19.03.6-ce-4	4.14.193	v20200904
1.15.11-20200814	1.15.11	19.03.6-ce-4	4.14.186	v20200814
1.15.11-20200723	1.15.11	19.03.6-ce	4.14.181	v20200723
1.15.11-20200710	1.15.11	19.03.6-ce	4.14.181	v20200710
1.15.11-20200709	1.15.11	19.03.6-ce	4.14.181	v20200709
1.15.11-20200615	1.15.11	19.03.6-ce	4.14.181	v20200615
1.15.11-20200609	1.15.11	19.03.6-ce	4.14.181	v20200609
1.15.11-20200531	1.15.11	18.09.9-ce	4.14.177	v20200531
1.15.11-20200507	1.15.11	18.09.9-ce	4.14.177	v20200507
1.15.11-20200423	1.15.11	18.09.9-ce	4.14.173	v20200423
1.15.10-20200406	1.15.10	18.09.9-ce	4.14.173	v20200406
1.15.10-20200228	1.15.10	18.09.9-ce	4.14.165	v20200228

Amazon EKS optimized accelerated Amazon Linux AMI

The tables below list the current and previous versions of the Amazon EKS optimized accelerated Amazon Linux AMI.

Kubernetes version 1.18

AMI version	kubelet version	Docker version	Kernel version	Packer version	NVIDIA driver version
1.18.9-2020112	61.18.9	19.03.6-ce-4	4.14.203	v20201126	450.51.06
1.18.9-2020111	71.18.9	19.03.6-ce-4	4.14.203	v20201117	450.51.06
1.18.9-2020111	21.18.9	19.03.6-ce-4	4.14.203	v20201112	450.51.06
1.18.8-2020100	71.18.8	19.03.6-ce-4	4.14.198	v20201007	418.87.00

Kubernetes version 1.17

AMI version	kubelet version	Docker version	Kernel version	Packer version	NVIDIA driver version
1.17.12-202011	2 6 .17.12	19.03.6-ce-4	4.14.203	v20201126	450.51.06
1.17.12-202011	1 7 .17.12	19.03.6-ce-4	4.14.203	v20201117	450.51.06
1.17.12-202011	1 2 .17.12	19.03.6-ce-4	4.14.203	v20201112	450.51.06
1.17.11-202010	0 7 .17.11	19.03.6-ce-4	4.14.198	v20201007	418.87.00
1.17.11-202010	0 2 .17.11	19.03.6-ce-4	4.14.198	v20201002	418.87.00
1.17.11-202009	21.17.11	19.03.6-ce-4	4.14.193	v20200921	418.87.00
1.17.9-2020090	41.17.9	19.03.6-ce-4	4.14.193	v20200904	418.87.00
1.17.9-2020081	41.17.9	19.03.6-ce-4	4.14.186	v20200814	418.87.00
1.17.9-2020072	31.17.9	19.03.6-ce	4.14.181	v20200723	418.87.00
1.17.7-2020071	01.17.7	19.03.6-ce	4.14.181	v20200710	418.87.00
1.17.7-2020070	91.17.7	19.03.6-ce	4.14.181	v20200709	418.87.00

Kubernetes version 1.16

AMI version	kubelet version	Docker version	Kernel version	Packer version	NVIDIA driver version
1.16.15-202011	2 6 .16.15	19.03.6-ce-4	4.14.203	v20201126	450.51.06
1.16.15-202011	1 7 .16.15	19.03.6-ce-4	4.14.203	v20201117	450.51.06
1.16.15-202011	1 2 .16.15	19.03.6-ce-4	4.14.203	v20201112	450.51.06
1.16.13-202010	0 7 .16.13	19.03.6-ce-4	4.14.198	v20201007	418.87.00
1.16.13-202010	0 2 .16.13	19.03.6-ce-4	4.14.198	v20201002	418.87.00
1.16.13-202009	21.16.13	19.03.6-ce-4	4.14.193	v20200921	418.87.00
1.16.13-202009	04.16.13	19.03.6-ce-4	4.14.193	v20200904	418.87.00
1.16.13-202008	14.16.13	19.03.6-ce-4	4.14.186	v20200814	418.87.00

AMI version	kubelet version	Docker version	Kernel version	Packer version	NVIDIA driver version
1.16.13-202007	2 3 .16.13	19.03.6-ce	4.14.181	v20200723	418.87.00
1.16.12-202007	1 0 .16.12	19.03.6-ce	4.14.181	v20200710	418.87.00
1.16.12-202007	0 9 .16.12	19.03.6-ce	4.14.181	v20200709	418.87.00
1.16.8-2020061	51.16.8	19.03.6-ce	4.14.181	v20200615	418.87.00
1.16.8-2020060	91.16.8	19.03.6-ce	4.14.181	v20200609	418.87.00
1.16.8-2020053	11.16.8	18.09.9-ce	4.14.177	v20200531	418.87.00
1.16.8-2020050	71.16.8	18.09.9-ce	4.14.177	v20200507	418.87.00
1.16.8-2020042	31.16.8	18.09.9-ce	4.14.173	v20200423	418.87.00

Kubernetes version 1.15

AMI version	kubelet version	Docker version	Kernel version	Packer version	NVIDIA driver version
1.15.12-202011	2 6 .15.12	19.03.6-ce-4	4.14.203	v20201126	450.51.06
1.15.12-202011	1 7 .15.12	19.03.6-ce-4	4.14.203	v20201117	450.51.06
1.15.12-202011	1 2 .15.12	19.03.6-ce-4	4.14.203	v20201112	450.51.06
1.15.11-202010	0 7 .15.11	19.03.6-ce-4	4.14.198	v20201007	418.87.00
1.15.11-202010	0 2 .15.11	19.03.6-ce-4	4.14.198	v20201002	418.87.00
1.15.11-202009	21.15.11	19.03.6-ce-4	4.14.193	v20200921	418.87.00
1.15.11-202009	04.15.11	19.03.6-ce-4	4.14.193	v20200904	418.87.00
1.15.11-202008	14.15.11	19.03.6-ce-4	4.14.186	v20200814	418.87.00
1.15.11-202007	2 3 .15.11	19.03.6-ce	4.14.181	v20200723	418.87.00
1.15.11-202007	1 0 .15.11	19.03.6-ce	4.14.181	v20200710	418.87.00
1.15.11-202007	0 9 .15.11	19.03.6-ce	4.14.181	v20200709	418.87.00
1.15.11-202006	1 5 .15.11	19.03.6-ce	4.14.181	v20200615	418.87.00
1.15.11-202006	0 9 .15.11	19.03.6-ce	4.14.181	v20200609	418.87.00
1.15.11-202005	3 1 .15.11	18.09.9-ce	4.14.177	v20200531	418.87.00
1.15.11-202005	0 7 .15.11	18.09.9-ce	4.14.177	v20200507	418.87.00
1.15.11-202004	2 3 .15.11	18.09.9-ce	4.14.173	v20200423	418.87.00
1.15.10-202004	0 6 .15.10	18.09.9-ce	4.14.173	v20200406	418.87.00
1.15.10-202002	2 8 .15.10	18.09.9-ce	4.14.165	v20200228	418.87.00

Retrieving Amazon EKS optimized Amazon Linux AMI IDs

You can programmatically retrieve the Amazon Machine Image (AMI) ID for Amazon EKS optimized AMIs by querying the AWS Systems Manager Parameter Store API. This parameter eliminates the need for you to manually look up Amazon EKS optimized AMI IDs. For more information about the Systems Manager Parameter Store API, see GetParameter. Your user account must have the ssm:GetParameter IAM permission to retrieve the Amazon EKS optimized AMI metadata.

You can retrieve the AMI ID with the AWS CLI or the AWS Management Console.

• AWS CLI – You can retrieve the image ID of the latest recommended Amazon EKS optimized Amazon Linux AMI with the following command by using the sub-parameter image_id. Replace <1.18> with a supported version (p. 73) and <region-code> with an Amazon EKS supported Region for which you want the AMI ID. Replace amazon-linux-2-gpu to see the accelerated AMI ID and amazon-linux-2-arm64 to see the Arm ID.

```
aws ssm get-parameter --name /aws/service/eks/optimized-ami/<1.18>/<amazon-linux-2>/
recommended/image_id --region <region-code> --query "Parameter.Value" --output text
```

Example output:

```
ami-<abcd1234efgh5678i>
```

• AWS Management Console – You can query for the recommended Amazon EKS optimized AMI ID using a URL. The URL opens the Amazon EC2 Systems Manager console with the value of the ID for the parameter. In the following URL, replace <1.18> with a supported version (p. 73) and <region-code> with an Amazon EKS supported Region for which you want the AMI ID. Replace <amazon-linux-2> with amazon-linux-2-gpu to see the accelerated AMI ID and amazon-linux-2-arm64 to see the Arm ID.

https://console.aws.amazon.com/systems-manager/parameters/%252Faws%252Fservice%252Feks %252Foptimized-ami%252F<1.18>%252F<amazon-linux-2>%252Frecommended%252Fimage_id/description?region=<reqion-code>

Amazon EKS optimized Amazon Linux AMI build script

Amazon Elastic Kubernetes Service (Amazon EKS) has open-sourced the build scripts that are used to build the Amazon EKS optimized AMI. These build scripts are now available on GitHub.

The Amazon EKS optimized Amazon Linux AMI is built on top of Amazon Linux 2, specifically for use as a node in Amazon EKS clusters. You can use this repository to view the specifics of how the Amazon EKS team configures kubelet, Docker, the AWS IAM Authenticator for Kubernetes, and more.

The build scripts repository includes a HashiCorp packer template and build scripts to generate an AMI. These scripts are the source of truth for Amazon EKS optimized AMI builds, so you can follow the GitHub repository to monitor changes to our AMIs. For example, perhaps you want your own AMI to use the same version of Docker that the EKS team uses for the official AMI.

The GitHub repository also contains the specialized bootstrap script that runs at boot time to configure your instance's certificate data, control plane endpoint, cluster name, and more.

Additionally, the GitHub repository contains our Amazon EKS node AWS CloudFormation templates. These templates make it easier to spin up an instance running the Amazon EKS optimized AMI and register it with a cluster.

For more information, see the repositories on GitHub at https://github.com/awslabs/amazon-eks-ami.

Amazon EKS optimized Ubuntu Linux AMIs

Canonical has partnered with Amazon EKS to create node AMIs that you can use in your clusters.

Canonical delivers a built-for-purpose Kubernetes Node OS image. This minimized Ubuntu image is optimized for Amazon EKS and includes the custom AWS kernel that is jointly developed with AWS. For more information, see Ubuntu and Amazon Elastic Kubernetes Service and Optimized support for Amazon EKS on Ubuntu 18.04.

Amazon EKS optimized Bottlerocket AMIs

The Amazon EKS optimized Bottlerocket AMI is built on top of Bottlerocket. The AMI is configured to work with Amazon EKS and it includes containerd and kubelet.

Select a link in one of the following tables to view the latest Amazon EKS optimized Bottlerocket AMI ID for a region and Kubernetes version. You can also retrieve the IDs with an AWS Systems Manager parameter using different tools. For more information, see Retrieving Amazon EKS optimized Bottlerocket AMI IDs (p. 169).

Kubernetes version 1.18.8

Region	x86	Arm
US East (Ohio) (us-east-2)	View AMI ID	View AMI ID
US East (N. Virginia) (us- east-1)	View AMI ID	View AMI ID
US West (Oregon) (us-west-2)	View AMI ID	View AMI ID
US West (N. California) (us- west-1)	View AMI ID	View AMI ID
Africa (Cape Town) (af- south-1)	View AMI ID	View AMI ID
Asia Pacific (Hong Kong) (ap-east-1)	View AMI ID	View AMI ID
Asia Pacific (Mumbai) (ap-south-1)	View AMI ID	View AMI ID
Asia Pacific (Tokyo) (ap- northeast-1)	View AMI ID	View AMI ID
Asia Pacific (Seoul) (ap- northeast-2)	View AMI ID	View AMI ID
Asia Pacific (Singapore) (ap- southeast-1)	View AMI ID	View AMI ID
Asia Pacific (Sydney) (ap- southeast-2)	View AMI ID	View AMI ID
Canada (Central) (ca- central-1)	View AMI ID	View AMI ID
Europe (Frankfurt) (eu- central-1)	View AMI ID	View AMI ID

Amazon EKS User Guide Bottlerocket

Region	x86	Arm
Europe (Ireland) (eu-west-1)	View AMI ID	View AMI ID
Europe (London) (eu-west-2)	View AMI ID	View AMI ID
Europe (Milan) (eu-south-1)	View AMI ID	View AMI ID
Europe (Paris) (eu-west-3)	View AMI ID	View AMI ID
Europe (Stockholm) (eu- north-1)	View AMI ID	View AMI ID
Middle East (Bahrain) (me-south-1)	View AMI ID	View AMI ID
South America (São Paulo) (sa-east-1)	View AMI ID	View AMI ID

Kubernetes version 1.17.11

Region	x86	Arm
US East (Ohio) (us-east-2)	View AMI ID	View AMI ID
US East (N. Virginia) (us- east-1)	View AMI ID	View AMI ID
US West (Oregon) (us-west-2)	View AMI ID	View AMI ID
US West (N. California) (us- west-1)	View AMI ID	View AMI ID
Africa (Cape Town) (af- south-1)	View AMI ID	View AMI ID
Asia Pacific (Hong Kong) (ap- east-1)	View AMI ID	View AMI ID
Asia Pacific (Mumbai) (ap- south-1)	View AMI ID	View AMI ID
Asia Pacific (Tokyo) (ap- northeast-1)	View AMI ID	View AMI ID
Asia Pacific (Seoul) (ap- northeast-2)	View AMI ID	View AMI ID
Asia Pacific (Singapore) (ap- southeast-1)	View AMI ID	View AMI ID
Asia Pacific (Sydney) (ap- southeast-2)	View AMI ID	View AMI ID
Canada (Central) (ca- central-1)	View AMI ID	View AMI ID
Europe (Frankfurt) (eu- central-1)	View AMI ID	View AMI ID

Amazon EKS User Guide Bottlerocket

Region	x86	Arm
Europe (Ireland) (eu-west-1)	View AMI ID	View AMI ID
Europe (London) (eu-west-2)	View AMI ID	View AMI ID
Europe (Milan) (eu-south-1)	View AMI ID	View AMI ID
Europe (Paris) (eu-west-3)	View AMI ID	View AMI ID
Europe (Stockholm) (eu- north-1)	View AMI ID	View AMI ID
Middle East (Bahrain) (me-south-1)	View AMI ID	View AMI ID
South America (São Paulo) (sa-east-1)	View AMI ID	View AMI ID

Kubernetes version 1.16.13

Region	x86	Arm
US East (Ohio) (us-east-2)	View AMI ID	View AMI ID
US East (N. Virginia) (us- east-1)	View AMI ID	View AMI ID
US West (Oregon) (us-west-2)	View AMI ID	View AMI ID
US West (N. California) (us- west-1)	View AMI ID	View AMI ID
Africa (Cape Town) (af- south-1)	View AMI ID	View AMI ID
Asia Pacific (Hong Kong) (ap- east-1)	View AMI ID	View AMI ID
Asia Pacific (Mumbai) (ap- south-1)	View AMI ID	View AMI ID
Asia Pacific (Tokyo) (ap- northeast-1)	View AMI ID	View AMI ID
Asia Pacific (Seoul) (ap- northeast-2)	View AMI ID	View AMI ID
Asia Pacific (Singapore) (ap- southeast-1)	View AMI ID	View AMI ID
Asia Pacific (Sydney) (ap- southeast-2)	View AMI ID	View AMI ID
Canada (Central) (ca- central-1)	View AMI ID	View AMI ID
Europe (Frankfurt) (eu- central-1)	View AMI ID	View AMI ID

Region	x86	Arm
Europe (Ireland) (eu-west-1)	View AMI ID	View AMI ID
Europe (London) (eu-west-2)	View AMI ID	View AMI ID
Europe (Milan) (eu-south-1)	View AMI ID	View AMI ID
Europe (Paris) (eu-west-3)	View AMI ID	View AMI ID
Europe (Stockholm) (eu- north-1)	View AMI ID	View AMI ID
Middle East (Bahrain) (me-south-1)	View AMI ID	View AMI ID
South America (São Paulo) (sa-east-1)	View AMI ID	View AMI ID

Retrieving Amazon EKS optimized Bottlerocket AMI IDs

You can programmatically retrieve the Amazon Machine Image (AMI) ID for Amazon EKS optimized AMIs by querying the AWS Systems Manager Parameter Store API. This parameter eliminates the need for you to manually look up Amazon EKS optimized AMI IDs. For more information about the Systems Manager Parameter Store API, see GetParameter. Your user account must have the ssm:GetParameter IAM permission to retrieve the Amazon EKS optimized AMI metadata.

You can retrieve the AMI ID with the AWS CLI or the AWS Management Console.

• AWS CLI – You can retrieve the image ID of the latest recommended Amazon EKS optimized Bottlerocket AMI with the following AWS CLI command by using the sub-parameter <code>image_id</code>. Replace <1.18> with a supported version (p. 73) and <region-code> with an Amazon EKS supported Region for which you want the AMI ID.

```
aws ssm get-parameter --name /aws/service/bottlerocket/aws-k8s-<1.18>/x86_64/latest/image_id --region <region-code> --query "Parameter.Value" --output text
```

Example output:

ami-<068ed1c8e99b4810c>

• AWS Management Console – You can query for the recommended Amazon EKS optimized AMI ID using a URL in the AWS Management Console. The URL opens the Amazon EC2 Systems Manager console with the value of the ID for the parameter. In the following URL, replace <1.18> with a supported version (p. 73) and <region-code> with an Amazon EKS supported Region for which you want the AMI ID.

https://console.aws.amazon.com/systems-manager/parameters/aws/service/bottlerocket/aws-k8s-<1.18>/x86_64/latest/image_id/description?region-code>

Amazon EKS optimized Windows AMIs

The Amazon EKS optimized AMI is built on top of Windows Server 2019, and is configured to serve as the base image for Amazon EKS nodes. The AMI is configured to work with Amazon EKS out of the box, and it includes Docker, kubelet, and the AWS IAM Authenticator.

Note

You can track security or privacy events for Windows Server with the Microsoft security update guide.

The AMI IDs for the latest Amazon EKS optimized AMI are shown in the following tables. Windows Server 2019 is a Long-Term Servicing Channel (LTSC) release and Windows Server, version 2004 is a Semi-Annual Channel (SAC) release. For more information, see Windows Server servicing channels: LTSC and SAC in the Microsoft documentation. You can also retrieve the IDs with an AWS Systems Manager parameter using different tools. For more information, see Retrieving Amazon EKS optimized Windows AMI IDs (p. 178).

Kubernetes version 1.18.8

Region	Windows Server 2019 Full	Windows Server 2019 Core	Windows Server 2004 Core
US East (Ohio) (us- east-2)	View AMI ID	View AMI ID	View AMI ID
US East (N. Virginia) (us-east-1)	View AMI ID	View AMI ID	View AMI ID
US West (Oregon) (us- west-2)	View AMI ID	View AMI ID	View AMI ID
US West (N. California) (us-west-1)	View AMI ID	View AMI ID	View AMI ID
Africa (Cape Town) (af-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Hong Kong) (ap-east-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Mumbai) (ap-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Tokyo) (ap-northeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Seoul) (ap- northeast-2)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Singapore) (ap-southeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Sydney) (ap-southeast-2)	View AMI ID	View AMI ID	View AMI ID
Canada (Central) (ca- central-1)	View AMI ID	View AMI ID	View AMI ID
China (Beijing) (cn- north-1)	View AMI ID	View AMI ID	View AMI ID
China (Ningxia) (cn- northwest-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Frankfurt) (eu- central-1)	View AMI ID	View AMI ID	View AMI ID

Region	Windows Server 2019 Full	Windows Server 2019 Core	Windows Server 2004 Core
Europe (Ireland) (eu- west-1)	View AMI ID	View AMI ID	View AMI ID
Europe (London) (eu- west-2)	View AMI ID	View AMI ID	View AMI ID
Europe (Milan) (eu- south-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Paris) (eu- west-3)	View AMI ID	View AMI ID	View AMI ID
Europe (Stockholm) (eu-north-1)	View AMI ID	View AMI ID	View AMI ID
Middle East (Bahrain) (me-south-1)	View AMI ID	View AMI ID	View AMI ID
South America (São Paulo) (sa-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- East) (us-gov-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- West) (us-gov- west-1)	View AMI ID	View AMI ID	View AMI ID

Kubernetes version 1.17.11

Region	Windows Server 2019 Full	Windows Server 2019 Core	Windows Server 2004 Core
US East (Ohio) (us- east-2)	View AMI ID	View AMI ID	View AMI ID
US East (N. Virginia) (us-east-1)	View AMI ID	View AMI ID	View AMI ID
US West (Oregon) (us- west-2)	View AMI ID	View AMI ID	View AMI ID
US West (N. California) (us-west-1)	View AMI ID	View AMI ID	View AMI ID
Africa (Cape Town) (af-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Hong Kong) (ap-east-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Mumbai) (ap-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Tokyo) (ap-northeast-1)	View AMI ID	View AMI ID	View AMI ID

Region	Windows Server 2019 Full	Windows Server 2019 Core	Windows Server 2004 Core
Asia Pacific (Seoul) (ap- northeast-2)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Singapore) (ap-southeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Sydney) (ap-southeast-2)	View AMI ID	View AMI ID	View AMI ID
Canada (Central) (ca- central-1)	View AMI ID	View AMI ID	View AMI ID
China (Beijing) (cn- north-1)	View AMI ID	View AMI ID	View AMI ID
China (Ningxia) (cn- northwest-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Frankfurt) (eu- central-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Ireland) (eu- west-1)	View AMI ID	View AMI ID	View AMI ID
Europe (London) (eu- west-2)	View AMI ID	View AMI ID	View AMI ID
Europe (Milan) (eu- south-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Paris) (eu- west-3)	View AMI ID	View AMI ID	View AMI ID
Europe (Stockholm) (eu-north-1)	View AMI ID	View AMI ID	View AMI ID
Middle East (Bahrain) (me-south-1)	View AMI ID	View AMI ID	View AMI ID
South America (São Paulo) (sa-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- East) (us-gov-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- West) (us-gov- west-1)	View AMI ID	View AMI ID	View AMI ID

Kubernetes version 1.16.13

Region	Windows Server 2019	Windows Server 2019	Windows Server 2004
	Full	Core	Core
US East (Ohio) (us- east-2)	View AMI ID	View AMI ID	View AMI ID

Region	Windows Server 2019 Full	Windows Server 2019 Core	Windows Server 2004 Core
US East (N. Virginia) (us-east-1)	View AMI ID	View AMI ID	View AMI ID
US West (Oregon) (us- west-2)	View AMI ID	View AMI ID	View AMI ID
US West (N. California) (us-west-1)	View AMI ID	View AMI ID	View AMI ID
Africa (Cape Town) (af- south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Hong Kong) (ap-east-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Mumbai) (ap-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Tokyo) (ap-northeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Seoul) (ap- northeast-2)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Singapore) (ap-southeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Sydney) (ap-southeast-2)	View AMI ID	View AMI ID	View AMI ID
Canada (Central) (ca- central-1)	View AMI ID	View AMI ID	View AMI ID
China (Beijing) (cn- north-1)	View AMI ID	View AMI ID	View AMI ID
China (Ningxia) (cn- northwest-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Frankfurt) (eu- central-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Ireland) (eu- west-1)	View AMI ID	View AMI ID	View AMI ID
Europe (London) (eu- west-2)	View AMI ID	View AMI ID	View AMI ID
Europe (Milan) (eu- south-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Paris) (eu- west-3)	View AMI ID	View AMI ID	View AMI ID
Europe (Stockholm) (eu-north-1)	View AMI ID	View AMI ID	View AMI ID

Region	Windows Server 2019 Full	Windows Server 2019 Core	Windows Server 2004 Core
Middle East (Bahrain) (me-south-1)	View AMI ID	View AMI ID	View AMI ID
South America (São Paulo) (sa-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- East) (us-gov-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- West) (us-gov- west-1)	View AMI ID	View AMI ID	View AMI ID

Kubernetes version 1.15.11

Region	Windows Server 2019 Full	Windows Server 2019 Core	Windows Server 2004 Core
US East (Ohio) (us- east-2)	View AMI ID	View AMI ID	View AMI ID
US East (N. Virginia) (us-east-1)	View AMI ID	View AMI ID	View AMI ID
US West (Oregon) (us- west-2)	View AMI ID	View AMI ID	View AMI ID
US West (N. California) (us-west-1)	View AMI ID	View AMI ID	View AMI ID
Africa (Cape Town) (af-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Hong Kong) (ap-east-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Mumbai) (ap-south-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Tokyo) (ap-northeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Seoul) (ap- northeast-2)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Singapore) (ap-southeast-1)	View AMI ID	View AMI ID	View AMI ID
Asia Pacific (Sydney) (ap-southeast-2)	View AMI ID	View AMI ID	View AMI ID
Canada (Central) (ca- central-1)	View AMI ID	View AMI ID	View AMI ID
China (Beijing) (cn- north-1)	View AMI ID	View AMI ID	View AMI ID

Region	Windows Server 2019 Full	Windows Server 2019 Core	Windows Server 2004 Core
China (Ningxia) (cn- northwest-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Frankfurt) (eu- central-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Ireland) (eu- west-1)	View AMI ID	View AMI ID	View AMI ID
Europe (London) (eu- west-2)	View AMI ID	View AMI ID	View AMI ID
Europe (Milan) (eu- south-1)	View AMI ID	View AMI ID	View AMI ID
Europe (Paris) (eu- west-3)	View AMI ID	View AMI ID	View AMI ID
Europe (Stockholm) (eu-north-1)	View AMI ID	View AMI ID	View AMI ID
Middle East (Bahrain) (me-south-1)	View AMI ID	View AMI ID	View AMI ID
South America (São Paulo) (sa-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- East) (us-gov-east-1)	View AMI ID	View AMI ID	View AMI ID
AWS GovCloud (US- West) (us-gov- west-1)	View AMI ID	View AMI ID	View AMI ID

Amazon EKS Windows AMI release calendar

The following table lists the release and end of support dates for Windows versions on Amazon EKS. If an end date is blank, it's because the version is still supported.

Windows version	Amazon EKS release	Amazon EKS end of support
Windows Server 2004 Core	8/19/2020	
Windows Server 2019 Full	10/7/2019	
Windows Server 2019 Core	10/7/2019	
Windows Server 1909 Core	10/7/2019	December 8, 2020

Amazon EKS optimized Windows AMI versions

This topic lists versions of the Amazon EKS optimized Windows AMIs and their corresponding versions of kubelet and Docker.

The Amazon EKS optimized AMI metadata, including the AMI ID, for each variant can be retrieved programmatically. For more information, see Retrieving Amazon EKS optimized Windows AMI IDs (p. 178).

AMIs are versioned by Kubernetes version and the release date of the AMI in the following format:

<k8s_major_version>.<k8s_minor_version>-<release_date>

Amazon EKS optimized Windows Server 2004 Core AMI

The tables below list the current and previous versions of the Amazon EKS optimized Windows AMI.

Kubernetes version 1.18

AMI version	kubelet version	Docker version
1.18-2020.10.29	1.18.8	18.09.7
1.18-2020.10.08	1.18.8	18.09.7

Kubernetes version 1.17

AMI version	kubelet version	Docker version
1.17-2020.10.29	1.17.11	18.09.7
1.17-2020.09.09	1.17.11	18.09.7
1.17-2020.08.13	1.17.9	18.09.7

Kubernetes version 1.16

AMI version	kubelet version	Docker version
1.16-2020.10.29	1.16.13	18.09.7
1.16-2020.09.09	1.16.13	18.09.7
1.16-2020.08.13	1.16.13	18.09.7

Kubernetes version 1.15

AMI version	kubelet version	Docker version
1.15-2020.10.29	1.15.11	18.09.7
1.15-2020.09.09	1.15.11	18.09.7
1.15-2020.08.13	1.15.11	18.09.7

Amazon EKS optimized Windows Server 2019 Core AMI

The tables below list the current and previous versions of the Amazon EKS optimized Windows AMI.

Kubernetes version 1.18

AMI version	kubelet version	Docker version
1.18-2020.10.29	1.18.8	18.09.7
1.18-2020.10.08	1.18.8	18.09.7

Kubernetes version 1.17

AMI version	kubelet version	Docker version
1.17-2020.10.29	1.17.11	18.09.7
1.17-2020.09.09	1.17.11	18.09.7
1.17-2020.08.13	1.17.9	18.09.7

Kubernetes version 1.16

AMI version	kubelet version	Docker version
1.16-2020.10.29	1.16.13	18.09.7
1.16-2020.09.09	1.16.13	18.09.7
1.16-2020.08.13	1.16.13	18.09.7

Kubernetes version 1.15

AMI version	kubelet version	Docker version
1.15-2020.10.29	1.15.11	18.09.7
1.15-2020.09.09	1.15.11	18.09.7
1.15-2020.08.13	1.15.11	18.09.7

Amazon EKS optimized Windows Server 2019 Full AMI

The tables below list the current and previous versions of the Amazon EKS optimized Windows AMI.

Kubernetes version 1.18

AMI version	kubelet version	Docker version
1.18-2020.10.29	1.18.8	18.09.7
1.18-2020.10.08	1.18.8	18.09.7

Kubernetes version 1.17

AMI version	kubelet version	Docker version
1.17-2020.10.29	1.17.11	18.09.7

AMI version	kubelet version	Docker version
1.17-2020.09.09	1.17.11	18.09.7
1.17-2020.08.13	1.17.9	18.09.7

Kubernetes version 1.16

AMI version	kubelet version	Docker version
1.16-2020.10.29	1.16.13	18.09.7
1.16-2020.09.09	1.16.13	18.09.7
1.16-2020.08.13	1.16.13	18.09.7

Kubernetes version 1.15

AMI version	kubelet version	Docker version
1.15-2020.10.29	1.15.11	18.09.7
1.15-2020.09.09	1.15.11	18.09.7
1.15-2020.08.13	1.15.11	18.09.7

Retrieving Amazon EKS optimized Windows AMI IDs

You can programmatically retrieve the Amazon Machine Image (AMI) ID for Amazon EKS optimized AMIs by querying the AWS Systems Manager Parameter Store API. This parameter eliminates the need for you to manually look up Amazon EKS optimized AMI IDs. For more information about the Systems Manager Parameter Store API, see GetParameter. Your user account must have the ssm:GetParameter IAM permission to retrieve the Amazon EKS optimized AMI metadata.

You can retrieve the AMI ID with the AWS CLI or the AWS Management Console.

AWS CLI – You can retrieve the image ID of the latest recommended Amazon EKS optimized Windows
 AMI with the following command by using the sub-parameter image_id. You can replace <1.18>
 (including <>) with any supported Amazon EKS version and can replace <region-code> with an
 Amazon EKS supported Region for which you want the AMI ID. Replace <Core> with Full to see the
 Windows Server full AMI ID. You can also replace <2019> with 2004 for the Core version only.

```
aws ssm get-parameter --name /aws/service/ami-windows-latest/Windows_Server-
<2019>-English-<Core>-EKS_Optimized-<1.18>/image_id --region <region-code> --query
"Parameter.Value" --output text
```

Example output:

```
ami-<ami-00a053f1635fffea0>
```

AWS Management Console – You can query for the recommended Amazon EKS optimized AMI ID using a URL. The URL opens the Amazon EC2 Systems Manager console with the value of the ID for the parameter. In the following URL, you can replace <1.18> (including <>) with any supported Amazon EKS version and can replace <region-code> with an Amazon EKS supported Region for which you

want the AMI ID. Replace <Core> with Full to see the Windows Server full AMI ID. You can also replace <2019> with 2004 for the Core version only.

https://console.aws.amazon.com/systems-manager/parameters/%252Faws%252Fservice %252Fami-windows-latest%252FWindows_Server-<2019>-English-<Core>-EKS_Optimized-<1.18> %252Fimage_id/description?region=<region-code>

Storage

This chapter covers storage options for Amazon EKS clusters.

The Storage classes (p. 180) topic uses the in-tree Amazon EBS storage provisioner.

Note

The existing in-tree Amazon EBS plugin is still supported, but by using a CSI driver, you benefit from the decoupling of Kubernetes upstream release cycle and CSI driver release cycle. Eventually, the in-tree plugin will be deprecated in favor of the CSI driver.

Topics

- Storage classes (p. 180)
- Amazon EBS CSI driver (p. 181)
- Amazon EFS CSI driver (p. 185)
- Amazon FSx for Lustre CSI driver (p. 190)

Storage classes

Amazon EKS clusters that were created prior to Kubernetes version 1.11 were not created with any storage classes. You must define storage classes for your cluster to use and you should define a default storage class for your persistent volume claims. For more information, see Storage classes in the Kubernetes documentation.

Note

This topic uses the in-tree Amazon EBS storage provisioner. The existing in-tree Amazon EBS plugin is still supported, but by using a CSI driver, you benefit from the decoupling of Kubernetes upstream release cycle and CSI driver release cycle. Eventually, the in-tree plugin will be deprecated in favor of the CSI driver.

To create an AWS storage class for your Amazon EKS cluster

1. Create an AWS storage class manifest file for your storage class. The gp2-storage-class.yaml example below defines a storage class called gp2 that uses the Amazon EBS gp2 volume type.

For more information about the options available for AWS storage classes, see AWS EBS in the Kubernetes documentation.

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: gp2
annotations:
    storageclass.kubernetes.io/is-default-class: "true"
provisioner: kubernetes.io/aws-ebs
parameters:
  type: gp2
fsType: ext4
```

2. Use kubectl to create the storage class from the manifest file.

```
kubectl create -f gp2-storage-class.yaml
```

Amazon EKS User Guide Amazon EBS CSI driver

Output:

```
storageclass "gp2" created
```

To define a default storage class

 List the existing storage classes for your cluster. A storage class must be defined before you can set it as a default.

```
kubectl get storageclass
```

Output:

```
NAME PROVISIONER AGE
gp2 kubernetes.io/aws-ebs 8m
```

Choose a storage class and set it as your default by setting the storageclass.kubernetes.io/ is-default-class=true annotation.

Output:

```
storageclass "gp2" patched
```

3. Verify that the storage class is now set as default.

```
kubectl get storageclass
```

Output:

```
gp2 (default) kubernetes.io/aws-ebs 12m
```

Amazon EBS CSI driver

The Amazon EBS Container Storage Interface (CSI) driver provides a CSI interface that allows Amazon EKS clusters to manage the lifecycle of Amazon EBS volumes for persistent volumes.

This topic shows you how to deploy the Amazon EBS CSI Driver to your Amazon EKS cluster and verify that it works. We recommend using version ν 0.8.0 of the driver.

Note

The driver is not supported on Fargate. Alpha features of the Amazon EBS CSI Driver are not supported on Amazon EKS clusters. The driver is in Beta release. It is well tested and supported by Amazon EKS for production use. Support for the driver will not be dropped, though details may change. If the schema or schematics of the driver changes, instructions for migrating to the next version will be provided.

For detailed descriptions of the available parameters and complete examples that demonstrate the driver's features, see the Amazon EBS Container Storage Interface (CSI) driver project on GitHub.

To deploy the Amazon EBS CSI driver to an Amazon EKS cluster

- Create an IAM policy called Amazon_EBS_CSI_Driver for your node instance profile that allows
 the Amazon EBS CSI Driver to make calls to AWS APIs on your behalf. Use the following AWS CLI
 commands to create the IAM policy in your AWS account. You can view the policy document on
 GitHub.
 - a. Download the policy document from GitHub.

```
curl -O https://raw.githubusercontent.com/kubernetes-sigs/aws-ebs-csi-driver/
v0.8.0/docs/example-iam-policy.json
```

b. Create the policy.

```
aws iam create-policy --policy-name Amazon_EBS_CSI_Driver \
--policy-document file://example-iam-policy.json
```

Take note of the policy ARN that is returned.

2. Get the IAM role name for your nodes. Use the following command to print the aws-auth configmap.

```
kubectl -n kube-system describe configmap aws-auth
```

Output:

Record the role name for any rolearn values that have the system:nodes group assigned to them. In the previous example output, the role name is eksctl-my-cluster-my-nodegroup-NodeInstanceRole-XXXXXXXXXXXXXXXXXXXXXXXI You should have one value for each node group in your cluster.

Attach the new Amazon_EBS_CSI_Driver IAM policy to each of the node IAM roles you identified
earlier with the following command, substituting the red text with your own AWS account number
and node IAM role name.

```
aws iam attach-role-policy \
--policy-arn arn:aws:iam::<111122223333>:policy/Amazon_EBS_CSI_Driver \
--role-name <eksctl-my-cluster-my-nodegroup-NodeInstanceRole-XXXXXXXXXXXXXXXX</pre>
```

4. If you want the driver to tag all Amazon EBS volumes that the Amazon EBS CSI driver creates with the same tag, complete the following steps. If you don't want the driver to tag the volumes that it creates, skip to step 5.

 Clone the Amazon EBS Container Storage Interface (CSI) driver GitHub repository to your computer.

```
git clone https://github.com/kubernetes-sigs/aws-ebs-csi-driver.git
```

b. Navigate to the base example folder.

```
cd aws-ebs-csi-driver/deploy/kubernetes/base/
```

c. Edit the controller.yaml file. Find the section of the file with the following text and add -extra-tags to it. The following text shows the section of the file with the existing and added text. This example will cause the controller to add department and environment tags to all volumes it creates.

d. Apply the modified manifest to your cluster.

```
kubectl apply -k ../base
```

5. Skip this step if you completed step 4. Deploy the Amazon EBS CSI Driver with the command that corresponds to the Region that your cluster is in.

Note

This commands require version 1.14 or later of kubectl. You can see your kubectl version with the following command. To install or upgrade your kubectl version, see Installing kubectl (p. 289).

```
kubectl version --client --short
```

All Regions other than China Regions.

```
kubectl apply -k "github.com/kubernetes-sigs/aws-ebs-csi-driver/deploy/kubernetes/
overlays/stable/?ref=master"
```

· Beijing and Ningxia China Regions.

```
kubectl apply -k "github.com/kubernetes-sigs/aws-ebs-csi-driver/deploy/kubernetes/
overlays/stable-cn/?ref=master"
```

To deploy a sample application and verify that the CSI driver is working

This procedure uses the Dynamic volume provisioning example from the Amazon EBS Container Storage Interface (CSI) driver GitHub repository to consume a dynamically-provisioned Amazon EBS volume.

Amazon EKS User Guide Amazon EBS CSI driver

 Clone the Amazon EBS Container Storage Interface (CSI) driver GitHub repository to your local system.

```
git clone https://github.com/kubernetes-sigs/aws-ebs-csi-driver.git
```

2. Navigate to the dynamic-provisioning example directory.

```
cd aws-ebs-csi-driver/examples/kubernetes/dynamic-provisioning/
```

 Deploy the ebs-sc storage class, ebs-claim persistent volume claim, and app sample application from the specs directory.

```
kubectl apply -f specs/
```

4. Describe the ebs-sc storage class.

```
kubectl describe storageclass ebs-sc
```

Output:

```
Name:
                 ebs-sc
IsDefaultClass: No
Annotations:
                 kubectl.kubernetes.io/last-applied-
configuration={"apiVersion":"storage.k8s.io/v1","kind":"StorageClass","metadata":
{"annotations":{}, "name": "ebs-
sc"}, "provisioner": "ebs.csi.aws.com", "volumeBindingMode": "WaitForFirstConsumer"}
Provisioner:
                       ebs.csi.aws.com
Parameters:
                       <none>
AllowVolumeExpansion: <unset>
MountOptions:
                       <none>
ReclaimPolicy:
                       Delete
VolumeBindingMode:
                       WaitForFirstConsumer
Events:
                       <none>
```

Note that the storage class uses the WaitForFirstConsumer volume binding mode. This means that volumes are not dynamically provisioned until a pod makes a persistent volume claim. For more information, see Volume Binding Mode in the Kubernetes documentation.

5. Watch the pods in the default namespace and wait for the app pod to become ready.

```
kubectl get pods --watch
```

6. List the persistent volumes in the default namespace. Look for a persistent volume with the default/ebs-claim claim.

```
kubectl get pv
```

Output:

NAME			CAPACITY	ACCESS MODES	RECLAIM POLICY
STATUS	CLAIM	STORAGECLASS	REASON	AGE	
pvc-37717	cd6-d0dc-11e9-b17f-0	06fad4858a5a	4Gi	RWO	Delete
Bound	default/ebs-claim	ebs-sc		30s	

7. Describe the persistent volume.

Amazon EKS User Guide Amazon EFS CSI driver

```
kubectl describe pv <pvc-37717cd6-d0dc-11e9-b17f-06fad4858a5a>
```

Output:

```
Name:
                  pvc-37717cd6-d0dc-11e9-b17f-06fad4858a5a
Labels:
                  <none>
Annotations:
                  pv.kubernetes.io/provisioned-by: ebs.csi.aws.com
Finalizers:
                  [kubernetes.io/pv-protection external-attacher/ebs-csi-aws-com]
StorageClass:
                  ebs-sc
Status:
                  Bound
                  default/ebs-claim
Claim:
Reclaim Policy:
                  Delete
Access Modes:
                  RWO
VolumeMode:
                  Filesystem
Capacity:
                  4Gi
Node Affinity:
 Required Terms:
   Term 0:
                 topology.ebs.csi.aws.com/zone in [<regiona>]
Message:
Source:
   Type:
                      CSI (a Container Storage Interface (CSI) volume source)
    Driver:
                     ebs.csi.aws.com
                      <vol-0d651e157c6d93445>
    VolumeHandle:
    ReadOnly:
                      false
    VolumeAttributes:
                          storage.kubernetes.io/
csiProvisionerIdentity=1567792483192-8081-ebs.csi.aws.com
Events:
```

The Amazon EBS volume ID is listed as the VolumeHandle.

8. Verify that the pod is successfully writing data to the volume.

```
kubectl exec -it app cat /data/out.txt
```

Output:

```
Wed Jul 8 13:52:09 UTC 2020

Wed Jul 8 13:52:14 UTC 2020

Wed Jul 8 13:52:19 UTC 2020

Wed Jul 8 13:52:24 UTC 2020

Wed Jul 8 13:52:29 UTC 2020

Wed Jul 8 13:52:34 UTC 2020
```

9. When you finish experimenting, delete the resources for this sample application to clean up.

```
kubectl delete -f specs/
```

Amazon EFS CSI driver

The Amazon EFS Container Storage Interface (CSI) driver provides a CSI interface that allows Kubernetes clusters running on AWS to manage the lifecycle of Amazon EFS file systems.

This topic shows you how to deploy the Amazon EFS CSI Driver to your Amazon EKS cluster and verify that it works.

Note

Alpha features of the Amazon EFS CSI Driver are not supported on Amazon EKS clusters.

For detailed descriptions of the available parameters and complete examples that demonstrate the driver's features, see the Amazon EFS Container Storage Interface (CSI) driver project on GitHub.

To deploy the Amazon EFS CSI driver to an Amazon EKS cluster

- Deploy the Amazon EFS CSI driver using the command that corresponds with the Region that your cluster is in. If your cluster contains nodes (it can also include AWS Fargate pods), then deploy the driver with the following command.
 - All Regions other than China Regions.

```
kubectl apply -k "github.com/kubernetes-sigs/aws-efs-csi-driver/deploy/kubernetes/
overlays/stable/ecr/?ref=release-1.0"
```

· Beijing and Ningxia China Regions.

```
kubectl apply -k "github.com/kubernetes-sigs/aws-efs-csi-driver/deploy/kubernetes/
overlays/stable/?ref=release-1.0"
```

If your cluster contains only Fargate pods (no nodes), then deploy the driver with the following command.

```
{\tt kubect1\ apply\ -f\ https://raw.githubusercontent.com/kubernetes-sigs/aws-efs-csi-driver/master/deploy/kubernetes/base/csidriver.yaml}
```

Note

- Starting with the 1.0.0 release, encryption of data in transit using TLS is enabled by default. Using encryption in transit, data will be encrypted during its transition over the network to the Amazon EFS service. To disable it and mount volumes using NFSv4, set the volumeAttributes field encryptInTransit to "false" in your persistent volume manifest. For an example manifest, see Encryption in Transit example on GitHub.
- Only static volume provisioning is supported. This means that an Amazon EFS file system needs to be created outside of Amazon EKS before being used by pods in your cluster.

Amazon EFS access points

The Amazon EFS CSI driver supports Amazon EFS access points, which are application-specific entry points into an Amazon EFS file system that make it easier to share a file system between multiple pods. Access points can enforce a user identity for all file system requests that are made through the access point, and enforce a root directory for each pod. For more information, see Amazon EFS access points on GitHub.

To create an Amazon EFS file system for your Amazon EKS cluster

 Locate the VPC ID for your Amazon EKS cluster. You can find this ID in the Amazon EKS console, or you can use the following AWS CLI command.

```
aws eks describe-cluster --name <cluster_name> --query
"cluster.resourcesVpcConfig.vpcId" --output text
```

Output:

```
vpc-<exampledb76d3e813>
```

2. Locate the CIDR range for your cluster's VPC. You can find this in the Amazon VPC console, or you can use the following AWS CLI command.

aws ec2 describe-vpcs --vpc-ids vpc-<exampledb76d3e813> --query "Vpcs[].CidrBlock" -output text

Output:

192.168.0.0/16

- 3. Create a security group that allows inbound NFS traffic for your Amazon EFS mount points.
 - a. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
 - b. Choose **Security Groups** in the left navigation panel, and then choose **Create security group**.
 - c. Enter a name and description for your security group, and choose the VPC that your Amazon EKS cluster is using.
 - d. Under Inbound rules, select Add rule.
 - e. Under Type, select NFS.
 - f. Under **Source**, select **Custom**, and paste the VPC CIDR range that you obtained in the previous step.
 - g. Choose Create security group.
- 4. Create the Amazon EFS file system for your Amazon EKS cluster.
 - a. Open the Amazon Elastic File System console at https://console.aws.amazon.com/efs/.
 - b. Choose File systems in the left navigation pane, and then choose Create file system.
 - c. On the Create file system page, choose Customize.
 - d. On the File system settings page, you don't need to enter or select any information, but can if desired, and then select Next.
 - e. On the Network access page, for Virtual Private Cloud (VPC), choose your VPC.

Note

If you don't see your VPC, at the top right of the console, make sure that the region that your VPC is in is selected.

- f. Under **Mount targets**, if a default security group is already listed, select the **X** in the top right corner of the box with the default security group name to remove it from each mount point, select the security group that you created in a previous step for each mount target, and then select **Next**.
- q. On the File system policy page, select Next.
- h. On the Review and create page, select Create.

Important

By default, new Amazon EFS file systems are owned by root:root, and only the root user (UID 0) has read-write-execute permissions. If your containers are not running as root, you must change the Amazon EFS file system permissions to allow other users to modify the file system. For more information, see Working with users, groups, and permissions at the Network File System (NFS) level in the Amazon Elastic File System User Guide.

To deploy a sample application and verify that the CSI driver is working

This procedure uses the Multiple Pods Read Write Many example from the Amazon EFS Container Storage Interface (CSI) driver GitHub repository to consume a statically provisioned Amazon EFS persistent volume and access it from multiple pods with the ReadWriteMany access mode.

 Clone the Amazon EFS Container Storage Interface (CSI) driver GitHub repository to your local system.

```
git clone https://github.com/kubernetes-sigs/aws-efs-csi-driver.git
```

2. Navigate to the multiple_pods example directory.

```
cd aws-efs-csi-driver/examples/kubernetes/multiple_pods/
```

3. Retrieve your Amazon EFS file system ID. You can find this in the Amazon EFS console, or use the following AWS CLI command.

```
aws efs describe-file-systems --query "FileSystems[*].FileSystemId" --output text
```

Output:

```
fs-<582a03f3>
```

4. Edit the specs/pv.yaml file and replace the volumeHandle value with your Amazon EFS file system ID.

```
apiVersion: v1
kind: PersistentVolume
metadata:
   name: efs-pv
spec:
   capacity:
    storage: <5Gi>
   volumeMode: Filesystem
   accessModes:
    - ReadWriteMany
   persistentVolumeReclaimPolicy: Retain
   storageClassName: efs-sc
   csi:
     driver: efs.csi.aws.com
   volumeHandle: fs-<582a03f3>
```

Note

Because Amazon EFS is an elastic file system, it does not enforce any file system capacity limits. The actual storage capacity value in persistent volumes and persistent volume claims is not used when creating the file system. However, since storage capacity is a required field in Kubernetes, you must specify a valid value, such as, <5Gi> in this example. This value does not limit the size of your Amazon EFS file system.

5. Deploy the efs-sc storage class, efs-claim persistent volume claim, efs-pv persistent volume, and app1 and app2 sample applications from the specs directory.

```
kubectl apply -f specs/
```

6. Watch the pods in the default namespace and wait for the app1 and app2 pods' STATUS become Running.

```
kubectl get pods --watch
```

Note

It may take a few minutes for the pods to reach the Running status.

 List the persistent volumes in the default namespace. Look for a persistent volume with the default/efs-claim claim.

```
kubectl get pv
```

Output:

```
NAME
        CAPACITY
                   ACCESS MODES
                                 RECLAIM POLICY
                                                  STATUS
                                                           CLAIM
STORAGECLASS
              REASON
                       AGE
                   RWX
                                  Retain
                                                   Bound
                                                           default/efs-claim
efs-pv
       5Gi
                                                                               efs-sc
                 2m50s
```

8. Describe the persistent volume.

```
kubectl describe pv efs-pv
```

Output:

```
Name:
                 efs-pv
Labels:
                 <none>
Annotations:
                kubectl.kubernetes.io/last-applied-configuration:
                   {"apiVersion": "v1", "kind": "PersistentVolume", "metadata":
{"annotations":{}, "name":"efs-pv"}, "spec":{"accessModes":["ReadWriteMany"], "capaci...
                pv.kubernetes.io/bound-by-controller: yes
                [kubernetes.io/pv-protection]
Finalizers:
StorageClass:
                efs-sc
                Bound
Status:
Claim:
                default/efs-claim
Reclaim Policy: Retain
Access Modes:
                RWX
VolumeMode:
                Filesystem
                5Gi
Capacity:
Node Affinity: <none>
Message:
Source:
    Type:
                       CSI (a Container Storage Interface (CSI) volume source)
    Driver:
                       efs.csi.aws.com
                      fs-<582a03f3>
    VolumeHandle:
                      false
    ReadOnly:
    VolumeAttributes: <none>
Events:
                       <none>
```

The Amazon EFS file system ID is listed as the VolumeHandle.

9. Verify that the app1 pod is successfully writing data to the volume.

```
kubectl exec -ti app1 -- tail /data/out1.txt
```

Output:

```
Thu Jul 23 21:44:02 UTC 2020
Thu Jul 23 21:44:07 UTC 2020
Thu Jul 23 21:44:12 UTC 2020
Thu Jul 23 21:44:17 UTC 2020
Thu Jul 23 21:44:22 UTC 2020
Thu Jul 23 21:44:27 UTC 2020
Thu Jul 23 21:44:27 UTC 2020
```

10. Verify that the app2 pod is shows the same data in the volume.

Amazon EKS User Guide Amazon FSx for Lustre CSI driver

```
kubectl exec -ti app2 -- tail /data/out1.txt
```

Output:

```
Thu Jul 23 21:44:47 UTC 2020
Thu Jul 23 21:44:52 UTC 2020
Thu Jul 23 21:44:57 UTC 2020
Thu Jul 23 21:45:02 UTC 2020
Thu Jul 23 21:45:07 UTC 2020
Thu Jul 23 21:45:12 UTC 2020
Thu Jul 23 21:45:12 UTC 2020
```

11. When you finish experimenting, delete the resources for this sample application to clean up.

```
kubectl delete -f specs/
```

Amazon FSx for Lustre CSI driver

Important

This capability is not available in China Regions.

The Amazon FSx for Lustre Container Storage Interface (CSI) driver provides a CSI interface that allows Amazon EKS clusters to manage the lifecycle of Amazon FSx for Lustre file systems.

This topic shows you how to deploy the Amazon FSx for Lustre CSI Driver to your Amazon EKS cluster and verify that it works. We recommend using version 0.4.0 of the driver.

Note

This driver is supported on Kubernetes version 1.18 and later Amazon EKS clusters and nodes. The driver is not supported on Fargate or Arm nodes. Alpha features of the Amazon FSx for Lustre CSI Driver are not supported on Amazon EKS clusters. The driver is in Beta release. It is well tested and supported by Amazon EKS for production use. Support for the driver will not be dropped, though details may change. If the schema or schematics of the driver changes, instructions for migrating to the next version will be provided.

For detailed descriptions of the available parameters and complete examples that demonstrate the driver's features, see the Amazon FSx for Lustre Container Storage Interface (CSI) driver project on GitHub.

Prerequisites

You must have:

- Version 1.18.190 or later of the AWS CLI installed. You can check your currently-installed version with the aws --version command. To install or upgrade the AWS CLI, see Installing the AWS CLI.
- An existing Amazon EKS cluster. If you don't currently have a cluster, see Getting started with Amazon EKS (p. 4) to create one.
- Version 0.33.0 or later of eksctl installed. You can check your currently-installed version with the eksctl version command. To install or upgrade eksctl, see Installing or upgrading eksctl (p. 298).
- The latest version of kubectl installed that aligns to your cluster version. You can check your currently-installed version with the kubectl version --short --client command. For more information, see Installing kubectl (p. 289).

To deploy the Amazon FSx for Lustre CSI driver to an Amazon EKS cluster

1. Create an AWS Identity and Access Management OIDC provider and associate it with your cluster.

```
eksctl utils associate-iam-oidc-provider \
    --region <region-code> \
    --cluster <prod> \
    --approve
```

- Create an IAM policy and service account that allows the driver to make calls to AWS APIs on your behalf.
 - a. Copy the following text and save it to a file named fsx-csi-driver.json.

```
"Version": "2012-10-17",
   "Statement":[
         "Effect": "Allow",
         "Action":[
            "iam:CreateServiceLinkedRole",
            "iam:AttachRolePolicy",
            "iam:PutRolePolicy"
         "Resource": "arn:aws:iam::*:role/aws-service-role/s3.data-
source.lustre.fsx.amazonaws.com/*"
      },
      {
         "Action": "iam: CreateServiceLinkedRole",
         "Effect": "Allow",
         "Resource": "*",
         "Condition":{
            "StringLike":{
                "iam:AWSServiceName":[
                   "fsx.amazonaws.com"
         }
      },
         "Effect": "Allow",
         "Action":[
            "s3:ListBucket",
            "fsx:CreateFileSystem",
            "fsx:DeleteFileSystem",
            "fsx:DescribeFileSystems"
         ٦,
         "Resource":[
            " * "
   ]
}
```

b. Create the policy.

```
aws iam create-policy \
    --policy-name <Amazon_FSx_Lustre_CSI_Driver> \
    --policy-document file://fsx-csi-driver.json
```

Take note of the policy Amazon Resource Name (ARN) that is returned.

Amazon EKS User Guide Amazon FSx for Lustre CSI driver

3. Create a Kubernetes service account for the driver and attach the policy to the service account. Replacing the ARN of the policy with the ARN returned in the previous step.

```
eksctl create iamserviceaccount \
    --region <region-code> \
    --name fsx-csi-controller-sa \
    --namespace kube-system \
    --cluster prod> \
    --attach-policy-arn arn:aws:iam::<111122223333:policy/Amazon_FSx_Lustre_CSI_Driver> \
    --approve
```

Output:

You'll see several lines of output as the service account is created. The last line of output is similar to the following example line.

```
[#] created serviceaccount "kube-system/fsx-csi-controller-sa"
```

Note the name of the AWS CloudFormation stack that was deployed. In the example output above, the stack is named eksctl-prod-addon-iamserviceaccount-kube-system-fsx-csi-controller-sa.

- Note the Role ARN for the role that was created.
 - a. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
 - b. Ensure that the console is set to the Region that you created your IAM role in and then select **Stacks**.
 - c. Select the stack named eksctl-prod-addon-iamserviceaccount-kube-system-fsx-csi-controller-sa.
 - d. Select the Outputs tab. The Role ARN is listed on the Output(1) page.
- 5. Deploy the driver with the following command.

```
kubectl apply -k "github.com/kubernetes-sigs/aws-fsx-csi-driver/deploy/kubernetes/
overlays/stable/?ref=master"
```

Output

```
Warning: kubectl apply should be used on resource created by either kubectl create --
save-config or kubectl apply
serviceaccount/fsx-csi-controller-sa configured
clusterrole.rbac.authorization.k8s.io/fsx-csi-external-provisioner-role created
clusterrolebinding.rbac.authorization.k8s.io/fsx-csi-external-provisioner-binding
created
deployment.apps/fsx-csi-controller created
daemonset.apps/fsx-csi-node created
csidriver.storage.k8s.io/fsx.csi.aws.com created
```

6. Patch the driver deployment to add the service account that you created in step 3, replacing the ARN with the ARN that you noted in step 4.

```
kubectl annotate serviceaccount -n kube-system <fsx-csi-controller-sa> \
  eks.amazonaws.com/role-arn=<arn:aws:iam::111122223333:role/eksctl-prod-addon-
iamserviceaccount-kube-sys-Role1-NPFTLHJ5PJF5> --overwrite=true
```

To deploy a Kubernetes storage class, persistent volume claim, and sample application to verify that the CSI driver is working

This procedure uses the Dynamic volume provisioning for Amazon S3 from the Amazon FSx for Lustre Container Storage Interface (CSI) driver GitHub repository to consume a dynamically-provisioned Amazon FSx for Lustre volume.

 Create an Amazon S3 bucket and a folder within it named export by creating and copying a file to the bucket.

```
aws s3 mb s3://<fsx-csi>
echo test-file >> testfile
aws s3 cp testfile s3://<fsx-csi>/export/testfile
```

Download the storageclass manifest with the following command.

```
\verb|curl -o| storageclass.yaml | https://raw.githubusercontent.com/kubernetes-sigs/aws-fsx-csi-driver/master/examples/kubernetes/dynamic_provisioning_s3/specs/storageclass.yaml| | total com/kubernetes-sigs/aws-fsx-csi-driver/master/examples/kubernetes/dynamic_provisioning_s3/specs/storageclass.yaml| | total com/kubernetes/dynamic_provisioning_s3/specs/storageclass.yaml| | total com/kubernetes/dynami
```

3. Edit the file and replace the existing, <example values> with your own.

```
parameters:
    subnetId: <subnet-056da83524edbe641>
    securityGroupIds: <sg-086f61ea73388fb6b>
    s3ImportPath: s3://<ml-training-data-000>
    s3ExportPath: s3://<ml-training-data-000/export>
    deploymentType: <SCRATCH_2>
```

- **subnetId** The subnet ID that the Amazon FSx for Lustre file system should be created in. Amazon FSx for Lustre is not supported in all Availability Zones. Open the Amazon FSx for Lustre console at https://console.aws.amazon.com/fsx/ to confirm that the subnet that you want to use is in a supported Availability Zone. The subnet can include your nodes, or can be a different subnet or VPC. If the subnet that you specify is not the same subnet that you have nodes in, then your VPCs must be connected, and you must ensure that you have the necessary ports open in your security groups.
- securityGroupIds The security group ID for your nodes.
- s3ImportPath The Amazon Simple Storage Service data repository that you want to copy data from to the persistent volume. Specify the fsx-csi bucket that you created in step 1.
- s3ExportPath The Amazon S3 data repository that you want to export new or modified files to. Specify the fsx-csi/export folder that you created in step 1.
- deploymentType The file system deployment type. Valid values are SCRATCH_1, SCRATCH_2, and PERSISTENT_1. For more information about deployment types, see Create your Amazon FSx for Lustre file system.

Note

The Amazon S3 bucket for s3ImportPath and s3ExportPath must be the same, otherwise the driver cannot create the Amazon FSx for Lustre file system. The s3ImportPath can stand alone. A random path will be created automatically like s3://ml-training-data-000/FSxLustre20190308T012310Z. The s3ExportPath cannot be used without specifying a value for S3ImportPath.

4. Create the storageclass.

```
kubectl apply -f storageclass.yaml
```

5. Download the persistent volume claim manifest.

Amazon EKS User Guide Amazon FSx for Lustre CSI driver

curl -o claim.yaml https://raw.githubusercontent.com/kubernetes-sigs/aws-fsx-csidriver/master/examples/kubernetes/dynamic_provisioning_s3/specs/claim.yaml

6. (Optional) Edit the claim.yaml file. Change the following <value> to one of the increment values listed below, based on your storage requirements and the deploymentType that you selected in a previous step.

storage: <1200Gi>

- SCRATCH_2 and PERSISTENT 1.2 TiB, 2.4 TiB, or increments of 2.4 TiB over 2.4 TiB.
- SCRATCH 1 1.2 TiB, 2.4 TiB, 3.6 TiB, or increments of 3.6 TiB over 3.6 TiB.
- 7. Create the persistent volume claim.

kubectl apply -f claim.yaml

8. Confirm that the file system is provisioned.

kubectl get pvc

Output.

ME STATU	S VOLUME	CAPACITY	ACCESS MODES	
STORAGECLASS c-claim Bound fsx-sc	AGE pvc-15dad3c1-2365-11ea-a836-02468c18769e 7m37s	1200Gi	RWX	

Note

The STATUS may show as Pending for 5-10 minutes, before changing to Bound. Don't continue with the next step until the STATUS is Bound.

9. Deploy the sample application.

kubectl apply -f https://raw.githubusercontent.com/kubernetes-sigs/aws-fsx-csi-driver/
master/examples/kubernetes/dynamic_provisioning_s3/specs/pod.yaml

10. Verify that the sample application is running.

```
kubectl get pods
```

Output

NAME	READY	STATUS	RESTARTS	AGE
fsx-app	1/1	Running	0	8s

Access Amazon S3 files from the Amazon FSx for Lustre file system

If you only want to import data and read it without any modification and creation, then you don't need a value for s3ExportPath in your storageclass.yaml file. Verify that data was written to the Amazon FSx for Lustre file system by the sample app.

```
kubectl exec -it fsx-app ls /data
```

Output.

Amazon EKS User Guide Amazon FSx for Lustre CSI driver

```
export out.txt
```

The sample app wrote the out.txt file to the file system.

Archive files to the s3ExportPath

For new files and modified files, you can use the Lustre user space tool to archive the data back to Amazon S3 using the value that you specified for s3ExportPath.

1. Export the file back to Amazon S3.

```
kubectl exec -ti fsx-app -- lfs hsm_archive /data/out.txt
```

Note


- New files aren't synced back to Amazon S3 automatically. In order to sync files to
 the s3ExportPath, you need to install the Lustre client in your container image and
 manually run the lfs hsm_archive command. The container should run in privileged
 mode with the CAP_SYS_ADMIN capability.
- This example uses a lifecycle hook to install the Lustre client for demonstration purpose. A normal approach is building a container image with the Lustre client.
- 2. Confirm that the out.txt file was written to the s3ExportPath folder in Amazon S3.

```
aws s3 ls fsx-csi/export/
```

Output

Amazon EKS networking

This chapter provides an overview of Amazon EKS networking. The following diagram shows key components of an Amazon EKS cluster, and the relationship of these components to a VPC.



The following explanations help you understand how components of the diagram relate to each other and which topics in this guide and other AWS guides that you can reference for more information.

- Amazon VPC and subnets All Amazon EKS resources are deployed to one Region in an existing subnet in an existing VPC. For more information, see VPCs and subnets in the Amazon VPC User Guide. Each subnet exists in one Availability Zone. The VPC and subnets must meet requirements such as the following:
 - VPCs and subnets must be tagged appropriately, so that Kubernetes knows that it can use
 them for deploying resources, such as load balancers. For more information, see VPC tagging
 requirement (p. 203) and Subnet tagging requirement (p. 204). If you deploy the VPC using an
 Amazon EKS provided AWS CloudFormation template (p. 199) or using eksctl, then the VPC and
 subnets are tagged appropriately for you.
 - A subnet may or may not have internet access. If a subnet does not have internet access, the pods
 deployed within it must be able to access other AWS services, such as Amazon ECR, to pull container
 images. For more information about using subnets that don't have internet access, see Private
 clusters (p. 92).
 - Any public subnets that you use must be configured to auto-assign public IP addresses for Amazon EC2 instances launched within them. For more information, see VPC IP addressing (p. 202).
 - The nodes and control plane must be able to communicate over all ports through appropriately tagged security groups. For more information, see Amazon EKS security group considerations (p. 204).
 - You can implement a network segmentation and tenant isolation network policy. Network policies are similar to AWS security groups in that you can create network ingress and egress rules. Instead of assigning instances to a security group, you assign network policies to pods using pod selectors and labels. For more information, see the section called "Installing Calico on Amazon EKS" (p. 239).

Amazon EKS User Guide Creating a VPC for Amazon EKS

You can deploy a VPC and subnets that meet the Amazon EKS requirements through manual configuration, or by deploying the VPC and subnets using <code>eksctl</code> (p. 298), or an Amazon EKS provided AWS CloudFormation template. Both <code>eksctl</code> and the AWS CloudFormation template create the VPC and subnets with the required configuration. For more information, see Creating a VPC for your Amazon EKS cluster (p. 199).

• Amazon EKS control plane – Deployed and managed by Amazon EKS in an Amazon EKS managed VPC. When you create the cluster, Amazon EKS creates and manages network interfaces in your account that have Amazon EKS <cluster name> in their description. These network interfaces allow AWS Fargate and Amazon EC2 instances to communicate with the control plane.

By default, the control plane exposes a public endpoint so that clients and nodes can communicate with the cluster. You can limit the internet client source IP addresses that can communicate with the public endpoint. Alternatively, you can enable a private endpoint and disable the public endpoint or enable both the public and private endpoints. To learn more about cluster endpoints, see Amazon EKS cluster endpoint access control (p. 56).

Clients in your on-premises network or other VPCs can communicate with the public or private-only endpoint, if you've configured connectivity between the VPC that the cluster is deployed to and the other networks. For more information about connecting your VPC to other networks, see the AWS Network-to-Amazon VPC connectivity options and Amazon VPC-to-Amazon VPC connectivity options technical papers.

• Amazon EC2 instances – Each Amazon EC2 node is deployed to one subnet. Each node is assigned a private IP address from a CIDR block assigned to the subnet. If the subnets were created using one of the Amazon EKS provided AWS CloudFormation templates (p. 199), then nodes deployed to public subnets are automatically assigned a public IP address by the subnet. Each node is deployed with the Pod networking (CNI) (p. 208) which, by default, assigns each pod a private IP address from the CIDR block assigned to the subnet that the node is in and adds the IP address as a secondary IP address to one of the network interfaces attached to the instance. This AWS resource is referred to as a network interface in the AWS Management Console and the Amazon EC2 API. Therefore, we use "network interface" in this documentation instead of "elastic network interface". The term "network interface" in this documentation always means "elastic network interface".

You can change this behavior by assigning additional CIDR blocks to your VPC and enabling CNI custom networking (p. 224), which assigns IP addresses to pods from different subnets than the node is deployed to. To use custom networking, you must enable it when you launch your nodes. You can also associate unique security groups with some of the pods running on many Amazon EC2 instance types. For more information, see Security groups for pods (p. 213).

By default, the source IP address of each pod that communicates with resources outside of the VPC is translated through network address translation (NAT) to the primary IP address of the primary network interface attached to the node. You can change this behavior to instead have a NAT device in a private subnet translate each pod's IP address to the NAT device's IP address. For more information, see External source network address translation (SNAT) (p. 209).

• Fargate pods – Deployed to private subnets only. Each pod is assigned a private IP address from the CIDR block assigned to the subnet. Fargate does not support all pod networking options. For more information, see AWS Fargate considerations (p. 137).

Creating a VPC for your Amazon EKS cluster

Amazon Virtual Private Cloud (Amazon VPC) enables you to launch AWS resources into a virtual network that you've defined. This virtual network closely resembles a traditional network that you'd operate in your own data center, with the benefits of using the scalable infrastructure of AWS. For more information, see the Amazon VPC User Guide and De-mystifying cluster networking for Amazon EKS nodes.

Amazon EKS User Guide Creating a VPC for Amazon EKS

If you want to use an existing VPC, then it must meet specific requirements for use with Amazon EKS. For more information, see Cluster VPC considerations (p. 202). This topic guides you through creating a VPC for your cluster using one of the following configurations:

Public and private subnets – This VPC has two public and two private subnets. One public and one
private subnet are deployed to the same Availability Zone. The other public and private subnets
are deployed to a second Availability Zone in the same Region. We recommend this option for all
production deployments. This option allows you to deploy your nodes to private subnets and allows
Kubernetes to deploy load balancers to the public subnets that can load balance traffic to pods
running on nodes in the private subnets.

Public IP addresses are automatically assigned to resources deployed to one of the public subnets, but public IP addresses are not assigned to any resources deployed to the private subnets. The nodes in private subnets can communicate with the cluster and other AWS services, and pods can communicate outbound to the internet through a NAT gateway that is deployed in each Availability Zone. A security group is deployed that denies all inbound traffic and allows all outbound traffic. The subnets are tagged so that Kubernetes is able to deploy load balancers to them. For more information about subnet tagging, see Subnet tagging requirement (p. 204). For more information about this type of VPC, see VPC with public and private subnets (NAT).

- Only public subnets This VPC has three public subnets that are deployed into different Availability
 Zones in the region. All nodes are automatically assigned public IP addresses and can send and
 receive internet traffic through an internet gateway. A security group is deployed that denies all
 inbound traffic and allows all outbound traffic. The subnets are tagged so that Kubernetes can
 deploy load balancers to them. For more information about subnet tagging, see Subnet tagging
 requirement (p. 204). For more information about this type of VPC, see VPC with a single public
 subnet.
- Only private subnets This VPC has three private subnets that are deployed into different Availability
 Zones in the Region. All nodes can optionally send and receive internet traffic through a NAT instance
 or NAT gateway. A security group is deployed that denies all inbound traffic and allows all outbound
 traffic. The subnets are tagged so that Kubernetes can deploy internal load balancers to them.
 For more information about subnet tagging, see Subnet tagging requirement (p. 204). For more
 information about this type of VPC, see VPC with a private subnet only and AWS Site-to-Site VPN
 access.

Important

There are additional requirements if the VPC does not have outbound internet access, such as via a NAT Instance, NAT Gateway, VPN, or Direct Connect. You must bypass the EKS cluster introspection by providing the cluster certificate authority and cluster API endpoint to the nodes. You also may need to configure VPC endpoints listed in Modifying cluster endpoint access (p. 57).

Important

If you deployed a VPC using eksctl or by using either of the Amazon EKS AWS CloudFormation VPC templates:

- On or after March 26, 2020 Public IPv4 addresses are automatically assigned by public subnets to new nodes deployed to public subnets.
- Before March 26, 2020 Public IPv4 addresses are not automatically assigned by public subnets to new nodes deployed to public subnets.

This change impacts new node groups deployed to public subnets in the following ways:

 Managed node groups (p. 103) – If the node group is deployed to a public subnet on or after April 22, 2020, the public subnet must have automatic assignment of public IP addresses enabled. For more information, see Modifying the public IPv4 addressing attribute for your subnet.

Amazon EKS User Guide Creating a VPC for Amazon EKS

Linux (p. 116), Windows (p. 124), or Arm (p. 160) self-managed node groups – If the node group is deployed to a public subnet on or after March 26, 2020, the public subnet must have automatic assignment of public IP addresses enabled or the nodes must be launched with a public IP address. For more information, see Modifying the public IPv4 addressing attribute for your subnet or Assigning a public IPv4 address during instance launch.

Creating a VPC for your Amazon EKS cluster

You can create a VPC with public and private subnets (p. 199), only public subnets (p. 200), or only private subnets (p. 201).

To create your cluster VPC with public and private subnets

- 1. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
- 2. From the navigation bar, select a Region that supports Amazon EKS.
- 3. Choose Create stack, With new resources (standard).
- 4. For Choose a template, select Specify an Amazon S3 template URL.
- 5. Paste the URL that corresponds to the Region that your cluster is in into the text area and choose **Next**:
 - All Regions other than China Regions.

https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/amazon-eks-vpc-private-subnets.yaml

Beijing and Ningxia China Regions.

 $\label{lem:https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/amazon-eks-vpc-private-subnets.yaml$

- 6. On the Specify Details page, fill out the parameters accordingly, and then choose Next.
 - Stack name: Choose a stack name for your AWS CloudFormation stack. For example, you can call
 it eks-vpc.
 - VpcBlock: Choose a CIDR range for your VPC. Each worker node, pod, and load balancer that you
 deploy is assigned an IP address from this block. The default value provides enough IP addresses
 for most implementations, but if it doesn't, then you can change it. For more information, see VPC
 and subnet sizing in the Amazon VPC User Guide. You can also add additional CIDR blocks to the
 VPC once it's created.
 - **PublicSubnetO1Block**: Specify a CIDR block for public subnet 1. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
 - **PublicSubnet02Block**: Specify a CIDR block for public subnet 2. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
 - **PrivateSubnet01Block**: Specify a CIDR block for private subnet 1. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
 - **PrivateSubnetO2Block**: Specify a CIDR block for private subnet 2. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
- 7. (Optional) On the Options page, tag your stack resources. Choose Next.
- 8. On the Review page, choose Create.
- 9. When your stack is created, select it in the console and choose **Outputs**.
- 10. Record the **SecurityGroups** value for the security group that was created. When you add nodes to your cluster, you must specify the ID of the security group. The security group is applied to the

Amazon EKS User Guide Creating a VPC for Amazon EKS

- elastic network interfaces that are created by Amazon EKS in your subnets that allows the control plane to communicate with your nodes. These network interfaces have Amazon EKS <cluster name> in their description.
- 11. Record the **VpcId** for the VPC that was created. You need this when you launch your node group template.
- 12. Record the **SubnetIds** for the subnets that were created and whether you created them as public or private subnets. When you add nodes to your cluster, you must specify the IDs of the subnets that you want to launch the nodes into.

To create your cluster VPC with only public subnets

- 1. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
- 2. From the navigation bar, select a Region that supports Amazon EKS.
- 3. Choose Create stack, With new resources (standard).
- 4. For Choose a template, select Specify an Amazon S3 template URL.
- 5. Paste the URL that corresponds to the Region that your cluster is in into the text area and choose **Next**:
 - All Regions other than China Regions.

https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/amazon-eks-vpc-sample.yaml

· Beijing and Ningxia China Regions.

 $\label{lem:https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/amazon-eks-vpc-sample.yaml$

- 6. On the Specify Details page, fill out the parameters accordingly, and then choose Next.
 - Stack name: Choose a stack name for your AWS CloudFormation stack. For example, you can call
 it eks-vpc.
 - VpcBlock: Choose a CIDR block for your VPC. Each worker node, pod, and load balancer that you
 deploy is assigned an IP address from this block. The default value provides enough IP addresses
 for most implementations, but if it doesn't, then you can change it. For more information, see VPC
 and subnet sizing in the Amazon VPC User Guide. You can also add additional CIDR blocks to the
 VPC once it's created.
 - **Subnet01Block**: Specify a CIDR block for subnet 1. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
 - **Subnet02Block**: Specify a CIDR block for subnet 2. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
 - **Subnet03Block**: Specify a CIDR block for subnet 3. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
- 7. (Optional) On the **Options** page, tag your stack resources. Choose **Next**.
- 8. On the **Review** page, choose **Create**.
- 9. When your stack is created, select it in the console and choose **Outputs**.
- 10. Record the **SecurityGroups** value for the security group that was created. When you add nodes to your cluster, you must specify the ID of the security group. The security group is applied to the elastic network interfaces that are created by Amazon EKS in your subnets that allows the control plane to communicate with your nodes. These network interfaces have Amazon EKS <cluster name> in their description.
- 11. Record the **VpcId** for the VPC that was created. You need this when you launch your node group template.

Amazon EKS User Guide Creating a VPC for Amazon EKS

12. Record the **SubnetIds** for the subnets that were created. When you add nodes to your cluster, you must specify the IDs of the subnets that you want to launch the nodes into.

To create your cluster VPC with only private subnets

- 1. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
- 2. From the navigation bar, select a Region that supports Amazon EKS.
- 3. Choose Create stack, With new resources (standard).
- 4. For Choose a template, select Specify an Amazon S3 template URL.
- Paste the URL that corresponds to the Region that your cluster is in into the text area and choose Next:
 - · All Regions other than China Regions.

· Beijing and Ningxia China Regions.

https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/amazon-eks-fully-private-vpc.yaml

- 6. On the Specify Details page, fill out the parameters accordingly, and then choose Next.
 - Stack name: Choose a stack name for your AWS CloudFormation stack. For example, you can call it eks-vpc.
 - VpcBlock: Choose a CIDR block for your VPC. Each worker node, pod, and load balancer that you
 deploy is assigned an IP address from this block. The default value provides enough IP addresses
 for most implementations, but if it doesn't, then you can change it. For more information, see VPC
 and subnet sizing in the Amazon VPC User Guide. You can also add additional CIDR blocks to the
 VPC once it's created.
 - **PrivateSubnet01Block**: Specify a CIDR block for subnet 1. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
 - **PrivateSubnet02Block**: Specify a CIDR block for subnet 2. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
 - PrivateSubnet03Block: Specify a CIDR block for subnet 3. The default value provides enough IP addresses for most implementations, but if it doesn't, then you can change it
- 7. (Optional) On the **Options** page, tag your stack resources. Choose **Next**.
- On the Review page, choose Create.
- 9. When your stack is created, select it in the console and choose **Outputs**.
- 10. Record the **SecurityGroups** value for the security group that was created. When you add nodes to your cluster, you must specify the ID of the security group. The security group is applied to the elastic network interfaces that Amazon EKS creates in your subnets to allow the control plane to communicate with your nodes. These network interfaces have Amazon EKS <cluster name> in their description.
- 11. Record the **VpcId** for the VPC that was created. You need this when you launch your node group template.
- 12. Record the **SubnetIds** for the subnets that were created. When you add nodes to your cluster, you must specify the IDs of the subnets that you want to launch the nodes into.

Next steps

After you have created your VPC, you can try the Getting started with Amazon EKS (p. 4) walkthrough, but you can skip the Create your Amazon EKS cluster VPC (p. 22) section and use these subnets and security groups for your cluster.

Cluster VPC considerations

When you create an Amazon EKS cluster, you specify the VPC subnets for your cluster to use. Amazon EKS requires subnets in at least two Availability Zones. We recommend a VPC with public and private subnets so that Kubernetes can create public load balancers in the public subnets that load balance traffic to pods running on nodes that are in private subnets.

When you create your cluster, you also specify all of the subnets that host resources for your cluster, such as nodes and load balancers.

Note

Internet-facing load balancers require a public subnet in your cluster. By default, nodes also require outbound internet access to the Amazon EKS APIs for cluster introspection and node registration at launch time. For clusters without outbound internet access, see Private clusters (p. 92).

To pull container images, they require access to the Amazon S3 and Amazon ECR APIs (and any other container registries, such as DockerHub). For more information, see Amazon EKS security group considerations (p. 204) and AWS IP Address Ranges in the AWS General Reference.

The subnets that you pass when you create the cluster influence where Amazon EKS places network interfaces that are used for the control plane to node communication.

It is possible to specify only public or private subnets when you create your cluster, but there are some limitations associated with these configurations:

- **Private-only**: Everything runs in a private subnet and Kubernetes cannot create internet-facing load balancers for your pods.
- **Public-only**: Everything runs in a public subnet, including your nodes.

Amazon EKS creates a network interface in your private subnets to facilitate communication to your nodes. This communication channel supports Kubernetes functionality such as kubectl exec and kubectl logs. The security group that you specify when you create your cluster is applied to the network interfaces that are created for your cluster control plane.

Your VPC must have DNS hostname and DNS resolution support. Otherwise, your nodes cannot register with your cluster. For more information, see Using DNS with Your VPC in the Amazon VPC User Guide.

VPC IP addressing

Nodes must be able to communicate with the control plane and other AWS services. If your nodes are deployed in a private subnet, then you must have either:

- Set up a default route for the subnet to a NAT gateway. The NAT gateway must be assigned a public IP address to provide internet access for the nodes.
- Configured several necessary settings for the subnet and taken the necessary actions listed in Private clusters (p. 92).

If self-managed nodes are deployed to a public subnet, the subnet must be configured to auto-assign public IP addresses. Otherwise, your node instances must be assigned a public IP address when they're

Amazon EKS User Guide VPC tagging requirement

launched. If managed nodes are deployed to a public subnet, the subnet must be configured to auto-assign public IP addresses. This is because, if they are not, then the nodes aren't assigned a public IP address. Determine whether your public subnets are configured to auto-assign public IP addresses with the following command.

```
aws ec2 describe-subnets \
    --filters "Name=vpc-id, Values=<VPC-ID>" | grep 'SubnetId\|MapPublicIpOnLaunch'
```

The output is as follows.

For any subnets that have MapPublicIpOnLaunch set to false, change the setting to true.

```
aws ec2 modify-subnet-attribute --map-public-ip-on-launch --subnet-id <subnet-aaaaaaaaaaaaa>
```

Important

If you used an Amazon EKS AWS CloudFormation template (p. 197) to deploy your VPC before March 26, 2020, then you need to change the setting for your public subnets.

You can define both private (RFC 1918), and public (non-RFC 1918) CIDR ranges within the VPC used for your Amazon EKS cluster. For more information, see Adding IPv4 CIDR blocks to a VPC in the Amazon VPC User Guide. When choosing the classless inter-domain routing (CIDR) blocks for your VPC and subnets, make sure that the blocks contain enough IP addresses for all of the Amazon EC2 nodes and pods that you plan to deploy. There should be at least one IP address for each of your pods. You can conserve IP address use by implementing a transit gateway with a shared services VPC. For more information, see Isolated VPCs with shared services and EKS VPC routable IP address conservation patterns in a hybrid network.

The Amazon EKS control plane creates up to 4 network interfaces in your VPC for each cluster. These network interfaces have Amazon EKS <cluster name> in their description. Be sure that the subnets that you specify have enough available IP addresses for the network interfaces and your pods.

VPC tagging requirement

When you create an Amazon EKS cluster that is earlier than version 1.15, Amazon EKS tags the VPC containing the subnets you specify in the following way so that Kubernetes can discover it:

Key	Value
kubernetes.io/cluster/ <cluster-name></cluster-name>	shared

- **Key**: The <cluster-name> value matches your Amazon EKS cluster's name.
- Value: The shared value allows more than one cluster to use this VPC.

This tag is not required or created by Amazon EKS for 1.15 or later clusters. If you deploy a 1.15 or later cluster to a VPC that already has this tag, the tag is not removed.

Subnet tagging requirement

When you create your Amazon EKS cluster, Amazon EKS tags the subnets you specify in the following way so that Kubernetes can discover them:

ŀ	Сеу	Value
1	<pre>subernetes.io/cluster/<cluster-name></cluster-name></pre>	shared

- **Key**: The <cluster-name> value matches your Amazon EKS cluster.
- Value: The shared value allows more than one cluster to use this subnet.

Private subnet tagging requirement for internal load balancers

Private subnets must be tagged as follows so that Kubernetes knows it can use the subnets for internal load balancers. If you use <code>eksctl</code> or an Amazon EKS AWS CloudFormation template to create your VPC after March 26, 2020, then the subnets are tagged appropriately when they're created. For more information about the Amazon EKS AWS CloudFormation VPC templates, see Creating a VPC for your Amazon EKS cluster (p. 197).

Key	Value
kubernetes.io/role/internal-elb	1

Public subnet tagging option for external load balancers

Public subnets must be tagged as follows so that Kubernetes knows to use only those subnets for external load balancers instead of choosing a public subnet in each Availability Zone (in lexicographical order by subnet ID). If you use <code>eksctl</code> or an Amazon EKS AWS CloudFormation template to create your VPC after March 26, 2020, then the subnets are tagged appropriately when they're created. For more information about the Amazon EKS AWS CloudFormation VPC templates, see Creating a VPC for your Amazon EKS cluster (p. 197).

Key	Value
kubernetes.io/role/elb	1

Amazon EKS security group considerations

The following sections describe the recommended or minimum required security group settings for the cluster, control plane, and node security groups of your cluster. These considerations are dependent on which Kubernetes version and Amazon EKS platform version you use.

Cluster security group

Amazon EKS clusters, starting with Kubernetes version 1.14 and platform version (p. 73) eks.3, create a cluster security group when they are created. This also happens when a cluster of an earlier version is upgraded to this Kubernetes version and platform version. A cluster security group is designed to allow all traffic from the control plane and managed node groups (p. 100) to flow freely between each other.

Amazon EKS User Guide Control plane and node security groups

By assigning the cluster security group to the elastic network interfaces created by Amazon EKS that allow the control plane to communicate with the managed node group instances, you don't need to configure complex security group rules to allow this communication. Any instance or network interface that is assigned this security group can freely communicate with other resources with this security group.

You can check for a cluster security group for your cluster in the AWS Management Console under the cluster's **Networking** section, or with the following AWS CLI command:

```
aws eks describe-cluster --name <cluster_name> --query
  cluster.resourcesVpcConfig.clusterSecurityGroupId
```

We recommend that you add the cluster security group to all existing and future node groups. For more information, see Security Groups for Your VPC in the *Amazon VPC User Guide*. Amazon EKS managed node groups (p. 100) are automatically configured to use the cluster security group.

	Protocol	Ports	Source	Destination
Recommended inbound traffic	All	All	Self	
Recommended outbound traffic	All	All		0.0.0/0

Restricting cluster traffic

If you need to limit the open ports between the control plane and nodes, the default cluster security group can be modified to allow only the following required minimum ports. The required minimum ports are the same as they were in previous Amazon EKS versions.

	Protocol	Port	Source	Destination
Minimum inbound traffic	ТСР	443	Cluster security group	
Minimum inbound traffic*	ТСР	10250	Cluster security group	
Minimum outbound traffic	ТСР	443		Cluster security group
Minimum outbound traffic*	ТСР	10250		Cluster security group

*Any protocol and ports that you expect your nodes to use for inter-node communication should be included, if required. Nodes also require outbound internet access to the Amazon EKS APIs for cluster introspection and node registration at launch time, or that you've implemented the required necessary settings in Private clusters (p. 92). To pull container images, they require access to Amazon S3, Amazon ECR APIs, and any other container registries that they need to pull images from, such as DockerHub. For more information, see AWS IP address ranges in the AWS General Reference.

Control plane and node security groups

For Amazon EKS clusters created earlier than Kubernetes version 1.14 and platform version (p. 73) eks.3, control plane to node communication was configured by manually creating a control plane security group and specifying that security group when you created the cluster. At cluster creation,

Amazon EKS User Guide Control plane and node security groups

this security group was then attached to the network interfaces created by Amazon EKS that allow communication between the control plane and the nodes. These network interfaces have Amazon EKS <cluster name> in their description.

Note

If you used the API directly, or a tool such as AWS CloudFormation to create your cluster and didn't specify a security group, then the default security group for the VPC was applied to the control plane cross-account network interfaces.

You can check the control plane security group for your cluster in the AWS Management Console under the cluster's **Networking** section (listed as **Additional security groups**), or with the following AWS CLI command:

```
aws eks describe-cluster --name <cluster_name> --query
cluster.resourcesVpcConfig.securityGroupIds
```

If you launch nodes with the AWS CloudFormation template in the Getting started with Amazon EKS (p. 4) walkthrough, AWS CloudFormation modifies the control plane security group to allow communication with the nodes. Amazon EKS strongly recommends that you use a dedicated security group for each control plane (one for each cluster). If you share a control plane security group with other Amazon EKS clusters or resources, you may block or disrupt connections to those resources.

The security group for the nodes and the security group for the control plane communication to the nodes have been set up to prevent communication to privileged ports in the nodes. If your applications require added inbound or outbound access from the control plane or nodes, you must add these rules to the security groups associated with your cluster. For more information, see Security Groups for Your VPC in the Amazon VPC User Guide.

Note

To allow proxy functionality on privileged ports or to run the CNCF conformance tests yourself, you must edit the security groups for your control plane and the nodes. The security group on the nodes' side needs to allow inbound access for ports 0-65535 from the control plane, and the control plane side needs to allow outbound access to the nodes on ports 0-65535.

Control Plane Security Group

	Protocol	Port range	Source	Destination
Minimum inbound traffic	ТСР	443	All node security groups When cluster endpoint private access (p. 56) is enabled: Any security groups that generate API server client traffic (such as kubectl commands on a bastion host within your cluster's VPC)	
Recommended inbound traffic	TCP	443	All node security groups When cluster endpoint private	

Amazon EKS User Guide Control plane and node security groups

	Protocol	Port range	Source	Destination
			access (p. 56) is enabled: Any security groups that generate API server client traffic (such as kubect1 commands on a bastion host within your cluster's VPC)	
Minimum outbound traffic	ТСР	10250		All node security groups
Recommended outbound traffic	ТСР	1025-65535		All node security groups

Node security group

	Protocol	Port range	Source	Destination
Minimum inbound traffic (from other nodes)	Any protocol that you expect your nodes to use for inter-node communication	Any ports that you expect your nodes to use for inter-node communication	All node security groups	
Minimum inbound traffic (from control plane)	ТСР	10250	Control plane security group	
Recommended inbound traffic	All	All 443, 1025-65535	All node security groups Control plane security group	
Minimum outbound traffic*	ТСР	443		Control plane security group
Recommended outbound traffic	All	All		0.0.0.0/0

*Nodes also require access to the Amazon EKS APIs for cluster introspection and node registration at launch time either through the internet or VPC endpoints. To pull container images, they require access to the Amazon S3 and Amazon ECR APIs (and any other container registries, such as DockerHub). For more information, see AWS IP address ranges in the AWS General Reference and Private clusters (p. 92).

If you have more than one security group associated to your nodes, then one of the security groups must have the following tag applied. If you have only one security group associated to your nodes, then the tag is optional. For more information about tagging, see Working with tags using the console (p. 310).

Key	Value
kubernetes.io/cluster/ <cluster-name></cluster-name>	owned

Pod networking (CNI)

Amazon EKS supports native VPC networking with the Amazon VPC Container Network Interface (CNI) plugin for Kubernetes. Using this plugin allows Kubernetes pods to have the same IP address inside the pod as they do on the VPC network. The plugin is an open-source project that is maintained on GitHub. For more information, see amazon-vpc-cni-k8s and Proposal: CNI plugin for Kubernetes networking over AWS VPC on GitHub. The Amazon VPC CNI plugin is fully supported for use on Amazon EKS and self-managed Kubernetes clusters on AWS.

Note

Kubernetes can use the Container Networking Interface (CNI) for configurable networking setups. The Amazon VPC CNI plugin might not meet requirements for all use cases. Amazon EKS maintains a network of partners that offer alternative CNI solutions with commercial support options. For more information, see Alternate compatible CNI plugins (p. 236).

When you create an Amazon EKS node, it has one network interface. All Amazon EC2 instance types support more than one network interface. The network interface attached to the instance when the instance is created is called the *primary network interface*. Any additional network interface attached to the instance is called a *secondary network interface*. Each network interface can be assigned multiple private IP addresses. One of the private IP addresses is the *primary IP address*, whereas all other addresses assigned to the network interface are *secondary IP addresses*. For more information about network interfaces, see Elastic network interfaces in the *Amazon EC2 User Guide for Linux Instances*. For more information about how many network interfaces and private IP addresses are supported for each network interface, see IP addresses per network interface per instance type in the *Amazon EC2 User Guide for Linux Instances*. For example, an m5.large instance type supports three network interfaces and ten private IP addresses for each network interface.

The Amazon VPC Container Network Interface (CNI) plugin for Kubernetes is deployed with each of your Amazon EC2 nodes in a Daemonset with the name aws-node. The plugin consists of two primary components:

L-IPAM daemon – Responsible for creating network interfaces and attaching the network interfaces
to Amazon EC2 instances, assigning secondary IP addresses to network interfaces, and maintaining
a warm pool of IP addresses on each node for assignment to Kubernetes pods when they are
scheduled. When the number of pods running on the node exceeds the number of addresses that can
be assigned to a single network interface, the plugin starts allocating a new network interface, as
long as the maximum number of network interfaces for the instance aren't already attached. There
are configuration variables that allow you to change the default value for when the plugin creates
new network interfaces. For more information, see WARM_ENI_TARGET, WARM_IP_TARGET and
MINIMUM_IP_TARGET on GitHub.

Each pod that you deploy is assigned one secondary private IP address from one of the network interfaces attached to the instance. Previously, it was mentioned that an m5.large instance supports three network interfaces and ten private IP addresses for each network interface. Even though an m5.large instance supports 30 private IP addresses, you can't deploy 30 pods to that node. To determine how many pods you can deploy to a node, use the following formula:

```
(Number of network interfaces for the instance type \times (the number of IP addressess per network interface - 1)) + 2
```

Using this formula, an m5.large instance type can support a maximum of 29 pods. For a list of the maximum number of pods supported by each instance type, see eni-max-pods.txt on GitHub. System pods count towards the maximum pods. For example, the CNI plugin and kube-proxy pods run on every node in a cluster, so you're only able to deploy 27 additional pods to an m5.large instance, not 29. Further, CoreDNS runs on some of the nodes in the cluster, which decrements the maximum pods by another one for the nodes it runs on.

By default, all pods deployed to a node are assigned the same security groups and are assigned private IP addresses from a CIDR block that is assigned to the subnet that one of the instance's network interfaces is connected to. You can assign IP addresses from a different CIDR block than the subnet that the primary network interface is connected to by configuring CNI custom networking (p. 224). You can also use CNI custom networking to assign all pods on a node the same security groups. The security groups assigned to all pods can be different than the security groups assigned to the primary network interface. You can assign unique security groups to pods deployed to many Amazon EC2 instance types using security groups for pods. For more information, see Security groups for pods (p. 213).

• **CNI plugin** – Responsible for wiring the host network (for example, configuring the network interfaces and virtual Ethernet pairs) and adding the correct network interface to the pod namespace.


Important

If you are using version 1.7.0 or later of the CNI plugin and you assign a custom pod security policy to the aws-node Kubernetes service account used for the aws-node pods deployed by the Daemonset, then the policy must have NET_ADMIN in its allowedCapabilities section along with hostNetwork: true and privileged: true in the policy's spec. For more information, see the section called "Pod security policy" (p. 353).

External source network address translation (SNAT)

Communication within a VPC (such as pod to pod) is direct between private IP addresses and requires no source network address translation (SNAT). When traffic is destined for an address outside of the VPC, the Amazon VPC CNI plugin for Kubernetes translates the private IP address of each pod to the primary private IP address assigned to the primary network interface (network interface) of the Amazon EC2 node that the pod is running on, by default. SNAT:

• Enables pods to communicate bi-directionally with the internet. The node must be in a public subnet and have a public or elastic IP address assigned to the primary private IP address of its primary network interface. The traffic is translated to and from the public or elastic IP address and routed to and from the internet by an internet gateway, as shown in the following picture.



Amazon EKS User Guide Configure plugin for IAM account

SNAT is necessary because the internet gateway can only translate between the primary private and public or elastic IP address assigned to the primary network interface of the Amazon EC2 instance node that pods are running on.


 Prevents a device in other private IP address spaces (for example, VPC peering, Transit VPC, or Direct Connect) from communicating directly to a pod that is not assigned the primary private IP address of the primary network interface of the Amazon EC2 instance node.

If the internet or devices in other private IP address spaces need to communicate with a pod that isn't assigned the primary private IP address assigned to the primary network interface of the Amazon EC2 instance node that the pod is running on, then:

- The node must be deployed in a private subnet that has a route to a NAT device in a public subnet.
- You need to enable external SNAT in the CNI plugin aws-node DaemonSet with the following command:

kubectl set env daemonset -n kube-system aws-node AWS_VPC_K8S_CNI_EXTERNALSNAT=true

After external SNAT is enabled, the CNI plugin doesn't translate a pod's private IP address to the primary private IP address assigned to the primary network interface of the Amazon EC2 instance node that the pod is running on when traffic is destined for an address outside of the VPC. Traffic from the pod to the internet is externally translated to and from the public IP address of the NAT device and routed to and from the internet by an internet gateway, as shown in the following picture.



Configuring the VPC CNI plugin to use IAM roles for service accounts

The Amazon VPC CNI plugin for Kubernetes is the networking plugin for pod networking in Amazon EKS clusters. The CNI plugin is responsible for allocating VPC IP addresses to Kubernetes nodes and configuring the necessary networking for pods on each node. The plugin requires IAM permissions, provided by the AWS managed policy Amazoneks_CNI_Policy, to make calls to AWS APIs on your behalf.

Amazon EKS User Guide Configure plugin for IAM account

Note

Regardless of whether you configure the VPC CNI plugin to use IAM roles for service accounts, the pods also have access to the permissions assigned to the the section called "Node IAM role" (p. 332), unless you block access to IMDS. For more information, see the section called "Restricting access to the instance profile" (p. 349).

Prerequisite

You must have an IAM OpenID Connect (OIDC) identity provider created for your cluster. To create one, see the section called "Enabling" (p. 341).

You can configure the VPC CNI plugin to use IAM roles for service accounts using eksct1 (p. 211) or the AWS Management Console (p. 211).

[eksctl]

 Check your eksctl version with the following command. This procedure assumes that you have installed eksctl and that your eksctl version is at least 0.33.0.

```
eksctl version
```

For more information about installing or upgrading eksct1, see Installing or upgrading eksct1 (p. 298).

Create a Kubernetes service account with the following command. Replace <cluster_name> with
your own value. This command deploys an AWS CloudFormation stack that creates an IAM role,
attaches the Amazoneks_CNI_Policy AWS managed policy to it, and binds the IAM role to the
service account.

```
eksctl create iamserviceaccount \
    --name aws-node \
    --namespace kube-system \
    --cluster <cluster_name> \
    --attach-policy-arn arn:aws:iam::aws:policy/AmazonEKS_CNI_Policy \
    --approve \
    --override-existing-serviceaccounts
```

Describe one of the pods and verify that the AWS_WEB_IDENTITY_TOKEN_FILE and AWS ROLE ARN environment variables exist.

```
kubectl exec -n kube-system aws-node-<9rgzw> env | grep AWS
```

Output:

```
AWS_VPC_K8S_CNI_LOGLEVEL=DEBUG
AWS_ROLE_ARN=arn:aws:iam::<111122223333>:role/eksctl-prod-addon-iamserviceaccount-kube-sys-Role1-<V66K5I6JLDGK>
AWS_WEB_IDENTITY_TOKEN_FILE=/var/run/secrets/eks.amazonaws.com/serviceaccount/token
```

[AWS Management Console]

You must create an an IAM account and then patch the Kubernetes service account to use the IAM account.

To create your CNI plugin IAM role with the AWS Management Console

1. Open the IAM console at https://console.aws.amazon.com/iam/.

Amazon EKS User Guide Configure plugin for IAM account

- 2. In the navigation panel, choose Roles, Create Role.
- 3. In the **Select type of trusted entity** section, choose **Web identity**.
- 4. In the **Choose a web identity provider** section:
 - 1. For **Identity provider**, choose the URL for your cluster.
 - 2. For Audience, choose sts.amazonaws.com.
- 5. Choose Next: Permissions.
- 6. In the **Attach Policy** section, select the AmazonEKS_CNI_Policy policy to use for your service account. Choose **Next: Tags**.
- 7. On the Add tags (optional) screen, you can add tags for the account. Choose Next: Review.
- 8. For **Role Name**, enter a name for your role, such as AmazonEKSCNIRole, and then choose **Create Role**.
- 9. After the role is created, choose the role in the console to open it for editing.
- 10. Choose the **Trust relationships** tab, and then choose **Edit trust relationship**.
 - a. Edit the OIDC provider suffix and change it from : aud to : sub.
 - b. Replace sts.amazonaws.com with system:serviceaccount:kube-system:aws-node.
 - c. If necessary, change <region-code> (including <>) to the Region code for your cluster.

The resulting line should look like the following example.

```
"oidc.eks.<region-code>.amazonaws.com/id/<EXAMPLED539D4633E53DE1B716D3041E>:sub":
"system:serviceaccount:kube-system:aws-node"
```

11. Choose **Update Trust Policy** to finish.

To patch the aws-node Kubernetes service account to use the CNI plugin IAM role

1. If you're using the Amazon EKS add-on with a 1.18 or later Amazon EKS cluster with platform version eks.3 or later, see the section called "Configure an Amazon EKS add-on" (p. 52), instead of completing this procedure. If you're not using the Amazon VPC CNI Amazon EKS add-on, then use the following command to annotate the aws-node service account with the ARN of the IAM role that you created previously. Be sure to substitute your own values for the <example values> to use with your pods.

```
kubectl annotate serviceaccount \
    -n kube-system aws-node \
    eks.amazonaws.com/role-arn=arn:aws:iam::<AWS_ACCOUNT_ID>:role/<AmazonEKSCNIRole>
```

2. Delete and re-create any existing pods that are associated with the service account to apply the credential environment variables. The mutating web hook does not apply them to pods that are already running. The following command deletes the existing the aws-node DaemonSet pods and deploys them with the service account annotation.

```
kubectl delete pods -n kube-system -l k8s-app=aws-node
```

3. Confirm that the pods all restarted.

```
kubectl get pods -n kube-system -l k8s-app=aws-node
```

4. Describe one of the pods and verify that the AWS_WEB_IDENTITY_TOKEN_FILE and AWS_ROLE_ARN environment variables exist.

```
kubectl exec -n kube-system aws-node-<9rgzw> env | grep AWS
```

Output:

```
AWS_VPC_K8S_CNI_LOGLEVEL=DEBUG
AWS_ROLE_ARN=arn:aws:iam::<AWS_ACCOUNT_ID>:role/<IAM_ROLE_NAME>
AWS_WEB_IDENTITY_TOKEN_FILE=/var/run/secrets/eks.amazonaws.com/serviceaccount/token
```

Remove the CNI policy from the node IAM role

If your the section called "Node IAM role" (p. 332) currently has the AmazonEKS_CNI_Policy IAM policy attached to it, and you've created a separate IAM role, attached the policy to it instead, and assigned it to the aws-node Kubernetes service account, then we recommend that you remove the policy from your node role.

- 1. Open the IAM console at https://console.aws.amazon.com/iam/.
- 2. In the left navigation, choose Roles, and then search for your node instance role.
- Choose the Permissions tab for your node instance role and then choose the X to the right of the Amazoneks_CNI_Policy.
- 4. Choose Detach to finish.

Security groups for pods

Security groups for pods integrate Amazon EC2 security groups with Kubernetes pods. You can use Amazon EC2 security groups to define rules that allow inbound and outbound network traffic to and from pods that you deploy to nodes running on many Amazon EC2 instance types. For a detailed explanation of this capability, see the Introducing security groups for pods blog post.

Considerations

Before deploying security groups for pods, consider the following limits and conditions:

- Your Amazon EKS cluster must be running Kubernetes version 1.17 and Amazon EKS platform version
 eks.3 or later. You can't use security groups for pods on Kubernetes clusters that you deployed to
 Amazon EC2.
- Traffic flow to and from pods with associated security groups are not subjected to Calico network policy (p. 239) enforcement and are limited to Amazon EC2 security group enforcement only. Community effort is underway to remove this limitation.
- Security groups for pods can't be used with pods deployed to Fargate.
- Security groups for pods can't be used with Windows nodes.
- Security groups for pods are supported by most Nitro-based Amazon EC2 instance families, including the m5, c5, r5, p3, m6g, c6g, and r6g instance families. The t3 instance family is not supported. For a complete list of supported instances, see the section called "Supported instances" (p. 217). Your nodes must be one of the supported instance types.
- Source NAT is disabled for outbound traffic from pods with assigned security groups so that outbound security group rules are applied. To access the internet, pods with assigned security groups must be launched on nodes that are deployed in a private subnet configured with a NAT gateway or instance. Pods with assigned security groups deployed to public subnets are not able to access the internet.
- Kubernetes services of type NodePort and LoadBalancer using instance targets with an externalTrafficPolicy set to Local are not supported with pods that you assign security groups

to. For more information about using a load balancer with instance targets, see the section called "Load balancer – Instance targets" (p. 261).

• If you're also using pod security policies to restrict access to pod mutation, then the eks-vpc-resource-controller and vpc-resource-controller Kubernetes service accounts must be specified in the Kubernetes ClusterRoleBinding for the the Role that your psp is assigned to. If you're using the default Amazon EKS psp, Role, and ClusterRoleBinding (p. 353), this is the eks:podsecuritypolicy:authenticated ClusterRoleBinding. For example, you would add the service accounts to the subjects: section, as shown in the following example:

```
subjects:
    - kind: Group
    apiGroup: rbac.authorization.k8s.io
    name: system:authenticated
    - kind: ServiceAccount
    name: vpc-resource-controller
    - kind: ServiceAccount
    name: eks-vpc-resource-controller
```

• If you're using custom networking (p. 224) and security groups for pods together, the security group specified by security groups for pods is used instead of the security group specified in the ENIconfig.

Deploy security groups for pods

To deploy security groups for pods

1. Check your current CNI plugin version with the following command.

```
kubectl describe daemonset aws-node --namespace kube-system | grep Image | cut -d "/" -
f 2
```

The output is similar to the following output.

```
amazon-k8s-cni:<1.7.7>
```

If your CNI plugin version is earlier than 1.7.7, then upgrade your CNI plugin to version 1.7.7 or later. For more information, see Amazon VPC CNI plugin for Kubernetes upgrades (p. 235).

2. Add the AmazonEKSVPCResourceController managed policy to the cluster role (p. 331) that is associated with your Amazon EKS cluster. The policy allows the role to manage network interfaces, their private IP addresses, and their attachment and detachment to and from instances. The following command adds the policy to a cluster role named <eksClusterRole>.

```
aws iam attach-role-policy \
    --policy-arn arn:aws:iam::aws:policy/AmazonEKSVPCResourceController \
    --role-name <eksClusterRole>
```

3. Enable the CNI plugin to manage network interfaces for pods by setting the ENABLE_POD_ENI variable to true in the aws-node DaemonSet. Once this setting is set to true, for each node in the cluster the plugin adds a label with the value vpc.amazonaws.com/has-trunk-attached=true. The VPC resource controller creates and attaches one special network interface called a trunk network interface with the description aws-k8s-trunk-eni.

```
kubectl set env daemonset aws-node -n kube-system ENABLE_POD_ENI=true
```

Note

The trunk network interface is included in the maximum number of network interfaces supported by the instance type. For a list of the maximum number of interfaces supported by each instance type, see IP addresses per network interface per instance type in the Amazon EC2 User Guide for Linux Instances. If your node already has the maximum number of standard network interfaces attached to it then the VPC resource controller will reserve a space. You will have to scale down your running pods enough for the controller to detach and delete a standard network interface, create the trunk network interface, and attach it to the instance.

You can see which of your nodes have aws-k8s-trunk-eni set to true with the following command.

```
kubectl get nodes -o wide -l vpc.amazonaws.com/has-trunk-attached=true
```

Once the trunk network interface is created, pods can be assigned secondary IP addresses from the trunk or standard network interfaces. The trunk interface is automatically deleted if the node is deleted.

When you deploy a security group for a pod in a later step, the VPC resource controller creates a special network interface called a *branch network interface* with a description of aws-k8s-branch-eni and associates the security groups to it. Branch network interfaces are created in addition to the standard and trunk network interfaces attached to the node. If are you using liveness or readiness probes, you also need to disable TCP early demux, so that the kubelet can connect to pods on branch network interfaces via TCP. To disable TCP early demux, run the following command:

```
kubectl patch daemonset aws-node \
  -n kube-system \
  -p '{"spec": {"template": {"spec": {"initContainers": [{"env":
  [{"name":"DISABLE_TCP_EARLY_DEMUX","value":"true"}],"name":"aws-vpc-cni-init"}]}}}'
```

4. Create a namespace to deploy resources to.

```
kubectl create namespace <my-namespace>
```

- 5. Deploy an Amazon EKS SecurityGroupPolicy to your cluster.
 - a. Save the following example security policy to a file named <my-security-group-policy.yaml>. You can replace podSelector with serviceAccountSelector if you'd rather select pods based on service account labels. You must specify one selector or the other. An empty podSelector (example: podSelector: {}) selects all pods in the namespace. An empty serviceAccountSelector selects all service accounts in the namespace. You must specify 1-5 security group IDs for groupIds. If you specify more than one ID, then the combination of all the rules in all the security groups are effective for the selected pods.

```
apiVersion: vpcresources.k8s.aws/v1beta1
kind: SecurityGroupPolicy
metadata:
  name: <my-security-group-policy>
  namespace: <my-namespace>
spec:
  <podSelector>:
    matchLabels:
        <role>: <my-role>
securityGroups:
    groupIds:
        - <sg-abc123>
```

Important

- The security groups that you specify in the policy must exist. If they don't exist, then, when you deploy a pod that matches the selector, your pod remains stuck in the creation process. If you describe the pod, you'll see an error message similar to the following one: An error occurred (InvalidSecurityGroupID.NotFound) when calling the CreateNetworkInterface operation: The securityGroup ID '<sg-abc123>' does not exist.
- The security group must allow inbound communication from the cluster security group (for kubelet) over any ports you've configured probes for.
- The security group must allow outbound communication to the cluster security group (for CoreDNS) over TCP and UDP port 53. The cluster security group must also allow inbound TCP and UDP port 53 communication from all security groups associated to pods.
- b. Deploy the policy.

```
kubectl apply -f <my-security-group-policy.yaml>
```

- 6. Deploy a sample application with a label that matches the <my-role> value for <podSelector> that you specified in the previous step.
 - a. Save the following contents to a file.

```
apiVersion: apps/v1
kind: Deployment
metadata:
 name: <my-deployment>
  namespace: <my-namespace>
  labels:
    app: <my-app>
spec:
  replicas: <1>
  selector:
    matchLabels:
     app: <my-app>
  template:
   metadata:
      labels:
        app: <my-app>
        role: <my-role>
      containers:
      - name: <my-container>
        image: <my-image>
        ports:
        - containerPort: <80>
```

b. Deploy the application with the following command. When you deploy the application, the CNI plugin matches the role label and the security groups that you specified in the previous step are applied to the pod.

```
kubectl apply -f <file-name-you-used-in-previous-step.yaml>
```

Note

• If your pod is stuck in the Waiting state and you see Insufficient permissions: Unable to create Elastic Network Interface. when you

- describe the pod, confirm that you added the IAM policy to the IAM cluster role in a previous step.
- If your pod is stuck in the Pending state, confirm that your node instance type is listed in the section called "Supported instances" (p. 217) and that that the maximum number of branch network interfaces supported by the instance type multiplied times the number of nodes in your node group hasn't already been met. For example, an m5.large instance supports nine branch network interfaces. If your node group has five nodes, then a maximum of 45 branch network interfaces can be created for the node group. The 46th pod that you attempt to deploy will sit in Pending state until another pod that has associated security groups is deleted.

If you run kubectl describe pod <my-deployment-xxxxxxxxxxxxxxxxxxxxx -n <my-namespace> and see a message similar to the following message, then it can be safely ignored. This message might appear when the CNI plugin tries to set up host networking and fails while the network interface is being created. The CNI plugin logs this event until the network interface is created.

```
Failed to create pod sandbox: rpc error: code =
Unknown desc = failed to set up sandbox container
"<e24268322e55c8185721f52df6493684f6c2c3bf4fd59c9c121fd4cdc894579f>" network for
pod "<my-deployment-59f5f68b58-c89wx>": networkPlugin
cni failed to set up pod "<my-deployment-59f5f68b58-c89wx_my-namespace>" network:
add cmd: failed to assign an IP address to container
```

You cannot exceed the maximum number of pods that can be run on the instance type. For a list of the maximum number of pods that you can run on each instance type, see eni-max-pods.txt on GitHub. When you delete a pod that has associated security groups, or delete the node that the pod is running on, the VPC resource controller deletes the branch network interface. If you delete a cluster with pods using pods for security groups, then the controller does not delete the branch network interfaces, so you'll need to delete them yourself.

Amazon EC2 supported instances and branch network interfaces

The following table lists the number of branch network interfaces that you can use with each supported Amazon EC2 instance type.

Instance type	Branch network interfaces
a1.medium	10
a1.large	9
a1.xlarge	18
a1.2xlarge	38
a1.4xlarge	54
a1.metal	54
c5.large	9
c5.xlarge	18
c5.2xlarge	38
c5.4xlarge	54

Instance type	Branch network interfaces
c5.9xlarge	54
c5.12xlarge	54
c5.18xlarge	107
c5.24xlarge	107
c5.metal	107
c5a.large	9
c5a.xlarge	18
c5a.2xlarge	38
c5a.4xlarge	54
c5a.8xlarge	54
c5a.12xlarge	54
c5a.16xlarge	107
c5a.24xlarge	107
c5d.large	9
c5d.xlarge	18
c5d.2xlarge	38
c5d.4xlarge	54
c5d.9xlarge	54
c5d.12xlarge	54
c5d.18xlarge	107
c5d.24xlarge	107
c5d.metal	107
c5n.large	9
c5n.xlarge	18
c5n.2xlarge	38
c5n.4xlarge	54
c5n.9xlarge	54
c5n.18xlarge	107
c5n.metal	107
c6g.medium	4
c6g.large	9

Instance type	Branch network interfaces
c6g.xlarge	18
c6g.2xlarge	38
c6g.4xlarge	54
c6g.8xlarge	54
c6g.12xlarge	54
c6g.16xlarge	107
c6g.metal	107
g4dn.xlarge	39
g4dn.2xlarge	39
g4dn.4xlarge	59
g4dn.8xlarge	58
g4dn.12xlarge	54
g4dn.16xlarge	118
g4dn.metal	107
i3en.large	5
i3en.xlarge	12
i3en.2xlarge	28
i3en.3xlarge	38
i3en.6xlarge	54
i3en.12xlarge	114
i3en.24xlarge	107
i3en.metal	107
inf1.xlarge	38
inf1.2xlarge	38
inf1.6xlarge	54
inf1.24xlarge	107
m5.large	9
m5.xlarge	18
m5.2xlarge	38
m5.4xlarge	54
m5.8xlarge	54

Instance type	Branch network interfaces
m5.12xlarge	54
m5.16xlarge	107
m5.24xlarge	107
m5.metal	107
m5a.large	9
m5a.xlarge	18
m5a.2xlarge	38
m5a.4xlarge	54
m5a.8xlarge	54
m5a.12xlarge	54
m5a.16xlarge	107
m5a.24xlarge	107
m5ad.large	9
m5ad.xlarge	18
m5ad.2xlarge	38
m5ad.4xlarge	54
m5ad.8xlarge	54
m5ad.12xlarge	54
m5ad.16xlarge	107
m5ad.24xlarge	107
m5d.large	9
m5d.xlarge	18
m5d.2xlarge	38
m5d.4xlarge	54
m5d.8xlarge	54
m5d.12xlarge	54
m5d.16xlarge	107
m5d.24xlarge	107
m5d.metal	107
m5dn.large	9
m5dn.xlarge	18

Instance type	Branch network interfaces
m5dn.2xlarge	38
m5dn.4xlarge	54
m5dn.8xlarge	54
m5dn.12xlarge	54
m5dn.16xlarge	107
m5dn.24xlarge	107
m5n.large	9
m5n.xlarge	18
m5n.2xlarge	38
m5n.4xlarge	54
m5n.8xlarge	54
m5n.12xlarge	54
m5n.16xlarge	107
m5n.24xlarge	107
m6g.medium	4
m6g.large	9
m6g.xlarge	18
m6g.2xlarge	38
m6g.4xlarge	54
m6g.8xlarge	54
m6g.12xlarge	54
m6g.16xlarge	107
m6g.metal	107
p3.2xlarge	38
p3.8xlarge	54
p3.16xlarge	114
p3dn.24xlarge	107
r5.large	9
r5.xlarge	18
r5.2xlarge	38
r5.4xlarge	54

Instance type	Branch network interfaces
r5.8xlarge	54
r5.12xlarge	54
r5.16xlarge	107
r5.24xlarge	107
r5.metal	107
r5a.large	9
r5a.xlarge	18
r5a.2xlarge	38
r5a.4xlarge	54
r5a.8xlarge	54
r5a.12xlarge	54
r5a.16xlarge	107
r5a.24xlarge	107
r5ad.large	9
r5ad.xlarge	18
r5ad.2xlarge	38
r5ad.4xlarge	54
r5ad.8xlarge	54
r5ad.12xlarge	54
r5ad.16xlarge	107
r5ad.24xlarge	107
r5d.large	9
r5d.xlarge	18
r5d.2xlarge	38
r5d.4xlarge	54
r5d.8xlarge	54
r5d.12xlarge	54
r5d.16xlarge	107
r5d.24xlarge	107
r5d.metal	107
r5dn.large	9

Instance type	Branch network interfaces
r5dn.xlarge	18
r5dn.2xlarge	38
r5dn.4xlarge	54
r5dn.8xlarge	54
r5dn.12xlarge	54
r5dn.16xlarge	107
r5dn.24xlarge	107
r5n.large	9
r5n.xlarge	18
r5n.2xlarge	38
r5n.4xlarge	54
r5n.8xlarge	54
r5n.12xlarge	54
r5n.16xlarge	107
r5n.24xlarge	107
r6g.medium	4
r6g.large	9
r6g.xlarge	18
r6g.2xlarge	38
r6g.4xlarge	54
r6g.8xlarge	54
r6g.12xlarge	54
r6g.16xlarge	107
z1d.large	13
z1d.xlarge	28
z1d.2xlarge	58
z1d.3xlarge	54
z1d.6xlarge	54
z1d.12xlarge	107
z1d.metal	107

CNI custom networking

By default, when new network interfaces are allocated for pods, ipamD uses the node's primary network interface's security groups and subnet. You might want your pods to use a different security group or subnet, within the same VPC as your control plane security group. For example:

- There are a limited number of IP addresses available in a subnet. This might limit the number of pods that can be created in the cluster. Using different subnets for pods allows you to increase the number of available IP addresses.
- For security reasons, your pods must use different security groups or subnets than the node's primary network interface.
- The nodes are configured in public subnets and you want the pods to be placed in private subnets using a NAT Gateway. For more information, see External source network address translation (SNAT) (p. 209).

Note

- You can configure custom networking for self-managed node groups or for managed node groups that were created with a launch template that uses a custom AMI (p. 114). The procedures in this topic require the Amazon VPC CNI plugin for Kubernetes version 1.4.0 or later. To check your CNI version, and upgrade if necessary, see Amazon VPC CNI plugin for Kubernetes upgrades (p. 235).
- Enabling a custom network effectively removes an available network interface (and all of its available IP addresses for pods) from each node that uses it. The primary network interface for the node is not used for pod placement when a custom network is enabled.
- The procedure in this topic instructs the CNI plugin to associate different security groups to secondary network interfaces than are associated to the primary network interface in the instance. All pods using the secondary network interfaces will still share use of the secondary network interfaces and will all use the same security groups. If you want to assign different security groups to individual pods, then you can use Security groups for pods (p. 213).
 Security groups for pods create additional network interfaces that can each be assigned a unique security group. security groups for pods can be used with or without custom networking.

To configure CNI custom networking

- 1. Associate a secondary CIDR block to your cluster's VPC. For more information, see Associating a Secondary IPv4 CIDR Block with Your VPC in the *Amazon VPC User Guide*.
- Create a subnet in your VPC for each Availability Zone, using your secondary CIDR block. Your
 custom subnets must be from a different VPC CIDR block than the subnet that your nodes were
 launched into. For more information, see Creating a subnet in your VPC in the Amazon VPC User
 Guide.
- Set the AWS_VPC_K8S_CNI_CUSTOM_NETWORK_CFG environment variable to true in the aws-node DaemonSet:

```
kubectl set env daemonset aws-node -n kube-system
AWS_VPC_K8S_CNI_CUSTOM_NETWORK_CFG=true
```

4. View the currently-installed CNI version.

```
kubectl describe daemonset aws-node --namespace kube-system | grep Image | cut -d "/" - f 2
```

Output:

```
amazon-k8s-cni:1.7.5
```

- 5. If you have version 1.3 or later of the CNI installed, you can skip to step 6. Define a new ENIConfig custom resource for your cluster.
 - a. Create a file called ENIConfig.yaml and paste the following content into it:

```
apiVersion: apiextensions.k8s.io/v1beta1
kind: CustomResourceDefinition
metadata:
  name: eniconfigs.crd.k8s.amazonaws.com
spec:
  scope: Cluster
  group: crd.k8s.amazonaws.com
  version: v1alpha1
  names:
   plural: eniconfigs
   singular: eniconfig
  kind: ENIConfig
```

b. Apply the file to your cluster with the following command:

```
kubectl apply -f ENIConfig.yaml
```

- 6. Create an ENIConfig custom resource for each subnet that you want to schedule pods in.
 - a. Create a unique file for each network interface configuration. Each file must include the following contents with a unique value for name. We highly recommend using a value for name that matches the Availability Zone of the subnet because this makes deployment of multi-AZ Auto Scaling groups simpler (see step 6c below).

In this example, a file named us-west-2a.yaml is created. Replace the <example values> for name, subnet, and securityGroups with your own values. In this example, we follow best practices and set the value for name to the Availability Zone that the subnet is in. If you don't have a specific security group that you want to attach for your pods, you can leave that value empty for now. Later, you will specify the node security group in the ENIConfig.

```
apiVersion: crd.k8s.amazonaws.com/v1alpha1
kind: ENIConfig
metadata:
  name: <us-west-2a>
spec:
  securityGroups:
    - <sg-0dff111a1d11c1c11>
  subnet: <subnet-011b111c1f11fdf11>
```

Note

Each subnet and security group combination requires its own custom resource. If you have multiple subnets in the same Availability Zone, use the following command to annotate the nodes in each subnet with the matching config name.

```
kubectl annotate node <node-name>.<region>.compute.internal
   k8s.amazonaws.com/eniConfig=<subnet1ConfigName>
```

b. Apply each custom resource file that you created to your cluster with the following command:

Amazon EKS User Guide CNI custom networking

```
kubectl apply -f <us-west-2a>.yaml
```

c. (Optional, but recommended for multi-Availability Zone node groups) By default, Kubernetes applies the Availability Zone of a node to the failure-domain.beta.kubernetes.io/zone label. If you named your ENIConfig custom resources after each Availability Zone in your VPC, as recommended in step 6a, then you can enable Kubernetes to automatically apply the corresponding ENIConfig for the node's Availability Zone with the following command.

 $\verb|kubectl| set env daemonset aws-node -n kube-system ENI_CONFIG_LABEL_DEF=failure-domain.beta.kubernetes.io/zone|$

Note

Ensure that an annotation with the key k8s.amazonaws.com/eniConfig for the ENI_CONFIG_ANNOTATION_DEF environment variable doesn't exist in the container spec for the aws-node daemonset. If it exists, it overrides the ENI_CONFIG_LABEL_DEF value, and should be removed. You can check to see if the variable is set with the kubectl describe daemonset aws-node -n kube-system | grep ENI_CONFIG_ANNOTATION_DEF command. If no output is returned, then the variable is not set.

- 7. Create a new self-managed node group. For managed node groups, use a custom AMI with a launch template (p. 114).
 - a. Determine the maximum number of pods that can be scheduled on each node using the following formula.

```
maxPods = (number of interfaces - 1) * (max IPv4 addresses per interface - 1) + 2
```

For example, the m5.large instance type supports three network interfaces and ten IPv4 addresses for each interface. Inserting the values into the formula, the instance can support up to 20 pods, as shown in the following calculation.

```
maxPods = (3 - 1) * (10 - 1) + 2 = 20
```

For more information about the maximum number of network interfaces for each instance type, see IP addresses per network interface per instance type in the *Amazon EC2 User Guide for Linux Instances*.

b. Follow the steps for Self-managed nodes in Launching self-managed Amazon Linux nodes (p. 116) to create a new self-managed node group. After you've opened the AWS CloudFormation template, enter values as described in the instructions. Specify the subnets that you specified in the ENIConfig resources that you deployed. For the BootstrapArguments field, enter the following value.

```
--use-max-pods false --kubelet-extra-args '--max-pods=<20>'
```

8. After your node group is created, record the security group that was created for subnet and apply the security group to the associated ENIConfig. Edit each ENIConfig with the following command, replacing <eniconfig-name> with your value:

```
kubectl edit eniconfig.crd.k8s.amazonaws.com/<eniconfig-name>
```

If you followed best practices from steps 6a and 6c, the eniconfig-name corresponds to the Availability Zone name.

Amazon EKS User Guide CNI metrics helper

The spec section should look like this:

```
spec:
    securityGroups:
    - <sg-0dff222a2d22c2c22>
    subnet: <subnet-022b22c2f22fdf22>
```

9. If you have any nodes in your cluster that had pods placed on them before you completed this procedure, you should terminate them. Only new nodes that are registered with the k8s.amazonaws.com/eniConfig label use the new custom networking feature.

CNI metrics helper

The CNI metrics helper is a tool that you can use to scrape network interface and IP address information, aggregate metrics at the cluster level, and publish the metrics to Amazon CloudWatch.

When managing an Amazon EKS cluster, you may want to know how many IP addresses have been assigned and how many are available. The CNI metrics helper helps you to:

- · Track these metrics over time
- Troubleshoot and diagnose issues related to IP assignment and reclamation
- · Provide insights for capacity planning

When a node is provisioned, the CNI plugin automatically allocates a pool of secondary IP addresses from the node's subnet to the primary network interface (eth0). This pool of IP addresses is known as the warm pool, and its size is determined by the node's instance type. For example, a c4.large instance can support three network interfaces and nine IP addresses per interface. The number of IP addresses available for a given pod is one less than the maximum (of ten) because one of the IP addresses is reserved for the elastic network interface itself. For more information, see IP Addresses Per Network Interface Per Instance Type in the Amazon EC2 User Guide for Linux Instances.

As the pool of IP addresses is depleted, the plugin automatically attaches another elastic network interface to the instance and allocates another set of secondary IP addresses to that interface. This process continues until the node can no longer support additional elastic network interfaces.

The following metrics are collected for your cluster and exported to CloudWatch:

- The maximum number of network interfaces that the cluster can support
- The number of network interfaces have been allocated to pods
- · The number of IP addresses currently assigned to pods
- The total and maximum numbers of IP addresses available
- The number of ipamD errors

Deploying the CNI metrics helper

The CNI metrics helper requires cloudwatch: PutMetricData permissions to send metric data to CloudWatch. This section helps you to create an IAM policy with those permissions, apply it to your node instance role, and then deploy the CNI metrics helper.

To create an IAM policy for the CNI metrics helper

 Create a file called allow_put_metrics_data.json and populate it with the following policy document.

Amazon EKS User Guide CNI metrics helper

Create an IAM policy called CNIMetricsHelperPolicy for your node instance profile that allows the CNI metrics helper to make calls to AWS APIs on your behalf. Use the following AWS CLI command to create the IAM policy in your AWS account.

```
aws iam create-policy --policy-name CNIMetricsHelperPolicy \
--description "Grants permission to write metrics to CloudWatch" \
--policy-document file://allow_put_metrics_data.json
```

Take note of the policy ARN that is returned.

Get the IAM role name for your nodes. Use the following command to print the aws-auth configmap.

```
kubectl -n kube-system describe configmap aws-auth
```

Output:

```
Name:
              aws-auth
Namespace: kube-system
Labels:
             <none>
Annotations: <none>
Data
====
mapRoles:
- groups:
  - system:bootstrappers
  - system:nodes
 rolearn: arn:aws:iam::<111122223333>:role/<eksctl-prod-nodegroup-standard-wo-
NodeInstanceRole-GKNS581EASPU>
  username: system:node:{{EC2PrivateDNSName}}
Events: <none>
```

Record the role name for any rolearn values that have the system:nodes group assigned to them. In the above example output, the role name is <eksctl-prod-nodegroup-standard-wo-NodeInstanceRole-GKNS581EASPU>. You should have one value for each node group in your cluster.

4. Attach the new CNIMetricsHelperPolicy IAM policy to each of the node IAM roles you identified earlier with the following command, substituting the red text with your own AWS account number and node IAM role name.

```
aws iam attach-role-policy \
--policy-arn arn:aws:iam::<111122223333>:policy/CNIMetricsHelperPolicy \
--role-name <eksctl-prod-nodegroup-standard-wo-NodeInstanceRole-GKNS581EASPU>
```

To deploy the CNI metrics helper

- Apply the CNI metrics helper manifest with the command that corresponds to the Region that your cluster is in.
 - · All regions other than China Regions.

```
kubectl apply -f https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/
release-1.7/config/v1.7/cni-metrics-helper.yaml
```

Beijing and Ningxia China Regions.

kubectl apply -f https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/master/
config/v1.7/cni-metrics-helper-cn.yam1

Creating a metrics dashboard

After you have deployed the CNI metrics helper, you can view the CNI metrics in the CloudWatch console. This topic helps you to create a dashboard for viewing your cluster's CNI metrics.

To create a CNI metrics dashboard

- 1. Open the CloudWatch console at https://console.aws.amazon.com/cloudwatch/.
- 2. In the left navigation, choose Metrics.
- 3. Under Custom Namespaces, choose Kubernetes.
- Choose CLUSTER_ID.
- 5. On the All metrics tab, select the metrics you want to add to the dashboard.
- 6. Choose Actions, and then Add to dashboard.
- In the Select a dashboard section, choose Create new and enter a name for your dashboard, such as "EKS-CNI-metrics".
- 8. In the **Select a widget type** section, choose **Number**.
- 9. In the **Customize the widget title** section, enter a logical name for your dashboard title, such as "EKS CNI metrics".
- 10. Choose **Add to dashboard** to finish. Now your CNI metrics are added to a dashboard that you can monitor, as shown below.



CNI configuration variables

The Amazon VPC CNI plugin for Kubernetes supports a number of configuration options, which are set through environment variables. The following environment variables are available, and all of them are optional.

AWS_VPC_CNI_NODE_PORT_SUPPORT

Type – Boolean

Default - true

Specifies whether NodePort services are enabled on a node's primary network interface. This requires additional iptables rules and that the kernel's reverse path filter on the primary interface is set to loose.

AWS_VPC_K8S_CNI_CUSTOM_NETWORK_CFG

Type - Boolean

Default - false

Specifies that your pods may use subnets and security groups, within the same VPC as your control plane resources, that are independent of your cluster's resourcesVpcConfig. By default, pods share the same subnet and security groups as the node's primary interface. Setting this variable to true causes ipamD to use the security groups and subnets in a node's ENIConfig for network interface allocation. You must create an ENIConfig custom resource definition for each subnet that your pods will reside in, and then annotate each node to use a specific ENIConfig (multiple nodes can be annotated with the same ENIConfig). Nodes can only be annotated with a single ENIConfig at a time, and the subnet in the ENIConfig must belong to the same Availability Zone that the node resides in. For more information, see CNI custom networking (p. 224).

ENI CONFIG ANNOTATION DEF

Type - String

Default - k8s.amazonaws.com/eniConfig

Specifies a node annotation key name. This should be used when AWS_VPC_K8S_CNI_CUSTOM_NETWORK_CFG=true. The annotation value will be used to set ENIConfig name. Annotations take precedence over labels.

ENI CONFIG LABEL DEF

Type - String

Default - k8s.amazonaws.com/eniConfig

Specifies a node label key name. This should be used when

AWS_VPC_K8S_CNI_CUSTOM_NETWORK_CFG=true. The label value will be used to set ENIConfig name. Annotations will take precedence over labels. To use labels, ensure that an annotation with the key k8s.amazonaws.com/eniConfig is defined and that a value for the annotation key ENI_CONFIG_ANNOTATION_DEF is not set on the node. To select an ENIConfig based upon Availability Zone, set this to failure-domain.beta.kubernetes.io/zone and create an ENIConfig custom resource for each Availability Zone, such as us-east-1a. For more information, see CNI custom networking (p. 224).

AWS_VPC_ENI_MTU - v1.6.0 and later

Type - Integer

Default - 9001

Used to configure the MTU size for attached ENIs. The valid range is from 576 to 9001.

AWS_VPC_K8S_CNI_EXTERNALSNAT

Type - Boolean

Default - false

Amazon EKS User Guide CNI configuration variables

Specifies whether an external NAT gateway should be used to provide SNAT of secondary network interface IP addresses. If set to true, the SNAT iptables rule and off-VPC IP rule are not applied, and these rules are removed if they have already been applied.

Disable SNAT if you need to allow inbound communication to your pods from external VPNs, direct connections, and external VPCs, and your pods do not need to access the internet directly via an Internet Gateway. Your nodes must be running in a private subnet and connected to the internet through an AWS NAT Gateway or another external NAT device.

For more information, see External source network address translation (SNAT) (p. 209).

AWS_VPC_K8S_CNI_RANDOMIZESNAT

Type - String

Default - prng

Valid values - hashrandom, prng, none

Specifies whether the SNAT iptables rule should randomize the outgoing ports for connections. This setting takes effect when AWS_VPC_K8S_CNI_EXTERNALSNAT=false, which is the default setting. The valid values are:

- prng A pseudo random number. The ——random—fully flag is added to the SNAT iptables rule. This option falls back to ——random for old versions of iptables that do not support ——random—fully.
- hashrandom A hash-based random number. The --random flag is added to the SNAT iptables rule.
- **none** Disables randomization and uses sequential port allocation for outgoing connections.

Note

Any options other than none cause outbound connections to be assigned a source port that's not necessarily part of the ephemeral port range set at the OS level (/proc/sys/net/ipv4/ip_local_port_range). This is relevant if you have NACLs restricting traffic based on the port range found in ip_local_port_range.

AWS_VPC_K8S_CNI_EXCLUDE_SNAT_CIDRS - v1.6.0 and later

Type - String

Default – empty

Specify a comma-separated list of IPv4 CIDRs to exclude from SNAT. For every item in the list, an iptables rule and off-VPC IP rule will be applied. If an item is not a valid IPv4 range it will be skipped. This should be used when AWS_VPC_K8S_CNI_EXTERNALSNAT=false.

WARM_ENI_TARGET

Type - Integer

Default - 1

Specifies the number of free network interfaces (and all of their available IP addresses) that the <code>ipamD</code> daemon should attempt to keep available for pod assignment on the node. By default, <code>ipamD</code> attempts to keep one network interface and all of its IP addresses available for pod assignment.

Note

The number of IP addresses for each network interface varies by instance type. For more information, see IP addresses per network interface per instance type in the *Amazon EC2 User Guide for Linux Instances*.

For example, an m4.4xlarge launches with one network interface and 30 IP addresses. If five pods are placed on the node and five free IP addresses are removed from the IP address warm pool, then ipamD attempts to allocate more interfaces until WARM_ENI_TARGET free interfaces are available on the node.

Note

If WARM_IP_TARGET is set, then this environment variable is ignored and the WARM_IP_TARGET behavior is used instead.

WARM_IP_TARGET

Type - Integer

Default - None

Specifies the number of free IP addresses that the <code>ipamD</code> daemon should attempt to keep available for pod assignment on the node. For example, if <code>WARM_IP_TARGET</code> is set to 10, then <code>ipamD</code> attempts to keep 10 free IP addresses available at all times. If the elastic network interfaces on the node are unable to provide these free addresses, <code>ipamD</code> attempts to allocate more interfaces until <code>WARM_IP_TARGET</code> free IP addresses are available.

Note

This environment variable overrides WARM_ENI_TARGET behavior.

MINIMUM_IP_TARGET – v1.6.0 and later

Type - Integer

Default - None

Specifies the number of total IP addresses that the ipamD daemon should attempt to allocate for pod assignment on the node. MINIMUM_IP_TARGET behaves identically to WARM_IP_TARGET, except that instead of setting a target number of free IP addresses to keep available at all times, it sets a target number for a floor on how many total IP addresses are allocated.

MINIMUM_IP_TARGET is for pre-scaling and WARM_IP_TARGET is for dynamic scaling. For example, suppose a cluster has an expected pod density of approximately 30 pods per node. If WARM_IP_TARGET is set to 30 to ensure there are enough IPs initially allocated by the CNI, then 30 pods are deployed to the node. The CNI will allocate an additional 30 IPs, for a total of 60, accelerating IP exhaustion in the relevant subnets. If instead, MINIMUM_IP_TARGET is set to 30 and WARM_IP_TARGET to 2, after the 30 pods are deployed, the CNI would allocate an additional 2 IPs. This still provides elasticity, but uses approximately half as many IPs as using WARM_IP_TARGET alone (32 IP addresses versus 60 IP addresses).

This also improves reliability of the cluster by reducing the number of calls necessary to allocate or deallocate private IP addresses, which may be throttled, especially at scaling-related times.

MAX ENI

Type - Integer

Default - None

Specifies the maximum number of network interfaces that will be attached to the node. When MAX_ENI is unset or less than or equal to 0, the setting is not used, and the maximum number of network interfaces is always equal to the maximum number for the instance type in question. Even when MAX_ENI is a positive number, it is limited by the maximum number for the instance type.

AWS VPC K8S CNI LOGLEVEL

Type - String

Default - DEBUG

Valid values - DEBUG, INFO, WARN, ERROR, or FATAL (not case sensitive)

Specifies the loglevel for ipamd.

AWS_VPC_K8S_CNI_LOG_FILE

Type - String

Default - Unset

Valid values: stdout or a file path

Specifies where to write the logging output of ipamd. You can specify stdout or override the default file, such as /var/log/aws-routed-eni/ipamd.log.

AWS_VPC_K8S_PLUGIN_LOG_FILE

Type – String

Default – Unset

Valid values - stdout or a file path.

Specifies where to write the logging output for the aws-cni plugin. You can specify stdout or override the default file, such as /var/log/aws-routed-eni/plugin.log.

AWS_VPC_K8S_PLUGIN_LOG_LEVEL

Type - String

Default - DEBUG

Valid values - DEBUG, INFO, WARN, ERROR, or FATAL (not case sensitive)

Specifies the log level for the aws-cni plugin.

INTROSPECTION_BIND_ADDRESS

Type - String

Default - 127.0.0.1:61679

Specifies the bind address for the introspection endpoint. A Unix domain socket can be specified with the unix: prefix before the socket path.

DISABLE_INTROSPECTION

Type - Boolean

Default - false

Specifies whether introspection endpoints are disabled on a node. Setting this to true will reduce the debugging information you can get from the node when running the aws-cni-support.sh script.

DISABLE_METRICS

Type - Boolean

Default - false

Specifies whether the Prometheus metrics endpoint is disabled or not for ipamd. By default metrics are published on:61678/metrics.

AWS_VPC_K8S_CNI_VETHPREFIX

Type - String

Default - eni

Specifies the veth prefix used to generate the host-side veth device name for the CNI. The prefix can be a maximum of four characters long.

ADDITIONAL_ENI_TAGS – v1.6.0 and later

Type – String

Default - { }

Amazon EKS User Guide CNI configuration variables

```
Example values - { "tag_key": "tag_val"}
```

Metadata applied to network interfaces help you categorize and organize your resources for billing or other purposes. Each tag consists of a custom-defined key and an optional value. Tag keys can have a maximum character length of 128 characters. Tag values can have a maximum length of 256 characters. The tags will be added to all network interfaces on the host.

Important

Custom tags should not contain the k8s.amazonaws.com prefix, because it is reserved. If the tag contains k8s.amazonaws.com, the tag addition will be ignored.

CLUSTER_NAME

```
Type – String
```

Default - ""

Specifies the cluster name to tag allocated network interfaces with.

Network interface tags related to allocation

This plugin interacts with the following tags on network interfaces:

- cluster.k8s.amazonaws.com/name Set to the cluster name of the aws-node daemonset which created the network interface.
- node.k8s.amazonaws.com/instance_id Set to the instance ID of the aws-node instance that allocated this ENI.
- node.k8s.amazonaws.com/no_manage Read by the aws-node daemonset to determine whether an ENI attached to the machine shouldn't be configured or used for private IP addresses. This tag is not set by the CNI plugin itself, but rather may be set by you to indicate that an ENI is intended for host networking pods, or for some other process unrelated to Kubernetes.

Note

Attaching an ENI with this tag results in an incorrect value for the kubelet's --max-pods configuration option. Consider also updating the MAX_ENI and --max-pods configuration options on this plugin and the kubelet, respectively if you are making use of this tag.

Notes

L-IPAMD (aws-node DaemonSet), running on every worker node, requires access to the Kubernetes API server. If it can't reach the Kubernetes API server, ipamd will exit and the CNI will not be able to get any IP addresses for pods. Confirm whether aws-node has access to the kubernetes API server.

```
kubectl get svc kubernetes
```

Output

```
NAME TYPE CLUSTER-IP EXTERNAL-IP PORT(S) AGE kubernetes ClusterIP <10.0.0.1> <none> 443/TCP 29d
```

SSH into a node to check whether the node can reach the API server.

```
telnet <10.0.0.1> 443
```

Output

```
Trying 10.0.0.1...
Connected to 10.0.0.1.
```

Amazon EKS User Guide CNI upgrades

```
Escape character is '^]'.
```

If you receive the last line of output, then the Kubernetes API server is reachable.

Amazon VPC CNI plugin for Kubernetes upgrades

When you launch an Amazon EKS cluster, a recent version of the Amazon VPC CNI plugin for Kubernetes is deployed to your cluster. The absolute latest version of the plugin is available on GitHub for a short grace period before new clusters are switched over to use it. Amazon EKS does not automatically upgrade the CNI plugin on your cluster when new versions are released. To get a newer version of the CNI plugin on existing clusters, you must manually upgrade the plugin.

The latest version that we recommend is version 1.7.5. You can view the different releases available for the plugin, and read the release notes for each version on GitHub. With version 1.7.0 and later, the privileged container capability was removed from the CNI pod (aws-node). The pod has the NET_ADMIN capability in its securityContext capabilities, which is required for the aws-node container to add iptables, routes, and rules to setup pod networking. An init container was also added to the aws-node pod, which has the privileged capability, so that it can setup reverse path filters and copy loopback plugins during aws-node pod start up.

Important

If you have assigned a custom pod security policy to the aws-node Kubernetes service account used for the aws-node pod, then the policy must have NET_ADMIN in its allowedCapabilities section along with hostNetwork: true and privileged: true in the policy's spec. For more information, see the section called "Pod security policy" (p. 353).

Use the following procedures to check your CNI plugin version and upgrade to the latest recommended version.

To check your Amazon VPC CNI plugin for Kubernetes version

Use the following command to print your cluster's CNI version:

```
kubectl describe daemonset aws-node --namespace kube-system | grep Image | cut -d "/" - f ^{2}
```

Output:

```
amazon-k8s-cni:1.6.3
```

In this example output, the CNI version is 1.6.3, which is earlier than the current recommended version, 1.7.5. Use the following procedure to upgrade the CNI.

To upgrade the Amazon VPC CNI plugin for Kubernetes

- If your CNI version is earlier than 1.7.5, and you are managing the plugin yourself, then use the appropriate command below to update your CNI version to the latest recommended version. If your cluster is running Kubernetes 1.18 or later with eks.3 platform version or later, and the plugin is managed by Amazon EKS, then to update the plugin, see the section called "Configure an Amazon EKS add-on" (p. 52).
 - US West (Oregon) (us-west-2)

```
kubectl apply -f https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/v1.7.5/
config/v1.7/aws-k8s-cni.yaml
```

• China (Beijing) (cn-north-1) or China (Ningxia) (cn-northwest-1)

Amazon EKS User Guide Alternate compatible CNI plugins

kubectl apply -f https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/v1.7.5/
config/v1.7/aws-k8s-cni-cn.yaml

AWS GovCloud (US-East) (us-gov-east-1)

kubectl apply -f https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/v1.7.5/
config/v1.7/aws-k8s-cni-us-gov-east-1.yaml

AWS GovCloud (US-West) (us-gov-west-1)

kubectl apply -f https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/v1.7.5/ config/v1.7/aws-k8s-cni-us-gov-west-1.yaml

- For all other Regions
 - · Download the manifest file.

curl -o aws-k8s-cni.yaml https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/ v1.7.5/config/v1.7/aws-k8s-cni.yaml

 Replace <region-code> in the following command with the Region that your cluster is in and then run the modified command to replace the Region code in the file (currently us-west-2).

sed -i -e 's/us-west-2/<region-code>/' aws-k8s-cni.yaml

· Apply the manifest file to your cluster.

kubectl apply -f aws-k8s-cni.yaml

Alternate compatible CNI plugins

Amazon EKS only officially supports the Amazon VPC CNI plugin (p. 208). Amazon EKS runs upstream Kubernetes and is certified Kubernetes conformant however, so alternate CNI plugins will work with Amazon EKS clusters. If you plan to use an alternate CNI plugin in production, then we strongly recommend that you either obtain commercial support, or have the in-house expertise to troubleshoot and contribute fixes to the open source CNI plugin project.

Amazon EKS maintains relationships with a network of partners that offer support for alternate compatible CNI plugins. Refer to the following partners' documentation for details on supported Kubernetes versions and qualifications and testing performed.

Partner	Product Documentation		
Tigera	Calico	Installation instructions	
Isovalent	Cilium	Installation instructions	
Weaveworks	Weave Net	Installation instructions	
VMware	Antrea	Installation instructions	

Amazon EKS aims to give you a wide selection of options to cover all use cases. If you develop a commercially supported Kubernetes CNI plugin that is not listed here, then please contact our partner team at aws-container-partners@amazon.com for more information.

Installing or upgrading CoreDNS

CoreDNS is supported on Amazon EKS clusters with Kubernetes version 1.15 or later. Clusters that were created with Kubernetes version 1.10 shipped with kube-dns as the default DNS and service discovery provider. If you have updated from a 1.10 cluster and you want to use CoreDNS for DNS and service discovery, then you must install CoreDNS and remove kube-dns.

To check if your cluster is already running CoreDNS, use the following command.

```
kubectl get pod -n kube-system -l k8s-app=kube-dns
```

If the output shows coredns in the pod names, then you're already running CoreDNS in your cluster. If not, use the following procedure to update your DNS and service discovery provider to CoreDNS.

Note

The service for CoreDNS is still called kube-dns for backward compatibility.

To install CoreDNS on an updated Amazon EKS cluster with kubect1

Add the {"eks.amazonaws.com/component": "kube-dns"} selector to the kube-dns
deployment for your cluster. This prevents the two DNS deployments from competing for control of
the same set of labels.

```
kubectl patch -n kube-system deployment/kube-dns --patch \
'{"spec":{"selector":{"matchLabels":{"eks.amazonaws.com/component":"kube-dns"}}}'
```

- 2. Deploy CoreDNS to your cluster.
 - a. Set your cluster's DNS IP address to the DNS_CLUSTER_IP environment variable.

```
export DNS_CLUSTER_IP=$(kubectl get svc -n kube-system kube-dns -o
jsonpath='{.spec.clusterIP}')
```

b. Replace <region-code> (including <>) with the Region code that your cluster is in.

```
export REGION="<region-code>"
```

- c. Download the CoreDNS manifest from the Amazon EKS resource bucket that corresponds to the Region that your cluster is in.
 - · All regions other than China Regions.

```
curl -o dns.yaml https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/dns.yaml
```

· Beijing and Ningxia China Regions.

```
curl -o dns.yaml https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/dns.yaml
```

d. Replace the variable placeholders in the dns.yaml file with your environment variable values and apply the updated manifest to your cluster. The following command completes this in one step.

```
cat dns.yaml | sed -e "s/REGION/$REGION/g" | sed -e "s/DNS_CLUSTER_IP/
$DNS_CLUSTER_IP/g" | kubectl apply -f -
```

e. Fetch the coredns pod name from your cluster.

Amazon EKS User Guide Upgrading CoreDNS

```
COREDNS_POD=$(kubectl get pod -n kube-system -l eks.amazonaws.com/component=coredns
\
-o jsonpath='{.items[0].metadata.name}')
```

f. Query the coredns pod to ensure that it's receiving requests.

```
kubectl get --raw /api/v1/namespaces/kube-system/pods/$COREDNS_POD:9153/proxy/
metrics \
| grep 'coredns_dns_request_count_total'
```

Note

It might take several minutes for the expected output to return properly, depending on the rate of DNS requests in your cluster.

In the following expected output, the number 23 is the DNS reguest count total.

```
# HELP coredns_dns_request_count_total Counter of DNS requests made per zone,
protocol and family.
# TYPE coredns_dns_request_count_total counter
coredns_dns_request_count_total{family="1",proto="udp",server="dns://:53",zone="."}
23
```

- Update CoreDNS to the recommended version for your cluster by completing the steps in Upgrading CoreDNS (p. 238).
- 4. Scale down the kube-dns deployment to zero replicas.

```
kubectl scale -n kube-system deployment/kube-dns --replicas=0
```

Clean up the old kube-dns resources.

```
kubectl delete -n kube-system deployment/kube-dns serviceaccount/kube-dns configmap/
kube-dns
```

Upgrading CoreDNS

1. Check the current version of your cluster's coredns deployment.

```
kubectl describe deployment coredns --namespace kube-system | grep Image | cut -d "/" -
f 3
```

Output:

```
coredns:v<1.1.3>
```

The recommended coredns versions for the corresponding Kubernetes versions are as follows:

Kubernetes version	1.18	1.17	1.16	1.15
CoreDNS	1.7.0	1.6.6	1.6.6	1.6.6

2. If your current coredns version is 1.5.0 or later, but earlier than the recommended version, then skip this step. If your current version is earlier than 1.5.0, then you need to modify the config map for coredns to use the forward plug-in, rather than the proxy plug-in.

Amazon EKS User Guide Installing Calico on Amazon EKS

a. Open the configmap with the following command.

```
kubectl edit configmap coredns -n kube-system
```

b. Replace proxy in the following line with forward. Save the file and exit the editor.

```
proxy . /etc/resolv.conf
```

3. If you originally deployed your cluster on Kubernetes 1.17 or earlier, then you may need to remove a deprecated term from your CoreDNS manifest.

Important

You must complete this before upgrading to CoreDNS version 1.7.0, but it's recommended that you complete this step even if you're upgrading to an earlier version.

a. Check to see if your CoreDNS manifest has the line.

```
kubectl get configmap coredns -n kube-system -o yaml |grep upstream
```

If no output is returned, your manifest doesn't have the line and you can skip to the next step to update CoreDNS. If output is returned, then you need to remove the line.

b. Edit the configmap with the following command, removing the line in the file that has the word upstream in it. Do not change anything else in the file. Once the line is removed, save the changes.

```
kubectl edit configmap coredns -n kube-system -o yaml
```

4. Retrieve your current coredns image:

```
kubectl get deployment coredns --namespace kube-system -
o=jsonpath='{$.spec.template.spec.containers[:1].image}'
```

5. Update coredns to the recommended version by taking the output from the previous step and replacing <1.7.0> (including <>) with your cluster's recommended coredns version:

Installing Calico on Amazon EKS

Project Calico is a network policy engine for Kubernetes. With Calico network policy enforcement, you can implement network segmentation and tenant isolation. This is useful in multi-tenant environments where you must isolate tenants from each other or when you want to create separate environments for development, staging, and production. Network policies are similar to AWS security groups in that you can create network ingress and egress rules. Instead of assigning instances to a security group, you assign network policies to pods using pod selectors and labels. The following procedure shows you how to install Calico on Linux nodes in your Amazon EKS cluster. To install Calico on Windows nodes, see Using Calico on Amazon EKS Windows Containers.

Note

• Calico is not supported when using Fargate with Amazon EKS.

Amazon EKS User Guide Installing Calico on Amazon EKS

- Calico adds rules to iptables on the node that may be higher priority than existing rules that you've already implemented outside of Calico. Consider adding existing iptables rules to your Calico policies to avoid having rules outside of Calico policy overridden by Calico.
- If you're using security groups for pods (p. 213), traffic flow to pods on branch network interfaces is not subjected to Calico network policy enforcement and is limited to Amazon EC2 security group enforcement only. Community effort is underway to remove this limitation.

To install Calico on your Amazon EKS Linux nodes

- 1. Apply the Calico manifest to your cluster by completing the option that corresponds to the Region that your cluster is in.
 - All regions other than China (Ningxia) or China (Beijing) Apply the Calico manifest from the aws/ amazon-vpc-cni-k8s GitHub project. This manifest creates DaemonSets in the kube-system namespace.

```
kubectl apply -f https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/v1.7.5/
config/v1.7/calico.yaml
```

- China (Ningxia) or China (Beijing)
 - 1. Download the Calico manifest with the following command.

```
curl -o calico.yaml https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/
v1.7.5/config/v1.7/calico.yaml
```

- 2. Modify the manifest.
 - a. View the manifest file or files that you downloaded and note the name of the image. Download the image locally with the following command.

```
docker pull image:<tag>
```

b. Tag the image to be pushed to an Amazon Elastic Container Registry repository in China with the following command.

```
docker tag image:<tag> <aws_account_id>.dkr.ecr.<cn-north-1>.amazonaws.com/
image:<tag>
```

c. Push the image to a China Amazon ECR repository with the following command.

```
docker push image:<tag> <aws_account_id>.dkr.ecr.<cn-north-1>.amazonaws.com/
image:<tag>
```

- d. Update the Kubernetes manifest file or files to reference the Amazon ECR image URL in your region.
- 3. Apply the Calico manifest. This manifest creates DaemonSets in the kube-system namespace.

```
kubectl apply -f calico.yaml
```

2. Watch the kube-system DaemonSets and wait for the calico-node DaemonSet to have the DESIRED number of pods in the READY state. When this happens, Calico is working.

```
kubectl get daemonset calico-node --namespace kube-system
```

Output:

Amazon EKS User Guide Stars policy demo

NAME AGE	DESIRED	CURRENT	READY	UP-TO-DATE	AVAILABLE	NODE SELECTOR
calico-node 38s	3	3	3	3	3	<none></none>

To delete Calico from your Amazon EKS cluster

• If you are done using Calico in your Amazon EKS cluster, you can delete the DaemonSet with the following command:

```
kubectl delete -f https://raw.githubusercontent.com/aws/amazon-vpc-cni-k8s/v1.7.5/
config/v1.7/calico.yaml
```

Stars policy demo

This section walks through the Stars policy demo provided by the Project Calico documentation. The demo creates a frontend, backend, and client service on your Amazon EKS cluster. The demo also creates a management GUI that shows the available ingress and egress paths between each service.

Before you create any network policies, all services can communicate bidirectionally. After you apply the network policies, you can see that the client can only communicate with the frontend service, and the backend only accepts traffic from the frontend.

To run the Stars policy demo

1. Apply the frontend, backend, client, and management UI services:

```
kubectl apply -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/
tutorials/stars-policy/manifests/00-namespace.yaml
kubectl apply -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/
tutorials/stars-policy/manifests/01-management-ui.yaml
kubectl apply -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/
tutorials/stars-policy/manifests/02-backend.yaml
kubectl apply -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/
tutorials/stars-policy/manifests/03-frontend.yaml
kubectl apply -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/
tutorials/stars-policy/manifests/04-client.yaml
```


2. Wait for all of the pods to reach the Running status:

```
kubectl get pods --all-namespaces --watch
```

To connect to the management UI, forward your local port 9001 to the management-ui service running on your cluster:

```
kubectl port-forward service/management-ui -n management-ui 9001
```

4. Open a browser on your local system and point it to http://localhost:9001/. You should see the management UI. The **C** node is the client service, the **F** node is the frontend service, and the **B** node is the backend service. Each node has full communication access to all other nodes (as indicated by the bold, colored lines).




5. Apply the following network policies to isolate the services from each other:

kubectl apply -n stars -f https://docs.projectcalico.org/v3.3/getting-started/ kubernetes/tutorials/stars-policy/policies/default-deny.yaml kubectl apply -n client -f https://docs.projectcalico.org/v3.3/getting-started/ kubernetes/tutorials/stars-policy/policies/default-deny.yaml

- 6. Refresh your browser. You see that the management UI can no longer reach any of the nodes, so they don't show up in the UI.
- 7. Apply the following network policies to allow the management UI to access the services:

```
kubectl apply -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/
tutorials/stars-policy/policies/allow-ui.yaml
kubectl apply -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/
tutorials/stars-policy/policies/allow-ui-client.yaml
```

8. Refresh your browser. You see that the management UI can reach the nodes again, but the nodes cannot communicate with each other.




9. Apply the following network policy to allow traffic from the frontend service to the backend service:

 ${\tt kubectl\ apply\ -f\ https://docs.projectcalico.org/v3.3/getting-started/kubernetes/tutorials/stars-policy/policies/backend-policy.yaml}$

10. Apply the following network policy to allow traffic from the client namespace to the frontend service:

kubectl apply -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/ tutorials/stars-policy/policies/frontend-policy.yaml



11. (Optional) When you are done with the demo, you can delete its resources with the following commands:

```
kubectl delete -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/
tutorials/stars-policy/manifests/04-client.yaml
kubectl delete -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/
tutorials/stars-policy/manifests/03-frontend.yaml
kubectl delete -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/
tutorials/stars-policy/manifests/02-backend.yaml
kubectl delete -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/
tutorials/stars-policy/manifests/01-management-ui.yaml
kubectl delete -f https://docs.projectcalico.org/v3.3/getting-started/kubernetes/
tutorials/stars-policy/manifests/00-namespace.yaml
```

Even after deleting the resources, there can still be iptables rules on the nodes that might interfere in unexpected ways with networking in your cluster. The only sure way to remove Calico is to terminate all of the nodes and recycle them. To terminate all nodes, either set the Auto Scaling Group desired count to 0, then back up to the desired number, or just terminate the nodes. If you

Amazon EKS User Guide Stars policy demo

are unable to recycle the nodes, then see Disabling and removing Calico Policy in the Calico GitHub repository for a last resort procedure.

Workloads

Your workloads are deployed in containers, which are deployed in pods in Kubernetes. A pod includes one or more containers. Typically, one or more pods that provide the same service are deployed in a Kubernetes service. Once you've deployed multiple pods that provide the same service, you can:

- View information about the workloads (p. 246) running on each of your clusters using the AWS Management Console.
- Vertically scale pods up or down with the Kubernetes Vertical Pod Autoscaler (p. 252).
- Horizontally scale the number of pods needed to meet demand up or down with the Kubernetes Horizontal Pod Autoscaler (p. 257).
- Create an external (for internet-accessible pods) or an internal (for private pods) load balancer (p. 260) to balance network traffic across pods. The load balancer routes traffic at Layer 4 of the OSI model.
- Create an Application load balancing on Amazon EKS (p. 267) to balance application traffic across pods. The application load balancer routes traffic at Layer 7 of the OSI model.
- If you're new to Kubernetes, this topic helps you Deploy a sample Linux workload (p. 248).
- You can restrict IP addresses that can be assigned to a service (p. 274) with externalIPs.

View workloads

Workloads define applications running on a Kubernetes cluster. Every workload controls pods. Pods are the fundamental unit of computing within a Kubernetes cluster and represent one or more containers that run together.

You can use the Amazon EKS console to view information about the Kubernetes workloads and pods running on your cluster.

Prerequisites

The IAM user or IAM role that you sign into the AWS Management Console with must meet the following requirements.

- Has the eks: AccessKubernetesApi and other necessary IAM permissions to view workloads
 attached to it. For an example IAM policy, see the section called "View nodes and workloads for all
 clusters in the AWS Management Console" (p. 324).
- Is mapped to Kubernetes user or group in the aws-auth configmap. For more information, see the section called "Managing users or IAM roles for your cluster" (p. 285).
- The Kubernetes user or group that the IAM user or role is mapped to in the configmap must be bound to a Kubernetes role or clusterrole that has permissions to view the resources in the namespaces that you want to view. For more information, see Using RBAC Authorization in the Kubernetes documentation. You can download the following example manifests that create a clusterrole and clusterrolebinding or a role and rolebinding:
 - View Kubernetes resources in all namespaces The group name in the file is eks-console-dashboard-full-access-group, which is the group that your IAM user or role needs to be mapped to in the aws-auth configmap. You can change the name of the group before applying it to your cluster, if desired, and then map your IAM user or role to that group in the configmap. To download the file, select the appropriate link for the Region that your cluster is in.

Amazon EKS User Guide View workloads

- · All Regions other than Beijing and Ningxia China
- Beijing and Ningxia China Regions
- View Kubernetes resources in a specific namespace The namespace in this file is default, so if you want to specify a different namespace, edit the file before applying it to your cluster. The group name in the file is eks-console-dashboard-restricted-access-group, which is the group that your IAM user or role needs to be mapped to in the aws-auth configmap. You can change the name of the group before applying it to your cluster, if desired, and then map your IAM user or role to that group in the configmap. To download the file, select the appropriate link for the Region that your cluster is in.
 - · All Regions other than Beijing and Ningxia China
 - · Beijing and Ningxia China Regions

To view workloads using the AWS Management Console

- Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. In the **Clusters** list, select the cluster that you want to view workloads for.
- 3. On the **Workloads** tab, you see a list of **Names** of all the Kubernetes workloads that are currently deployed to your cluster, the **Pod count**, and **Status** for each workload.

Important

If you can't see any workloads, or you see a **Your current user or role does not have access to Kubernetes objects on this EKS cluster**, you may need to select a different namespace from the **All Namespaces** drop-down list. If you're still having problems, see the prerequisites for this topic. If you don't resolve the issue, you can still view and manage your Amazon EKS cluster on the **Configuration** tab, but you won't be able to see information about your workloads.

You can deploy the following types of workloads on a cluster.

- Deployment Ensures that a specific number of pods run and includes logic to deploy changes.
- ReplicaSet Ensures that a specific number of pods run. Can be controlled by deployments.
- StatefulSet Manages the deployment of stateful applications.
- DaemonSet Ensures that a copy of a pod runs on all (or some) nodes in the cluster.
- Job Creates one or more pods and ensures that a specified number of them run to completion.

For more information, see Workloads in the Kubernetes documentation.

By default, all Amazon EKS clusters have the following workloads:

- coredns –A Deployment that deploys two replicas of the coredns pods. The pods provide name
 resolution for all pods in the cluster. Two pods are deployed by default for high availability,
 regardless of the number of nodes deployed in your cluster. For more information, see the section
 called "Installing or upgrading CoreDNS" (p. 237). The pods can be deployed to any node type.
 However, they can be deployed to Fargate nodes only if your cluster includes a Fargate profile with
 a namespace that matches the namespace for the workload.
- aws-node A DaemonSet that deploys one pod to each Amazon EC2 node in your cluster. The
 pod runs the Amazon Virtual Private Cloud (Amazon VPC) CNI controller, which provides VPC
 networking functionality to the pods and nodes in your cluster. For more information, see the
 section called "Pod networking (CNI)" (p. 208). This workload isn't deployed to Fargate nodes
 because Fargate already contains the Amazon VPC CNI controller.
- kube-proxy A DaemonSet that deploys one pod to each Amazon EC2 node in your cluster. The
 pods maintain network rules on nodes that enable networking communication to your pods.
 For more information, see kube-proxy in the Kubernetes documentation. This workload isn't
 deployed to Fargate nodes.

View workload details

Selecting the link in the **Name** column for one of the **Workloads** shows you the following information:

- The Status, Namespace, and Selectors (if any) assigned to the workload.
- The list of Pods managed by the workload, their Status and Created date and time.
- The Kubernetes Labels and Annotations assigned to the workload. These could have been assigned by you, by Kubernetes, or by the Amazon EKS API when the workload was created.

Some of the detailed information that you see when inspecting a workload might be different depending on the type of workload. To learn more about the unique properties of each workload type, see Workloads in the Kubernetes documentation.

View pod details

Pods are the fundamental unit of computing within a Kubernetes cluster and represent one or more containers that run together. Each workload controls one of more pods running on the cluster. Pods are designed as relatively ephemeral and immutable objects. Over time it's normal to have pods start and stop while your cluster is running. Pods starting or stopping reflect changes in your workloads as well as changes in the scale of your cluster. For more information, see Pods in the Kubernetes documentation.

When viewing a workload, select a link in the **Name** column for one of the **Pods** to see the following information about the pod:

- The Kubernetes Namespace that the pod is in and the pod's Status.
- The node on which the pod is running. The node might be an Amazon EC2 instance or a Fargate pod. For more information about viewing nodes, see the section called "View nodes" (p. 98).
- The **Containers** in the pod. Selecting the name of a container provides the **Image**, **Ports**, **Mounts**, and **Arguments** provided when the pod was started. Pods can define two types of containers. The first is *application* containers, which are containers that run as long as the pod is running. The second is *init* containers, which are containers that serve as processes that run during pod startup. You can see both types of containers on the pod detail page.
- The Kubernetes **Labels** and **Annotations** assigned to the pod.

Deploy a sample Linux workload

In this topic, you create a Kubernetes manifest and deploy it to your cluster.

Prerequisites

- You must have an existing Kubernetes cluster to deploy a sample application. If you don't have an existing cluster, you can deploy an Amazon EKS cluster using one of the Getting started with Amazon EKS (p. 4) quides.
- You must have kubect1 installed on your computer. For more information, see Installing kubect1 (p. 289).
- kubectl must be configured to communicate with your cluster. For more information, see Create a kubeconfig for Amazon EKS (p. 281).

To deploy a sample application

1. Create a Kubernetes namespace for the sample app.

```
kubectl create namespace <my-namespace>
```

- 2. Create a Kubernetes service and deployment.
 - a. Save the following contents to a file named sample-service.yaml on your computer. If you're deploying to AWS Fargate (p. 136) pods, then make sure that the value for namespace matches the namespace that you defined in your AWS Fargate profile (p. 142). This sample deployment will pull a container image from a public repository, deploy three replicas of it to your cluster, and create a Kubernetes service with its own IP address that can be accessed from within the cluster only. To access the service from outside the cluster, you need to deploy a load balancer (p. 260) or ALB Ingress Controller (p. 267).

The image is a multi-architecture image, so if your cluster includes both x86 and Arm nodes, then the pod can be scheduled on either type of hardware architecture. Kubernetes will deploy the appropriate hardware image based on the hardware type of the node it schedules the pod on. Alternatively, if you only want the deployment to run on nodes with a specific hardware architecture, or your cluster only contains one hardware architecture, then remove either amd64 or arm64 from the example that follows.

```
apiVersion: v1
kind: Service
metadata:
 name: my-service
 namespace: my-namespace
  labels:
    app: my-app
spec:
  selector:
    app: my-app
  ports:
    - protocol: TCP
      port: 80
      targetPort: 80
apiVersion: apps/v1
kind: Deployment
metadata:
 name: my-deployment
 namespace: my-namespace
 labels:
    app: my-app
spec:
  replicas: 3
  selector:
    matchLabels:
     app: my-app
  template:
    metadata:
      labels:
        app: my-app
    spec:
      affinity:
        nodeAffinity:
          requiredDuringSchedulingIgnoredDuringExecution:
            nodeSelectorTerms:
            - matchExpressions:
              - key: beta.kubernetes.io/arch
                operator: In
```

Amazon EKS User Guide Sample workload deployment

```
values:
    - amd64
    - arm64

containers:
    name: nginx
    image: public.ecr.aws/z9d2n7e1/nginx:1.19.5
    ports:
    - containerPort: 80
```

To learn more about Kubernetes services and deployments, see the Kubernetes documentation. The containers in the sample manifest do not use network storage, but they may be able to. For more information, see Storage (p. 180). Though not implemented in this example, we recommend that you create Kubernetes service accounts for your pods, and associate them to AWS IAM accounts. Specifying service accounts enables your pods to have the minimum permissions that they require to interact with other services. For more information, see IAM roles for service accounts (p. 336)

b. Deploy the application.

```
kubectl apply -f <sample-service.yaml>
```

3. View all resources that exist in the my-namespace namespace.

```
kubectl get all -n my-namespace
```

Output

NAME		I	READY	STAT	US	RESTARTS	S AGE	
pod/my-deployment-77	76d8f8fd8-78v	w66 1	L/1	Runn	ing	0	27m	
pod/my-deployment-77	76d8f8fd8-dk	jfr 1	L/1	Runn	ing	0	27m	
pod/my-deployment-77	76d8f8fd8-wm	qj6 1	L/1	Runn	ing	0	27m	
NAME	TYPE	CLUST	ER-IP		EXTE	RNAL-IP	PORT(S)	AGE
service/my-service	ClusterIP	10.10	00.190.	12	<non< td=""><td>.e></td><td>80/TCP</td><td>32m</td></non<>	.e>	80/TCP	32m
NAME		READY	UP-I	O-DAT	E	AVAILABLE	AGE	
deployment.apps/my-d	deployment	3/3	3			3	27m	
NAME			I	ESIRE	D	CURRENT	READY	AGE
replicaset.apps/my-d	deployment-7	76d8£8£	Ed8 3	3		3	3	27m

In the output, you see the service and deployment that are specified in the sample manifest deployed in the previous step. You also see three pods, which are due to specifying 3 for replicas in the sample manifest. For more information about pods, see Pods in the Kubernetes documentation. Kubernetes automatically created the replicaset resource, even though it wasn't specified in the sample manifest. For more information about ReplicaSets, see ReplicaSet in the Kubernetes documentation.

Note

Kubernetes will maintain the number of replicas specified in the manifest. If this were a production deployment and you wanted Kubernetes to horizontally scale the number of replicas or vertically scale the compute resources for the pods, you'd need to use the Horizontal Pod Autoscaler (p. 257) and the Vertical Pod Autoscaler (p. 252).

4. View the details of the deployed service.

```
kubectl -n <my-namespace> describe service <my-service>
```

Abbreviated output

Amazon EKS User Guide Sample workload deployment

```
Name:
              my-service
Namespace:
              my-namespace
Labels:
              app=my-app
Annotations:
              kubectl.kubernetes.io/last-applied-configuration:
                {"apiVersion":"v1", "kind": "Service", "metadata": { "annotations":
app=my-app
Type:
              ClusterIP
IP:
              10.100.190.12
Port:
              <unset> 80/TCP
TargetPort:
              80/TCP
. . .
```

In the output, the value for IP: is a unique IP address that can be reached from any pod within the cluster.

5. View the details of one of the pods that was deployed.

```
kubectl -n <my-namespace> describe pod <my-deployment-776d8f8fd8-78w66>
```

Abbreviated output

```
Name:
             my-deployment-776d8f8fd8-78w66
Namespace:
             my-namespace
Priority:
             0
Node:
             ip-192-168-9-36.us-west-2.compute.internal/192.168.9.36
TP:
             192.168.16.57
IPs:
 IP:
               192.168.16.57
Controlled By: ReplicaSet/my-deployment-776d8f8fd8
Conditions:
                  Status
 Type
 Initialized
                 True
 Ready
                   True
 ContainersReady True
 PodScheduled
                   True
Events:
 Type
         Reason
                           From
Message
                           ----
 Normal Scheduled 3m20s default-scheduler
      Successfully assigned my-namespace/my-deployment-776d8f8fd8-78w66 to
 ip-192-168-9-36.us-west-2.compute.internal
```

In the output, the value for IP: is a unique IP that is assigned to the pod from the CIDR block assigned to the subnet that the node is in, by default. If you'd prefer that pods be assigned IP addresses from different CIDR blocks than the subnet that the node is in, you can change the default behavior. For more information, see CNI custom networking (p. 224). You can also see that the Kubernetes scheduler scheduled the pod on the node with the IP address 192.168.9.36.

6. Execute a shell on one of the pods by replacing the <value> below with a value returned for one of your pods in step 3.

```
kubectl exec -it <my-deployment-776d8f8fd8-78w66> -n <my-namespace> -- /bin/bash
```

7. View the DNS resolver configuration file.

```
cat /etc/resolv.conf
```

Output

```
nameserver 10.100.0.10
search my-namespace.svc.cluster.local svc.cluster.local cluster.local us-
west-2.compute.internal
options ndots:5
```

In the previous output, the value for nameserver is the cluster's nameserver and is automatically assigned as the name server for any pod deployed to the cluster.

- 8. Disconnect from the pod by typing exit.
- 9. Remove the sample service, deployment, pods, and namespace.

```
kubectl delete namespace <my-namespace>
```

Vertical Pod Autoscaler

The Kubernetes Vertical Pod Autoscaler automatically adjusts the CPU and memory reservations for your pods to help "right size" your applications. This adjustment can improve cluster resource utilization and free up CPU and memory for other pods. This topic helps you to deploy the Vertical Pod Autoscaler to your cluster and verify that it is working.

Install the metrics server

The Kubernetes metrics server is an aggregator of resource usage data in your cluster. It is not deployed by default in Amazon EKS clusters, but it provides metrics that are required by the Vertical Pod Autoscaler. This topic explains how to deploy the Kubernetes metrics server on your Amazon EKS cluster.

Note

You can also use Prometheus to provide metrics for the Vertical Pod Autoscaler. For more information, see Control plane metrics with Prometheus (p. 305).

If you have already deployed the metrics server to your cluster, you can move on to the next section. You can check for the metrics server with the following command.

```
kubectl -n kube-system get deployment/metrics-server
```

If this command returns a NotFound error, then you must deploy the metrics server to your Amazon EKS cluster.

To deploy the Metrics Server

1. Deploy the Metrics Server with the following command:

```
{\tt kubect1~apply~-f~https://github.com/kubernetes-sigs/metrics-server/releases/download/v0.3.7/components.yaml}
```

Verify that the metrics-server deployment is running the desired number of pods with the following command.

Amazon EKS User Guide Deploy the Vertical Pod Autoscaler

```
kubectl get deployment metrics-server -n kube-system
```

Output

```
NAME READY UP-TO-DATE AVAILABLE AGE metrics-server 1/1 1 1 6m
```

Deploy the Vertical Pod Autoscaler

In this section, you deploy the Vertical Pod Autoscaler to your cluster.

To deploy the Vertical Pod Autoscaler

- 1. Open a terminal window and navigate to a directory where you would like to download the Vertical Pod Autoscaler source code.
- 2. Clone the kubernetes/autoscaler GitHub repository.

```
git clone https://github.com/kubernetes/autoscaler.git
```

Change to the vertical-pod-autoscaler directory.

```
cd autoscaler/vertical-pod-autoscaler/
```

4. (Optional) If you have already deployed another version of the Vertical Pod Autoscaler, remove it with the following command.

```
./hack/vpa-down.sh
```

- 5. If your cluster isn't in the China (Beijing) or China (Ningxia) Region, skip to step 6. Edit the manifest files in ./vertical-pod-autoscaler/deploy using the following steps.
 - 1. View the manifest file or files that you downloaded and note the name of the image. Download the image locally with the following command.

```
docker pull image:<tag>
```

2. Tag the image to be pushed to an Amazon Elastic Container Registry repository in China with the following command.

```
docker tag image:<tag> <aws_account_id>.dkr.ecr.<cn-north-1>.amazonaws.com/
image:<tag>
```

3. Push the image to a China Amazon ECR repository with the following command.

```
docker push image:<tag> <aws_account_id>.dkr.ecr.<cn-north-1>.amazonaws.com/
image:<tag>
```

- 4. Update the Kubernetes manifest file or files to reference the Amazon ECR image URL in your region.
- 6. Deploy the Vertical Pod Autoscaler to your cluster with the following command.

```
./hack/vpa-up.sh
```

7. Verify that the Vertical Pod Autoscaler pods have been created successfully.

```
kubectl get pods -n kube-system
```

Output:

NAME	READY	STATUS	RESTARTS	AGE
aws-node-949vx	1/1	Running	0	122m
aws-node-b4nj8	1/1	Running	0	122m
coredns-6c75b69b98-r9x68	1/1	Running	0	133m
coredns-6c75b69b98-rt9bp	1/1	Running	0	133m
kube-proxy-bkm6b	1/1	Running	0	122m
kube-proxy-hpqm2	1/1	Running	0	122m
metrics-server-8459fc497-kfj8w	1/1	Running	0	83m
vpa-admission-controller-68c748777d-ppspd	1/1	Running	0	7s
vpa-recommender-6fc8c67d85-gljpl	1/1	Running	0	8s
vpa-updater-786b96955c-bqp9d	1/1	Running	0	8s

Test your Vertical Pod Autoscaler installation

In this section, you deploy a sample application to verify that the Vertical Pod Autoscaler is working.

To test your Vertical Pod Autoscaler installation

1. Deploy the hamster.yaml Vertical Pod Autoscaler example with the following command.

```
kubectl apply -f examples/hamster.yaml
```

2. Get the pods from the hamster example application.

```
kubectl get pods -l app=hamster
```

Output:

hamster-c7d89d6db-rqlf5	1/1	Running	0	48s
hamster-c7d89d6db-znvz5	-	Running	0	48s

3. Describe one of the pods to view its CPU and memory reservation.

```
kubectl describe pod hamster-<c7d89d6db-rglf5>
```

```
Name:
               hamster-c7d89d6db-rglf5
Namespace:
               default
Priority:
               ip-192-168-9-44.<region-code>.compute.internal/192.168.9.44
Node:
Start Time:
               Fri, 27 Sep 2019 10:35:15 -0700
Labels:
               app=hamster
               pod-template-hash=c7d89d6db
Annotations:
               kubernetes.io/psp: eks.privileged
               vpaUpdates: Pod resources updated by hamster-vpa: container 0:
Status:
               Running
IP:
               192.168.23.42
               <none>
Controlled By: ReplicaSet/hamster-c7d89d6db
```

Amazon EKS User Guide Test your Vertical Pod Autoscaler installation

```
Containers:
 hamster:
   Container ID: docker://
e76c2413fc720ac395c33b64588c82094fc8e5d590e373d5f818f3978f577e24
                  k8s.gcr.io/ubuntu-slim:0.1
   Image:
   Image ID:
                 docker-pullable://k8s.gcr.io/ubuntu-
slim@sha256:b6f8c3885f5880a4f1a7cf717c07242eb4858fdd5a84b5ffe35b1cf680ea17b1
   Port:
   Host Port:
                  <none>
   Command:
     /bin/sh
   Args:
     -c
     while true; do timeout 0.5s yes >/dev/null; sleep 0.5s; done
   State:
                Running
     Started:
                   Fri, 27 Sep 2019 10:35:16 -0700
   Ready:
                   True
   Restart Count: 0
   Requests:
     cpu:
                 100m
                 50Mi
     memory:
```

You can see that the original pod reserves 100 millicpu of CPU and 50 mebibytes of memory. For this example application, 100 millicpu is less than the pod needs to run, so it is CPU-constrained. It also reserves much less memory than it needs. The Vertical Pod Autoscaler <code>vpa-recommender</code> deployment analyzes the <code>hamster</code> pods to see if the CPU and memory requirements are appropriate. If adjustments are needed, the <code>vpa-updater</code> relaunches the pods with updated values.

Wait for the vpa-updater to launch a new hamster pod. This should take a minute or two. You can monitor the pods with the following command.

Note

If you are not sure that a new pod has launched, compare the pod names with your previous list. When the new pod launches, you will see a new pod name.

```
kubectl get --watch pods -l app=hamster
```

When a new hamster pod is started, describe it and view the updated CPU and memory reservations.

```
kubectl describe pod hamster-<c7d89d6db-jxgfv>
```

```
Name:
               hamster-c7d89d6db-jxgfv
Namespace:
                default
Priority:
               ip-192-168-9-44.<region-code>.compute.internal/192.168.9.44
Node:
               Fri, 27 Sep 2019 10:37:08 -0700
Start Time:
Labels:
                app=hamster
                pod-template-hash=c7d89d6db
Annotations:
               kubernetes.io/psp: eks.privileged
               vpaUpdates: Pod resources updated by hamster-vpa: container 0: cpu
request, memory request
               Running
Status:
               192.168.3.140
TP:
IPs:
               <none>
Controlled By: ReplicaSet/hamster-c7d89d6db
Containers:
 hamster:
```

Amazon EKS User Guide Test your Vertical Pod Autoscaler installation

```
Container ID:
docker://2c3e7b6fb7ce0d8c86444334df654af6fb3fc88aad4c5d710eac3b1e7c58f7db
                 k8s.gcr.io/ubuntu-slim:0.1
   Image:
                  docker-pullable://k8s.gcr.io/ubuntu-
   Image ID:
slim@sha256:b6f8c3885f5880a4f1a7cf717c07242eb4858fdd5a84b5ffe35b1cf680ea17b1
   Port:
                  <none>
   Host Port:
                  <none>
   Command:
     /bin/sh
   Args:
     while true; do timeout 0.5s yes >/dev/null; sleep 0.5s; done
                 Running
   State:
     Started:
                  Fri, 27 Sep 2019 10:37:08 -0700
   Ready:
                  True
   Restart Count: 0
   Requests:
                 587m
     cpu:
     memory:
               262144k
```

Here you can see that the CPU reservation has increased to 587 millicpu, which is over five times the original value. The memory has increased to 262,144 Kilobytes, which is around 250 mebibytes, or five times the original value. This pod was under-resourced, and the Vertical Pod Autoscaler corrected our estimate with a much more appropriate value.

6. Describe the hamster-vpa resource to view the new recommendation.

```
kubectl describe vpa/hamster-vpa
```

```
Name:
             hamster-vpa
Namespace:
              default
Labels:
             <none>
Annotations: kubectl.kubernetes.io/last-applied-configuration:
               {"apiVersion": "autoscaling.k8s.io/
v1beta2", "kind": "VerticalPodAutoscaler", "metadata": { "annotations": { }, "name": "hamster-
vpa", "namespace": "d...
API Version: autoscaling.k8s.io/v1beta2
             VerticalPodAutoscaler
Kind:
Metadata:
 Creation Timestamp: 2019-09-27T18:22:51Z
 Generation:
                       23
  Resource Version:
                      14411
 Self Link:
                       /apis/autoscaling.k8s.io/v1beta2/namespaces/default/
verticalpodautoscalers/hamster-vpa
 UID:
                      d0d85fb9-e153-11e9-ae53-0205785d75b0
Spec:
  Target Ref:
   API Version: apps/v1
    Kind:
                 Deployment
                hamster
    Name:
Status:
  Conditions:
   Last Transition Time: 2019-09-27T18:23:28Z
    Status:
                           True
                          RecommendationProvided
   Type:
  Recommendation:
    Container Recommendations:
      Container Name: hamster
      Lower Bound:
        Cpu:
                550m
```

Amazon EKS User Guide Horizontal Pod Autoscaler

```
Memory: 262144k
Target:
    Cpu: 587m
    Memory: 262144k
Uncapped Target:
    Cpu: 587m
    Memory: 262144k
Upper Bound:
    Cpu: 21147m
    Memory: 387863636
Events: <none>
```

7. When you finish experimenting with the example application, you can delete it with the following command.

```
kubectl delete -f examples/hamster.yaml
```

Horizontal Pod Autoscaler

The Kubernetes Horizontal Pod Autoscaler automatically scales the number of pods in a deployment, replication controller, or replica set based on that resource's CPU utilization. This can help your applications scale out to meet increased demand or scale in when resources are not needed, thus freeing up your nodes for other applications. When you set a target CPU utilization percentage, the Horizontal Pod Autoscaler scales your application in or out to try to meet that target.

The Horizontal Pod Autoscaler is a standard API resource in Kubernetes that simply requires that a metrics source (such as the Kubernetes metrics server) is installed on your Amazon EKS cluster to work. You do not need to deploy or install the Horizontal Pod Autoscaler on your cluster to begin scaling your applications. For more information, see Horizontal Pod Autoscaler in the Kubernetes documentation.

Use this topic to prepare the Horizontal Pod Autoscaler for your Amazon EKS cluster and to verify that it is working with a sample application.

Note

This topic is based on the Horizontal pod autoscaler walkthrough in the Kubernetes documentation.

Install the metrics server

The Kubernetes metrics server is an aggregator of resource usage data in your cluster. The metrics server is not deployed by default in Amazon EKS clusters, but it provides metrics that are required by the Horizontal Pod Autoscaler. This topic explains how to deploy the Kubernetes metrics server on your Amazon EKS cluster.

If you have already deployed the metrics server to your cluster, you can move on to the next section. You can check for the metrics server with the following command.

```
kubectl -n kube-system get deployment/metrics-server
```

If this command returns a NotFound error, then you must deploy the metrics server to your Amazon EKS cluster.

To deploy the Metrics Server

1. Deploy the Metrics Server with the following command:

Amazon EKS User Guide Run a Horizontal Pod Autoscaler test application

 ${\tt kubect1~apply~-f~https://github.com/kubernetes-sigs/metrics-server/releases/download/v0.3.7/components.yaml}$

Verify that the metrics-server deployment is running the desired number of pods with the following command.

```
kubectl get deployment metrics-server -n kube-system
```

Output

NAME	READY	UP-TO-DATE	AVAILABLE	AGE
metrics-server	1/1	1	1	6m

Run a Horizontal Pod Autoscaler test application

In this section, you deploy a sample application to verify that the Horizontal Pod Autoscaler is working.

Note

This example is based on the Horizontal pod autoscaler walkthrough in the Kubernetes documentation.

To test your Horizontal Pod Autoscaler installation

1. Deploy a simple Apache web server application with the following command.

```
kubectl apply -f https://k8s.io/examples/application/php-apache.yaml
```

This Apache web server pod is given a 500 millicpu CPU limit and it is serving on port 80.

2. Create a Horizontal Pod Autoscaler resource for the php-apache deployment.

```
kubectl autoscale deployment php-apache --cpu-percent=50 --min=1 --max=10
```

This command creates an autoscaler that targets 50 percent CPU utilization for the deployment, with a minimum of one pod and a maximum of ten pods. When the average CPU load is below 50 percent, the autoscaler tries to reduce the number of pods in the deployment, to a minimum of one. When the load is greater than 50 percent, the autoscaler tries to increase the number of pods in the deployment, up to a maximum of ten. For more information, see How does the Horizontal Pod Autoscaler work? in the Kubernetes documentation.

3. Describe the autoscaler with the following command to view its details.

```
kubectl describe hpa
```

```
Name:
                                                        php-apache
Namespace:
                                                         default
Labels:
                                                         <none>
Annotations:
                                                         <none>
                                                        Thu, 11 Jun 2020 16:05:41 -0500
CreationTimestamp:
Reference:
                                                        Deployment/php-apache
Metrics:
                                                         ( current / target )
                                                       <unknown> / 50%
 resource cpu on pods (as a percentage of request):
Min replicas:
```

Amazon EKS User Guide Run a Horizontal Pod Autoscaler test application

Max replicas: Deployment pods: 1 current / 0 desired Conditions: Туре Status Reason Message True SucceededGetScale AbleToScale the HPA controller was able to get the target's current scale ScalingActive False FailedGetResourceMetric the HPA was unable to compute the replica count: did not receive metrics for any ready pods Events: Type From Reason Message _____ Warning FailedGetResourceMetric 42s (x2 over 57s) horizontal-pod-autoscaler unable to get metrics for resource cpu: no metrics returned from resource metrics API Warning FailedComputeMetricsReplicas 42s (x2 over 57s) horizontal-pod-autoscaler invalid metrics (1 invalid out of 1), first error is: failed to get cpu utilization: unable to get metrics for resource cpu: no metrics returned from resource metrics API Warning FailedGetResourceMetric 12s (x2 over 27s) horizontal-pod-autoscaler did not receive metrics for any ready pods Warning FailedComputeMetricsReplicas 12s (x2 over 27s) horizontal-pod-autoscaler invalid metrics (1 invalid out of 1), first error is: failed to get cpu utilization: did not receive metrics for any ready pods

As you can see, the current CPU load is <unknown>, because there's no load on the server yet. The pod count is already at its lowest boundary (one), so it cannot scale in.

4. Create a load for the web server by running a container.

```
kubectl run -it --rm load-generator --image=busybox /bin/sh --generator=run-pod/v1
```

If you don't receive a command prompt after several seconds, you may need to press Enter. From the command prompt, enter the following command to generate load and cause the autoscaler to scale out the deployment.

```
while true; do wget -q -O- http://php-apache; done
```

5. To watch the deployment scale out, periodically run the following command in a separate terminal from the terminal that you ran the previous step in.

```
kubectl get hpa
```

Output:

NAME	REFERENCE	TARGETS	MINPODS	MAXPODS	REPLICAS	AGE
php-apache	Deployment/php-apache	250%/50%	1	10	5	4m44s

As long as actual CPU percentage is higher than the target percentage, then the replica count increases, up to 10. In this case, it's 250%, so the number of REPLICAS continues to increase.

Note

It may take a few minutes before you see the replica count reach its maximum. If only 6 replicas, for example, are necessary for the CPU load to remain at or under 50%, then the load won't scale beyond 6 replicas.

6. Stop the load. In the terminal window you're generating the load in (from step 4), stop the load by holding down the Ctrl+C keys. You can watch the replicas scale back to 1 by running the following command again.

Amazon EKS User Guide Network load balancing

kubectl get hpa			
-----------------	--	--	--

Output

NAME	REFERENCE	TARGETS	MINPODS	MAXPODS	REPLICAS	AGE
php-apache	Deployment/php-apache	0%/50%	1	10	1	25m

Note

The default timeframe for scaling back down is five minutes, so it will take some time before you see the replica count reach 1 again, even when the current CPU percentage is 0 percent. The timeframe is modifiable. For more information, see Horizontal Pod Autoscaler in the Kubernetes documentation.

7. When you are done experimenting with your sample application, delete the php-apache resources.

kubectl delete deployment.apps/php-apache service/php-apache horizontalpodautoscaler.autoscaling/php-apache

Network load balancing on Amazon EKS

You can load balance network traffic across pods using the AWS Network Load Balancer (NLB) or Classic Load Balancer (CLB). To learn more about the differences between the two types, see Elastic Load Balancing features on the AWS web site. You can deploy an AWS load balancer to a public or private subnet.

Network traffic is load balanced at L4 of the OSI model. To load balance application traffic at L7, see the section called "Application load balancing" (p. 267). To learn more about the differences between the two types of load balancing, see Elastic Load Balancing features on the AWS web site.

In Amazon EKS, you can load balance network traffic to an NLB (*instance* or *IP* targets) or a CLB (*instance* target only). For more information about NLB target types, see Target type in the User Guide for Network Load Balancers. When you load balance network traffic to instance targets, the Kubernetes in-tree load balancing controller creates the NLB or CLB. To load balance network traffic to IP target types, the AWS Load Balancer Controller creates an NLB. For more information, see AWS load balancer controller on GitHub. The in-tree load balancing controller is included in Kubernetes. To use the AWS Load Balancer Controller, you must deploy it to your cluster.

Prerequisites

Before you can load balance network traffic to an application, you must meet the following requirements.

- Have an existing cluster. If you don't have an existing cluster, see Getting started with Amazon EKS (p. 4).
- Public subnets must be tagged as follows so that Kubernetes knows to use only those subnets for
 external load balancers instead of choosing a public subnet in each Availability Zone (in lexicographical
 order by subnet ID). If you use eksctl or an Amazon EKS AWS CloudFormation template to create
 your VPC after March 26, 2020, then the subnets are tagged appropriately when they're created. For
 more information about the Amazon EKS AWS CloudFormation VPC templates, see Creating a VPC for
 your Amazon EKS cluster (p. 197).

Key	Value
kubernetes.io/role/elb	1

Private subnets must be tagged as follows so that Kubernetes knows it can use the subnets for internal
load balancers. If you use eksctl or an Amazon EKS AWS CloudFormation template to create your
VPC after March 26, 2020, then the subnets are tagged appropriately when they're created. For more
information about the Amazon EKS AWS CloudFormation VPC templates, see Creating a VPC for your
Amazon EKS cluster (p. 197).

Key	Value
kubernetes.io/role/internal-elb	1

Considerations

• Use of the UDP protocol is supported with the load balancer on Amazon EKS clusters with the following platform versions. For more information, see the section called "Platform versions" (p. 73).

Amazon EKS version	Platform version
1.18	.1
1.17	.2
1.16	.3
1.15	.4

- You can only use NLB *IP* targets with the Amazon EKS VPC CNI plugin (p. 208). You can use NLB *instance* targets with the Amazon EKS VPC CNI plugin or alternate compatible CNI plugins (p. 236).
- You can only use IP targets with NLB. You can't use IP targets with CLBs.
- You can only use NLB *IP* targets with clusters running at least Amazon EKS version 1.18. To upgrade your current version, see the section called "Updating a cluster" (p. 43).
- The configuration of your load balancer is controlled by annotations that are added to the manifest for your service. If you want to add tags to the load balancer when (or after) it's created, add the following annotation in your service specification. For more information, see Other ELB annotations in the Kubernetes documentation.

```
service.beta.kubernetes.io/aws-load-balancer-additional-resource-tags
```

If you're using Amazon EKS 1.16 or later, you can assign elastic IP addresses to the Network Load
Balancer by adding the following annotation. Replace the <example-values> (including <>) with the
Allocation IDs of your elastic IP addresses. The number of Allocation IDs must match the number of
subnets used for the load balancer.

```
service.beta.kubernetes.io/aws-load-balancer-eip-allocations: eipalloc-
<xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx,eipalloc-<yyyyyyyyyyyyyyyy
```

Load balancer – Instance targets

NLB or CLBs with instance targets are created by the Kubernetes in-tree load balancing controller. The in-tree controller is included with Kubernetes, so you don't need to deploy it to your cluster. You can use NLB instance targets with pods deployed to nodes, but not to Fargate. To load balance network traffic across pods deployed to Fargate, you must use IP targets (p. 262). By default, external (public) Classic Load Balancers are created when you deploy a Kubernetes service of type LoadBalancer. To deploy a Network Load Balancer instead, apply the following annotation to your service:

service.beta.kubernetes.io/aws-load-balancer-type: nlb

Important

Do not edit this annotation after creating your service. If you need to modify it, delete the service object and create it again with the desired value for this annotation.

To deploy a load balancer to a private subnet, your service specification must have the following annotation:

```
service.beta.kubernetes.io/aws-load-balancer-internal: "true"
```

For internal load balancers, your Amazon EKS cluster must be configured to use at least one private subnet in your VPC. Kubernetes examines the route table for your subnets to identify whether they are public or private. Public subnets have a route directly to the internet using an internet gateway, but private subnets do not.

For an example service manifest that specifies a load balancer, see Type LoadBalancer in the Kubernetes documentation. For more information about using Network Load Balancer with Kubernetes, see Network Load Balancer support on AWS in the Kubernetes documentation.

Load balancer - IP targets

NLBs with IP targets are created by the AWS Load Balancer Controller (you cannot use CLBs with IP targets). To use the controller, you must deploy it to your cluster. You can use NLB IP targets with pods deployed to Amazon EC2 nodes or Fargate. For more information about the controller, see AWS Load Balancer Controller on GitHub. The controller creates and manages the NLB. Your Kubernetes service must be created as type LoadBalancer. For more information, see Type LoadBalancer in the Kubernetes documentation.

To create a load balancer that uses IP targets, add the following annotation to a service manifest and deploy your service.

```
service.beta.kubernetes.io/aws-load-balancer-type: "nlb-ip"
```

Important

Do not edit this annotation after creating your service. If you need to modify it, delete the service object and create it again with the desired value for this annotation. You can only use NLB *IP* targets with clusters running at least Amazon EKS version 1.18. To upgrade your current version, see the section called "Updating a cluster" (p. 43).

To deploy the AWS Load Balancer Controller to an Amazon EKS cluster

In the following steps, replace the <example values> (including <>) with your own values.

 Determine whether you have an existing IAM OpenID Connect (OIDC) provider created for your cluster.

```
aws eks describe-cluster --name <cluster_name> --query "cluster.identity.oidc.issuer"
    --output text
```

Output

https://oidc.eks.<region-code>.amazonaws.com/id/EXAMPLED539D4633E53DE1B716D3041E

If no output is returned, create an IAM OIDC provider and associate it with your cluster. Alternately, you can create the provider using the console (p. 341).

```
eksctl utils associate-iam-oidc-provider \
    --region <region-code> \
    --cluster <my-cluster> \
    --approve
```

- 2. Download an IAM policy for the AWS Load Balancer Controller that allows it to make calls to AWS APIs on your behalf. You can view the policy document on GitHub. Use the command that corresponds to the Region that your cluster is in.
 - · All Regions other than China Regions.

```
curl -o iam_policy.json https://raw.githubusercontent.com/kubernetes-sigs/aws-load-
balancer-controller/v2.1.0/docs/install/iam_policy.json
```

Beijing and Ningxia China Regions.

```
curl -o iam_policy_cn.json https://raw.githubusercontent.com/kubernetes-sigs/aws-
load-balancer-controller/v2.1.0/docs/install/iam_policy_cn.json
```

3. Create an IAM policy using the policy downloaded in the previous step. Change iam_policy.json to iam_policy_cn.json in the following command, if you downloaded that file instead.

```
aws iam create-policy \
    --policy-name <AWSLoadBalancerControllerIAMPolicy> \
    --policy-document file://iam_policy.json
```

Take note of the policy ARN that is returned.

4. Create an IAM role and Kubernetes service account named aws-load-balancer-controller in the kube-system namespace, a cluster role, and a cluster role binding for the Load Balancer Controller to use with the following command.

```
eksctl create iamserviceaccount \
   --cluster=<my-cluster> \
   --namespace=kube-system \
   --name=aws-load-balancer-controller \
   --attach-policy-arn=arn:aws:iam::<AWS_ACCOUNT_ID>:policy/
<AWSLoadBalancerControllerIAMPolicy> \
   --override-existing-serviceaccounts \
   --approve
```

- 5. If you currently have the AWS ALB Ingress Controller for Kubernetes installed, uninstall it. The AWS Load Balancer Controller replaces the functionality of the AWS ALB Ingress Controller for Kubernetes.
 - a. Check to see if the controller is currently installed.

```
kubectl get deployment -n kube-system alb-ingress-controller
```

Output (if it is installed). Skip to step 5.2.

```
NAME READY UP-TO-DATE AVAILABLE AGE alb-ingress-controller 1/1 1 1 122d
```

Output (if it isn't installed). If it isn't installed, skip to step 6.

```
Error from server (NotFound): deployments.apps "alb-ingress-controller" not found
```

b. If the controller is installed, enter the following commands to remove it.

```
kubectl delete -f https://raw.githubusercontent.com/kubernetes-sigs/aws-alb-ingress-controller/v1.1.8/docs/examples/alb-ingress-controller.yaml kubectl delete -f https://raw.githubusercontent.com/kubernetes-sigs/aws-alb-ingress-controller/v1.1.8/docs/examples/rbac-role.yaml
```

- c. If you removed the AWS ALB Ingress Controller for Kubernetes, add the following IAM policy to the IAM account created in step 4. The policy allows the AWS Load Balancer Controller access to the resources that were created by the ALB Ingress Controller for Kubernetes.
 - a. Download the IAM policy. You can also view the policy.

```
curl -o iam_policy_v1_to_v2_additional.json https://raw.githubusercontent.com/
kubernetes-sigs/aws-load-balancer-controller/v2.1.0/docs/install/
iam_policy_v1_to_v2_additional.json
```

b. Create the IAM policy and note the ARN returned.

```
aws iam create-policy \
   --policy-name <AWSLoadBalancerControllerAdditionalIAMPolicy> \
   --policy-document file://iam_policy_v1_to_v2_additional.json
```

- c. Open the AWS CloudFormation console and select the eksctl-<your-cluster-name>-addon-iamserviceaccount-kube-system-aws-load-balancer-controller stack that was deployed in step 4 by eksctl. Select the Resources tab, and then select the link in the Physical ID column. Note the value for Role ARN for use in the next step.
- d. Attach the IAM policy to the IAM role.

```
aws iam attach-role-policy \
--role-name eksctl-<your-cluster-name>-addon-iamserviceaccount-kube-sys-Role1-
<1DZ86GS3UBRGN>\
--policy-arn arn:aws:iam::111122223333:policy/
AWSLoadBalancerControllerAdditionalIAMPolicy
```

- 6. Install the AWS Load Balancer Controller using Helm. If you'd prefer to install the controller manually, then skip to the next step.
 - a. Install the TargetGroupBinding custom resource definitions.

```
kubectl apply -k "https://raw.githubusercontent.com/aws/eks-charts/master/stable/
aws-load-balancer-controller/crds/crds.yaml"
```

b. Add the eks-charts repository.

```
helm repo add eks https://aws.github.io/eks-charts
```

c. Install the AWS Load Balancer Controller using the command that corresponds to the Region that your cluster is in.

Important

If you are deploying the controller to Amazon EC2 nodes that you have restricted access to the Amazon EC2 instance metadata service (IMDS) (p. 349) from, or if you are

deploying to Fargate, then you need to add the following flags to the command that you run:

- --set region=<region-code>--set vpcId=<vpc-xxxxxxxx>
- · All Regions other than China Regions.

```
helm upgrade -i aws-load-balancer-controller eks/aws-load-balancer-controller \
--set clusterName=<cluster-name> \
--set serviceAccount.create=false \
--set serviceAccount.name=aws-load-balancer-controller \
-n kube-system
```

· Beijing and Ningxia China Regions.

```
helm upgrade -i aws-load-balancer-controller eks/aws-load-balancer-controller \
--set clusterName=<cluster-name> \
--set serviceAccount.create=false \
--set serviceAccount.name=aws-load-balancer-controller \
--set image.repository=918309763551.dkr.ecr.cn-north-1.amazonaws.com.cn/amazon/aws-load-balancer-controller \
-n kube-system
```

Important

The deployed chart does not receive security updates automatically. You need to manually upgrade to a newer chart when it becomes available.

- 7. Install the controller manually. If you already installed the controller using the previous step, then don't complete this step.
 - Install cert-manager to inject certificate configuration into the webhooks.
 - Install on Kubernetes 1.16 or later.

```
kubectl apply --validate=false -f https://github.com/jetstack/cert-manager/
releases/download/v1.0.2/cert-manager.yaml
```

• Install on Kubernetes 1.15 or earlier.

```
kubectl apply --validate=false -f https://github.com/jetstack/cert-manager/
releases/download/v1.0.2/cert-manager-legacy.yaml
```

- b. Install the controller.
 - a. Download the controller specification. For more information about the controller, see the documentation on GitHub.

```
curl -o v2_1_0_full.yaml https://raw.githubusercontent.com/kubernetes-sigs/aws-load-balancer-controller/v2.1.0/docs/install/v2_1_0_full.yaml
```

- b. Edit the saved yaml file. In the Deployment spec section set the --cluster-name value to your Amazon EKS cluster name. It is recommended that you delete the ServiceAccount from the yaml specification. Doing so will preserve the eksctl-created iamserviceaccount if you delete the installation.
- c. Apply the file.

```
kubectl apply -f v2_1_0_full.yaml
```

8. Verify that the controller is installed.

```
kubectl get deployment -n kube-system aws-load-balancer-controller
```

Output

```
NAME READY UP-TO-DATE AVAILABLE AGE aws-load-balancer-controller 1/1 1 84s
```

(Optional) To deploy a sample application

- 1. Deploy a sample application.
 - a. Save the following contents to a yaml file on your computer.

```
apiVersion: apps/v1
kind: Deployment
metadata:
 name: sample-app
spec:
 replicas: 3
 selector:
   matchLabels:
     app: nginx
  template:
    metadata:
      labels:
        app: nginx
    spec:
      containers:
        - name: nginx
          image: public.ecr.aws/z9d2n7e1/nginx:1.19.5
          ports:
            - name: http
              containerPort: 80
```

b. Apply the manifest to the cluster.

```
kubectl apply -f <file-name-you-specified>.yaml
```

- 2. Create a service of type LoadBalancer with an annotation to create an NLB with IP targets.
 - a. Save the following contents to a yaml file on your computer.

```
apiVersion: v1
kind: Service
metadata:
  name: sample-service
  annotations:
    service.beta.kubernetes.io/aws-load-balancer-type: nlb-ip
spec:
  ports:
    - port: 80
    targetPort: 80
    protocol: TCP
type: LoadBalancer
```

Amazon EKS User Guide Application load balancing

```
selector:
app: nginx
```

b. Apply the manifest to the cluster.

```
kubectl apply -f <file-name-you-specified>.yaml
```

3. Verify that the service was deployed.

```
kubectl get svc sample-service
```

Output

- 4. Open the Amazon EC2 AWS Management Console. Select Target Groups (under Load Balancing) in the left panel. Find the Target group that was created in a previous step. The name in the Load balancer column will be a part of the name returned in the previous step. For example, k8s-default-nlbipsvc-xxxxxxxxxx. The Target type is IP.
- 5. Select the **Target group** to view its details. Under **Registered targets**, you should see three IP addresses of the three replicas deployed in a previous step. Wait until all the status of all targets is **healthy** before continuing. It may take several minutes before all targets are healthy. The targets may have an unhealthy state before changing to healthy.
- 6. Send traffic to the service replacing the example value with the value returned in a previous step for the EXTERNAL-IP.

```
curl <k8s-default-samplese-xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx.elb.us-west-2.amazonaws.com>
```

Output

```
<!DOCTYPE html>
<html>
<head>
<title>Welcome to nginx!</title>
...
```

7. When you're finished with the sample deployment and service, remove them.

```
kubectl delete service sample-service
kubectl delete deployment sample-app
```

Application load balancing on Amazon EKS

You can load balance application traffic across pods using the AWS Application Load Balancer (ALB). To learn more, see What is an Application Load Balancer? in the Application Load Balancers User Guide. ALBs can be used with pods deployed to nodes or to AWS Fargate. You can deploy an ALB to public or private subnets.

Application traffic is balanced at L7 of the OSI model. To load balance network traffic at L4, see the section called "Network load balancing" (p. 260). To learn more about the differences between the two types of load balancing, see Elastic Load Balancing features on the AWS web site.

Prerequisites

Before you can load balance application traffic to an application, you must meet the following requirements.

- Have an existing cluster. If you don't have an existing cluster, see *Getting started with Amazon EKS* (p. 4).
- Public subnets must be tagged as follows so that Kubernetes knows to use only those subnets for
 external load balancers instead of choosing a public subnet in each Availability Zone (in lexicographical
 order by subnet ID). If you use eksctl or an Amazon EKS AWS CloudFormation template to create
 your VPC after March 26, 2020, then the subnets are tagged appropriately when they're created. For
 more information about the Amazon EKS AWS CloudFormation VPC templates, see Creating a VPC for
 your Amazon EKS cluster (p. 197).

Key	Value
kubernetes.io/role/elb	1

Private subnets must be tagged as follows so that Kubernetes knows it can use the subnets for internal
load balancers. If you use eksctl or an Amazon EKS AWS CloudFormation template to create your
VPC after March 26, 2020, then the subnets are tagged appropriately when they're created. For more
information about the Amazon EKS AWS CloudFormation VPC templates, see Creating a VPC for your
Amazon EKS cluster (p. 197).

Key	Value
kubernetes.io/role/internal-elb	1

The AWS Load Balancer Controller (formerly named AWS ALB Ingress Controller) creates ALBs and the necessary supporting AWS resources whenever a Kubernetes Ingress resource is created on the cluster with the kubernetes.io/ingress.class: alb annotation. The Ingress resource configures the ALB to route HTTP or HTTPS traffic to different pods within the cluster. To ensure that your Ingress objects use the AWS Load Balancer Controller, add the following annotation to your Kubernetes Ingress specification. For more information, see Ingress specification on GitHub.

```
annotations:
kubernetes.io/ingress.class: alb
```

The AWS Load Balancer Controller supports the following traffic modes:

• Instance – Registers nodes within your cluster as targets for the ALB. Traffic reaching the ALB is routed to NodePort for your service and then proxied to your pods. This is the default traffic mode. You can also explicitly specify it with the alb.ingress.kubernetes.io/target-type: instance annotation.

Note

Your Kubernetes service must specify the NodePort type to use this traffic mode.

• IP – Registers pods as targets for the ALB. Traffic reaching the ALB is directly routed to pods for your service. You must specify the alb.ingress.kubernetes.io/target-type: ip annotation to use this traffic mode. The IP target type is required when target pods are running on Fargate.

To tag ALBs created by the controller, add the following annotation to the controller: alb.ingress.kubernetes.io/tags. For a list of all available annotations supported by the AWS Load Balancer Controller, see Ingress annotations on GitHub.

Amazon EKS User Guide Application load balancing

This topic shows you how to configure the AWS Load Balancer Controller to work with your Amazon EKS cluster. For more information about the controller, see AWS Load Balancer Controller on GitHub.

To deploy the AWS Load Balancer Controller to an Amazon EKS cluster

In the following steps, replace the <example values> (including <>) with your own values.

 Determine whether you have an existing IAM OpenID Connect (OIDC) provider created for your cluster.

```
aws eks describe-cluster --name <cluster_name> --query "cluster.identity.oidc.issuer"
    --output text
```

Output

```
https://oidc.eks.<region-code>.amazonaws.com/id/EXAMPLED539D4633E53DE1B716D3041E
```

If no output is returned, create an IAM OIDC provider and associate it with your cluster. Alternately, you can create the provider using the console (p. 341).

```
eksctl utils associate-iam-oidc-provider \
    --region <region-code> \
    --cluster <my-cluster> \
    --approve
```

- 2. Download an IAM policy for the AWS Load Balancer Controller that allows it to make calls to AWS APIs on your behalf. You can view the policy document on GitHub. Use the command that corresponds to the Region that your cluster is in.
 - · All Regions other than China Regions.

```
curl -o iam_policy.json https://raw.githubusercontent.com/kubernetes-sigs/aws-load-
balancer-controller/v2.1.0/docs/install/iam_policy.json
```

Beijing and Ningxia China Regions.

```
curl -o iam_policy_cn.json https://raw.githubusercontent.com/kubernetes-sigs/aws-load-balancer-controller/v2.1.0/docs/install/iam_policy_cn.json
```

3. Create an IAM policy using the policy downloaded in the previous step. Change iam_policy.json to iam_policy_cn.json in the following command, if you downloaded that file instead.

```
aws iam create-policy \
    --policy-name <AWSLoadBalancerControllerIAMPolicy> \
    --policy-document file://iam_policy.json
```

Take note of the policy ARN that is returned.

4. Create an IAM role and Kubernetes service account named aws-load-balancer-controller in the kube-system namespace, a cluster role, and a cluster role binding for the Load Balancer Controller to use with the following command.

```
eksctl create iamserviceaccount \
    --cluster=<my-cluster> \
    --namespace=kube-system \
    --name=aws-load-balancer-controller \
    --attach-policy-arn=arn:aws:iam::<AWS_ACCOUNT_ID>:policy/
<AWSLoadBalancerControllerIAMPolicy> \
```

Amazon EKS User Guide Application load balancing

```
--override-existing-serviceaccounts \
--approve
```

- If you currently have the AWS ALB Ingress Controller for Kubernetes installed, uninstall it. The AWS Load Balancer Controller replaces the functionality of the AWS ALB Ingress Controller for Kubernetes.
 - a. Check to see if the controller is currently installed.

```
kubectl get deployment -n kube-system alb-ingress-controller
```

Output (if it is installed). Skip to step 5.2.

```
NAME READY UP-TO-DATE AVAILABLE AGE alb-ingress-controller 1/1 1 1 122d
```

Output (if it isn't installed). If it isn't installed, skip to step 6.

```
{\tt Error \ from \ server \ (NotFound): \ deployments.apps \ "alb-ingress-controller" \ not \ found}
```

b. If the controller is installed, enter the following commands to remove it.

```
kubectl delete -f https://raw.githubusercontent.com/kubernetes-sigs/aws-alb-
ingress-controller/v1.1.8/docs/examples/alb-ingress-controller.yaml
kubectl delete -f https://raw.githubusercontent.com/kubernetes-sigs/aws-alb-
ingress-controller/v1.1.8/docs/examples/rbac-role.yaml
```

- c. If you removed the AWS ALB Ingress Controller for Kubernetes, add the following IAM policy to the IAM account created in step 4. The policy allows the AWS Load Balancer Controller access to the resources that were created by the ALB Ingress Controller for Kubernetes.
 - a. Download the IAM policy. You can also view the policy.

```
curl -o iam_policy_v1_to_v2_additional.json https://raw.githubusercontent.com/
kubernetes-sigs/aws-load-balancer-controller/v2.1.0/docs/install/
iam_policy_v1_to_v2_additional.json
```

b. Create the IAM policy and note the ARN returned.

```
aws iam create-policy \
  --policy-name <AWSLoadBalancerControllerAdditionalIAMPolicy> \
  --policy-document file://iam_policy_v1_to_v2_additional.json
```

- c. Open the AWS CloudFormation console and select the eksctl-<your-cluster-name>-addon-iamserviceaccount-kube-system-aws-load-balancer-controller stack that was deployed in step 4 by eksctl. Select the Resources tab, and then select the link in the Physical ID column. Note the value for Role ARN for use in the next step.
- d. Attach the IAM policy to the IAM role.

```
aws iam attach-role-policy \
--role-name eksctl-<your-cluster-name>-addon-iamserviceaccount-kube-sys-Role1-
<1DZ86GS3UBRGN>\
--policy-arn arn:aws:iam::111122223333:policy/
AWSLoadBalancerControllerAdditionalIAMPolicy
```

Install the AWS Load Balancer Controller using Helm. If you'd prefer to install the controller manually, then skip to the next step.

Amazon EKS User Guide Application load balancing

a. Install the TargetGroupBinding custom resource definitions.

```
kubectl apply -k "https://raw.githubusercontent.com/aws/eks-charts/master/stable/
aws-load-balancer-controller/crds/crds.yaml"
```

b. Add the eks-charts repository.

```
helm repo add eks https://aws.github.io/eks-charts
```

 Install the AWS Load Balancer Controller using the command that corresponds to the Region that your cluster is in.

Important

If you are deploying the controller to Amazon EC2 nodes that you have restricted access to the Amazon EC2 instance metadata service (IMDS) (p. 349) from, or if you are deploying to Fargate, then you need to add the following flags to the command that you run:

- --set region=<region-code>
- --set vpcId=<vpc-xxxxxxxx>
- · All Regions other than China Regions.

```
helm upgrade -i aws-load-balancer-controller eks/aws-load-balancer-controller \
--set clusterName=<cluster-name> \
--set serviceAccount.create=false \
--set serviceAccount.name=aws-load-balancer-controller \
-n kube-system
```

· Beijing and Ningxia China Regions.

```
helm upgrade -i aws-load-balancer-controller eks/aws-load-balancer-controller \
--set clusterName=<cluster-name> \
--set serviceAccount.create=false \
--set serviceAccount.name=aws-load-balancer-controller \
--set image.repository=918309763551.dkr.ecr.cn-north-1.amazonaws.com.cn/amazon/aws-load-balancer-controller \
-n kube-system
```

Important

The deployed chart does not receive security updates automatically. You need to manually upgrade to a newer chart when it becomes available.

- 7. Install the controller manually. If you already installed the controller using the previous step, then don't complete this step.
 - a. Install cert-manager to inject certificate configuration into the webhooks.
 - Install on Kubernetes 1.16 or later.

```
kubectl apply --validate=false -f https://github.com/jetstack/cert-manager/releases/download/v1.0.2/cert-manager.yaml
```

• Install on Kubernetes 1.15 or earlier.

Amazon EKS User Guide Application load balancing

kubectl apply --validate=false -f https://github.com/jetstack/cert-manager/ releases/download/v1.0.2/cert-manager-legacy.yaml

- b. Install the controller.
 - a. Download the controller specification. For more information about the controller, see the documentation on GitHub.

```
curl -o v2_1_0_full.yaml https://raw.githubusercontent.com/kubernetes-sigs/aws-load-balancer-controller/v2.1.0/docs/install/v2_1_0_full.yaml
```

- b. Edit the saved yaml file. In the Deployment spec section set the --cluster-name value to your Amazon EKS cluster name. It is recommended that you delete the ServiceAccount from the yaml specification. Doing so will preserve the eksctl-created iamserviceaccount if you delete the installation.
- c. Apply the file.

```
kubectl apply -f v2_1_0_full.yaml
```

8. Verify that the controller is installed.

```
kubectl get deployment -n kube-system aws-load-balancer-controller
```

Output

NAME	READY	UP-TO-DATE	AVAILABLE	AGE
aws-load-balancer-controller	1/1	1	1	84s

To share an application load balancer across multiple ingress resources using IngressGroups

To join an Ingress to an Ingress group, add the following annotation to a Kubernetes Ingress resource specification.

```
alb.ingress.kubernetes.io/group.name: <my-group>
```

The group name must be:

- 63 characters or less in length.
- Consist of lower case alphanumeric characters, –, and ., and must start and end with an alphanumeric character.

The controller will automatically merge ingress rules for all Ingresses in the same Ingress group and support them with a single ALB. Most annotations defined on an Ingress only apply to the paths defined by that Ingress. By default, Ingress resources don't belong to any Ingress group.

Warning

Potential security risk: You should only specify an Ingress group for an Ingress when all Kubernetes users with RBAC permission to create or modify Ingress resources are within the same trust boundary. If you add the annotation with a group name, other Kubernetes users may create or modify their Ingresses to belong to the same Ingress group. Doing so can cause undesirable behavior, such as overwriting existing rules with higher priority rules.

You can add an order number of your Ingress resource.

Amazon EKS User Guide Application load balancing

```
alb.ingress.kubernetes.io/group.order: <'10'>
```

The number can be between 1-1000. The lowest number for all Ingresses in the same Ingress group is evaluated first. All Ingresses without this annotation are evaluated with a value of zero. Duplicate rules with a higher number can overwrite rules with a lower number. By default, the rule order between Ingresses within the same Ingress group are determined by the lexical order of an Ingress' namespace and name.

Important

Ensure that each Ingress in the same Ingress group has a unique priority number. You can't have duplicate order numbers across Ingresses.

To deploy a sample application

You can run the sample application on a cluster that has Amazon EC2 nodes only, Fargate pods, or both.

1. If you're not deploying to Fargate, skip this step. Create a Fargate profile. The command that follows only works for clusters that were created with eksctl. If you didn't create your cluster with eksctl, then you can create the profile with the the AWS Management Console (p. 143), using the same values for name and namespace that are in the command below.

```
eksctl create fargateprofile --cluster <my-cluster> --region <region-code> --name <alb-sample-app> --namespace game-2048
```

2. Deploy the game 2048 as a sample application to verify that the AWS Load Balancer Controller creates an AWS ALB as a result of the Ingress object.

```
kubectl apply -f https://raw.githubusercontent.com/kubernetes-sigs/aws-load-balancer-
controller/v2.1.0/docs/examples/2048/2048_full.yaml
```

3. After a few minutes, verify that the Ingress resource was created with the following command.

```
kubectl get ingress/ingress-2048 -n game-2048
```

Output:

```
NAME CLASS HOSTS ADDRESS

PORTS AGE

ingress-2048 <none> * k8s-game2048-ingress2-xxxxxxxxxxx-yyyyyyyyyvy.us-
west-2.elb.amazonaws.com 80 2m32s
```

Note

If your Ingress has not been created after several minutes, run the following command to view the Load Balancer Controller logs. These logs may contain error messages that can help you diagnose any issues with your deployment.

```
kubectl logs -n kube-system deployment.apps/aws-load-balancer-controller
```

- 4. Open a browser and navigate to the ADDRESS URL from the previous command output to see the sample application.
- 5. When you finish experimenting with your sample application, delete it with the following commands.

 $\label{local_kubernetes_sigs_aws_load_balancer-controller_v2.1.0_docs_examples_2048_2048_full.yaml} \\$

Restricting external IP addresses that can be assigned to services

Kubernetes services can be reached from inside of a cluster through:

- A cluster IP address that is assigned automatically by Kubernetes
- Any IP address that you specify for the externalIPs property in a service spec. External IP addresses are not managed by Kubernetes and are the responsibility of the cluster administrator. External IP addresses specified with externalIPs are different than the external IP address assigned to a service of type LoadBalancer by a cloud provider.

To learn more about Kubernetes services, see Service in the Kubernetes documentation. You can restrict the IP addresses that can be specified for externalIPs in a service spec.

To restrict the IP addresses that can be specified for externalIPs in a service spec

 Deploy cert-manager to manage webhook certificates. For more information, see the cert-manager documentation.

```
kubectl apply -f https://github.com/jetstack/cert-manager/releases/download/v1.1.0/
cert-manager.yaml
```

2. Verify that the cert-manager pods are running.

```
kubectl get pods -n cert-manager
```

Output

NAME	READY	STATUS	RESTARTS	AGE
cert-manager-58c8844bb8-nlx7q	1/1	Running	0	15s
cert-manager-cainjector-745768f6ff-696h5	1/1	Running	0	15s
cert-manager-webhook-67cc76975b-4v4nk	1/1	Running	0	14s

3. Review your existing services to ensure that none of them have external IP addresses assigned to them that aren't contained within the CIDR block you want to limit addresses to.

```
kubectl get services --all-namespaces
```

NAMESPACE		NAME		TYPE
CLUSTER-IP	EXTERNAL-IP	PORT(S)	AGE	
cert-manager		cert-manager		ClusterIP
10.100.102.137	<none></none>	9402/TCP	20m	
cert-manager		cert-manager-webho	ClusterIP	
10.100.6.136	<none></none>	443/TCP	20m	
default		kubernetes		ClusterIP
10.100.0.1	<none></none>	443/TCP	2d1h	
externalip-valida	tion-system	externalip-valida	tion-webhook-service	ClusterIP
10.100.234.179	<none></none>	443/TCP	16s	
kube-system		kube-dns		ClusterIP
10.100.0.10	<none></none>	53/UDP,53/TCP	2d1h	
my-namespace		my-service		ClusterIP
10.100.128.10	192.168.1.1	80/TCP	149m	

Amazon EKS User Guide Restrict service external IP address assignment

If any of the values are IP addresses that are not within the block you want to restrict access to, you'll need to change the addresses to be within the block, and redeploy the services. For example, the my-service service in the previous output has an external IP address assigned to it that isn't within the CIDR block example in step 5.

- 4. Download the external IP webhook manifest for the Region that your cluster is in. You can also view the source code for the webhook on GitHub.
 - All Regions except Beijing and Ningxia China Regions

```
curl -o externalip-webhook.yaml https://s3.us-west-2.amazonaws.com/amazon-eks/docs/
externalip-webhook.yaml
```

· Beijing and Ningxia China Regions

```
curl -o externalip-webhook.yaml https://s3.cn-north-1.amazonaws.com.cn/amazon-eks/
docs/externalip-webhook.yaml
```

5. Open the downloaded file in your editor and remove the # at the start of the following lines.

```
#args:
#- --allowed-external-ip-cidrs=10.0.0.0/8
```

Replace 10.0.0.0/8 with your own CIDR block. You can specify as many blocks as you like. If specifying mutiple blocks, add a comma between blocks.

6. If necessary, change the following address to a different address from the following table, depending on the Region your cluster is in, and then save the file.

image: 602401143452.dkr.ecr.us-west-2.amazonaws.com/externalip-webhook:v1.0.0

Region	Address
ZHY and BJS	961992271922.dkr.ecr.cn- northwest-1.amazonaws.com.cn/externalip- webhook:v1.0.0
HKG	800184023465.dkr.ecr.ap- east-1.amazonaws.com/externalip- webhook:v1.0.0
ВАН	558608220178.dkr.ecr.me- south-1.amazonaws.com/externalip- webhook:v1.0.0
СРТ	877085696533.dkr.ecr.af- south-1.amazonaws.com/externalip- webhook:v1.0.0
MXP	590381155156.dkr.ecr.eu- south-1.amazonaws.com/externalip- webhook:v1.0.0

Amazon EKS User Guide Restrict service external IP address assignment


7. Apply the manifest to your cluster.

kubectl apply -f externalip-webhook.yaml

An attempt to deploy a service to your cluster with an IP address specified for externalIPs that is not contained in the blocks that you specified in step 5 will fail.

Cluster authentication

Amazon EKS uses IAM to provide authentication to your Kubernetes cluster (through the aws eks gettoken command, available in version 1.16.156 or later of the AWS CLI, or the AWS IAM Authenticator for Kubernetes), but it still relies on native Kubernetes Role Based Access Control (RBAC) for authorization. This means that IAM is only used for authentication of valid IAM entities. All permissions for interacting with your Amazon EKS cluster's Kubernetes API is managed through the native Kubernetes RBAC system.



Topics

- Installing aws-iam-authenticator (p. 277)
- Create a kubeconfig for Amazon EKS (p. 281)
- Managing users or IAM roles for your cluster (p. 285)

Installing aws-iam-authenticator

Amazon EKS uses IAM to provide authentication to your Kubernetes cluster through the AWS IAM authenticator for Kubernetes. You can configure the stock kubectl client to work with Amazon EKS by installing the AWS IAM authenticator for Kubernetes and modifying your kubectl configuration file to use it for authentication.

Note

If you're running the AWS CLI version 1.16.156 or later, then you don't need to install the authenticator. Instead, you can use the aws eks get-token command. For more information, see Create kubeconfig manually (p. 283).

If you're unable to use the AWS CLI version 1.16.156 or later to create the kubeconfig file, then you can install the AWS IAM authenticator for Kubernetes on macOS (p. 278), Linux (p. 279), or Windows (p. 280).

To install aws-iam-authenticator with Homebrew

The easiest way to install the aws-iam-authenticator is with Homebrew.

1. If you do not already have Homebrew installed on your Mac, install it with the following command.

```
/bin/bash -c "$(curl -fsSL https://raw.githubusercontent.com/Homebrew/install/master/install.sh)"
```

2. Install the aws-iam-authenticator with the following command.

```
brew install aws-iam-authenticator
```

Test that the aws-iam-authenticator binary works.

```
aws-iam-authenticator help
```

To install aws-iam-authenticator on macOS

You can also install the AWS-vended version of the aws-iam-authenticator by following these steps.

- 1. Download the Amazon EKS vended aws-iam-authenticator binary from Amazon S3 using the command that corresponds to the Region that your cluster is in.
 - · All Regions other than China Regions.

```
curl -o aws-iam-authenticator https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/darwin/amd64/aws-iam-authenticator
```

· Beijing and Ningxia China Regions.

```
curl -o aws-iam-authenticator https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/darwin/amd64/aws-iam-authenticator
```

- 2. (Optional) Verify the downloaded binary with the SHA-256 sum provided in the same bucket prefix.
 - a. Download the SHA-256 sum for your system using the command that corresponds to the Region that your cluster is in.
 - · All Regions other than China Regions.

```
curl -o aws-iam-authenticator.sha256 https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/darwin/amd64/aws-iam-authenticator.sha256
```

• Beijing and Ningxia China Regions.

```
curl -o aws-iam-authenticator.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/darwin/amd64/aws-iam-authenticator.sha256
```

b. Check the SHA-256 sum for your downloaded binary.

```
openssl sha1 -sha256 aws-iam-authenticator
```

c. Compare the generated SHA-256 sum in the command output against your downloaded aws-iam-authenticator.sha256 file. The two should match.

Amazon EKS User Guide Installing aws-iam-authenticator

3. Apply execute permissions to the binary.

```
chmod +x ./aws-iam-authenticator
```

 Copy the binary to a folder in your \$PATH. We recommend creating a \$HOME/bin/aws-iamauthenticator and ensuring that \$HOME/bin comes first in your \$PATH.

mkdir -p \$HOME/bin && cp ./aws-iam-authenticator \$HOME/bin/aws-iam-authenticator &&
 export PATH=\$PATH:\$HOME/bin

5. Add \$HOME/bin to your PATH environment variable.

```
echo 'export PATH=$PATH:$HOME/bin' >> ~/.bash_profile
```

Test that the aws-iam-authenticator binary works.

```
aws-iam-authenticator help
```

To install aws-iam-authenticator on Linux

- 1. Download the Amazon EKS vended aws-iam-authenticator binary from Amazon S3 using the command that corresponds to the Region that your cluster is in. To download the Arm version, change amd64 to arm64 before running the command.
 - · All Regions other than China Regions.

```
curl -o aws-iam-authenticator https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/linux/amd64/aws-iam-authenticator
```

· Beijing and Ningxia China Regions.

```
curl -o aws-iam-authenticator https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/linux/amd64/aws-iam-authenticator
```

- 2. (Optional) Verify the downloaded binary with the SHA-256 sum provided in the same bucket prefix.
 - a. Download the SHA-256 sum for your system using the command that corresponds to the Region that your cluster is in. To download the Arm version, change <amd64> to arm64 before running the command.
 - · All Regions other than China Regions.

```
curl -o aws-iam-authenticator.sha256 https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/linux/amd64/aws-iam-authenticator.sha256
```

• Beijing and Ningxia China Regions.

```
curl -o aws-iam-authenticator.sha256 https://amazon-eks.s3.cn-
north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/linux/amd64/aws-iam-
authenticator.sha256
```

b. Check the SHA-256 sum for your downloaded binary.

```
openssl sha1 -sha256 aws-iam-authenticator
```

Amazon EKS User Guide Installing aws-iam-authenticator

- c. Compare the generated SHA-256 sum in the command output against your downloaded aws-iam-authenticator.sha256 file. The two should match.
- 3. Apply execute permissions to the binary.

```
chmod +x ./aws-iam-authenticator
```

 Copy the binary to a folder in your \$PATH. We recommend creating a \$HOME/bin/aws-iamauthenticator and ensuring that \$HOME/bin comes first in your \$PATH.

```
mkdir -p $HOME/bin && cp ./aws-iam-authenticator $HOME/bin/aws-iam-authenticator &&
    export PATH=$PATH:$HOME/bin
```

Add \$HOME/bin to your PATH environment variable.

```
echo 'export PATH=$PATH:$HOME/bin' >> ~/.bashrc
```

6. Test that the aws-iam-authenticator binary works.

```
aws-iam-authenticator help
```

To install aws-iam-authenticator on Windows with Chocolatey

- 1. If you do not already have Chocolatey installed on your Windows system, see Installing chocolatey.
- Open a PowerShell terminal window and install the aws-iam-authenticator package with the following command:

```
choco install -y aws-iam-authenticator
```

Test that the aws-iam-authenticator binary works.

```
aws-iam-authenticator help
```

To install aws-iam-authenticator on Windows

- Open a PowerShell terminal window and download the Amazon EKS vended aws-iamauthenticator binary from Amazon S3 using the command that corresponds to the Region that your cluster is in.
 - · All Regions other than China Regions.

```
curl -o aws-iam-authenticator.exe https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/windows/amd64/aws-iam-authenticator.exe
```

· Beijing and Ningxia China Regions.

```
curl -o aws-iam-authenticator.exe https://amazon-eks.s3.cn-
north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/windows/amd64/aws-iam-
authenticator.exe
```

- 2. (Optional) Verify the downloaded binary with the SHA-256 sum provided in the same bucket prefix.
 - a. Download the SHA-256 sum for your system using the command that corresponds to the Region that your cluster is in.

Amazon EKS User Guide Create a kubeconfig for Amazon EKS

· All Regions other than China Regions.

```
curl -o aws-iam-authenticator.sha256 https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/windows/amd64/aws-iam-authenticator.exe.sha256
```

Beijing and Ningxia China Regions.

```
curl -o aws-iam-authenticator.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/windows/amd64/aws-iam-authenticator.exe.sha256
```

b. Check the SHA-256 sum for your downloaded binary.

```
Get-FileHash aws-iam-authenticator.exe
```

- c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match, although the PowerShell output will be uppercase.
- 3. Copy the binary to a folder in your PATH. If you have an existing directory in your PATH that you use for command line utilities, copy the binary to that directory. Otherwise, complete the following steps.
 - a. Create a new directory for your command line binaries, such as C:\bin.
 - b. Copy the aws-iam-authenticator.exe binary to your new directory.
 - c. Edit your user or system PATH environment variable to add the new directory to your PATH.
 - d. Close your PowerShell terminal and open a new one to pick up the new PATH variable.
- 4. Test that the aws-iam-authenticator binary works.

```
aws-iam-authenticator help
```

If you have an existing Amazon EKS cluster, create a kubeconfig file for that cluster. For more information, see Create a kubeconfig for Amazon EKS (p. 281). Otherwise, see Creating an Amazon EKS cluster (p. 35) to create a new Amazon EKS cluster.

Create a kubeconfig for Amazon EKS

In this section, you create a kubeconfig file for your cluster (or update an existing one).

This section offers two procedures to create or update your kubeconfig. You can quickly create or update a kubeconfig with the AWS CLI update-kubeconfig command automatically by using the AWS CLI, or you can create a kubeconfig manually using the AWS CLI or the aws-iam-authenticator.

Amazon EKS uses the aws eks get-token command, available in version 1.16.156 or later of the AWS CLI or the AWS IAM Authenticator for Kubernetes with kubectl for cluster authentication. If you have installed the AWS CLI on your system, then by default the AWS IAM Authenticator for Kubernetes will use the same credentials that are returned with the following command:

```
aws sts get-caller-identity
```

For more information, see Configuring the AWS CLI in the AWS Command Line Interface User Guide.

Create kubeconfig automatically

To create your kubeconfig file with the AWS CLI

 Ensure that you have version 1.16.156 or later of the AWS CLI installed. To install or upgrade the AWS CLI, see Installing the AWS Command Line Interface in the AWS Command Line Interface User Guide.

Note

Your system's Python version must be 2.7.9 or later. Otherwise, you receive hostname doesn't match errors with AWS CLI calls to Amazon EKS.

You can check your AWS CLI version with the following command:

aws --version

Important

Package managers such yum, apt-get, or Homebrew for macOS are often behind several versions of the AWS CLI. To ensure that you have the latest version, see Installing the AWS Command Line Interface in the AWS Command Line Interface User Guide.

- Use the AWS CLI update-kubeconfig command to create or update your kubeconfig for your cluster.
 - By default, the resulting configuration file is created at the default kubeconfig path (.kube/config) in your home directory or merged with an existing kubeconfig at that location. You can specify another path with the --kubeconfig option.
 - You can specify an IAM role ARN with the --role-arn option to use for authentication when you issue kubectl commands. Otherwise, the IAM entity in your default AWS CLI or SDK credential chain is used. You can view your default AWS CLI or SDK identity by running the aws sts getcaller-identity command.
 - For more information, see the help page with the aws eks update-kubeconfig help command or see update-kubeconfig in the AWS CLI Command Reference.

Note

To run the following command, you must have permission to the use the eks:DescribeCluster API action with the cluster that you specify. For more information, see Amazon EKS identity-based policy examples (p. 322).

aws eks --region <region-code> update-kubeconfig --name <cluster_name>

3. Test your configuration.

kubectl get svc

Note

If you receive any authorization or resource type errors, see Unauthorized or access denied (kubectl) (p. 366) in the troubleshooting section.

Output:

NAME TYPE CLUSTER-IP EXTERNAL-IP PORT(S) AGE svc/kubernetes ClusterIP 10.100.0.1 <none> 443/TCP 1m

Create kubeconfig manually

To create your kubeconfig file manually

1. Create the default ~/.kube directory if it does not already exist.

```
mkdir -p ~/.kube
```

- Open your favorite text editor and copy one of the kubeconfig code blocks below into it, depending on your preferred client token method.
 - To use the AWS CLI aws eks get-token command (requires version 1.16.156 or later of the AWS CLI):

```
apiVersion: v1
clusters:
- cluster:
   server: <endpoint-url>
    certificate-authority-data: <base64-encoded-ca-cert>
 name: kubernetes
contexts:
- context:
   cluster: kubernetes
   user: aws
 name: aws
current-context: aws
kind: Config
preferences: {}
users:
- name: aws
 user:
     apiVersion: client.authentication.k8s.io/v1alpha1
     command: aws
      args:
       - "eks"
        - "get-token"
        - "--cluster-name"
        - "<cluster-name>"
       # - "--role"
        # - "<role-arn>"
      # env:
        # - name: AWS PROFILE
        # value: "<aws-profile>"
```

• To use the AWS IAM authenticator for Kubernetes:

```
apiVersion: v1
clusters:
    cluster:
    server: <endpoint-url>
        certificate-authority-data: <base64-encoded-ca-cert>
    name: kubernetes
contexts:
    context:
    cluster: kubernetes
    user: aws
    name: aws
current-context: aws
kind: Config
preferences: {}
users:
```

Amazon EKS User Guide Create kubeconfig manually

```
- name: aws
user:
    exec:
    apiVersion: client.authentication.k8s.io/v1alpha1
    command: aws-iam-authenticator
    args:
        - "token"
        - "-i"
        - "<cluster-name>"
        # - "-r"
        # - "<role-arn>"
# env:
    # - name: AWS_PROFILE
# value: "<aws-profile>"
```

- Replace the <endpoint-url> with the endpoint URL that was created for your cluster.
- 4. Replace the <base64-encoded-ca-cert> with the certificateAuthority.data that was created for your cluster.
- 5. Replace the <cluster-name> with your cluster name.
- 6. (Optional) To assume an IAM role to perform cluster operations instead of the default AWS credential provider chain, uncomment the -r or --role and <role-arn> lines and substitute an IAM role ARN to use with your user.
- 7. (Optional) To always use a specific named AWS credential profile (instead of the default AWS credential provider chain), uncomment the env lines and substitute <aws-profile> with the profile name to use.
- 8. Save the file to the default kubectl folder, with your cluster name in the file name. For example, if your cluster name is <devel>, save the file to ~/.kube/config-<devel>.
- 9. Add that file path to your KUBECONFIG environment variable so that kubectl knows where to look for your cluster configuration.
 - For Bash shells on macOS or Linux:

```
export KUBECONFIG=$KUBECONFIG:~/.kube/config-<devel>
```

· For PowerShell on Windows:

```
$ENV:KUBECONFIG="{0};{1}" -f $ENV:KUBECONFIG, "$ENV:userprofile\.kube\config-
<devel>"
```

- 10. (Optional) Add the configuration to your shell initialization file so that it is configured when you open a shell.
 - · For Bash shells on macOS:

```
echo 'export KUBECONFIG=$KUBECONFIG:~/.kube/config-<devel>' >> ~/.bash_profile
```

· For Bash shells on Linux:

```
echo 'export KUBECONFIG=$KUBECONFIG:~/.kube/config-<devel>' >> ~/.bashrc
```

· For PowerShell on Windows:

```
[System.Environment]::SetEnvironmentVariable('KUBECONFIG', $ENV:KUBECONFIG, 'Machine')
```

11. Test your configuration.

```
kubectl get svc
```

Note

If you receive any authorization or resource type errors, see Unauthorized or access denied (kubectl) (p. 366) in the troubleshooting section.

Output:

svc/kubernetes ClusterIP 10.100.0.1 <none> 443/TCP 1m</none>	NAME	TYPE	CLUSTER-IP	EXTERNAL-IP	PORT(S)	AGE
	svc/kubernetes	ClusterIP	10.100.0.1	<none></none>	443/TCP	1m

Managing users or IAM roles for your cluster

When you create an Amazon EKS cluster, the IAM entity user or role, such as a federated user that creates the cluster, is automatically granted system:masters permissions in the cluster's RBAC configuration in the control plane. This IAM entity does not appear in the ConfigMap, or any other visible configuration, so make sure to keep track of which IAM entity originally created the cluster. To grant additional AWS users or roles the ability to interact with your cluster, you must edit the aws-auth ConfigMap within Kubernetes.

Note

For more information about different IAM identities, see Identities (Users, Groups, and Roles) in the IAM User Guide. For more information on Kubernetes RBAC configuration, see Using RBAC Authorization. For all ConfigMap settings, see Full Configuration Format on GitHub.

The aws-auth ConfigMap is applied as part of the Getting started with Amazon EKS (p. 4) guide which provides a complete end-to-end walkthrough from creating an Amazon EKS cluster to deploying a sample Kubernetes application. It is initially created to allow your nodes to join your cluster, but you also use this ConfigMap to add RBAC access to IAM users and roles. If you have not launched nodes and applied the aws-auth ConfigMap, you can do so with the following procedure.

To apply the aws-auth ConfigMap to your cluster

1. Check to see if you have already applied the aws-auth ConfigMap.

```
kubectl describe configmap -n kube-system aws-auth
```

If you receive an error stating "Error from server (NotFound): configmaps "aws-auth" not found", then proceed with the following steps to apply the stock ConfigMap.

- 2. Download, edit, and apply the AWS authenticator configuration map.
 - Download the configuration map using the command that corresponds to the Region that your cluster is in.
 - All Regions other than China Regions.

```
curl -o aws-auth-cm.yaml https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/aws-auth-cm.yaml
```

· Beijing and Ningxia China Regions.

```
curl -o aws-auth-cm.yaml https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//
cloudformation/2020-10-29/aws-auth-cm.yaml
```

b. Open the file with your favorite text editor. Replace <ARN of instance role (not instance profile)> with the Amazon Resource Name (ARN) of the IAM role associated with your nodes, and save the file. Do not modify any other lines in this file.

Important

The role ARN cannot include a path. The format of the role ARN must be arn:aws:iam::<123456789012>:role/<role-name>. For more information, see aws-auth ConfigMap does not grant access to the cluster (p. 373).

You can inspect the AWS CloudFormation stack outputs for your worker node groups and look for the following values:

- InstanceRoleARN (for node groups that were created with eksctl)
- **NodeInstanceRole** (for node groups that were created with Amazon EKS vended AWS CloudFormation templates in the AWS Management Console)
- c. Apply the configuration. This command may take a few minutes to finish.

```
kubectl apply -f aws-auth-cm.yaml
```

Note

If you receive any authorization or resource type errors, see Unauthorized or access denied (kubectl) (p. 366) in the troubleshooting section.

3. Watch the status of your nodes and wait for them to reach the Ready status.

```
kubectl get nodes --watch
```

To add an IAM user or role to an Amazon EKS cluster

- 1. Ensure that the AWS credentials that kubectl is using are already authorized for your cluster. The IAM user that created the cluster has these permissions by default.
- 2. Open the aws-auth ConfigMap.

```
kubectl edit -n kube-system configmap/aws-auth
```

Note

If you receive an error stating "Error from server (NotFound): configmaps "awsauth" not found", then use the previous procedure to apply the stock ConfigMap.

Example ConfigMap:

```
apiVersion: v1
data:
```

- 3. Add your IAM users, roles, or AWS accounts to the configMap. You cannot add IAM groups to the configMap.
 - To add an IAM role (for example, for federated users): add the role details to the mapRoles section of the ConfigMap, under data. Add this section if it does not already exist in the file. Each entry supports the following parameters:
 - rolearn: The ARN of the IAM role to add.
 - username: The user name within Kubernetes to map to the IAM role.
 - groups: A list of groups within Kubernetes to which the role is mapped. For more information, see Default Roles and Role Bindings in the Kubernetes documentation.
 - To add an IAM user: add the user details to the mapUsers section of the ConfigMap, under data. Add this section if it does not already exist in the file. Each entry supports the following parameters:
 - userarn: The ARN of the IAM user to add.
 - username: The user name within Kubernetes to map to the IAM user.
 - **groups**: A list of groups within Kubernetes to which the user is mapped to. For more information, see Default Roles and Role Bindings in the Kubernetes documentation.

For example, the block below contains:

- A mapRoles section that adds the node instance role so that nodes can register themselves with the cluster.
- A mapUsers section with the AWS users admin from the default AWS account, and ops-user from another AWS account. Both users are added to the system:masters group.

Replace all <example-values> (including <>) with your own values.

- 4. Save the file and exit your text editor.
- 5. Ensure that the Kubernetes user or group that you mapped the IAM user or role to is bound to a Kubernetes role with a RoleBinding or CluserRoleBinding. For more information, see Using RBAC Authorization in the Kubernetes documentation. You can download the following example manifests that create a clusterrole and clusterrolebinding or a role and rolebinding:
 - View Kubernetes resources in all namespaces The group name in the file is eks-console-dashboard-full-access-group, which is the group that your IAM user or role needs to be mapped to in the aws-auth configmap. You can change the name of the group before applying it to your cluster, if desired, and then map your IAM user or role to that group in the configmap. To download the file, select the appropriate link for the Region that your cluster is in.
 - · All Regions other than Beijing and Ningxia China
 - · Beijing and Ningxia China Regions
 - View Kubernetes resources in a specific namespace The namespace in this file is default, so if you want to specify a different namespace, edit the file before applying it to your cluster. The group name in the file is eks-console-dashboard-restricted-access-group, which is the group that your IAM user or role needs to be mapped to in the aws-auth configmap. You can change the name of the group before applying it to your cluster, if desired, and then map your IAM user or role to that group in the configmap. To download the file, select the appropriate link for the Region that your cluster is in.
 - · All Regions other than Beijing and Ningxia China
 - Beijing and Ningxia China Regions
- 6. (Optional) If you want the users you've added to the configmap to be able to the section called "View nodes" (p. 98) or the section called "View workloads" (p. 246) in the AWS Management Console, then the user or role must have the appropriate permissions to view the resources in Kubernetes, but also need to have the appropriate IAM permissions to view those resources in the AWS Management Console. For more information, see the section called "View nodes and workloads for all clusters in the AWS Management Console" (p. 324).

Cluster management

This chapter includes the following topics to help you manage your cluster. You can also view information about your nodes (p. 98) and workloads (p. 246) using the AWS Management Console.

- Installing kubect1 (p. 289) Learn how to install kubect1; a command line tool for managing Kubernetes.
- The eksctl command line utility (p. 298) Learn how to install a simple command line utility for creating and managing Kubernetes clusters on Amazon EKS.
- Tutorial: Deploy the Kubernetes Dashboard (web UI) (p. 299) Learn how to install the dashboard, a web-based user interface for your Kubernetes cluster and applications.
- Installing the Kubernetes Metrics Server (p. 304) The Kubernetes Metrics Server is an aggregator of resource usage data in your cluster. It is not deployed by default in your cluster, but is used by Kubernetes add-ons, such as the Kubernetes Dashboard and Horizontal Pod Autoscaler (p. 257). In this topic you learn how to install the Metrics Server.
- Control plane metrics with Prometheus (p. 305) The Kubernetes API server exposes a number of metrics that are useful for monitoring and analysis. This topic explains how to deploy Prometheus and some of the ways that you can use it to view and analyze what your cluster is doing.
- Using Helm with Amazon EKS (p. 308) The Helm package manager for Kubernetes helps you install and manage applications on your Kubernetes cluster. This topic helps you install and run the Helm binaries so that you can install and manage charts using the Helm CLI on your local computer.
- Tagging your Amazon EKS resources (p. 309) To help you manage your Amazon EKS resources, you can assign your own metadata to each resource in the form of *tags*. This topic describes tags and shows you how to create them.
- Amazon EKS service quotas (p. 312) Your AWS account has default quotas, formerly referred to as limits, for each AWS service. Learn about the quotas for Amazon EKS and how to increase them.

Installing kubect1

Kubernetes uses a command line utility called kubectl for communicating with the cluster API server. The kubectl binary is available in many operating system package managers, and this option is often much easier than a manual download and install process. You can follow the instructions for your specific operating system or package manager in the Kubernetes documentation to install.

This topic helps you to download and install the Amazon EKS vended kubectl binaries for macOS (p. 289), Linux (p. 291), and Windows (p. 292) operating systems. These binaries are identical to the upstream community versions, and are not unique to Amazon EKS or AWS.

Note

You must use a kubectl version that is within one minor version difference of your Amazon EKS cluster control plane. For example, a 1.17 kubectl client should work with Kubernetes 1.16, 1.17 and 1.18 clusters.

All Regions except China (Ningxia) and China (Beijing)

To install kubectl if you're in a China Region, see the section called "China Regions" (p. 293).

[To install kubect1 on macOS]

 Download the Amazon EKS vended kubect1 binary for your cluster's Kubernetes version from Amazon S3:

• Kubernetes 1.18:

 $\verb|curl -o| kubectl | https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/darwin/amd64/kubectl|$

Kubernetes 1.17:

 $\verb|curl -o| kubectl | https://amazon-eks.s3.us-west-2.amazonaws.com/1.17.12/2020-11-02/bin/darwin/amd64/kubectl|$

• Kubernetes 1.16:

 $\verb|curl -o| kubectl https://amazon-eks.s3.us-west-2.amazonaws.com/1.16.15/2020-11-02/bin/darwin/amd64/kubectl|$

Kubernetes 1.15:

curl -o kubectl https://amazon-eks.s3.us-west-2.amazonaws.com/1.15.12/2020-11-02/bin/ darwin/amd64/kubectl

- 2. (Optional) Verify the downloaded binary with the SHA-256 sum for your binary.
 - a. Download the SHA-256 sum for your cluster's Kubernetes version for macOS:
 - Kubernetes 1.18:

```
curl -o kubectl.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.18.9/2020-11-02/bin/darwin/amd64/kubectl.sha256
```

Kubernetes 1.17:

```
curl -o kubectl.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.17.12/2020-11-02/bin/darwin/amd64/kubectl.sha256
```

• Kubernetes 1.16:

```
curl -o kubectl.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.16.15/2020-11-02/bin/darwin/amd64/kubectl.sha256
```

• Kubernetes 1.15:

```
curl -o kubectl.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.15.12/2020-11-02/bin/darwin/amd64/kubectl.sha256
```

b. Check the SHA-256 sum for your downloaded binary.

```
openssl sha1 -sha256 kubectl
```

- c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match.
- 3. Apply execute permissions to the binary.

```
chmod +x ./kubectl
```

4. Copy the binary to a folder in your PATH. If you have already installed a version of kubectl, then we recommend creating a \$HOME/bin/kubectl and ensuring that \$HOME/bin comes first in your \$PATH.

Amazon EKS User Guide All Regions except China (Ningxia) and China (Beijing)

mkdir -p \$HOME/bin && cp ./kubectl \$HOME/bin/kubectl && export PATH=\$PATH:\$HOME/bin

(Optional) Add the \$HOME/bin path to your shell initialization file so that it is configured when you open a shell.

```
echo 'export PATH=$PATH:$HOME/bin' >> ~/.bash_profile
```

6. After you install kubect1, you can verify its version with the following command:

```
kubectl version --short --client
```

[To install kubect1 on Linux]

- 1. Download the Amazon EKS vended kubectl binary for your cluster's Kubernetes version from Amazon S3. To download the Arm version, change amd64 to arm64 before running the command.
 - Kubernetes 1.18:

```
curl -o kubectl https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/linux/amd64/kubectl
```

• Kubernetes 1.17:

```
\verb|curl -o| kubectl https://amazon-eks.s3.us-west-2.amazonaws.com/1.17.12/2020-11-02/bin/linux/amd64/kubectl|
```

Kubernetes 1.16:

```
curl -o kubectl https://amazon-eks.s3.us-west-2.amazonaws.com/1.16.15/2020-11-02/bin/
linux/amd64/kubectl
```

• Kubernetes 1.15:

```
curl -o kubectl https://amazon-eks.s3.us-west-2.amazonaws.com/1.15.12/2020-11-02/bin/linux/amd64/kubectl
```

- 2. (Optional) Verify the downloaded binary with the SHA-256 sum for your binary.
 - a. Download the SHA-256 sum for your cluster's Kubernetes version for Linux. To download the Arm version, change <amd64> to arm64 before running the command.
 - Kubernetes 1.18:

```
curl -o kubectl.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.18.9/2020-11-02/bin/linux/amd64/kubectl.sha256
```

• Kubernetes 1.17:

```
curl -o kubectl.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.17.12/2020-11-02/bin/linux/amd64/kubectl.sha256
```

• Kubernetes 1.16:

```
curl -o kubectl.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.16.15/2020-11-02/bin/linux/amd64/kubectl.sha256
```

Amazon EKS User Guide All Regions except China (Ningxia) and China (Beijing)

Kubernetes 1.15:

```
curl -o kubectl.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.15.12/2020-11-02/bin/linux/amd64/kubectl.sha256
```

b. Check the SHA-256 sum for your downloaded binary.

```
openssl sha1 -sha256 kubectl
```

- c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match.
- 3. Apply execute permissions to the binary.

```
chmod +x ./kubectl
```

4. Copy the binary to a folder in your PATH. If you have already installed a version of kubectl, then we recommend creating a \$HOME/bin/kubectl and ensuring that \$HOME/bin comes first in your \$PATH.

```
mkdir -p $HOME/bin && cp ./kubectl $HOME/bin/kubectl && export PATH=$PATH:$HOME/bin
```

5. (Optional) Add the \$HOME/bin path to your shell initialization file so that it is configured when you open a shell.

Note

This step assumes you are using the Bash shell; if you are using another shell, change the command to use your specific shell initialization file.

```
echo 'export PATH=$PATH:$HOME/bin' >> ~/.bashrc
```

6. After you install kubect1, you can verify its version with the following command:

```
kubectl version --short --client
```

[To install kubectl on Windows]

- 1. Open a PowerShell terminal.
- Download the Amazon EKS vended kubect1 binary for your cluster's Kubernetes version from Amazon S3:
 - Kubernetes 1.18:

```
curl -o kubectl.exe https://amazon-eks.s3.us-west-2.amazonaws.com/1.18.9/2020-11-02/bin/windows/amd64/kubectl.exe
```

Kubernetes 1.17:

```
curl -o kubectl.exe https://amazon-eks.s3.us-west-2.amazonaws.com/1.17.12/2020-11-02/bin/windows/amd64/kubectl.exe
```

• Kubernetes 1.16:

```
curl -o kubectl.exe https://amazon-eks.s3.us-west-2.amazonaws.com/1.16.15/2020-11-02/bin/windows/amd64/kubectl.exe
```

• Kubernetes 1.15:

curl -o kubectl.exe https://amazon-eks.s3.us-west-2.amazonaws.com/1.15.12/2020-11-02/bin/windows/amd64/kubectl.exe

- 3. (Optional) Verify the downloaded binary with the SHA-256 sum for your binary.
 - a. Download the SHA-256 sum for your cluster's Kubernetes version for Windows:
 - Kubernetes 1.18:

```
curl -o kubectl.exe.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.18.9/2020-11-02/bin/windows/amd64/kubectl.exe.sha256
```

Kubernetes 1.17:

```
curl -o kubectl.exe.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.17.12/2020-11-02/bin/windows/amd64/kubectl.exe.sha256
```

Kubernetes 1.16:

```
curl -o kubectl.exe.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.16.15/2020-11-02/bin/windows/amd64/kubectl.exe.sha256
```

Kubernetes 1.15:

```
curl -o kubectl.exe.sha256 https://amazon-eks.s3.us-
west-2.amazonaws.com/1.15.12/2020-11-02/bin/windows/amd64/kubectl.exe.sha256
```

b. Check the SHA-256 sum for your downloaded binary.

```
Get-FileHash kubectl.exe
```

- c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match, although the PowerShell output will be uppercase.
- 4. Copy the binary to a folder in your PATH. If you have an existing directory in your PATH that you use for command line utilities, copy the binary to that directory. Otherwise, complete the following steps.
 - a. Create a new directory for your command line binaries, such as C:\bin.
 - b. Copy the kubectl.exe binary to your new directory.
 - c. Edit your user or system PATH environment variable to add the new directory to your PATH.
 - d. Close your PowerShell terminal and open a new one to pick up the new PATH variable.
- 5. After you install kubect1, you can verify its version with the following command:

```
kubectl version --short --client
```

China Regions

Complete these instructions if you're in the China (Beijing) or China (Ningxia) Region. To install kubectl if you're any any other Region, see the section called "All Regions except China (Ningxia) and China (Beijing)" (p. 289).

[To install kubect1 on macOS]

- Download the Amazon EKS vended kubect1 binary for your cluster's Kubernetes version from Amazon S3:
 - Kubernetes 1.18:

 $\verb|curl -o| kubectl | https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/darwin/amd64/kubectl|$

• Kubernetes 1.17:

 $\verb|curl -o| kubectl https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.17.12/2020-11-02/bin/darwin/amd64/kubectl|$

Kubernetes 1.16:

 $\verb|curl -o| kubectl https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.16.15/2020-11-02/bin/darwin/amd64/kubectl|$

• Kubernetes 1.15:

 $\verb|curl -o| kubectl https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.15.12/2020-11-02/bin/darwin/amd64/kubectl|$

- 2. (Optional) Verify the downloaded binary with the SHA-256 sum for your binary.
 - a. Download the SHA-256 sum for your cluster's Kubernetes version for macOS:
 - Kubernetes 1.18:

curl -o kubectl.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/darwin/amd64/kubectl.sha256

Kubernetes 1.17:

curl -o kubectl.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.17.12/2020-11-02/bin/darwin/amd64/kubectl.sha256

Kubernetes 1.16:

curl -o kubectl.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.16.15/2020-11-02/bin/darwin/amd64/kubectl.sha256

• Kubernetes 1.15:

curl -o kubectl.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.15.12/2020-11-02/bin/darwin/amd64/kubectl.sha256

b. Check the SHA-256 sum for your downloaded binary.

openssl sha1 -sha256 kubectl

- c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match.
- 3. Apply execute permissions to the binary.

chmod +x ./kubectl

4. Copy the binary to a folder in your PATH. If you have already installed a version of kubectl, then we recommend creating a \$HOME/bin/kubectl and ensuring that \$HOME/bin comes first in your \$PATH.

mkdir -p \$HOME/bin && cp ./kubectl \$HOME/bin/kubectl && export PATH=\$PATH:\$HOME/bin

(Optional) Add the \$HOME/bin path to your shell initialization file so that it is configured when you open a shell.

echo 'export PATH=\$PATH:\$HOME/bin' >> ~/.bash_profile

6. After you install kubect1, you can verify its version with the following command:

kubectl version --short --client

[To install kubect1 on Linux]

- Download the Amazon EKS vended kubectl binary for your cluster's Kubernetes version from Amazon S3. To download the Arm version, change amd64 to arm64 before running the command.
 - Kubernetes 1.18:

curl -o kubectl https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/ bin/linux/amd64/kubectl

Kubernetes 1.17:

curl -o kubectl https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.17.12/2020-11-02/ bin/linux/amd64/kubectl

• Kubernetes 1.16:

curl -o kubectl https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.16.15/2020-11-02/bin/linux/amd64/kubectl

Kubernetes 1.15:

curl -o kubectl https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.15.12/2020-11-02/bin/linux/amd64/kubectl

- 2. (Optional) Verify the downloaded binary with the SHA-256 sum for your binary.
 - a. Download the SHA-256 sum for your cluster's Kubernetes version for Linux. To download the Arm version, change <amd64> to arm64 before running the command.
 - Kubernetes 1.18:

curl -o kubectl.sha256 https://amazon-eks.s3.cnnorth-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/linux/amd64/kubectl.sha256

• Kubernetes 1.17:

curl -o kubectl.sha256 https://amazon-eks.s3.cnnorth-1.amazonaws.com.cn/1.17.12/2020-11-02/bin/linux/amd64/kubectl.sha256

Kubernetes 1.16:

```
curl -o kubectl.sha256 https://amazon-eks.s3.cn-
north-1.amazonaws.com.cn/1.16.15/2020-11-02/bin/linux/amd64/kubectl.sha256
```

Kubernetes 1.15:

```
curl -o kubectl.sha256 https://amazon-eks.s3.cn-
north-1.amazonaws.com.cn/1.15.12/2020-11-02/bin/linux/amd64/kubectl.sha256
```

b. Check the SHA-256 sum for your downloaded binary.

```
openssl sha1 -sha256 kubectl
```

- c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match.
- 3. Apply execute permissions to the binary.

```
chmod +x ./kubectl
```

Copy the binary to a folder in your PATH. If you have already installed a version of kubectl, then
we recommend creating a \$HOME/bin/kubectl and ensuring that \$HOME/bin comes first in your
\$PATH.

```
mkdir -p $HOME/bin && cp ./kubectl $HOME/bin/kubectl && export PATH=$PATH:$HOME/bin
```

5. (Optional) Add the \$HOME/bin path to your shell initialization file so that it is configured when you open a shell.

Note

This step assumes you are using the Bash shell; if you are using another shell, change the command to use your specific shell initialization file.

```
echo 'export PATH=$PATH:$HOME/bin' >> ~/.bashrc
```

6. After you install kubect1 , you can verify its version with the following command:

```
kubectl version --short --client
```

[To install kubectl on Windows]

- 1. Open a PowerShell terminal.
- Download the Amazon EKS vended kubect1 binary for your cluster's Kubernetes version from Amazon S3:
 - Kubernetes 1.18:

```
curl -o kubectl.exe https://amazon-eks.s3.cn-
north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/windows/amd64/kubectl.exe
```

Kubernetes 1.17:

```
curl -o kubectl.exe https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.17.12/2020-11-02/bin/windows/amd64/kubectl.exe
```

Kubernetes 1.16:

```
curl -o kubectl.exe https://amazon-eks.s3.cn-
north-1.amazonaws.com.cn/1.16.15/2020-11-02/bin/windows/amd64/kubectl.exe
```

• Kubernetes 1.15:

```
curl -o kubectl.exe https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.15.12/2020-11-02/bin/windows/amd64/kubectl.exe
```

- 3. (Optional) Verify the downloaded binary with the SHA-256 sum for your binary.
 - a. Download the SHA-256 sum for your cluster's Kubernetes version for Windows:
 - Kubernetes 1.18:

```
curl -o kubectl.exe.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.18.9/2020-11-02/bin/windows/amd64/kubectl.exe.sha256
```

Kubernetes 1.17:

```
curl -o kubectl.exe.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.17.12/2020-11-02/bin/windows/amd64/kubectl.exe.sha256
```

• Kubernetes 1.16:

```
curl -o kubectl.exe.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.16.15/2020-11-02/bin/windows/amd64/kubectl.exe.sha256
```

Kubernetes 1.15:

```
curl -o kubectl.exe.sha256 https://amazon-eks.s3.cn-north-1.amazonaws.com.cn/1.15.12/2020-11-02/bin/windows/amd64/kubectl.exe.sha256
```

b. Check the SHA-256 sum for your downloaded binary.

```
Get-FileHash kubectl.exe
```

- c. Compare the generated SHA-256 sum in the command output against your downloaded SHA-256 file. The two should match, although the PowerShell output will be uppercase.
- 4. Copy the binary to a folder in your PATH. If you have an existing directory in your PATH that you use for command line utilities, copy the binary to that directory. Otherwise, complete the following steps.
 - a. Create a new directory for your command line binaries, such as C:\bin.
 - b. Copy the kubectl.exe binary to your new directory.
 - c. Edit your user or system PATH environment variable to add the new directory to your PATH.
 - d. Close your PowerShell terminal and open a new one to pick up the new PATH variable.
- 5. After you install kubect1, you can verify its version with the following command:

```
kubectl version --short --client
```

The eksctl command line utility

This topic covers <code>eksctl</code>, a simple command line utility for creating and managing Kubernetes clusters on Amazon EKS. The <code>eksctl</code> command line utility provides the fastest and easiest way to create a new cluster with nodes for Amazon EKS.

For more information and to see the official documentation, visit https://eksctl.io/.

Installing or upgrading eksctl

This section helps you to install or upgrade the latest version of the eksctl command line utility.

You can install eksct1 on macOS (p. 298), Linux (p. 298), or Windows (p. 299).

[To install or upgrade eksctl on macOS using Homebrew]

The easiest way to get started with Amazon EKS and macOS is by installing eksct1 with Homebrew. The eksct1 Homebrew recipe installs eksct1 and any other dependencies that are required for Amazon EKS, such as kubect1. The recipe also installs the aws-iam-authenticator (p. 277), which is required if you don't have the AWS CLI version 1.16.156 or higher installed.

1. If you do not already have Homebrew installed on macOS, install it with the following command.

```
/bin/bash -c "$(curl -fsSL https://raw.githubusercontent.com/Homebrew/install/master/install.sh)"
```

2. Install the Weaveworks Homebrew tap.

brew tap weaveworks/tap

- Install or upgrade eksctl.
 - Install eksct1 with the following command:

```
brew install weaveworks/tap/eksctl
```

If eksctl is already installed, run the following command to upgrade:

```
brew upgrade eksctl && brew link --overwrite eksctl
```

4. Test that your installation was successful with the following command.

eksctl version

Note

The GitTag version should be at least 0.33.0. If not, check your terminal output for any installation or upgrade errors, or manually download an archive of the release from https://github.com/weaveworks/eksctl/releases/download/0.33.0/eksctl_Darwin_amd64.tar.gz, extract eksctl, and then execute it.

[To install or upgrade eksctl on Linux using curl]

1. Download and extract the latest release of eksctl with the following command.

Amazon EKS User Guide Tutorial: Deploy Kubernetes Dashboard

curl --silent --location "https://github.com/weaveworks/eksctl/releases/latest/
download/eksctl_\$(uname -s)_amd64.tar.gz" | tar xz -C /tmp

2. Move the extracted binary to /usr/local/bin.

sudo mv /tmp/eksctl /usr/local/bin

3. Test that your installation was successful with the following command.

eksctl version

Note

The GitTag version should be at least 0.33.0. If not, check your terminal output for any installation or upgrade errors, or replace the address in step 1 with https://github.com/weaveworks/eksctl/releases/download/0.33.0/eksctl_Linux_amd64.tar.gz and complete steps 1-3 again.

[To install or upgrade eksctl on Windows using Chocolatey]

- 1. If you do not already have Chocolatey installed on your Windows system, see Installing Chocolatey.
- 2. Install or upgrade eksctl.
 - Install the binaries with the following command:

choco install -y eksctl

• If they are already installed, run the following command to upgrade:

choco upgrade -y eksctl

3. Test that your installation was successful with the following command.


eksctl version

Note

The GitTag version should be at least 0.33.0. If not, check your terminal output for any installation or upgrade errors, or manually download an archive of the release from https://github.com/weaveworks/eksctl/releases/download/0.33.0/eksctl_Windows_amd64.zip, extract eksctl. and then execute it.

Tutorial: Deploy the Kubernetes Dashboard (web UI)

This tutorial guides you through deploying the Kubernetes Dashboard to your Amazon EKS cluster, complete with CPU and memory metrics. It also helps you to create an Amazon EKS administrator service account that you can use to securely connect to the dashboard to view and control your cluster.



Prerequisites

This tutorial assumes the following:

- You have created an Amazon EKS cluster by following the steps in Getting started with Amazon EKS (p. 4).
- The security groups for your control plane elastic network interfaces and nodes follow the recommended settings in Amazon EKS security group considerations (p. 204).
- You are using a kubectl client that is configured to communicate with your Amazon EKS cluster (p. 27).

Step 1: Deploy the Kubernetes Metrics Server

The Kubernetes Metrics Server is an aggregator of resource usage data in your cluster, and it is not deployed by default in Amazon EKS clusters. The Kubernetes Dashboard uses the metrics server to gather metrics for your cluster, such as CPU and memory usage over time.

To deploy the Metrics Server

1. Deploy the Metrics Server with the following command:

kubectl apply -f https://github.com/kubernetes-sigs/metrics-server/releases/download/v0.3.7/components.yaml

Verify that the metrics-server deployment is running the desired number of pods with the following command.

kubectl get deployment metrics-server -n kube-system

Output

Amazon EKS User Guide Step 2: Deploy the Kubernetes dashboard

```
NAME READY UP-TO-DATE AVAILABLE AGE metrics-server 1/1 1 1 6m
```

Step 2: Deploy the Kubernetes dashboard

Complete the instructions for the option that corresponds to the Region that your cluster is in.

All Regions other than Beijing and Ningxia China

```
kubectl apply -f https://raw.githubusercontent.com/kubernetes/dashboard/v2.0.5/aio/
deploy/recommended.yaml
```

- · Beijing and Ningxia China
 - 1. Download the Kubernetes Dashboard manifest with the following command.

```
curl -o recommended.yaml https://raw.githubusercontent.com/kubernetes/dashboard/v2.0.5/aio/deploy/recommended.yaml
```

- 2. Edit the manifest files using the following steps.
 - a. View the manifest file or files that you downloaded and note the name of the image. Download the image locally with the following command.

```
docker pull image:<tag>
```

b. Tag the image to be pushed to an Amazon Elastic Container Registry repository in China with the following command.

```
docker tag image:<tag> <aws_account_id>.dkr.ecr.<cn-north-1>.amazonaws.com/
image:<tag>
```

c. Push the image to a China Amazon ECR repository with the following command.

```
docker push image:<tag> <aws_account_id>.dkr.ecr.<cn-north-1>.amazonaws.com/
image:<tag>
```

- d. Update the Kubernetes manifest file or files to reference the Amazon ECR image URL in your region.
- 3. Apply the manifest to your cluster with the following command.

```
kubectl apply -f recommended.yaml
```

Output:

```
namespace/kubernetes-dashboard created
serviceaccount/kubernetes-dashboard created
service/kubernetes-dashboard created
secret/kubernetes-dashboard-certs created
secret/kubernetes-dashboard-csrf created
secret/kubernetes-dashboard-key-holder created
configmap/kubernetes-dashboard-settings created
role.rbac.authorization.k8s.io/kubernetes-dashboard created
clusterrole.rbac.authorization.k8s.io/kubernetes-dashboard created
rolebinding.rbac.authorization.k8s.io/kubernetes-dashboard created
clusterrolebinding.rbac.authorization.k8s.io/kubernetes-dashboard created
```

Amazon EKS User Guide Step 3: Create an eks-admin service account and cluster role binding

```
deployment.apps/kubernetes-dashboard created
service/dashboard-metrics-scraper created
deployment.apps/dashboard-metrics-scraper created
```

Step 3: Create an eks-admin service account and cluster role binding

By default, the Kubernetes Dashboard user has limited permissions. In this section, you create an eks-admin service account and cluster role binding that you can use to securely connect to the dashboard with admin-level permissions. For more information, see Managing Service Accounts in the Kubernetes documentation.

To create the eks-admin service account and cluster role binding

Important

The example service account created with this procedure has full cluster-admin (superuser) privileges on the cluster. For more information, see Using RBAC authorization in the Kubernetes documentation.

1. Create a file called eks-admin-service-account.yaml with the text below. This manifest defines a service account and cluster role binding called eks-admin.

```
apiVersion: v1
kind: ServiceAccount
metadata:
 name: eks-admin
 namespace: kube-system
apiVersion: rbac.authorization.k8s.io/v1beta1
kind: ClusterRoleBinding
metadata:
  name: eks-admin
roleRef:
  apiGroup: rbac.authorization.k8s.io
  kind: ClusterRole
 name: cluster-admin
subjects:
- kind: ServiceAccount
  name: eks-admin
  namespace: kube-system
```

2. Apply the service account and cluster role binding to your cluster.

```
kubectl apply -f eks-admin-service-account.yaml
```

Output:

```
serviceaccount "eks-admin" created clusterrolebinding.rbac.authorization.k8s.io "eks-admin" created
```

Step 4: Connect to the dashboard

Now that the Kubernetes Dashboard is deployed to your cluster, and you have an administrator service account that you can use to view and control your cluster, you can connect to the dashboard with that service account.

To connect to the Kubernetes dashboard

1. Retrieve an authentication token for the eks-admin service account. Copy the <authentication_token> value from the output. You use this token to connect to the dashboard.

```
kubectl -n kube-system describe secret (kubectl -n kube-system get secret | grep eks-admin | awk '<math>\{print $1\}')
```

Output:

Name: eks-admin-token-b5zv4

Namespace: kube-system Labels: <none>

Annotations: kubernetes.io/service-account.name=eks-admin

kubernetes.io/service-account.uid=bcfe66ac-39be-11e8-97e8-026dce96b6e8

Type: kubernetes.io/service-account-token

Data ====


ca.crt: 1025 bytes
namespace: 11 bytes

token: <authentication_token>

2. Start the kubectl proxy.

kubectl proxy

- To access the dashboard endpoint, open the following link with a web browser: http:// localhost:8001/api/v1/namespaces/kubernetes-dashboard/services/https:kubernetes-dashboard:/ proxy/#!/login.
- 4. Choose **Token**, paste the <authentication_token> output from the previous command into the **Token** field, and choose **SIGN IN**.



Note

It may take a few minutes before CPU and memory metrics appear in the dashboard.

Step 5: Next steps

After you have connected to your Kubernetes Dashboard, you can view and control your cluster using your eks-admin service account. For more information about using the dashboard, see the project documentation on GitHub.

Installing the Kubernetes Metrics Server

The Kubernetes Metrics Server is an aggregator of resource usage data in your cluster, and it is not deployed by default in Amazon EKS clusters. The Metrics Server is commonly used by other Kubernetes add ons, such as the Horizontal Pod Autoscaler (p. 257) or the Kubernetes Dashboard (p. 299). For more information, see Resource metrics pipeline in the Kubernetes documentation. This topic explains how to deploy the Kubernetes Metrics Server on your Amazon EKS cluster.

To deploy the Metrics Server

1. Deploy the Metrics Server with the following command:

kubectl apply -f https://github.com/kubernetes-sigs/metrics-server/releases/download/v0.3.7/components.yaml

Verify that the metrics-server deployment is running the desired number of pods with the following command.

Amazon EKS User Guide Prometheus metrics

```
kubectl get deployment metrics-server -n kube-system
```

Output

```
NAME READY UP-TO-DATE AVAILABLE AGE metrics-server 1/1 1 1 6m
```

Control plane metrics with Prometheus

The Kubernetes API server exposes a number of metrics that are useful for monitoring and analysis. These metrics are exposed internally through a metrics endpoint that refers to the /metrics HTTP API. Like other endpoints, this endpoint is exposed on the Amazon EKS control plane. This topic explains some of the ways you can use this endpoint to view and analyze what your cluster is doing.

Viewing the raw metrics

To view the raw metrics output, use kubect1 with the --raw flag. This command allows you to pass any HTTP path and returns the raw response.

```
kubectl get --raw /metrics
```

Example output:

```
# HELP rest_client_requests_total Number of HTTP requests, partitioned by status code,
method, and host.
# TYPE rest_client_requests_total counter
rest_client_requests_total{code="200",host="127.0.0.1:21362",method="POST"} 4994
rest_client_requests_total{code="200",host="127.0.0.1:443",method="DELETE"} 1
rest_client_requests_total{code="200",host="127.0.0.1:443",method="GET"} 1.326086e+06
rest client requests total{code="200",host="127.0.0.1:443",method="PUT"} 862173
rest_client_requests_total{code="404",host="127.0.0.1:443",method="GET"} 2
rest_client_requests_total{code="409",host="127.0.0.1:443",method="POST"} 3
rest_client_requests_total{code="409",host="127.0.0.1:443",method="PUT"} 8
# HELP ssh_tunnel_open_count Counter of ssh tunnel total open attempts
# TYPE ssh_tunnel_open_count counter
ssh tunnel open count 0
# HELP ssh_tunnel_open_fail_count Counter of ssh tunnel failed open attempts
# TYPE ssh_tunnel_open_fail_count counter
ssh_tunnel_open_fail_count 0
```

This raw output returns verbatim what the API server exposes. These metrics are represented in a Prometheus format. This format allows the API server to expose different metrics broken down by line. Each line includes a metric name, tags, and a value.

```
<metric_name>{"<tag>"="<value>"[<,...>]} <value>
```

While this endpoint is useful if you are looking for a specific metric, you typically want to analyze these metrics over time. To do this, you can deploy Prometheus into your cluster. Prometheus is a monitoring and time series database that scrapes exposed endpoints and aggregates data, allowing you to filter, graph, and query the results.

Deploying Prometheus

This topic helps you deploy Prometheus into your cluster with Helm V3. If you already have Helm installed, you can check your version with the helm version command. Helm is a package manager for Kubernetes clusters. For more information about Helm and how to install it, see Using Helm with Amazon EKS (p. 308).

After you configure Helm for your Amazon EKS cluster, you can use it to deploy Prometheus with the following steps.

To deploy Prometheus using Helm

1. Create a Prometheus namespace.

```
kubectl create namespace prometheus
```

2. Deploy Prometheus.

```
helm install prometheus prometheus-community/prometheus \
--namespace prometheus \
--set
alertmanager.persistentVolume.storageClass="gp2",server.persistentVolume.storageClass="gp2"
```

Note

If you get the error Error: failed to download "stable/prometheus" (hint: running `helm repo update` may help) when executing this command, run helm repo update, and then try running the Step 2 command again. If you get the error Error: rendered manifests contain a resource that already exists, run helm uninstall your-release-name -n namespace, then try running the Step 2 command again.

3. Verify that all of the pods in the prometheus namespace are in the READY state.

```
kubectl get pods -n prometheus
```


Output:

NAME	READY	STATUS	RESTARTS	AGE
prometheus-alertmanager-59b4c8c744-r7bgp	1/2	Running	0	48s
prometheus-kube-state-metrics-7cfd87cf99-jkz2f	1/1	Running	0	48s
prometheus-node-exporter-jcjqz	1/1	Running	0	48s
prometheus-node-exporter-jxv2h	1/1	Running	0	48s
prometheus-node-exporter-vbdks	1/1	Running	0	48s
prometheus-pushgateway-76c444b68c-82tnw	1/1	Running	0	48s
prometheus-server-775957f748-mmht9	1/2	Running	0	48s


4. Use kubectl to port forward the Prometheus console to your local machine.

```
kubectl --namespace=prometheus port-forward deploy/prometheus-server 9090
```

- 5. Point a web browser to localhost:9090 to view the Prometheus console.
- 6. Choose a metric from the **insert metric at cursor** menu, then choose **Execute**. Choose the **Graph** tab to show the metric over time. The following image shows container_memory_usage_bytes over time.



7. From the top navigation bar, choose **Status**, then **Targets**.



Amazon EKS User Guide Using Helm

All of the Kubernetes endpoints that are connected to Prometheus using service discovery are displayed.

Using Helm with Amazon EKS

The Helm package manager for Kubernetes helps you install and manage applications on your Kubernetes cluster. For more information, see the Helm documentation. This topic helps you install and run the Helm binaries so that you can install and manage charts using the Helm CLI on your local system.

Important

Before you can install Helm charts on your Amazon EKS cluster, you must configure kubectl to work for Amazon EKS. If you have not already done this, see Create a kubeconfig for Amazon EKS (p. 281) before proceeding. If the following command succeeds for your cluster, you're properly configured.

```
kubectl get svc
```

To install the Helm binaries on your local system

- 1. Run the appropriate command for your client operating system.
 - If you're using macOS with Homebrew, install the binaries with the following command.

```
brew install helm
```

• If you're using Windows with Chocolatey, install the binaries with the following command.

```
choco install kubernetes-helm
```

• If you're using Linux, install the binaries with the following commands.

```
curl https://raw.githubusercontent.com/helm/helm/master/scripts/get-helm-3 >
  get_helm.sh
chmod 700 get_helm.sh
./get_helm.sh
```

- 2. To pick up the new binary in your PATH, Close your current terminal window and open a new one.
- 3. Confirm that Helm is running with the following command.

```
helm help
```

- 4. At this point, you can run any Helm commands (such as helm install <chart_name>) to install, modify, delete, or query Helm charts in your cluster. If you're new to Helm and don't have a specific chart to install, you can:
 - Experiment by installing an example chart. See Install an example chart in the Helm Quickstart guide.
 - Create an example chart and push it to Amazon ECR. For more information, see Pushing a Helm chart in the Amazon Elastic Container Registry User Guide.
 - Install an Amazon EKS chart from the eks-charts GitHub repo or from ArtifactHub.

Tagging your Amazon EKS resources

To help you manage your Amazon EKS resources, you can assign your own metadata to each resource using *tags*. This topic provides an overview of the tags function and shows how you can create tags.

Contents

- Tag basics (p. 309)
- Tagging your resources (p. 309)
- Tag restrictions (p. 310)
- Working with tags using the console (p. 310)
- Working with tags using the CLI, API, or eksctl (p. 311)

Tag basics

A tag is a label that you assign to an AWS resource. Each tag consists of a *key* and an optional *value*, both of which you define.

Tags enable you to categorize your AWS resources by, for example, purpose, owner, or environment. When you have many resources of the same type, you can quickly identify a specific resource based on the tags you've assigned to it. For example, you can define a set of tags for your Amazon EKS clusters to help you track each cluster's owner and stack level. We recommend that you devise a consistent set of tag keys for each resource type. You can then search and filter the resources based on the tags that you add.

Tags are not automatically assigned to your resources. After you add a tag, you can edit tag keys and values or remove tags from a resource at any time. If you delete a resource, any tags for the resource are also deleted.

Tags don't have any semantic meaning to Amazon EKS and are interpreted strictly as a string of characters. You can set the value of a tag to an empty string, but you can't set the value of a tag to null. If you add a tag that has the same key as an existing tag on that resource, the new value overwrites the earlier value.

You can tag new or existing cluster resources using the AWS Management Console, the AWS CLI, or the Amazon EKS API. You can tag only new cluster resources using eksctl.

If you use AWS Identity and Access Management (IAM), you can control which users in your AWS account have permission to manage tags.

Tagging your resources

You can tag new or existing Amazon EKS clusters and managed node groups.

If you're using the Amazon EKS console, then you can apply tags to new or existing resources at any time. You can do this by using the **Tags** tab on the relevant resource page. If you're using eksctl, then you can apply tags to resources when they are created using the --tags option.

If you're using the Amazon EKS API, the AWS CLI, or an AWS SDK, you can apply tags to new resources using the tags parameter on the relevant API action. You can apply tags to existing resources using the TagResource API action. For more information, see TagResource.

Some resource-creating actions enable you to specify tags for a resource when the resource is created. If tags cannot be applied while a resource is being created, the resource fails to be created. This mechanism

Amazon EKS User Guide Tag restrictions

ensures that resources you intended to tag on creation are either created with specified tags or not created at all. If you tag resources at the time of creation, you don't need to run custom tagging scripts after creating a resource.

The following table describes the Amazon EKS resources that can be tagged and the resources that can be tagged on creation.

Tagging support for Amazon EKS resources

Resource	Supports tags	Supports tag propagation	Supports tagging on creation (Amazon EKS API, AWS CLI, AWS SDK, and eksct1)
Amazon EKS clusters	Yes	No. Cluster tags do not propagate to any other resources associated with the cluster.	Yes
Amazon EKS managed node groups	Yes	No. Managed node group tags do not propagate to any other resources associated with the node group.	Yes
Amazon EKS Fargate profiles	Yes	No. Fargate profile tags do not propagate to any other resources associated with the Fargate profile, such as the pods that are scheduled with it.	Yes

Tag restrictions

The following basic restrictions apply to tags:

- Maximum number of tags per resource 50
- For each resource, each tag key must be unique, and each tag key can have only one value.
- Maximum key length 128 Unicode characters in UTF-8
- Maximum value length 256 Unicode characters in UTF-8
- If your tagging schema is used across multiple AWS services and resources, remember that other services may have restrictions on allowed characters. Generally allowed characters are letters, numbers, spaces representable in UTF-8, and the following characters: + = . _ : / @.
- · Tag keys and values are case sensitive.
- Don't use aws:, AWS:, or any upper or lowercase combination of such as a prefix for either keys or values. These are reserved only for AWS use. You can't edit or delete tag keys or values with this prefix. Tags with this prefix do not count against your tags-per-resource limit.

Working with tags using the console

Using the Amazon EKS console, you can manage the tags associated with new or existing clusters and managed node groups.

When you select a resource-specific page in the Amazon EKS console, it displays a list of those resources. For example, if you select **Clusters** from the navigation panel, the console displays a list of Amazon EKS clusters. When you select a resource from one of these lists (for example, a specific cluster) that supports tags, you can view and manage its tags on the **Tags** tab.

Adding tags on an individual resource on creation

You can add tags to Amazon EKS clusters, managed node groups, and Fargate profiles when you create them. For more information, see Creating an Amazon EKS cluster (p. 35).

Adding and deleting tags on an individual resource

Amazon EKS allows you to add or delete tags associated with your clusters directly from the resource's page.

To add or delete a tag on an individual resource

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. From the navigation bar, select the Region to use.
- 3. In the navigation panel, choose Clusters.
- 4. Choose a specific cluster. Select the **Configuration** tab. On the **Tags** tab, choose **Manage tags**.
- 5. On the **Update tags** page, add or delete your tags as necessary.
 - To add a tag choose **Add tag** and then specify the key and value for each tag.
 - To delete a tag choose Remove tag.
- 6. Repeat this process for each tag you want to add or delete, and then choose **Update** to finish.

Working with tags using the CLI, API, or eksctl

Use the following AWS CLI commands or Amazon EKS API operations to add, update, list, and delete the tags for your resources. You can only use eksctl to add tags to new resources.

Tagging support for Amazon EKS resources

Task	AWS CLI	AWS Tools for Windows PowerShell	API action
Add or overwrite one or more tags.	tag-resource	Add-EKSResourceTag	TagResource
Delete one or more tags.	untag-resource	Remove-EKSResourceTag	UntagResource

The following examples show how to tag or untag resources using the AWS CLI.

Example 1: Tag an existing cluster

The following command tags an existing cluster.

aws eks tag-resource --resource-arn <resource_ARN> --tags <team>=<devs>

Example 2: Untag an existing cluster

Amazon EKS User Guide Service guotas

The following command deletes a tag from an existing cluster.

```
aws eks untag-resource --resource-arn <resource_ARN> --tag-keys <tag_key>
```

Example 3: List tags for a resource

The following command lists the tags associated with an existing resource.

```
aws eks list-tags-for-resource --resource-arn <resource_ARN>
```

Some resource-creating actions enable you to specify tags when you create the resource. The following actions support tagging when creating a resource.

Task	AWS CLI	AWS Tools for Windows PowerShell	API action	eksctl
Create a cluster	create- cluster	New-EKSCluster	CreateClust	create cluster
Create a managed node group*	create- nodegroup	New-EKSNodegroup	CreateNodeg	r cre ate nodegroup
Create a Fargate profile	create- fargate- profile	New- EKSFargateProfile	CreateFarga	t ereate le.htm fargateprofi

*If you want to also tag the Amazon EC2 instances when creating a managed node group, create the managed node group using a launch template. For more information, see the section called "Tagging Amazon EC2 instances" (p. 113). If your instances already exist, you can manually tag the instances. For more information, see Tagging your resources in the Amazon EC2 User Guide for Linux Instances.

Amazon EKS service quotas

Amazon EKS has integrated with Service Quotas, an AWS service that enables you to view and manage your quotas from a central location. For more information, see What Is Service Quotas? in the Service Quotas User Guide. Service Quotas makes it easy to look up the value of your Amazon EKS and AWS Fargate service guotas using the AWS Management Console and AWS CLI.

To view Amazon EKS and Fargate service quotas using the AWS Management Console

- 1. Open the Service Quotas console at https://console.aws.amazon.com/servicequotas/.
- 2. In the navigation panel, choose AWS services.
- 3. From the AWS services list, search for and select Amazon Elastic Kubernetes Service (Amazon EKS) or AWS Fargate.

In the **Service quotas** list, you can see the service quota name, applied value (if it is available), AWS default quota, and whether the quota value is adjustable.

- 4. To view additional information about a service quota, such as the description, choose the quota name.
- (Optional) To request a quota increase, select the quota that you want to increase, select Request quota increase, enter or select the required information, and select Request.

Amazon EKS User Guide Service guotas

To work more with service quotas using the AWS Management Console see the Service Quotas User Guide. To request a quota increase, see Requesting a Quota Increase in the Service Quotas User Guide.

To view Amazon EKS and Fargate service quotas using the AWS CLI

Run the following command to view your Amazon EKS quotas.

```
aws service-quotas list-aws-default-service-quotas \
    --query 'Quotas[*].{Adjustable:Adjustable,Name:QuotaName,Value:Value,Code:QuotaCode}' \
     --service-code eks \
     --output table
```

Run the following command to view your Fargate quotas.

```
aws service-quotas list-aws-default-service-quotas \
    --query 'Quotas[*].{Adjustable:Adjustable,Name:QuotaName,Value:Value,Code:QuotaCode}' \
     --service-code fargate \
     --output table
```

Note

The quota returned is the maximum number of Amazon ECS tasks or Amazon EKS pods running concurrently on Fargate in this account in the current Region.

To work more with service quotas using the AWS CLI, see the Service Quotas AWS CLI Command Reference. To request a quota increase, see the request-service-quota-increase command in the AWS CLI Command Reference.

The following tables provide the default quotas (also referred to as limits) for Amazon EKS and AWS Fargate for an AWS account.

Amazon EKS service quotas

The following quotas are Amazon EKS service quotas. Most of these service quotas are listed under the Amazon Elastic Kubernetes Service (Amazon EKS) namespace in the Service Quotas console. To request a quota increase, see Requesting a quota increase in the Service Quotas User Guide.

Service quota	Description	Default quota value	Adjustable
Clusters	The maximum number of EKS clusters in this account in the current Region.	100	Yes
Control plane security groups per cluster	The maximum number of control plane security groups per cluster (these are specified when you create the cluster).	4	No
Managed node groups per cluster	The maximum number of managed node groups per cluster.	30	Yes
Nodes per managed node group	The maximum number of nodes per managed node group.	450	Yes

Amazon EKS User Guide Service quotas

Service quota	Description	Default quota value	Adjustable
Public endpoint access CIDR ranges per cluster	The maximum number of public endpoint access CIDR ranges per cluster (these are specified when you create or update the cluster).	40	No
Fargate profiles per cluster	The maximum number Fargate profiles per cluster.	10	Yes
Selectors per Fargate profile	The maximum number selectors per Fargate profile	5	Yes
Label pairs per Fargate profile selector	The maximum number of label pairs per Fargate profile selector	5	Yes

AWS Fargate service quotas

The following quota is an Amazon EKS on AWS Fargate service quota. The service quota is listed under the AWS Fargate namespace in the Service Quotas console. To request a quota increase, see Requesting a quota increase in the Service Quotas User Guide.

Service quota	Description	Default quota value	Adjustable
Fargate On-Demand resource count	The maximum number of Amazon ECS tasks and Amazon EKS pods running concurrently on Fargate in this account in the current Region.	500	Yes

Security in Amazon EKS

Cloud security at AWS is the highest priority. As an AWS customer, you benefit from a data center and network architecture that is built to meet the requirements of the most security-sensitive organizations.

Security is a shared responsibility between AWS and you. The shared responsibility model describes this as security *of* the cloud and security *in* the cloud:

- Security of the cloud AWS is responsible for protecting the infrastructure that runs AWS services in the AWS Cloud. For Amazon EKS, AWS is responsible for the Kubernetes control plane, which includes the control plane nodes and etcd database. Third-party auditors regularly test and verify the effectiveness of our security as part of the AWS compliance programs. To learn about the compliance programs that apply to Amazon EKS, see AWS Services in Scope by Compliance Program.
- **Security in the cloud** Your responsibility includes the following areas.
 - The security configuration of the data plane, including the configuration of the security groups that allow traffic to pass from the Amazon EKS control plane into the customer VPC
 - The configuration of the nodes and the containers themselves
 - The node's operating system (including updates and security patches)
 - Other associated application software:
 - Setting up and managing network controls, such as firewall rules
 - · Managing platform-level identity and access management, either with or in addition to IAM
 - The sensitivity of your data, your company's requirements, and applicable laws and regulations

This documentation helps you understand how to apply the shared responsibility model when using Amazon EKS. The following topics show you how to configure Amazon EKS to meet your security and compliance objectives. You also learn how to use other AWS services that help you to monitor and secure your Amazon EKS resources.

Note

Linux containers are made up of control groups (cgroups) and namespaces that help limit what a container can access, but all containers share the same Linux kernel as the host Amazon EC2 instance. Running a container as the root user (UID 0) or granting a container access to host resources or namespaces such as the host network or host PID namespace are strongly discouraged, because doing so reduces the effectiveness of the isolation that containers provide.

Topics

- Identity and access management for Amazon EKS (p. 315)
- Logging and monitoring in Amazon EKS (p. 346)
- Compliance validation for Amazon EKS (p. 347)
- Resilience in Amazon EKS (p. 347)
- Infrastructure security in Amazon EKS (p. 348)
- Configuration and vulnerability analysis in Amazon EKS (p. 349)
- Amazon EKS security best practices (p. 349)
- Pod security policy (p. 353)

Identity and access management for Amazon EKS

AWS Identity and Access Management (IAM) is an AWS service that helps an administrator securely control access to AWS resources. IAM administrators control who can be *authenticated* (signed in) and

Amazon EKS User Guide Audience

authorized (have permissions) to use Amazon EKS resources. IAM is an AWS service that you can use with no additional charge.

Audience

How you use AWS Identity and Access Management (IAM) differs, depending on the work that you do in Amazon EKS.

Service user – If you use the Amazon EKS service to do your job, then your administrator provides you with the credentials and permissions that you need. As you use more Amazon EKS features to do your work, you might need additional permissions. Understanding how access is managed can help you request the right permissions from your administrator. If you cannot access a feature in Amazon EKS, see Troubleshooting Amazon EKS identity and access (p. 346).

Service administrator – If you're in charge of Amazon EKS resources at your company, you probably have full access to Amazon EKS. It's your job to determine which Amazon EKS features and resources your employees should access. You must then submit requests to your IAM administrator to change the permissions of your service users. Review the information on this page to understand the basic concepts of IAM. To learn more about how your company can use IAM with Amazon EKS, see How Amazon EKS works with IAM (p. 319).

IAM administrator – If you're an IAM administrator, you might want to learn details about how you can write policies to manage access to Amazon EKS. To view example Amazon EKS identity-based policies that you can use in IAM, see Amazon EKS identity-based policy examples (p. 322).

Authenticating with identities

Authentication is how you sign in to AWS using your identity credentials. For more information about signing in using the AWS Management Console, see Signing in to the AWS Management Console as an IAM user or root user in the IAM User Guide.

You must be *authenticated* (signed in to AWS) as the AWS account root user, an IAM user, or by assuming an IAM role. You can also use your company's single sign-on authentication or even sign in using Google or Facebook. In these cases, your administrator previously set up identity federation using IAM roles. When you access AWS using credentials from another company, you are assuming a role indirectly.

To sign in directly to the AWS Management Console, use your password with your root user email address or your IAM user name. You can access AWS programmatically using your root user or IAM users access keys. AWS provides SDK and command line tools to cryptographically sign your request using your credentials. If you don't use AWS tools, you must sign the request yourself. Do this using Signature Version 4, a protocol for authenticating inbound API requests. For more information about authenticating requests, see Signature Version 4 signing process in the AWS General Reference.

Regardless of the authentication method that you use, you might also be required to provide additional security information. For example, AWS recommends that you use multi-factor authentication (MFA) to increase the security of your account. To learn more, see Using multi-factor authentication (MFA) in AWS in the IAM User Guide.

AWS account root user

When you first create an AWS account, you begin with a single sign-in identity that has complete access to all AWS services and resources in the account. This identity is called the AWS account *root user* and is accessed by signing in with the email address and password that you used to create the account. We strongly recommend that you do not use the root user for your everyday tasks, even the administrative ones. Instead, adhere to the best practice of using the root user only to create your first IAM user. Then securely lock away the root user credentials and use them to perform only a few account and service management tasks.

IAM users and groups

An *IAM user* is an identity within your AWS account that has specific permissions for a single person or application. An IAM user can have long-term credentials such as a user name and password or a set of access keys. To learn how to generate access keys, see Managing access keys for IAM users in the *IAM User Guide*. When you generate access keys for an IAM user, make sure you view and securely save the key pair. You cannot recover the secret access key in the future. Instead, you must generate a new access key pair.

An *IAM group* is an identity that specifies a collection of IAM users. You can't sign in as a group. You can use groups to specify permissions for multiple users at a time. Groups make permissions easier to manage for large sets of users. For example, you could have a group named *IAMAdmins* and give that group permissions to administer IAM resources.

Users are different from roles. A user is uniquely associated with one person or application, but a role is intended to be assumable by anyone who needs it. Users have permanent long-term credentials, but roles provide temporary credentials. To learn more, see When to create an IAM user (instead of a role) in the IAM User Guide.

IAM roles

An *IAM role* is an identity within your AWS account that has specific permissions. It is similar to an IAM user, but is not associated with a specific person. You can temporarily assume an IAM role in the AWS Management Console by switching roles. You can assume a role by calling an AWS CLI or AWS API operation or by using a custom URL. For more information about methods for using roles, see Using IAM roles in the *IAM User Guide*.

IAM roles with temporary credentials are useful in the following situations:

- **Temporary IAM user permissions** An IAM user can assume an IAM role to temporarily take on different permissions for a specific task.
- Federated user access Instead of creating an IAM user, you can use existing identities from AWS
 Directory Service, your enterprise user directory, or a web identity provider. These are known as
 federated users. AWS assigns a role to a federated user when access is requested through an identity
 provider. For more information about federated users, see Federated users and roles in the IAM User
 Guide.
- Cross-account access You can use an IAM role to allow someone (a trusted principal) in a different account to access resources in your account. Roles are the primary way to grant cross-account access. However, with some AWS services, you can attach a policy directly to a resource (instead of using a role as a proxy). To learn the difference between roles and resource-based policies for cross-account access, see How IAM roles differ from resource-based policies in the IAM User Guide.
- Cross-service access Some AWS services use features in other AWS services. For example, when you make a call in a service, it's common for that service to run applications in Amazon EC2 or store objects in Amazon S3. A service might do this using the calling principal's permissions, using a service role, or using a service-linked role.
 - Principal permissions When you use an IAM user or role to perform actions in AWS, you are
 considered a principal. Policies grant permissions to a principal. When you use some services, you
 might perform an action that then triggers another action in a different service. In this case, you
 must have permissions to perform both actions. To see whether an action requires additional
 dependent actions in a policy, see Actions, Resources, and Condition Keys for Amazon Elastic
 Kubernetes Service in the Service Authorization Reference.
 - Service role A service role is an IAM role that a service assumes to perform actions on your behalf.
 Service roles provide access only within your account and cannot be used to grant access to services in other accounts. An IAM administrator can create, modify, and delete a service role from within IAM. For more information, see Creating a role to delegate permissions to an AWS service in the IAM User Guide.

Amazon EKS User Guide Managing access using policies

- Service-linked role A service-linked role is a type of service role that is linked to an AWS service. The service can assume the role to perform an action on your behalf. Service-linked roles appear in your IAM account and are owned by the service. An IAM administrator can view, but not edit the permissions for service-linked roles.
- Applications running on Amazon EC2 You can use an IAM role to manage temporary credentials
 for applications that are running on an EC2 instance and making AWS CLI or AWS API requests.
 This is preferable to storing access keys within the EC2 instance. To assign an AWS role to an EC2
 instance and make it available to all of its applications, you create an instance profile that is attached
 to the instance. An instance profile contains the role and enables programs that are running on the
 EC2 instance to get temporary credentials. For more information, see Using an IAM role to grant
 permissions to applications running on Amazon EC2 instances in the IAM User Guide.

To learn whether to use IAM roles or IAM users, see When to create an IAM role (instead of a user) in the IAM User Guide.

Managing access using policies

You control access in AWS by creating policies and attaching them to IAM identities or AWS resources. A policy is an object in AWS that, when associated with an identity or resource, defines their permissions. You can sign in as the root user or an IAM user, or you can assume an IAM role. When you then make a request, AWS evaluates the related identity-based or resource-based policies. Permissions in the policies determine whether the request is allowed or denied. Most policies are stored in AWS as JSON documents. For more information about the structure and contents of JSON policy documents, see Overview of JSON policies in the IAM User Guide.

Administrators can use AWS JSON policies to specify who has access to what. That is, which **principal** can perform **actions** on what **resources**, and under what **conditions**.

Every IAM entity (user or role) starts with no permissions. In other words, by default, users can do nothing, not even change their own password. To give a user permission to do something, an administrator must attach a permissions policy to a user. Or the administrator can add the user to a group that has the intended permissions. When an administrator gives permissions to a group, all users in that group are granted those permissions.

IAM policies define permissions for an action regardless of the method that you use to perform the operation. For example, suppose that you have a policy that allows the iam: GetRole action. A user with that policy can get role information from the AWS Management Console, the AWS CLI, or the AWS API.

Identity-based policies

Identity-based policies are JSON permissions policy documents that you can attach to an identity, such as an IAM user, group of users, or role. These policies control what actions users and roles can perform, on which resources, and under what conditions. To learn how to create an identity-based policy, see Creating IAM policies in the IAM User Guide.

Identity-based policies can be further categorized as *inline policies* or *managed policies*. Inline policies are embedded directly into a single user, group, or role. Managed policies are standalone policies that you can attach to multiple users, groups, and roles in your AWS account. Managed policies include AWS managed policies and customer managed policies. To learn how to choose between a managed policy or an inline policy, see Choosing between managed policies and inline policies in the *IAM User Guide*.

Resource-based policies

Resource-based policies are JSON policy documents that you attach to a resource. Examples of resource-based policies are IAM *role trust policies* and Amazon S3 *bucket policies*. In services that support resource-based policies, service administrators can use them to control access to a specific resource. For the

Amazon EKS User Guide How Amazon EKS works with IAM

resource where the policy is attached, the policy defines what actions a specified principal can perform on that resource and under what conditions. You must specify a principal in a resource-based policy. Principals can include accounts, users, roles, federated users, or AWS services.

Resource-based policies are inline policies that are located in that service. You can't use AWS managed policies from IAM in a resource-based policy.

Access control lists (ACLs)

Access control lists (ACLs) control which principals (account members, users, or roles) have permissions to access a resource. ACLs are similar to resource-based policies, although they do not use the JSON policy document format.

Amazon S3, AWS WAF, and Amazon VPC are examples of services that support ACLs. To learn more about ACLs, see Access control list (ACL) overview in the Amazon Simple Storage Service Developer Guide.

Other policy types

AWS supports additional, less-common policy types. These policy types can set the maximum permissions granted to you by the more common policy types.

- Permissions boundaries A permissions boundary is an advanced feature in which you set the
 maximum permissions that an identity-based policy can grant to an IAM entity (IAM user or role).
 You can set a permissions boundary for an entity. The resulting permissions are the intersection of
 entity's identity-based policies and its permissions boundaries. Resource-based policies that specify
 the user or role in the Principal field are not limited by the permissions boundary. An explicit deny
 in any of these policies overrides the allow. For more information about permissions boundaries, see
 Permissions boundaries for IAM entities in the IAM User Guide.
- Service control policies (SCPs) SCPs are JSON policies that specify the maximum permissions for
 an organization or organizational unit (OU) in AWS Organizations. AWS Organizations is a service for
 grouping and centrally managing multiple AWS accounts that your business owns. If you enable all
 features in an organization, then you can apply service control policies (SCPs) to any or all of your
 accounts. The SCP limits permissions for entities in member accounts, including each AWS account
 root user. For more information about Organizations and SCPs, see How SCPs work in the AWS
 Organizations User Guide.
- Session policies Session policies are advanced policies that you pass as a parameter when you programmatically create a temporary session for a role or federated user. The resulting session's permissions are the intersection of the user or role's identity-based policies and the session policies. Permissions can also come from a resource-based policy. An explicit deny in any of these policies overrides the allow. For more information, see Session policies in the IAM User Guide.

Multiple policy types

When multiple types of policies apply to a request, the resulting permissions are more complicated to understand. To learn how AWS determines whether to allow a request when multiple policy types are involved, see Policy evaluation logic in the *IAM User Guide*.

How Amazon EKS works with IAM

Before you use IAM to manage access to Amazon EKS, you should understand what IAM features are available to use with Amazon EKS. To get a high-level view of how Amazon EKS and other AWS services work with IAM, see AWS services that work with IAM in the IAM User Guide.

Topics

Amazon EKS identity-based policies (p. 320)

Amazon EKS User Guide How Amazon EKS works with IAM

- Amazon EKS resource-based policies (p. 321)
- Authorization based on Amazon EKS tags (p. 321)
- Amazon EKS IAM roles (p. 322)

Amazon EKS identity-based policies

With IAM identity-based policies, you can specify allowed or denied actions and resources as well as the conditions under which actions are allowed or denied. Amazon EKS supports specific actions, resources, and condition keys. To learn about all of the elements that you use in a JSON policy, see IAM JSON policy elements reference in the IAM User Guide.

Actions

Administrators can use AWS JSON policies to specify who has access to what. That is, which **principal** can perform **actions** on what **resources**, and under what **conditions**.

The Action element of a JSON policy describes the actions that you can use to allow or deny access in a policy. Policy actions usually have the same name as the associated AWS API operation. There are some exceptions, such as *permission-only actions* that don't have a matching API operation. There are also some operations that require multiple actions in a policy. These additional actions are called *dependent actions*.

Include actions in a policy to grant permissions to perform the associated operation.

Policy actions in Amazon EKS use the following prefix before the action: eks:. For example, to grant someone permission to get descriptive information about an Amazon EKS cluster, you include the DescribeCluster action in their policy. Policy statements must include either an Action or NotAction element.

To specify multiple actions in a single statement, separate them with commas as follows:

```
"Action": ["eks:<action1>", "eks:<action2>"]
```

You can specify multiple actions using wildcards (*). For example, to specify all actions that begin with the word Describe, include the following action:

```
"Action": "eks:Describe*"
```

To see a list of Amazon EKS actions, see Actions Defined by Amazon Elastic Kubernetes Service in the IAM User Guide.

Resources

Administrators can use AWS JSON policies to specify who has access to what. That is, which **principal** can perform **actions** on what **resources**, and under what **conditions**.

The Resource JSON policy element specifies the object or objects to which the action applies. Statements must include either a Resource or a NotResource element. As a best practice, specify a resource using its Amazon Resource Name (ARN). You can do this for actions that support a specific resource type, known as resource-level permissions.

For actions that don't support resource-level permissions, such as listing operations, use a wildcard (*) to indicate that the statement applies to all resources.

```
"Resource": "*"
```

Amazon EKS User Guide How Amazon EKS works with IAM

The Amazon EKS cluster resource has the following ARN:

```
arn: ${Partition}: eks: ${Region}: ${Account}: cluster/${ClusterName}
```

For more information about the format of ARNs, see Amazon resource names (ARNs) and AWS service namespaces.

For example, to specify the dev cluster in your statement, use the following ARN:

```
"Resource": "arn:aws:eks:<region-code>:123456789012:cluster/dev"
```

To specify all clusters that belong to a specific account and Region, use the wildcard (*):

```
"Resource": "arn:aws:eks:<region-code>:123456789012:cluster/*"
```

Some Amazon EKS actions, such as those for creating resources, cannot be performed on a specific resource. In those cases, you must use the wildcard (*).

```
"Resource": "*"
```

To see a list of Amazon EKS resource types and their ARNs, see Resources Defined by Amazon Elastic Kubernetes Service in the *IAM User Guide*. To learn with which actions you can specify the ARN of each resource, see Actions Defined by Amazon Elastic Kubernetes Service.

Condition keys

Amazon EKS does not provide any service-specific condition keys, but it does support using some global condition keys. To see all AWS global condition keys, see AWS global condition context keys in the IAM User Guide.

Examples

To view examples of Amazon EKS identity-based policies, see Amazon EKS identity-based policy examples (p. 322).

When you create an Amazon EKS cluster, the IAM entity user or role, such as a federated user that creates the cluster, is automatically granted <code>system:masters</code> permissions in the cluster's RBAC configuration in the control plane. This IAM entity does not appear in the ConfigMap, or any other visible configuration, so make sure to keep track of which IAM entity originally created the cluster. To grant additional AWS users or roles the ability to interact with your cluster, you must edit the <code>aws-auth</code> ConfigMap within Kubernetes.

For additional information about working with the ConfigMap, see Managing users or IAM roles for your cluster (p. 285).

Amazon EKS resource-based policies

Amazon EKS does not support resource-based policies.

Authorization based on Amazon EKS tags

You can attach tags to Amazon EKS resources or pass tags in a request to Amazon EKS. To control access based on tags, you provide tag information in the condition element of a policy using the eks:ResourceTag/<key-name>, aws:RequestTag/<key-name>, or aws:TagKeys condition

Amazon EKS User Guide Identity-based policy examples

keys. For more information about tagging Amazon EKS resources, see Tagging your Amazon EKS resources (p. 309).

Amazon EKS IAM roles

An IAM role is an entity within your AWS account that has specific permissions.

Using temporary credentials with Amazon EKS

You can use temporary credentials to sign in with federation, assume an IAM role, or to assume a cross-account role. You obtain temporary security credentials by calling AWS STS API operations such as AssumeRole or GetFederationToken.

Amazon EKS supports using temporary credentials.

Service-linked roles

Service-linked roles allow AWS services to access resources in other services to complete an action on your behalf. Service-linked roles appear in your IAM account and are owned by the service. An IAM administrator can view but not edit the permissions for service-linked roles.

Amazon EKS supports service-linked roles. For details about creating or managing Amazon EKS service-linked roles, see Using Service-Linked Roles for Amazon EKS (p. 326).

Service roles

This feature allows a service to assume a service role on your behalf. This role allows the service to access resources in other services to complete an action on your behalf. Service roles appear in your IAM account and are owned by the account. This means that an IAM administrator can change the permissions for this role. However, doing so might break the functionality of the service.

Amazon EKS supports service roles. For more information, see Amazon EKS cluster IAM role (p. 330) and Amazon EKS node IAM role (p. 332).

Choosing an IAM role in Amazon EKS

When you create a cluster resource in Amazon EKS, you must choose a role to allow Amazon EKS to access several other AWS resources on your behalf. If you have previously created a service role, then Amazon EKS provides you with a list of roles to choose from. It's important to choose a role that has the Amazon EKS managed policies attached to it. For more information, see Check for an existing cluster role (p. 330) and Check for an existing node role (p. 332).

Amazon EKS identity-based policy examples

By default, IAM users and roles don't have permission to create or modify Amazon EKS resources. They also can't perform tasks using the AWS Management Console, AWS CLI, or AWS API. An IAM administrator must create IAM policies that grant users and roles permission to perform specific API operations on the specified resources they need. The administrator must then attach those policies to the IAM users or groups that require those permissions.

To learn how to create an IAM identity-based policy using these example JSON policy documents, see Creating policies on the JSON tab in the *IAM User Guide*.

When you create an Amazon EKS cluster, the IAM entity user or role, such as a federated user that creates the cluster, is automatically granted system:masters permissions in the cluster's RBAC configuration in the control plane. This IAM entity does not appear in the ConfigMap, or any other visible configuration, so make sure to keep track of which IAM entity originally created the cluster. To grant additional AWS users or roles the ability to interact with your cluster, you must edit the aws-auth ConfigMap within Kubernetes.

Amazon EKS User Guide Identity-based policy examples

For additional information about working with the ConfigMap, see Managing users or IAM roles for your cluster (p. 285).

Topics

- Policy best practices (p. 323)
- Using the Amazon EKS console (p. 323)
- View nodes and workloads for all clusters in the AWS Management Console (p. 324)
- Allow users to view their own permissions (p. 325)
- Update a Kubernetes cluster (p. 326)
- List or describe all clusters (p. 326)

Policy best practices

Identity-based policies are very powerful. They determine whether someone can create, access, or delete Amazon EKS resources in your account. These actions can incur costs for your AWS account. When you create or edit identity-based policies, follow these guidelines and recommendations:

- Get started using AWS managed policies To start using Amazon EKS quickly, use AWS managed
 policies to give your employees the permissions they need. These policies are already available in
 your account and are maintained and updated by AWS. For more information, see Get started using
 permissions with AWS managed policies in the IAM User Guide.
- **Grant least privilege** When you create custom policies, grant only the permissions required to perform a task. Start with a minimum set of permissions and grant additional permissions as necessary. Doing so is more secure than starting with permissions that are too lenient and then trying to tighten them later. For more information, see **Grant least privilege** in the *IAM User Guide*.
- Enable MFA for sensitive operations For extra security, require IAM users to use multi-factor authentication (MFA) to access sensitive resources or API operations. For more information, see Using multi-factor authentication (MFA) in AWS in the IAM User Guide.
- Use policy conditions for extra security To the extent that it's practical, define the conditions under
 which your identity-based policies allow access to a resource. For example, you can write conditions to
 specify a range of allowable IP addresses that a request must come from. You can also write conditions
 to allow requests only within a specified date or time range, or to require the use of SSL or MFA. For
 more information, see IAM JSON policy elements: Condition in the IAM User Guide.

Using the Amazon EKS console

To access the Amazon EKS console, you must have a minimum set of permissions. These permissions must allow you to list and view details about the Amazon EKS resources in your AWS account. If you create an identity-based policy that is more restrictive than the minimum required permissions, the console won't function as intended for entities (IAM users or roles) with that policy.

Important

If you see an **Error loading Namespaces** error in the console, or don't see anything on the **Overview** or **Workloads** tabs, see Can't see workloads or nodes and receive an error in the AWS Management Console (p. 372) to resolve the issue. If you don't resolve the issue, you can still view and manage aspects of your Amazon EKS cluster on the **Configuration** tab.

To ensure that those entities can still use the Amazon EKS console, create a policy with your own unique name, such as AmazonEKSAdminPolicy. Attach the policy to the entities. For more information, see Adding permissions to a user in the IAM User Guide.

Important

The following example policy will allow you to view information on the **Configuration** tab in the console. To view information on the **Nodes** and **Workloads** in the AWS Management Console, you need additional IAM permissions, as well as Kubernetes permissions. For more information,

see the the section called "View nodes and workloads for all clusters in the AWS Management Console" (p. 324) example policy.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "eks:*"
            "Resource": "*"
        },
            "Effect": "Allow",
            "Action": "iam:PassRole",
            "Resource": "*",
            "Condition": {
                "StringEquals": {
                     "iam:PassedToService": "eks.amazonaws.com"
            }
        }
    ]
}
```

You don't need to allow minimum console permissions for users that are making calls only to the AWS CLI or the AWS API. Instead, allow access to only the actions that match the API operation that you're trying to perform.

View nodes and workloads for all clusters in the AWS Management Console

This example shows how you can create a policy that allows a user to the section called "View nodes" (p. 98) and the section called "View workloads" (p. 246) for all clusters.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "eks:DescribeNodegroup",
                "eks:ListNodegroups",
                "eks:DescribeCluster",
                "eks:ListClusters",
                "eks:AccessKubernetesApi",
                "ssm:GetParameter",
                "eks:ListUpdates",
                "eks:ListFargateProfiles"
            "Resource": "*"
        }
   ]
}
```

Important

The policy must be attached to a user or role that is mapped to a Kubernetes user or group in the aws-auth configmap. The user or group must be a subject in a rolebinding or clusterrolebinding that is bound to a Kubernetes role or clusterrole that has the necessary permissions to view the Kubernetes resources. For more information about adding

IAM users or roles to the aws-auth configmap, see the section called "Managing users or IAM roles for your cluster" (p. 285). To create roles and role bindings, see Using RBAC Authorization in the Kubernetes documentation. You can download the following example manifests that create a clusterrole and clusterrolebinding or a role and rolebinding:

- View Kubernetes resources in all namespaces The group name in the file is eks-console-dashboard-full-access-group, which is the group that your IAM user or role needs to be mapped to in the aws-auth configmap. You can change the name of the group before applying it to your cluster, if desired, and then map your IAM user or role to that group in the configmap. To download the file, select the appropriate link for the Region that your cluster is in.
 - · All Regions other than Beijing and Ningxia China
 - · Beijing and Ningxia China Regions
- View Kubernetes resources in a specific namespace The namespace in this file is default, so if you want to specify a different namespace, edit the file before applying it to your cluster. The group name in the file is eks-console-dashboard-restricted-access-group, which is the group that your IAM user or role needs to be mapped to in the aws-auth configmap. You can change the name of the group before applying it to your cluster, if desired, and then map your IAM user or role to that group in the configmap. To download the file, select the appropriate link for the Region that your cluster is in.
 - · All Regions other than Beijing and Ningxia China
 - · Beijing and Ningxia China Regions

Allow users to view their own permissions

This example shows how you might create a policy that allows IAM users to view the inline and managed policies that are attached to their user identity. This policy includes permissions to complete this action on the console or programmatically using the AWS CLI or AWS API.

```
{
    "Version": "2012-10-17",
    "Statement": [
            "Sid": "ViewOwnUserInfo",
            "Effect": "Allow",
            "Action": [
                "iam:GetUserPolicy",
                "iam:ListGroupsForUser",
                "iam:ListAttachedUserPolicies",
                "iam:ListUserPolicies",
                "iam:GetUser"
            "Resource": ["arn:aws:iam::*:user/${aws:username}"]
            "Sid": "NavigateInConsole",
            "Effect": "Allow",
            "Action": [
                "iam:GetGroupPolicy",
                "iam:GetPolicyVersion",
                "iam:GetPolicy",
                "iam:ListAttachedGroupPolicies",
                "iam:ListGroupPolicies",
                "iam:ListPolicyVersions",
                "iam:ListPolicies",
                "iam:ListUsers"
            "Resource": "*"
```

```
}
```

Update a Kubernetes cluster

This example shows how you can create a policy that allows a user to update the Kubernetes version of any *dev* cluster for an account, in any region.

List or describe all clusters

This example shows how you can create a policy that allows a user read-only access to list or describe all clusters. An account must be able to list and describe clusters to use the update-kubeconfig AWS CLI command.

Using Service-Linked Roles for Amazon EKS

Amazon Elastic Kubernetes Service uses AWS Identity and Access Management (IAM) service-linked roles. A service-linked role is a unique type of IAM role that is linked directly to Amazon EKS. Service-linked roles are predefined by Amazon EKS and include all the permissions that the service requires to call other AWS services on your behalf.

Topics

- Using Roles for Amazon EKS (p. 326)
- Using Roles for Amazon EKS node groups (p. 328)

Using Roles for Amazon EKS

Amazon Elastic Kubernetes Service uses AWS Identity and Access Management (IAM) service-linked roles. A service-linked role is a unique type of IAM role that is linked directly to Amazon EKS. Service-linked roles are predefined by Amazon EKS and include all the permissions that the service requires to call other AWS services on your behalf.

Amazon EKS User Guide Using Service-Linked Roles

A service-linked role makes setting up Amazon EKS easier because you don't have to manually add the necessary permissions. Amazon EKS defines the permissions of its service-linked roles, and unless defined otherwise, only Amazon EKS can assume its roles. The defined permissions include the trust policy and the permissions policy, and that permissions policy cannot be attached to any other IAM entity.

You can delete a service-linked role only after first deleting their related resources. This protects your Amazon EKS resources because you can't inadvertently remove permission to access the resources.

For information about other services that support service-linked roles, see AWS Services That Work with IAM and look for the services that have **Yes** in the **Service-Linked Role** column. Choose a **Yes** with a link to view the service-linked role documentation for that service.

Service-Linked Role Permissions for Amazon EKS

Amazon EKS uses the service-linked role named **AWSServiceRoleForAmazonEKS** – These permissions are required for Amazon EKS to manage clusters in your account. These policies are related to management of the following resources: network interfaces, security groups, logs, and VPCs.

Note

The **AWSServiceRoleForAmazonEKS** service-linked role is distinct from the role required for cluster creation. For more information, see Amazon EKS cluster IAM role (p. 330).

The AWSServiceRoleForAmazonEKS service-linked role trusts the following services to assume the role:

eks.amazonaws.com

The role permissions policy allows Amazon EKS to complete the following actions on the specified resources:

AmazonEKSServiceRolePolicy

You must configure permissions to allow an IAM entity (such as a user, group, or role) to create, edit, or delete a service-linked role. For more information, see Service-Linked Role Permissions in the IAM User Guide.

Creating a Service-Linked Role for Amazon EKS

You don't need to manually create a service-linked role. When you create a cluster in the AWS Management Console, the AWS CLI, or the AWS API, Amazon EKS creates the service-linked role for you.

If you delete this service-linked role, and then need to create it again, you can use the same process to recreate the role in your account. When you create a cluster, Amazon EKS creates the service-linked role for you again.

Editing a Service-Linked Role for Amazon EKS

Amazon EKS does not allow you to edit the AWSServiceRoleForAmazonEKS service-linked role. After you create a service-linked role, you cannot change the name of the role because various entities might reference the role. However, you can edit the description of the role using IAM. For more information, see Editing a Service-Linked Role in the *IAM User Guide*.

Deleting a Service-Linked Role for Amazon EKS

If you no longer need to use a feature or service that requires a service-linked role, we recommend that you delete that role. That way you don't have an unused entity that is not actively monitored or maintained. However, you must clean up your service-linked role before you can manually delete it.

Cleaning Up a Service-Linked Role

Before you can use IAM to delete a service-linked role, you must first delete any resources used by the role.

Note

If the Amazon EKS service is using the role when you try to delete the resources, then the deletion might fail. If that happens, wait for a few minutes and try the operation again.

To delete Amazon EKS resources used by the AWSServiceRoleForAmazonEKS

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. Choose a cluster.
- 3. On the cluster page, if there are any managed node groups in the **Node Groups** section, select each one individually, and then choose **Delete**.
- 4. Type the name of the node group in the deletion confirmation window, and then choose **Confirm** to delete.
- 5. Repeat this procedure for any other node groups in the cluster. Wait for all of the delete operations to finish.
- 6. On the cluster page choose **Delete**.
- 7. Repeat this procedure for any other clusters in your account.

Manually Delete the Service-Linked Role

Use the IAM console, the AWS CLI, or the AWS API to delete the AWSServiceRoleForAmazonEKS service-linked role. For more information, see Deleting a Service-Linked Role in the IAM User Guide.

Supported Regions for Amazon EKS Service-Linked Roles

Amazon EKS supports using service-linked roles in all of the regions where the service is available. For more information, see Amazon EKS Service Endpoints and Quotas.

Using Roles for Amazon EKS node groups

Amazon EKS uses AWS Identity and Access Management (IAM) service-linked roles. A service-linked role is a unique type of IAM role that is linked directly to Amazon EKS. Service-linked roles are predefined by Amazon EKS and include all the permissions that the service requires to call other AWS services on your behalf.

A service-linked role makes setting up Amazon EKS easier because you don't have to manually add the necessary permissions. Amazon EKS defines the permissions of its service-linked roles, and unless defined otherwise, only Amazon EKS can assume its roles. The defined permissions include the trust policy and the permissions policy, and that permissions policy cannot be attached to any other IAM entity.

You can delete a service-linked role only after first deleting their related resources. This protects your Amazon EKS resources because you can't inadvertently remove permission to access the resources.

For information about other services that support service-linked roles, see AWS Services That Work with IAM and look for the services that have **Yes** in the **Service-Linked Role** column. Choose a **Yes** with a link to view the service-linked role documentation for that service.

Service-Linked Role Permissions for Amazon EKS

Amazon EKS uses the service-linked role named **AWSServiceRoleForAmazonEKSNodegroup** – These permissions are required for managing nodegroups in your account. These policies are related to

Amazon EKS User Guide Using Service-Linked Roles

management of the following resources: Auto Scaling groups, security groups, launch templates and IAM instance profiles..

The AWSServiceRoleForAmazonEKSNodegroup service-linked role trusts the following services to assume the role:

· eks-nodegroup.amazonaws.com

The role permissions policy allows Amazon EKS to complete the following actions on the specified resources:

AWSServiceRoleForAmazonEKSNodegroup

You must configure permissions to allow an IAM entity (such as a user, group, or role) to create, edit, or delete a service-linked role. For more information, see Service-Linked Role Permissions in the IAM User Guide.

Creating a Service-Linked Role for Amazon EKS

You don't need to manually create a service-linked role. When you CreateNodegroup in the AWS Management Console, the AWS CLI, or the AWS API, Amazon EKS creates the service-linked role for you.

Important

This service-linked role can appear in your account if you completed an action in another service that uses the features supported by this role. If you were using the Amazon EKS service before January 1, 2017, when it began supporting service-linked roles, then Amazon EKS created the AWSServiceRoleForAmazonEKSNodegroup role in your account. To learn more, see A New Role Appeared in My IAM Account.

Creating a Service-Linked Role in Amazon EKS (AWS API)

You don't need to manually create a service-linked role. When you create a managed node group in the AWS Management Console, the AWS CLI, or the AWS API, Amazon EKS creates the service-linked role for you.

If you delete this service-linked role, and then need to create it again, you can use the same process to recreate the role in your account. When you create another managed node group, Amazon EKS creates the service-linked role for you again.

Editing a Service-Linked Role for Amazon EKS

Amazon EKS does not allow you to edit the AWSServiceRoleForAmazonEKSNodegroup service-linked role. After you create a service-linked role, you cannot change the name of the role because various entities might reference the role. However, you can edit the description of the role using IAM. For more information, see Editing a Service-Linked Role in the IAM User Guide.

Deleting a Service-Linked Role for Amazon EKS

If you no longer need to use a feature or service that requires a service-linked role, we recommend that you delete that role. That way you don't have an unused entity that is not actively monitored or maintained. However, you must clean up your service-linked role before you can manually delete it.

Cleaning Up a Service-Linked Role

Before you can use IAM to delete a service-linked role, you must first delete any resources used by the role.

Note

If the Amazon EKS service is using the role when you try to delete the resources, then the deletion might fail. If that happens, wait for a few minutes and try the operation again.

To delete Amazon EKS resources used by the AWSServiceRoleForAmazonEKSNodegroup

- 1. Open the Amazon EKS console at https://console.aws.amazon.com/eks/home#/clusters.
- 2. Choose a cluster.
- 3. On the cluster page, if there are any managed node groups in the **Node Groups** section, select each one individually, and then choose **Delete**.
- 4. Type the name of the cluster in the deletion confirmation window, and then choose **Confirm** to delete.
- Repeat this procedure for any other node groups in the cluster and for any other clusters in your account.

Manually Delete the Service-Linked Role

Use the IAM console, the AWS CLI, or the AWS API to delete the AWSServiceRoleForAmazonEKSNodegroup service-linked role. For more information, see Deleting a Service-Linked Role in the IAM User Guide.

Supported Regions for Amazon EKS Service-Linked Roles

Amazon EKS supports using service-linked roles in all of the regions where the service is available. For more information, see Amazon EKS Service Endpoints and Quotas.

Amazon EKS cluster IAM role

Kubernetes clusters managed by Amazon EKS make calls to other AWS services on your behalf to manage the resources that you use with the service. Before you can create Amazon EKS clusters, you must create an IAM role with the following IAM policies:

• AmazonEKSClusterPolicy

Note

Prior to April 16, 2020, AmazonEKSServicePolicy was also required and the suggested name was eksServiceRole. With the AWSServiceRoleForAmazonEKS service-linked role, that policy is no longer required for clusters created on or after April 16, 2020.

Check for an existing cluster role

You can use the following procedure to check and see if your account already has the Amazon EKS cluster role.

To check for the eksClusterRole in the IAM console

- 1. Open the IAM console at https://console.aws.amazon.com/iam/.
- 2. In the navigation panel, choose Roles.
- 3. Search the list of roles for eksClusterRole. If a role that includes eksClusterRole does not exist, then see Creating the Amazon EKS cluster role (p. 331) to create the role. If a role that includes eksClusterRole does exist, then select the role to view the attached policies.
- 4. Choose Permissions.
- 5. Ensure that the **AmazonEKSClusterPolicy** managed policy is attached to the role. If the policy is attached, your Amazon EKS cluster role is properly configured.
- 6. Choose Trust Relationships, Edit Trust Relationship.
- 7. Verify that the trust relationship contains the following policy. If the trust relationship matches the policy below, choose **Cancel**. If the trust relationship does not match, copy the policy into the **Policy Document** window and choose **Update Trust Policy**.

Amazon EKS User Guide Cluster IAM role

Creating the Amazon EKS cluster role

You can use the AWS Management Console (p. 331) or AWS CloudFormation (p. 331) to create the cluster role if you do not already have one for your account.

To create your Amazon EKS cluster role in the IAM console

- 1. Open the IAM console at https://console.aws.amazon.com/iam/.
- 2. Choose Roles, then Create role.
- Choose EKS from the list of services, then EKS Cluster for your use case, and then Next: Permissions.
- Choose Next: Tags.
- 5. (Optional) Add metadata to the role by attaching tags as key–value pairs. For more information about using tags in IAM, see Tagging IAM Entities in the IAM User Guide.
- 6. Choose Next: Review.
- 7. For **Role name**, enter a unique name for your role, such as eksClusterRole, then choose **Create**

To create your Amazon EKS cluster role with AWS CloudFormation

Save the following AWS CloudFormation template to a text file on your local system.

```
AWSTemplateFormatVersion: '2010-09-09'
Description: 'Amazon EKS Cluster Role'
Resources:
  eksClusterRole:
    Type: AWS::IAM::Role
    Properties:
      AssumeRolePolicyDocument:
        Version: '2012-10-17'
        Statement:
        - Effect: Allow
          Principal:
            Service:
            - eks.amazonaws.com
          Action:
          - sts:AssumeRole
      ManagedPolicyArns:
        - arn:aws:iam::aws:policy/AmazonEKSClusterPolicy
```

Amazon EKS User Guide Node IAM role

```
Outputs:

RoleArn:
Description: The role that Amazon EKS will use to create AWS resources for Kubernetes clusters
Value: !GetAtt eksClusterRole.Arn
Export:
Name: !Sub "${AWS::StackName}-RoleArn"
```

Note

Prior to April 16, 2020, ManagedPolicyArns had an entry for arn:aws:iam::aws:policy/AmazonEKSServicePolicy. With the AWSServiceRoleForAmazonEKS service-linked role, that policy is no longer required.

- 2. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
- Choose Create stack.
- For Specify template, select Upload a template file, and then choose Choose file.
- 5. Choose the file you created earlier, and then choose Next.
- 6. For Stack name, enter a name for your role, such as eksClusterRole, and then choose Next.
- On the Configure stack options page, choose Next.
- On the Review page, review your information, acknowledge that the stack might create IAM resources, and then choose Create stack.

Amazon EKS node IAM role

The Amazon EKS node kubelet daemon makes calls to AWS APIs on your behalf. Nodes receive permissions for these API calls through an IAM instance profile and associated policies. Before you can launch nodes and register them into a cluster, you must create an IAM role for those nodes to use when they are launched. This requirement applies to nodes launched with the Amazon EKS optimized AMI provided by Amazon, or with any other node AMIs that you intend to use. Before you create nodes, you must create an IAM role with the following IAM policies:

- AmazonEKSWorkerNodePolicy
- AmazonEC2ContainerRegistryReadOnly

Check for an existing node role

You can use the following procedure to check and see if your account already has the Amazon EKS node role.

To check for the NodeInstanceRole in the IAM console

- 1. Open the IAM console at https://console.aws.amazon.com/iam/.
- 2. In the navigation panel, choose Roles.
- 3. Search the list of roles for NodeInstanceRole. If a role that contains NodeInstanceRole does not exist, then see Creating the Amazon EKS node IAM role (p. 333) to create the role. If a role that contains NodeInstanceRole does exist, then select the role to view the attached policies.
- 4. Choose Permissions.
- 5. Ensure that the AmazonEKSWorkerNodePolicy and AmazonEC2ContainerRegistryReadOnly managed policies are attached to the role. If the policies are attached, your Amazon EKS node role is properly configured.

Note

If the AmazonEKS_CNI_Policy policy is attached to the role, we recommend removing it and attaching it to an IAM role that is mapped to the aws-node Kubernetes service account instead. For more information, see the section called "Configure plugin for IAM account" (p. 210).

- 6. Choose Trust Relationships, Edit Trust Relationship.
- 7. Verify that the trust relationship contains the following policy. If the trust relationship matches the policy below, choose **Cancel**. If the trust relationship does not match, copy the policy into the **Policy Document** window and choose **Update Trust Policy**.

Creating the Amazon EKS node IAM role

If you created your nodes by following the steps in the Getting started with the AWS Management Console (p. 15) or Getting started with eksctl (p. 4) topics, then the node role already exists and you don't need to manually create it. You can use the AWS Management Console or AWS CloudFormation to create the Amazon EKS node role if you do not already have one for your account. You can create the node role with the AWS Management Console (p. 333) or AWS CloudFormation (p. 334).

To create your Amazon EKS node role in the IAM console

- 1. Open the IAM console at https://console.aws.amazon.com/iam/.
- Choose Roles, then Create role.
- Choose EC2 from the list of Common use cases under Choose a use case, then choose Next: Permissions.
- 4. In the **Filter policies** box, enter AmazonEKSWorkerNodePolicy. Check the box to the left of **AmazonEKSWorkerNodePolicy**.
- 5. In the **Filter policies** box, enter AmazonEC2ContainerRegistryReadOnly. Check the box to the left of **AmazonEC2ContainerRegistryReadOnly**.
- 6. The AmazonEKS_CNI_Policy policy must be attached to either this role or to a different role that is mapped to the aws-node Kubernetes service account. We recommend assigning the policy to the role associated to the Kubernetes service account instead of assigning it to this role. For more information, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).
- 7. Choose **Next: Tags**.
- 8. (Optional) Add metadata to the role by attaching tags as key–value pairs. For more information about using tags in IAM, see Tagging IAM Entities in the IAM User Guide.
- Choose Next: Review.
- For Role name, enter a unique name for your role, such as NodeInstanceRole. For Role description, replace the current text with descriptive text such as Amazon EKS - Node Group Role, then choose Create role.

To create your Amazon EKS node role using AWS CloudFormation

- 1. Open the AWS CloudFormation console at https://console.aws.amazon.com/cloudformation.
- 2. Choose Create stack and then choose With new resources (standard).
- For Specify template, select Amazon S3 URL.
- 4. Paste the URL that corresponds to the Region that your cluster is in into the **Amazon S3 URL** text area and choose **Next** twice:
 - · All Regions other than China Regions.

https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-29/amazon-eks-nodegroup-role.yaml

· Beijing and Ningxia China Regions.

 $\label{lem:https://s3.cn-north-1.amazonaws.com.cn/amazon-eks//cloudformation/2020-10-29/amazon-eks-nodegroup-role.yaml$

- 5. On the **Specify stack details** page, for **Stack name** enter a name such as **eks-node-group-instance-role** and choose **Next**.
- 6. (Optional) On the **Configure stack options** page, you can choose to tag your stack resources. Choose **Next**.
- 7. On the **Review** page, check the box in the **Capabilities** section and choose **Create stack**.
- 8. When your stack is created, select it in the console and choose **Outputs**.
- 9. Record the **NodeInstanceRole** value for the IAM role that was created. You need this when you create your node group.
- 10. (Optional, but recommended) One of the IAM policies attached to the role by the AWS CloudFormation template in a previous step is the **AmazonEKS_CNI_Policy** managed policy. The policy must be attached to this role or to a role associated to the Kubernetes aws-node service account that is used for the Amazon EKS VPC CNI plugin. We recommend assigning the policy to the role associated to the Kubernetes service account. For more information, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).

Pod execution role

The Amazon EKS pod execution role is required to run pods on AWS Fargate infrastructure.

When your cluster creates pods on AWS Fargate infrastructure, the components running on the Fargate infrastructure need to make calls to AWS APIs on your behalf to do things like pull container images from Amazon ECR or route logs to other AWS services. The Amazon EKS pod execution role provides the IAM permissions to do this.

When you create a Fargate profile, you must specify a pod execution role for the Amazon EKS components that run on the Fargate infrastructure using the profile. This role is added to the cluster's Kubernetes Role based access control (RBAC) for authorization, so that the kubelet that is running on the Fargate infrastructure can register with your Amazon EKS cluster. This is what allows Fargate infrastructure to appear in your cluster as nodes.

The containers running in the Fargate pod cannot assume the IAM permissions associated with the pod execution role. To give the containers in your Fargate pod permissions to access other AWS services, you must use the section called "IAM roles for service accounts" (p. 336).

Before you create a Fargate profile, you must create an IAM role with the following IAM policy:

AmazonEKSFargatePodExecutionRolePolicy

Check for an existing pod execution role

You can use the following procedure to check and see if your account already has the Amazon EKS pod execution role.

To check for the AmazonEKSFargatePodExecutionRole in the IAM console

- 1. Open the IAM console at https://console.aws.amazon.com/iam/.
- 2. In the navigation panel, choose Roles.
- Search the list of roles for AmazonEKSFargatePodExecutionRole. If the role does not exist, see Creating the Amazon EKS pod execution role (p. 335) to create the role. If the role does exist, select the role to view the attached policies.
- Choose Permissions.
- 5. Ensure that the **AmazonEKSFargatePodExecutionRolePolicy** Amazon managed policy is attached to the role. If the policy is attached, then your Amazon EKS pod execution role is properly configured.
- 6. Choose Trust Relationships, Edit Trust Relationship.
- Verify that the trust relationship contains the following policy. If the trust relationship matches the
 policy below, choose Cancel. If the trust relationship does not match, copy the policy into the Policy
 Document window and choose Update Trust Policy.

Creating the Amazon EKS pod execution role

You can use the following procedure to create the Amazon EKS pod execution role if you do not already have one for your account.

To create an AWS Fargate pod execution role with the AWS Management Console

- 1. Open the IAM console at https://console.aws.amazon.com/iam/.
- 2. Choose Roles, then Create role.
- 3. Choose **EKS** from the list of services, **EKS Fargate pod** for your use case, and then **Next: Permissions**.
- 4. Choose Next: Tags.
- 5. (Optional) Add metadata to the role by attaching tags as key–value pairs. For more information about using tags in IAM, see Tagging IAM Entities in the IAM User Guide.
- 6. Choose Next: Review.
- For Role name, enter a unique name for your role, such as AmazonEKSFargatePodExecutionRole, then choose Create role.

IAM roles for service accounts

With IAM roles for service accounts on Amazon EKS clusters, you can associate an IAM role with a Kubernetes service account. This service account can then provide AWS permissions to the containers in any pod that uses that service account. With this feature, you no longer need to provide extended permissions to the the section called "Node IAM role" (p. 332) so that pods on that node can call AWS APIs.

Applications must sign their AWS API requests with AWS credentials. This feature provides a strategy for managing credentials for your applications, similar to the way that Amazon EC2 instance profiles provide credentials to Amazon EC2 instances. Instead of creating and distributing your AWS credentials to the containers or using the Amazon EC2 instance's role, you can associate an IAM role with a Kubernetes service account. The applications in the pod's containers can then use an AWS SDK or the AWS CLI to make API requests to authorized AWS services.

Important

Even if you assign an IAM role to a Kubernetes service account, the pod still also has the permissions assigned to the the section called "Node IAM role" (p. 332), unless you block pod access to the IMDS. For more information, see the section called "Restricting access to the instance profile" (p. 349).

The IAM roles for service accounts feature provides the following benefits:

- Least privilege By using the IAM roles for service accounts feature, you no longer need to provide extended permissions to the node IAM role so that pods on that node can call AWS APIs. You can scope IAM permissions to a service account, and only pods that use that service account have access to those permissions. This feature also eliminates the need for third-party solutions such as kiam or kube2iam.
- **Credential isolation** A container can only retrieve credentials for the IAM role that is associated with the service account to which it belongs. A container never has access to credentials that are intended for another container that belongs to another pod.
- Auditability Access and event logging is available through CloudTrail to help ensure retrospective auditing.

To get started, see Enabling IAM roles for service accounts on your cluster (p. 341).

For an end-to-end walkthrough using eksctl, see Configuring the VPC CNI plugin to use IAM roles for service accounts (p. 210).

IAM roles for service accounts technical overview

In 2014, AWS Identity and Access Management added support for federated identities using OpenID Connect (OIDC). This feature allows you to authenticate AWS API calls with supported identity providers and receive a valid OIDC JSON web token (JWT). You can pass this token to the AWS STS AssumeRoleWithWebIdentity API operation and receive IAM temporary role credentials. You can use these credentials to interact with any AWS service, like Amazon S3 and DynamoDB.

Kubernetes has long used service accounts as its own internal identity system. Pods can authenticate with the Kubernetes API server using an auto-mounted token (which was a non-OIDC JWT) that only the Kubernetes API server could validate. These legacy service account tokens do not expire, and rotating the signing key is a difficult process. In Kubernetes version 1.12, support was added for a new ProjectedServiceAccountToken feature, which is an OIDC JSON web token that also contains the service account identity, and supports a configurable audience.

Amazon EKS now hosts a public OIDC discovery endpoint per cluster containing the signing keys for the ProjectedServiceAccountToken JSON web tokens so external systems, like IAM, can validate and accept the OIDC tokens issued by Kubernetes.

IAM role configuration

In IAM, you create an IAM role with a trust relationship that is scoped to your cluster's OIDC provider, the service account namespace, and (optionally) the service account name, and then attach the IAM policy that you want to associate with the service account. You can add multiple entries in the StringEquals and StringLike conditions below to use multiple service accounts or namespaces with the role.

• To scope a role to a specific service account:

• To scope a role to an entire namespace (to use the namespace as a boundary):

Service account configuration

In Kubernetes, you define the IAM role to associate with a service account in your cluster by adding the eks.amazonaws.com/role-arn annotation to the service account.

```
apiVersion: v1
kind: ServiceAccount
metadata:
  annotations:
    eks.amazonaws.com/role-arn: arn:aws:iam::<AWS_ACCOUNT_ID>:role/<IAM_ROLE_NAME>
```

Pod configuration

The Amazon EKS Pod Identity Webhook on the cluster watches for pods that are associated with service accounts with this annotation and applies the following environment variables to them.

```
AWS_ROLE_ARN=arn:aws:iam::<AWS_ACCOUNT_ID>:role/<IAM_ROLE_NAME>
AWS_WEB_IDENTITY_TOKEN_FILE=/var/run/secrets/eks.amazonaws.com/serviceaccount/token
```

Note

Your cluster does not need to use the mutating web hook to configure the environment variables and token file mounts; you can choose to configure pods to add these environment variables manually.

Important

If your Amazon EKS cluster is running Kubernetes version 1.17 or earlier, you need to add the following environment variable to all pods that use IAM roles for service accounts in China Regions, whether you use the mutating web hook or configure the environment variables manually.

```
AWS_DEFAULT_REGION=<region-code>
```

Supported versions of the AWS SDK (p. 340) look for these environment variables first in the credential chain provider. The role credentials are used for pods that meet this criteria.

Note

When a pod uses AWS credentials from an IAM role associated with a service account, the AWS CLI or other SDKs in the containers for that pod use the credentials provided by that role. The pod still has access to the credentials provided to the the section called "Node IAM role" (p. 332) too, unless you restrict access to those credentials. For more information, see the section called "Restricting access to the instance profile" (p. 349).

By default, only containers that run as root have the proper file system permissions to read the web identity token file. You can provide these permissions by having your containers run as root, or by providing the following security context for the containers in your manifest. The fsGroup ID is arbitrary, and you can choose any valid group ID. For more information about the implications of setting a security context for your pods, see Configure a Security Context for a Pod or Container in the Kubernetes documentation.

```
apiVersion: apps/v1
kind: Deployment
metadata:
  name: <my-app>
spec:
  template:
    metadata:
      labels:
        app: <my-app>
    spec:
      serviceAccountName: <my-app>
      containers:
      - name: <my-app>
        image: <my-app>:latest
      securityContext:
        fsGroup: <1337>
```

The kubelet requests and stores the token on behalf of the pod. By default, the kubelet refreshes the token if it is older than 80 percent of its total TTL, or if the token is older than 24 hours. You can modify the expiration duration for any account, except the default service account, with settings in

your pod spec. For more information, see Service Account Token Volume Projection in the Kubernetes documentation.

Cross-account IAM permissions

You can configure cross-account IAM permissions either by creating an identity provider from another account's cluster or by using chained AssumeRole operations. In the following examples, Account A owns an Amazon EKS cluster that supports IAM roles for service accounts. Pods running on that cluster need to assume IAM permissions from Account B.

Example: Create an identity provider from another account's cluster

Example

In this example, Account A would provide Account B with the OIDC issuer URL from their cluster. Account B follows the instructions in Enabling IAM roles for service accounts on your cluster (p. 341) and Creating an IAM role and policy for your service account (p. 342) using the OIDC issuer URL from Account A's cluster. Then a cluster administrator annotates the service account in Account A's cluster to use the role from Account B.

```
apiVersion: v1
kind: ServiceAccount
metadata:
  annotations:
    eks.amazonaws.com/role-arn: arn:aws:iam::<ACCOUNT_B_AWS_ACCOUNT_ID>:role/
<IAM_ROLE_NAME>
```

Example: Use chained AssumeRole operations

Example

In this example, Account B creates an IAM policy with the permissions to give to pods in Account A's cluster. Account B attaches that policy to an IAM role with a trust relationship that allows AssumeRole permissions to Account A (1111111111111), as shown below.

Account A creates a role with a trust policy that gets credentials from the identity provider created with the cluster's OIDC issuer URL, as shown below.

```
"Action": "sts:AssumeRoleWithWebIdentity"
}
]
}
```

Account A attaches a policy to that role with the following permissions to assume the role that Account B created.

The application code for pods to assume Account B's role uses two profiles: account_b_role and account_a_role. The account_b_role profile uses the account_a_role profile as its source. For the AWS CLI, the ~/.aws/config file would look like the following example.

To specify chained profiles for other AWS SDKs, consult their documentation.

Using a supported AWS SDK

The containers in your pods must use an AWS SDK version that supports assuming an IAM role via an OIDC web identity token file. AWS SDKs that are included in Linux distribution package managers may not be new enough to support this feature. Be sure to use at least the minimum SDK versions listed below:

```
Java (Version 2) — 2.10.11
Java — 1.11.704
Go — 1.23.13
Python (Boto3) — 1.9.220
Python (botocore) — 1.12.200
AWS CLI — 1.16.232
Node — 2.521.0
Ruby — 2.11.345
C++ — 1.7.174
.NET — 3.3.659.1
PHP — 3.110.7
```

Many popular Kubernetes add-ons, such as the Cluster Autoscaler and the AWS load balancer controller (p. 269) support IAM roles for service accounts. The Amazon VPC CNI plugin for Kubernetes has been updated with a supported version of the AWS SDK for Go, and you can use the IAM roles for service accounts feature to provide the required permissions for the CNI to work.

To ensure that you are using a supported SDK, follow the installation instructions for your preferred SDK at Tools for Amazon Web Services when you build your containers.

Enabling IAM roles for service accounts on your cluster

Your cluster has an OpenID Connect issuer URL associated with it. You can view the URL within the Amazon EKS console, or you can use the following AWS CLI command to retrieve it.

Important

You must use at least version 1.18.190 or 2.1.7 of the AWS CLI to receive the proper output from this command. For more information, see Installing the AWS CLI in the AWS Command Line Interface User Guide.

aws eks describe-cluster --name <cluster_name> --query "cluster.identity.oidc.issuer" -output text

Output:

https://oidc.eks.<region-code>.amazonaws.com/id/EXAMPLED539D4633E53DE1B716D3041E

To use IAM roles for service accounts in your cluster, you must create an IAM OIDC identity provider using either eksct1 (p. 341) or the AWS Management Console (p. 341).

To create an IAM OIDC identity provider for your cluster with eksctl

1. Check your eksctl version with the following command. This procedure assumes that you have installed eksctl and that your eksctl version is at least 0.33.0.

eksctl version

For more information about installing or upgrading eksctl, see Installing or upgrading eksctl (p. 298).

2. Create your OIDC identity provider for your cluster with the following command. Substitute <cluster_name> with your own value.

eksctl utils associate-iam-oidc-provider --cluster <cluster_name> --approve

To create an IAM OIDC identity provider for your cluster with the AWS Management Console

 Retrieve the OIDC issuer URL from the Amazon EKS console description of your cluster or use the following AWS CLI command. Replace <cluster_name> (including <>) with your own value.

Important

You must use at least version 1.18.190 or 2.1.7 of the AWS CLI to receive the proper output from this command. For more information, see Installing the AWS CLI in the AWS Command Line Interface User Guide.

aws eks describe-cluster --name <cluster_name> --query "cluster.identity.oidc.issuer" --output text

- 2. Open the IAM console at https://console.aws.amazon.com/iam/.
- 3. In the navigation panel, choose **Identity Providers**, and then choose **Add Provider**.
- 4. For **Provider Type**, choose **OpenID Connect**.
- 5. For Provider URL, paste the OIDC issuer URL for your cluster, and then choose Get thumbprint.
- 6. For Audience, enter sts.amazonaws.com and choose Add provider.

After you have enabled the IAM OIDC identity provider for your cluster, you can create IAM roles to associate with a service account in your cluster. For more information, see Creating an IAM role and policy for your service account (p. 342)

Creating an IAM role and policy for your service account

You must create an IAM policy that specifies the permissions that you would like the containers in your pods to have. You have several ways to create a new IAM permission policy. One way is to copy a complete AWS managed policy that already does some of what you're looking for and then customize it to your specific requirements. For more information, see Creating a New Policy in the IAM User Guide.

You must also create an IAM role for your Kubernetes service accounts to use before you associate it with a service account. The trust relationship is scoped to your cluster and service account so that each cluster and service account combination requires its own role. You can then attach a specific IAM policy to the role that gives the containers in your pods the permissions you desire. The following procedures describe how to do this.

Create an IAM policy

In this procedure, we offer two example policies that you can use for your application:

- A policy to allow read-only access to an Amazon S3 bucket. You could store configuration information
 or a bootstrap script in this bucket, and the containers in your pod can read the file from the bucket
 and load it into your application.
- A policy to allow paid container images from AWS Marketplace.
- 1. Open the IAM console at https://console.aws.amazon.com/iam/.
- 2. In the navigation panel, choose **Policies** and then choose **Create policy**.
- Choose the JSON tab.
- 4. In the **Policy Document** field, paste one of the following policies to apply to your service accounts, or paste your own policy document into the field. You can also use the visual editor to construct your own policy.

The example below allows permission to the <my-pod-secrets-bucket> Amazon S3 bucket. You can modify the policy document to suit your specific needs.

The example below gives the required permissions to use a paid container image from AWS Marketplace.

```
{
    "Version": "2012-10-17",
    "Statement": [
```

```
{
    "Action": [
        "aws-marketplace:RegisterUsage"
],
    "Effect": "Allow",
    "Resource": "*"
}
]
```

- Choose Review policy.
- 6. Enter a name and description for your policy and then choose Create policy.
- 7. Record the Amazon Resource Name (ARN) of the policy to use later when you create your role.

Create an IAM role for a service account.

Create an IAM role for your service accounts. You can use eksctl (p. 343), the AWS Management Console (p. 343), or the AWS CLI (p. 344) to create the role.

To create your IAM role with eksctl

Create the service account and IAM role with the following command. Replace the <example values> (including <>) with your own values.

Note

This command only works for clusters that were created with eksctl. If you didn't create your cluster with eksctl, then use the instructions on the AWS Management Console or AWS CLI tabs.

```
eksctl create iamserviceaccount \
    --name <service_account_name> \
    --namespace <service_account_namespace> \
    --cluster <cluster_name> \
    --attach-policy-arn <IAM_policy_ARN> \
    --approve \
    --override-existing-serviceaccounts
```

An AWS CloudFormation template was deployed that created an IAM role and attached the IAM policy to it. The role was associated with a Kubernetes service account. If the service account doesn't exist, it is created in the namespace that you provided. If the service account does exist, then it is annotated with eks.amazonaws.com/role-arn: arn:aws:iam::<your-account-id>:role/<iam-role-name-that-was-created>.

To create your IAM role with the AWS Management Console

1. Retrieve the OIDC issuer URL from the Amazon EKS console description of your cluster, or use the following AWS CLI command. Replace the <example values> (including <>) with your own values.

Important

You must use at least version 1.18.190 or 2.1.7 of the AWS CLI to receive the proper output from this command. For more information, see Installing the AWS CLI in the AWS Command Line Interface User Guide.

```
aws eks describe-cluster --name <cluster_name> --query "cluster.identity.oidc.issuer"
    --output text
```

- 2. Open the IAM console at https://console.aws.amazon.com/iam/.
- 3. In the navigation panel, choose Roles, Create Role.
- 4. In the **Select type of trusted entity** section, choose **Web identity**.

- 5. In the Choose a web identity provider section:
 - 1. For Identity provider, choose the URL for your cluster.
 - 2. For Audience, choose sts.amazonaws.com.
- 6. Choose Next: Permissions.
- 7. In the **Attach Policy** section, select the IAM policy that has the permissions that you want your service account to use. Choose **Next: Tags**.
- 8. On the Add tags (optional) screen, you can add tags for the account. Choose Next: Review.
- 9. For Role Name, enter a name for your role and then choose Create Role.
- 10. After the role is created, choose the role in the console to open it for editing.
- 11. Choose the **Trust relationships** tab, and then choose **Edit trust relationship**.
 - a. Edit the OIDC provider suffix and change it from : aud to : sub.
 - b. Replace sts.amazonaws.com with your service account ID.

Note

If you don't have an existing service account, then you need to create one. For more information, see Configure Service Accounts for Pods in the Kubernetes documentation. For the service account to be able to use Kubernetes permissions, you must create a Role, or ClusterRole and then bind the role to the service account. For more information, see Using RBAC Authorization in the Kubernetes documentation. When the AWS VPC CNI plugin (p. 208) is deployed, for example, the deployment manifest creates a service account, cluster role, and cluster role binding. You can view the manifest on GitHub.

c. If necessary, change region-code to the Region code returned in the output from step 1.

The resulting line should look like this.

```
"oidc.eks.<region-code>.amazonaws.com/id/<EXAMPLED539D4633E53DE1B716D3041E>:sub":
"system:serviceaccount:<SERVICE_ACCOUNT_NAMESPACE>:<SERVICE_ACCOUNT_NAME>"
```

- 12. Choose **Update Trust Policy** to finish.
- 13. Associate the IAM role with a Kubernetes service account. For more information, see Associate an IAM role to a service account (p. 345).

To create your IAM role with the AWS CLI

1. Set your AWS account ID to an environment variable with the following command.

```
AWS_ACCOUNT_ID=$(aws sts get-caller-identity --query "Account" --output text)
```

2. Set your OIDC identity provider to an environment variable with the following command. Replace the <example values> (including <>) with your own values.

Important

You must use at least version 1.18.190 or 2.1.7 of the AWS CLI to receive the proper output from this command. For more information, see Installing the AWS CLI in the AWS Command Line Interface User Guide.

```
OIDC_PROVIDER=$(aws eks describe-cluster --name <cluster-name> --query "cluster.identity.oidc.issuer" --output text | sed -e "s/^https:\/\//")
```

Copy the following code block to your computer and replace <namespace> and <serviceaccount-name> with your own values.

```
read -r -d '' TRUST RELATIONSHIP <<EOF
  "Version": "2012-10-17",
  "Statement": [
      "Effect": "Allow",
      "Principal": {
        "Federated": "arn:aws:iam::${AWS_ACCOUNT_ID}:oidc-provider/${OIDC_PROVIDER}"
      "Action": "sts:AssumeRoleWithWebIdentity",
      "Condition": {
        "StringEquals": {
          "${OIDC_PROVIDER}:sub": "system:serviceaccount:<namespace>:<service-account-
name>"
      }
    }
  ]
}
EOF
echo "${TRUST_RELATIONSHIP}" > trust.json
```

- 4. Run the modified code block from the previous step to create a file named trust.json.
- 5. Run the following AWS CLI command to create the role, replacing your IAM role name and description.

```
aws iam create-role --role-name <IAM_ROLE_NAME> --assume-role-policy-document file://
trust.json --description "<IAM_ROLE_DESCRIPTION>"
```

6. Run the following command to attach your IAM policy to your role, replacing your IAM role name and policy ARN.

```
aws iam attach-role-policy --role-name <IAM_ROLE_NAME> --policy-arn=<IAM_POLICY_ARN>
```

7. Associate the IAM role with a Kubernetes service account. For more information, see Associate an IAM role to a service account (p. 345).

Associate an IAM role to a service account

In Kubernetes, you define the IAM role to associate with a service account in your cluster by adding the following annotation to the service account.

Note

If you created an IAM role to use with your service account using eksctl, this has already been done for you with the service account that you specified when creating the role.

```
apiVersion: v1
kind: ServiceAccount
metadata:
   annotations:
    eks.amazonaws.com/role-arn: arn:aws:iam::<AWS_ACCOUNT_ID>:role/<IAM_ROLE_NAME>
```

To patch a service account to use an IAM role

Use the following command to annotate your service account with the ARN of the IAM role that
you want to use with your service account. Be sure to substitute your own values for the <example
values> to use with your pods.

Amazon EKS User Guide Troubleshooting

kubectl annotate serviceaccount -n <SERVICE_ACCOUNT_NAMESPACE> <SERVICE_ACCOUNT_NAME> \
eks.amazonaws.com/role-arn=arn:aws:iam::<AWS_ACCOUNT_ID>:role/<IAM_ROLE_NAME>

Note

If you don't have an existing service account, then you need to create one. For more information, see Configure Service Accounts for Pods in the Kubernetes documentation. For the service account to be able to use Kubernetes permissions, you must create a Role, or ClusterRole and then bind the role to the service account. For more information, see Using RBAC Authorization in the Kubernetes documentation. When the AWS VPC CNI plugin (p. 208) is deployed, for example, the deployment manifest creates a service account, cluster role, and cluster role binding. You can view the manifest on GitHub to use as an example.

2. Delete and re-create any existing pods that are associated with the service account to apply the credential environment variables. The mutating web hook does not apply them to pods that are already running. The following command deletes the existing the aws-node DaemonSet pods and deploys them with the service account annotation. You can modify the namespace, deployment type, and label to update your specific pods.

```
kubectl delete pods -n <kube-system> -l <k8s-app=aws-node>
```

Confirm that the pods all restarted.

```
kubectl get pods -n <kube-system> -l <k8s-app=aws-node>
```

4. Describe one of the pods and verify that the AWS_WEB_IDENTITY_TOKEN_FILE and AWS_ROLE_ARN environment variables exist.

```
kubectl exec -n kube-system aws-node-<9rgzw> env | grep AWS
```

Output:

```
AWS_VPC_K8S_CNI_LOGLEVEL=DEBUG
AWS_ROLE_ARN=arn:aws:iam::<AWS_ACCOUNT_ID>:role/<IAM_ROLE_NAME>
AWS_WEB_IDENTITY_TOKEN_FILE=/var/run/secrets/eks.amazonaws.com/serviceaccount/token
```

Troubleshooting Amazon EKS identity and access

To diagnose and fix common issues that you might encounter when working with Amazon EKS and IAM see Troubleshooting IAM (p. 372).

Logging and monitoring in Amazon EKS

Amazon EKS control plane logging provides audit and diagnostic logs directly from the Amazon EKS control plane to CloudWatch Logs in your account. These logs make it easy for you to secure and run your clusters. You can select the exact log types you need, and logs are sent as log streams to a group for each Amazon EKS cluster in CloudWatch. For more information, see Amazon EKS Control Plane Logging (p. 66).

Note

When you check the Amazon EKS authenticator logs in Amazon CloudWatch, you'll see entries that contain text similar to the following example text.

Amazon EKS User Guide Compliance validation

Entries that contain this text are expected. The username is an Amazon EKS internal service role that performs specific operations for managed node groups and Fargate.

Amazon EKS is integrated with AWS CloudTrail, a service that provides a record of actions taken by a user, role, or an AWS service in Amazon EKS. CloudTrail captures all API calls for Amazon EKS as events. The calls captured include calls from the Amazon EKS console and code calls to the Amazon EKS API operations. For more information, see Logging Amazon EKS API calls with AWS CloudTrail (p. 358).

The Kubernetes API server exposes a number of metrics that are useful for monitoring and analysis. For more information, see Control plane metrics with Prometheus (p. 305).

Compliance validation for Amazon EKS

Third-party auditors assess the security and compliance of Amazon EKS as part of multiple AWS compliance programs. These include SOC, PCI, ISO, HIPAA, and others.

For a list of AWS services in scope of specific compliance programs, see AWS services in scope by compliance program. For general information, see AWS compliance programs.

You can download third-party audit reports using AWS Artifact. For more information, see Downloading reports in AWS Artifact.

Your compliance responsibility when using Amazon EKS is determined by the sensitivity of your data, your company's compliance objectives, and applicable laws and regulations. AWS provides the following resources to help with compliance:

- Security and compliance quick start guides These deployment guides discuss architectural
 considerations and provide steps for deploying security- and compliance-focused baseline
 environments on AWS.
- Architecting for HIPAA security and compliance paper This paper describes how companies can use AWS to create HIPAA-compliant applications.
- AWS compliance resources This collection of workbooks and guides might apply to your industry and location.
- AWS Config This AWS service assesses how well your resource configurations comply with internal practices, industry guidelines, and regulations.
- AWS Security Hub This AWS service provides a comprehensive view of your security state within AWS that helps you check your compliance with security industry standards and best practices.

Resilience in Amazon EKS

The AWS global infrastructure is built around AWS Regions and Availability Zones. AWS Regions provide multiple physically separated and isolated Availability Zones, which are connected with low-latency, high-throughput, and highly redundant networking. With Availability Zones, you can design and operate applications and databases that automatically fail over between Availability Zones without interruption. Availability Zones are more highly available, fault tolerant, and scalable than traditional single or multiple data center infrastructures.

Amazon EKS runs Kubernetes control plane instances across multiple Availability Zones to ensure high availability. Amazon EKS automatically detects and replaces unhealthy control plane instances, and it provides automated version upgrades and patching for them.

Amazon EKS User Guide Infrastructure security

This control plane consists of at least two API server nodes and three etcd nodes that run across three Availability Zones within a Region. Amazon EKS automatically detects and replaces unhealthy control plane instances, restarting them across the Availability Zones within the Region as needed. Amazon EKS leverages the architecture of AWS Regions in order to maintain high availability. Because of this, Amazon EKS is able to offer an SLA for API server endpoint availability.

For more information about AWS Regions and Availability Zones, see AWS global infrastructure.

Infrastructure security in Amazon EKS

As a managed service, Amazon EKS is protected by the AWS global network security procedures that are described in the Amazon Web Services: Overview of security processes paper.

You use AWS published API calls to access Amazon EKS through the network. Clients must support Transport Layer Security (TLS) 1.0 or later. We recommend TLS 1.2 or later. Clients must also support cipher suites with perfect forward secrecy (PFS) such as Ephemeral Diffie-Hellman (DHE) or Elliptic Curve Ephemeral Diffie-Hellman (ECDHE). Most modern systems such as Java 7 and later support these modes.

Additionally, requests must be signed by using an access key ID and a secret access key that is associated with an IAM principal. Or you can use the AWS Security Token Service (AWS STS) to generate temporary security credentials to sign requests.

When you create an Amazon EKS cluster, you specify the VPC subnets for your cluster to use. Amazon EKS requires subnets in at least two Availability Zones. We recommend a VPC with public and private subnets so that Kubernetes can create public load balancers in the public subnets that load balance traffic to pods running on nodes that are in private subnets.

For more information about VPC considerations, see Cluster VPC considerations (p. 202).

If you create your VPC and node groups with the AWS CloudFormation templates provided in the Getting started with Amazon EKS (p. 4) walkthrough, then your control plane and node security groups are configured with our recommended settings.

For more information about security group considerations, see Amazon EKS security group considerations (p. 204).

When you create a new cluster, Amazon EKS creates an endpoint for the managed Kubernetes API server that you use to communicate with your cluster (using Kubernetes management tools such as kubectl). By default, this API server endpoint is public to the internet, and access to the API server is secured using a combination of AWS Identity and Access Management (IAM) and native Kubernetes Role Based Access Control (RBAC).

You can enable private access to the Kubernetes API server so that all communication between your nodes and the API server stays within your VPC. You can limit the IP addresses that can access your API server from the internet, or completely disable internet access to the API server.

For more information about modifying cluster endpoint access, see Modifying cluster endpoint access (p. 57).

You can implement network policies with tools such as Project Calico (p. 239). Project Calico is a third party open source project. For more information, see the Project Calico documentation.

Configuration and vulnerability analysis in Amazon EKS

Security is a critical consideration for configuring and maintaining Kubernetes clusters and applications. The Center for Internet Security (CIS) Kubernetes Benchmark provides guidance for Amazon EKS node security configurations. The benchmark:

- Is applicable to Amazon EC2 nodes (both managed and self-managed) where you are responsible for security configurations of Kubernetes components.
- Provides a standard, community-approved way to ensure that you have configured your Kubernetes cluster and nodes securely when using Amazon EKS.
- Consists of four sections; control plane logging configuration, node security configurations, policies, and managed services.
- Supports all of the Kubernetes versions currently available in Amazon EKS and can be run using kubebench, a standard open source tool for checking configuration using the CIS benchmark on Kubernetes clusters.

To learn more, see Introducing The CIS Amazon EKS Benchmark.

Amazon EKS platform versions represent the capabilities of the cluster control plane, including which Kubernetes API server flags are enabled and the current Kubernetes patch version. New clusters are deployed with the latest platform version. For details, see Amazon EKS platform versions (p. 73).

You can update an Amazon EKS cluster (p. 43) to newer Kubernetes versions. As new Kubernetes versions become available in Amazon EKS, we recommend that you proactively update your clusters to use the latest available version. For more information about Kubernetes versions in EKS, see Amazon EKS Kubernetes versions (p. 68).

Track security or privacy events for Amazon Linux 2 at the Amazon Linux Security Center or subscribe to the associated RSS feed. Security and privacy events include an overview of the issue affected, packages, and instructions for updating your instances to correct the issue.

You can use Amazon Inspector to check for unintended network accessibility of your nodes and for vulnerabilities on those Amazon EC2 instances.

Amazon EKS security best practices

This topic provides security best practices for your cluster.

Restricting access to the IMDS and Amazon EC2 instance profile credentials

By default, the Amazon EC2 instance metadata service (IMDS) provides the credentials assigned to the node IAM role (p. 332) to the instance, and any container running on the instance. When you use IAM roles for service accounts (p. 336), it updates the credential chain of the pod to use the IAM roles for service accounts token. The pod, however, can still inherit the rights of the instance profile assigned to the node. We recommended that you block pod access to IMDS to minimize the permissions available to your containers if:

• You've implemented IAM roles for service accounts and have assigned necessary permissions directly to all pods that require access to AWS services.

• No pods in your cluster require access to IMDS for other reasons, such as retrieving the current Region.

For more information, see Retrieving Security Credentials from Instance Metadata. You can prevent access to IMDS from your instance and containers using one of the following options.

Important

If you use the AWS Load Balancer Controller in your cluster, you may need to change your load balancer configuration. For more information, see To deploy the AWS Load Balancer Controller to an Amazon EKS cluster (p. 262).

• Block access to IMDSv1 from the node and all containers and block access to IMDSv2 for all containers that don't use host networking – Your instance and pods that have hostNetwork: true in their pod spec use host networking. To implement this option, complete the steps in the row and column that apply to your situation.

Deployment method	New node group	Existing node group
Managed nodes without a custom launch template	Not possible using any deployment method other than eksctl. If deploying with eksctl, use thedisable-pod-imds option with eksctl create nodegroup. eksctl can be used because it creates a launch template based on options you specify and deploys the node group using that launch template.	We recommend creating a new node group with a custom launch template that includes the settings in the New node group column of the next row of this table.
Managed nodes with a custom launch template	Set the following settings in the launch template's (p. 112) Advanced details: • Metadata accessible – Enabled • Metadata version – V2 only (token required) • Metadata response hop limit – 1	Update your launch template with the settings in the New column and then update your node group (p. 108) using the new launch template version.
Self-managed	If creating the node group using the AWS Management Console Download the selfmanaged node group AWS CloudFormation template for your Region and operating system. Linux – All Regions other than China (Beijing) and China (Ningxia) https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10-	If updating or migrating the node group using the AWS Management Console Download the selfmanaged node group AWS CloudFormation template for your Region and operating system. Linux – All Regions other than China (Beijing) and China (Ningxia) https://s3.us-west-2.amazonaws.com/amazon-eks/cloudformation/2020-10

Deployment method	New node group	Existing node group
	amazon-eks- nodegroup.yaml	amazon-eks- nodegroup.yaml
	• Linux – China (Beijing) and China (Ningxia)	Linux – China (Beijing) and China (Ningxia)
	https://s3.cn- north-1.amazonaws.com. amazon-eks// cloudformation/2020-10 amazon-eks- nodegroup.yaml	amazon-eks//
	 Windows – All Regions other than China (Beijing) and China (Ningxia) 	 Windows – All Regions other than China (Beijing) and China (Ningxia)
	https://s3.us- west-2.amazonaws.com/ amazon-eks/ cloudformation/2020-10 amazon-eks-windows- nodegroup.yaml	https://s3.us- west-2.amazonaws.com/ amazon-eks/ cloudformation/2020-10-2 amazon-eks-windows- nodegroup.yaml
	 Windows – China (Beijing) and China (Ningxia) 	Windows – China (Beijing) and China (Ningxia)
	https://s3.cn- north-1.amazonaws.com. amazon-eks// cloudformation/2020-10 amazon-eks-windows- nodegroup.yaml	amazon-eks//
	Edit the file. Change the line that says	Edit the file. Change the line that says
	2 to	<pre>it : HttpPutResponseHopLimit 2 to it : HttpPutResponseHopLimit 1 and save the file.</pre>
	3. Deploy the node group using the instructions in the section called "Amazon Linux" (p. 116) or the section called "Windows" (p. 124). For the instruction about specifying an AWS CloudFormation template, instead of selecting Amazon S3 URL, select Upload a template file, then select Choose file, choose your edited file,	3. Update your self-managed node group using the instructions in ??? (p. 133). For the instruction about specifying an AWS CloudFormation template, instead of selecting Amazon S3 URL, select Upload a template file, then select Choose file, choose your edited file, and then continue on with the instructions. Set the value of DisableIMDSv1 to

Amazon EKS User Guide Restricting access to the instance profile

Deployment method	New node group	Existing node group
	the instructions. Set the value of DisableIMDSv1 to true too. • If creating the node group using eksctl, use the disable-pod-imds option with eksctl create nodegroup.	Important Each time you update the node group, for any reason, such as a new AMI or Kubernetes version, you need to change the previous settings in the template again. If migrating the node group using eksctl, then when you create the new node group, use thedisable-pod- imds option with eksctl create nodegroup.
		Important Each time you update the node group, for any reason, such as a new AMI or Kubernetes version, make sure to use this option when creating your new node group.

• Block access to IMDSv1 and IMDSv2 for all containers that don't use host networking – Your instance and pods that have hostNetwork: true in their pod spec use host networking, but for legacy reasons still require access to IMDSv1. Run the following iptables commands on each of your Amazon Linux nodes (as root) or include them in your instance bootstrap user data script.

```
yum install -y iptables-services
iptables --insert FORWARD 1 --in-interface eni+ --destination 169.254.169.254/32 --jump
DROP
iptables-save | tee /etc/sysconfig/iptables
systemctl enable --now iptables
```

Important

- The previous rule applies only to network interfaces within the node that have a name that starts with eni, which is all network interfaces that the CNI plugin creates for pods that don't use host networking. Traffic to the IMDS is not dropped for the node, or for pods that use host networking, such as kube-proxy and the CNI plugin.
- If you implement network policy, using a tool such as Calico (p. 239), the previous rule may be overridden. When implementing network policy, ensure that it doesn't override this rule, or that your policy includes this rule.
- If you've applied security groups to pods and therefore, have branch network interfaces, in addition to the previous command, also run the following command.

```
iptables -t mangle -A POSTROUTING -o vlan+ --destination 169.254.169.254/32 -- jump DROP
```

For more information about branch network interfaces, see Security groups for pods (p. 213).

Pod security policy

The Kubernetes pod security policy admission controller validates pod creation and update requests against a set of rules. By default, Amazon EKS clusters ship with a fully permissive security policy with no restrictions. For more information, see Pod Security Policies in the Kubernetes documentation.

Note

The pod security policy admission controller is only enabled on Amazon EKS clusters running Kubernetes version 1.13 or later. You must update your cluster's Kubernetes version to at least 1.13 to use pod security policies. For more information, see Updating a Cluster (p. 43).

Amazon EKS default pod security policy

Amazon EKS clusters with Kubernetes version 1.13 and higher have a default pod security policy named eks.privileged. This policy has no restriction on what kind of pod can be accepted into the system, which is equivalent to running Kubernetes with the PodSecurityPolicy controller disabled.

Note

This policy was created to maintain backwards compatibility with clusters that did not have the PodSecurityPolicy controller enabled. You can create more restrictive policies for your cluster and for individual namespaces and service accounts and then delete the default policy to enable the more restrictive policies.

You can view the default policy with the following command.

```
kubectl get psp eks.privileged
```

Output:

NAME VOLUMES	PRIV	CAPS	SELINUX	RUNASUSER	FSGROUP	SUPGROUP	READONLYROOTFS
eks.privileged *	true	*	RunAsAny	RunAsAny	RunAsAny	RunAsAny	false

For more details, you can describe the policy with the following command.

```
kubectl describe psp eks.privileged
```

Output:

```
Name: eks.privileged
Settings:
 Allow Privileged:
                                           true
 Allow Privilege Escalation:
                                           0xc0004ce5f8
 Default Add Capabilities:
                                           <none>
 Required Drop Capabilities:
                                           <none>
 Allowed Capabilities:
 Allowed Volume Types:
 Allow Host Network:
                                           true
 Allow Host Ports:
                                           0-65535
 Allow Host PID:
                                           true
```

Amazon EKS User Guide Amazon EKS default pod security policy

```
Allow Host IPC:
                                          true
Read Only Root Filesystem:
                                          false
SELinux Context Strategy: RunAsAny
  User:
                                          <none>
  Role:
                                          <none>
  Type:
                                          <none>
 Level:
                                          <none>
Run As User Strategy: RunAsAny
 Ranges:
                                          <none>
FSGroup Strategy: RunAsAny
 Ranges:
                                          <none>
Supplemental Groups Strategy: RunAsAny
 Ranges:
                                          <none>
```

The following example shows the full YAML file for the eks.privileged pod security policy, its cluster role, and cluster role binding.

```
apiVersion: policy/v1beta1
kind: PodSecurityPolicy
metadata:
  name: eks.privileged
  annotations:
    kubernetes.io/description: 'privileged allows full unrestricted access to
      pod features, as if the PodSecurityPolicy controller was not enabled.'
    seccomp.security.alpha.kubernetes.io/allowedProfileNames: '*'
  labels:
    kubernetes.io/cluster-service: "true"
    eks.amazonaws.com/component: pod-security-policy
spec:
 privileged: true
  allowPrivilegeEscalation: true
  allowedCapabilities:
  volumes:
  - '*'
  hostNetwork: true
  hostPorts:
  - min: 0
   max: 65535
  hostIPC: true
  hostPID: true
  runAsUser:
   rule: 'RunAsAny'
  seLinux:
   rule: 'RunAsAny'
  {\tt supplementalGroups:}
   rule: 'RunAsAny'
  fsGroup:
    rule: 'RunAsAny'
  readOnlyRootFilesystem: false
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRole
metadata:
  name: eks:podsecuritypolicy:privileged
  labels:
    kubernetes.io/cluster-service: "true"
    eks.amazonaws.com/component: pod-security-policy
rules:
 apiGroups:
  - policy
  resourceNames:
```

Amazon EKS User Guide Amazon EKS default pod security policy

```
- eks.privileged
  resources:
  - podsecuritypolicies
  verbs:
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
  name: eks:podsecuritypolicy:authenticated
  annotations:
   kubernetes.io/description: 'Allow all authenticated users to create privileged pods.'
    kubernetes.io/cluster-service: "true"
    eks.amazonaws.com/component: pod-security-policy
roleRef:
  apiGroup: rbac.authorization.k8s.io
  kind: ClusterRole
  name: eks:podsecuritypolicy:privileged
subjects:
  - kind: Group
   apiGroup: rbac.authorization.k8s.io
    name: system:authenticated
```

To delete the default pod security policy

After you create custom pod security policies for your cluster, you can delete the default Amazon EKS eks.privileged pod security policy to enable your custom policies.

- 1. Create a file called privileged-podsecuritypolicy.yaml and paste the full eks.privileged YAML file contents from the preceding example into it (this allows you to delete the pod security policy, the ClusterRole, and the ClusterRoleBinding associated with it).
- 2. Delete the YAML with the following command.

```
kubectl delete -f privileged-podsecuritypolicy.yaml
```

To install or restore the default pod security policy

If you are upgrading from an earlier version of Kubernetes, or have modified or deleted the default Amazon EKS eks.privileged pod security policy, you can restore it with the following steps.

 Create a file called privileged-podsecuritypolicy.yaml and paste the YAML file contents below into it.

```
apiVersion: policy/v1beta1
kind: PodSecurityPolicy
metadata:
   name: eks.privileged
   annotations:
   kubernetes.io/description: 'privileged allows full unrestricted access to
        pod features, as if the PodSecurityPolicy controller was not enabled.'
        seccomp.security.alpha.kubernetes.io/allowedProfileNames: '*'
labels:
        kubernetes.io/cluster-service: "true"
        eks.amazonaws.com/component: pod-security-policy
spec:
    privileged: true
allowPrivilegeEscalation: true
```

```
allowedCapabilities:
  volumes:
  - '*'
  hostNetwork: true
  hostPorts:
  - min: 0
   max: 65535
  hostIPC: true
  hostPID: true
  runAsUser:
   rule: 'RunAsAny'
  seLinux:
   rule: 'RunAsAny'
  {\tt supplementalGroups:}
   rule: 'RunAsAny'
  fsGroup:
   rule: 'RunAsAny'
  readOnlyRootFilesystem: false
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRole
metadata:
  name: eks:podsecuritypolicy:privileged
  labels:
    kubernetes.io/cluster-service: "true"
    eks.amazonaws.com/component: pod-security-policy
rules:
- apiGroups:
  - policy
 resourceNames:
  - eks.privileged
  resources:
  - podsecuritypolicies
  verbs:
  - 1156
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
 name: eks:podsecuritypolicy:authenticated
  annotations:
   kubernetes.io/description: 'Allow all authenticated users to create privileged
pods.'
  labels:
    kubernetes.io/cluster-service: "true"
    eks.amazonaws.com/component: pod-security-policy
roleRef:
  apiGroup: rbac.authorization.k8s.io
  kind: ClusterRole
 name: eks:podsecuritypolicy:privileged
subjects:
  - kind: Group
    apiGroup: rbac.authorization.k8s.io
    name: system:authenticated
```

2. Apply the YAML with the following command.

```
kubectl apply -f privileged-podsecuritypolicy.yaml
```

AWS services integrated with Amazon EKS

Amazon EKS works with other AWS services to provide additional solutions for your business challenges. This topic identifies services that either use Amazon EKS to add functionality, or services that Amazon EKS uses to perform tasks.

Contents

- Creating Amazon EKS resources with AWS CloudFormation (p. 357)
- Logging Amazon EKS API calls with AWS CloudTrail (p. 358)
- Amazon EKS on AWS Outposts (p. 361)
- Use App Mesh with Kubernetes (p. 358)
- Amazon EKS on AWS Local Zones (p. 363)
- Deep Learning Containers (p. 364)

Creating Amazon EKS resources with AWS CloudFormation

Amazon EKS is integrated with AWS CloudFormation, a service that helps you model and set up your AWS resources so that you can spend less time creating and managing your resources and infrastructure. You create a template that describes all the AWS resources that you want, for example an Amazon EKS cluster, and AWS CloudFormation takes care of provisioning and configuring those resources for you.

When you use AWS CloudFormation, you can reuse your template to set up your Amazon EKS resources consistently and repeatedly. Just describe your resources once, and then provision the same resources over and over in multiple AWS accounts and Regions.

Amazon EKS and AWS CloudFormation templates

To provision and configure resources for Amazon EKS and related services, you must understand AWS CloudFormation templates. Templates are formatted text files in JSON or YAML. These templates describe the resources that you want to provision in your AWS CloudFormation stacks. If you're unfamiliar with JSON or YAML, you can use AWS CloudFormation Designer to help you get started with AWS CloudFormation templates. For more information, see What is AWS CloudFormation Designer? in the AWS CloudFormation User Guide.

Amazon EKS supports creating clusters and node groups in AWS CloudFormation. For more information, including examples of JSON and YAML templates for your Amazon EKS resources, see Amazon EKS resource type reference in the AWS CloudFormation User Guide.

Learn more about AWS CloudFormation

To learn more about AWS CloudFormation, see the following resources:

AWS CloudFormation

- AWS CloudFormation User Guide
- AWS CloudFormation Command Line Interface User Guide

Use App Mesh with Kubernetes

App Mesh is a service mesh that makes it easy to monitor and control services. App Mesh standardizes how your services communicate, giving you end-to-end visibility and helping to ensure high availability for your applications. App Mesh gives you consistent visibility and network traffic controls for every service in an application. You can get started using App Mesh with Kubernetes by completing the Getting started with AWS App Mesh and Kubernetes tutorial in the AWS App Mesh User Guide. The tutorial recommends that you have an existing Kubernetes cluster and applications deployed that you want to use App Mesh with.

Logging Amazon EKS API calls with AWS CloudTrail

Amazon EKS is integrated with AWS CloudTrail, a service that provides a record of actions taken by a user, role, or an AWS service in Amazon EKS. CloudTrail captures all API calls for Amazon EKS as events, including calls from the Amazon EKS console and from code calls to the Amazon EKS API operations.

If you create a trail, you can enable continuous delivery of CloudTrail events to an Amazon S3 bucket, including events for Amazon EKS. If you don't configure a trail, you can still view the most recent events in the CloudTrail console in **Event history**. Using the information collected by CloudTrail, you can determine the request that was made to Amazon EKS, the IP address from which the request was made, who made the request, when it was made, and additional details.

To learn more about CloudTrail, see the AWS CloudTrail User Guide.

Amazon EKS information in CloudTrail

CloudTrail is enabled on your AWS account when you create the account. When activity occurs in Amazon EKS, that activity is recorded in a CloudTrail event along with other AWS service events in **Event history**. You can view, search, and download recent events in your AWS account. For more information, see Viewing events with CloudTrail event history.

For an ongoing record of events in your AWS account, including events for Amazon EKS, create a trail. A *trail* enables CloudTrail to deliver log files to an Amazon S3 bucket. By default, when you create a trail in the console, the trail applies to all AWS Regions. The trail logs events from all Regions in the AWS partition and delivers the log files to the Amazon S3 bucket that you specify. Additionally, you can configure other AWS services to further analyze and act upon the event data collected in CloudTrail logs. For more information, see the following:

- Overview for creating a trail
- CloudTrail supported services and integrations
- Configuring Amazon SNS notifications for CloudTrail
- Receiving CloudTrail log files from multiple regions and Receiving CloudTrail log files from multiple accounts

All Amazon EKS actions are logged by CloudTrail and are documented in the Amazon EKS API Reference. For example, calls to the CreateCluster, ListClusters and DeleteCluster sections generate entries in the CloudTrail log files.

Every event or log entry contains information about who generated the request. The identity information helps you determine the following:

- Whether the request was made with root or AWS Identity and Access Management (IAM) user credentials.
- Whether the request was made with temporary security credentials for a role or federated user.
- · Whether the request was made by another AWS service.

For more information, see the CloudTrail userIdentity element.

Understanding Amazon EKS log file entries

A trail is a configuration that enables delivery of events as log files to an Amazon S3 bucket that you specify. CloudTrail log files contain one or more log entries. An event represents a single request from any source and includes information about the requested action, the date and time of the action, request parameters, and so on. CloudTrail log files aren't an ordered stack trace of the public API calls, so they don't appear in any specific order.

The following example shows a CloudTrail log entry that demonstrates the CreateCluster action.

```
"eventVersion": "1.05",
"userIdentity": {
  "type": "IAMUser",
  "principalId": "AKIAIOSFODNN7EXAMPLE",
  "arn": "arn:aws:iam::111122223333:user/username",
  "accountId": "111122223333",
  "accessKeyId": "AKIAIOSFODNN7EXAMPLE",
  "userName": "username"
},
"eventTime": "2018-05-28T19:16:43Z",
"eventSource": "eks.amazonaws.com",
"eventName": "CreateCluster",
"awsRegion": "<region-code>"
"sourceIPAddress": "205.251.233.178",
"userAgent": "PostmanRuntime/6.4.0",
"requestParameters": {
  "resourcesVpcConfig": {
    "subnetIds": [
      "subnet-a670c2df",
      "subnet-4f8c5004"
    ]
  },
  "roleArn": "arn:aws:iam::111122223333:role/AWSServiceRoleForAmazonEKS-CAC1G1VH3ZKZ",
  "clusterName": "test"
"responseElements": {
  "cluster": {
    "clusterName": "test",
    "status": "CREATING",
    "createdAt": 1527535003.208,
    "certificateAuthority": {},
    "arn": "arn:aws:eks:<region-code>:111122223333:cluster/test",
    "roleArn": "arn:aws:iam::111122223333:role/AWSServiceRoleForAmazonEKS-CAC1G1VH3ZKZ",
    "version": "1.10",
    "resourcesVpcConfig":
      "securityGroupIds": [],
      "vpcId": "vpc-21277358",
      "subnetIds": [
        "subnet-a670c2df",
        "subnet-4f8c5004"
```

```
]
}
}

requestID": "a7a0735d-62ab-11e8-9f79-81ce5b2b7d37",
"eventID": "eab22523-174a-499c-9dd6-91e7be3ff8e3",
"readOnly": false,
"eventType": "AwsApiCall",
"recipientAccountId": "111122223333"
}
```

Log Entries for Amazon EKS Service Linked Roles

The Amazon EKS service linked roles make API calls to AWS resources. You will see CloudTrail log entries with username: AWSServiceRoleForAmazonEKS and username: AWSServiceRoleForAmazonEKSNodegroup for calls made by the Amazon EKS service linked roles. For more information about Amazon EKS and service linked roles, see Using Service-Linked Roles for Amazon EKS (p. 326).

The following example shows a CloudTrail log entry that demonstrates a DeleteInstanceProfile action made by the AWSServiceRoleForAmazonEKSNodegroup service linked role, noted in the sessionContext.

```
"eventVersion": "1.05",
    "userIdentity": {
        "type": "AssumedRole",
        "principalId": "AROA3WHGPEZ7SJ2CW55C5:EKS",
        "arn": "arn:aws:sts::111122223333:assumed-role/AWSServiceRoleForAmazonEKSNodegroup/
EKS",
        "accountId": "111122223333",
        "accessKeyId": "AKIAIOSFODNN7EXAMPLE",
        "sessionContext": {
            "sessionIssuer": {
                "type": "Role",
                "principalId": "AROA3WHGPEZ7SJ2CW55C5",
                "arn": "arn:aws:iam::111122223333:role/aws-service-role/eks-
nodegroup.amazonaws.com/AWSServiceRoleForAmazonEKSNodegroup",
                "accountId": "111122223333",
                "userName": "AWSServiceRoleForAmazonEKSNodegroup"
            "webIdFederationData": {},
            "attributes": {
                "mfaAuthenticated": "false",
                "creationDate": "2020-02-26T00:56:33Z"
        "invokedBy": "eks-nodegroup.amazonaws.com"
    "eventTime": "2020-02-26T00:56:34Z",
    "eventSource": "iam.amazonaws.com",
    "eventName": "DeleteInstanceProfile",
    "awsRegion": "us-east-1",
    "sourceIPAddress": "eks-nodegroup.amazonaws.com",
    "userAgent": "eks-nodegroup.amazonaws.com",
    "requestParameters": {
        "instanceProfileName": "eks-11111111-2222-3333-4444-abcdef123456"
    "responseElements": null,
    "requestID": "11111111-2222-3333-4444-abcdef123456",
    "eventID": "11111111-2222-3333-4444-abcdef123456",
    "eventType": "AwsApiCall",
    "recipientAccountId": "111122223333"
```

}

Amazon EKS on AWS Outposts

You can create and run Amazon EKS nodes on AWS Outposts. AWS Outposts enables native AWS services, infrastructure, and operating models in on-premises facilities. In AWS Outposts environments, you can use the same AWS APIs, tools, and infrastructure that you use in the AWS Cloud. Amazon EKS nodes on AWS Outposts is ideal for low-latency workloads that need to be run in close proximity to on-premises data and applications. For more information about AWS Outposts, see the AWS Outposts User Guide.

Prerequisites

The following are the prerequisites for using Amazon EKS nodes on AWS Outposts:

- · You must have installed and configured an Outpost in your on-premises data center.
- · You must have a reliable network connection between your Outpost and its AWS Region.
- The AWS Region for the Outpost must support Amazon EKS. For a list of supported Regions, see Amazon EKS service endpoints in the AWS General Reference.

Considerations

- AWS Identity and Access Management, Application Load Balancer, Network Load Balancer, Classic Load Balancer, and Amazon Route 53 run in the AWS Region, not on Outposts. This will increase latencies between the services and the containers.
- AWS Fargate is not available on AWS Outposts.
- Managed node groups cannot be deployed to nodes on an Outpost.
- · You cannot use AWS Outposts in China Regions

Network connectivity considerations


The following are network connectivity considerations for Amazon EKS AWS Outposts:

- If network connectivity between your Outpost and its AWS Region is lost, your nodes will continue to run. However, you cannot create new nodes or take new actions on existing deployments until connectivity is restored. In case of instance failures, the instance will not be automatically replaced. The Kubernetes control plane runs in the Region, and missing heartbeats caused by things like a loss of connectivity to the Availability Zone could lead to failures. The failed heartbeats will lead to pods on the Outposts being marked as unhealthy, and eventually the node status will time out and pods will be marked for eviction. For more information, see Node Controller in the Kubernetes documentation.
- We recommend that you provide reliable, highly available, and low-latency connectivity between your Outpost and its AWS Region.

Creating Amazon EKS nodes on an Outpost

Creating Amazon EKS nodes on an Outpost is similar to creating Amazon EKS nodes in the AWS Cloud. When you create an Amazon EKS node on an Outpost, you must specify a subnet associated with your Outpost.

An Outpost is an extension of an AWS Region, and you can extend a VPC in an account to span multiple Availability Zone and any associated Outpost locations. When you configure your Outpost, you associate a subnet with it to extend your Regional VPC environment to your on-premises facility. Instances on an Outpost appear as part of your Regional VPC, similar to an Availability Zone with associated subnets.



To create Amazon EKS nodes on an Outpost with the AWS CLI, specify a security group and a subnet associated with your Outpost.

To create an Amazon EKS node group on an Outpost

1. Create a VPC.

```
aws ec2 create-vpc --cidr-block <10.0.0/16>
```

 Create Outpost subnets. The --outpost-arn parameter must be specified for the subnet to be created for the Outpost. (This step is different for AWS Outposts.)

```
aws ec2 create-subnet --vpc-id <vpc-xxxxxxxxx> --cidr-block <10.0.3.0/24> \
    --outpost-arn arn:aws:outposts:<us-west-2>:123456789012:outpost/<op-
xxxxxxxxxxxxxxxx<>
```

Create a cluster, specifying the subnets for the Outpost. (This step is different for AWS Outposts.)

```
aws eks --region <region-code> create-cluster --name <eks-outpost> --role-arn \
    arn:aws:iam::123456789012:role/<eks-service-role-AWSServiceRoleForAmazonEKS-OUTPOST>
    \
    --resources-vpc-config subnetIds=<subnet-xxxxxxxxx>,<subnet-
yyyyyyyy>,securityGroupIds=<sg-xxxxxxxxx>
```

4. Create the node group. Specify an instance type that is available on your Outpost. (This step is different for AWS Outposts.)

Amazon EKS User Guide Use App Mesh with Kubernetes

5. Deploy applications and services.

```
kubectl apply -f kubernetes/deployment.yaml
```

Use App Mesh with Kubernetes

App Mesh is a service mesh that makes it easy to monitor and control services. App Mesh standardizes how your services communicate, giving you end-to-end visibility and helping to ensure high availability for your applications. App Mesh gives you consistent visibility and network traffic controls for every service in an application. You can get started using App Mesh with Kubernetes by completing the Getting started with AWS App Mesh and Kubernetes tutorial in the AWS App Mesh User Guide. The tutorial recommends that you have existing services deployed to Kubernetes that you want to use App Mesh with.

Amazon EKS on AWS Local Zones

An AWS Local Zone is an extension of an AWS Region in geographic proximity to your users. Local Zones have their own connections to the internet and support AWS Direct Connect. Resources created in a Local Zone can serve local users with low-latency communications. For more information, see Local Zones.

Amazon EKS supports running certain infrastructure, including Amazon EC2 instances, Amazon EBS volumes, and Application Load Balancers from a Local Zone as part of your cluster. There are several considerations when using Local Zone infrastructure as part of your Amazon EKS cluster.

Kubernetes versions

Only Amazon EKS clusters running Kubernetes versions 1.17 and later can use Local Zone compute resources.

Nodes

Amazon EKS does not support creating managed node groups in AWS Local Zones. You must create self-managed nodes using the Amazon EC2 API or AWS CloudFormation. **Do not use eksctl to create your cluster or nodes in Local Zones**. For details and options, follow the instructions in Self-managed nodes (p. 116).

Network architecture

The Amazon EKS managed Kubernetes control plane always runs in the AWS Region. The Amazon EKS managed Kubernetes control plane cannot run in the Local Zone. Since Local Zones appear as a subnet within your VPC, Kubernetes sees your Local Zone resources as part of that subnet.

The Amazon EKS Kubernetes cluster communicates with the Amazon EC2 instances you run in the AWS Region or Local Zone using Amazon EKS managed elastic network interfaces. To learn more about Amazon EKS networking architecture, see Amazon EKS networking (p. 196).

Amazon EKS User Guide Deep Learning Containers

Unlike regional subnets, Amazon EKS cannot place network interfaces into your Local Zone subnets. This means that you must not specify Local Zone subnets when you create your cluster.

After the cluster is created, tag your Local Zone subnets with the Amazon EKS cluster name. For more information, see Subnet tagging requirement (p. 204). You can then deploy self-managed nodes to the Local Zone subnets and the nodes will be able to join your Amazon EKS cluster.

Deep Learning Containers

AWS Deep Learning Containers are a set of Docker images for training and serving models in TensorFlow on Amazon EKS and Amazon Elastic Container Service (Amazon ECS). Deep Learning Containers provide optimized environments with TensorFlow, Nvidia CUDA (for GPU instances), and Intel MKL (for CPU instances) libraries and are available in Amazon ECR.

To get started using AWS Deep Learning Containers on Amazon EKS, see AWS Deep Learning Containers on Amazon EKS in the AWS Deep Learning AMI Developer Guide.

Amazon EKS troubleshooting

This chapter covers some common errors that you may see while using Amazon EKS and how to work around them.

Insufficient capacity

If you receive the following error while attempting to create an Amazon EKS cluster, then one of the Availability Zones you specified does not have sufficient capacity to support a cluster.

Cannot create cluster 'example-cluster' because region-1d, the targeted Availability Zone, does not currently have sufficient capacity to support the cluster. Retry and choose from these Availability Zones: region-1a, region-1b, region-1c

Retry creating your cluster with subnets in your cluster VPC that are hosted in the Availability Zones returned by this error message.

Nodes fail to join cluster

There are a few common reasons that prevent nodes from joining the cluster:

- The aws-auth-cm.yaml file does not have the correct IAM role ARN for your nodes. Ensure that the node IAM role ARN (not the instance profile ARN) is specified in your aws-auth-cm.yaml file. For more information, see Launching self-managed Amazon Linux nodes (p. 116).
- The ClusterName in your node AWS CloudFormation template does not exactly match the name of
 the cluster you want your nodes to join. Passing an incorrect value to this field results in an incorrect
 configuration of the node's /var/lib/kubelet/kubeconfig file, and the nodes will not join the
 cluster.
- The node is not tagged as being *owned* by the cluster. Your nodes must have the following tag applied to them, where <cluster-name> is replaced with the name of your cluster.

Key	Value
kubernetes.io/cluster/ <cluster-name></cluster-name>	owned

- The nodes may not be able to access the cluster using a public IP address. Ensure that nodes deployed in public subnets are assigned a public IP address. If not, you can associate an elastic IP address to a node after it's launched. For more information, see Associating an elastic IP address with a running instance or network interface. If the public subnet is not set to automatically assign public IP addresses to instances deployed to it, then we recommend enabling that setting. For more information, see Modifying the public IPv4 addressing attribute for your subnet. If the node is deployed to a private subnet, then the subnet must have a route to a NAT gateway that has a public IP address assigned to it.
- The STS endpoint for the Region that you're deploying the nodes to is not enabled for your account. To enable the region, see Activating and deactivating AWS STS in an AWS Region.

Unauthorized or access denied (kubectl)

If you receive one of the following errors while running kubectl commands, then your kubectl is not configured properly for Amazon EKS or the IAM user or role credentials that you are using do not map to a Kubernetes RBAC user with sufficient permissions in your Amazon EKS cluster.

- could not get token: AccessDenied: Access denied
- error: You must be logged in to the server (Unauthorized)
- error: the server doesn't have a resource type "svc"

This could be because the cluster was created with one set of AWS credentials (from an IAM user or role), and kubectl is using a different set of credentials.

When an Amazon EKS cluster is created, the IAM entity (user or role) that creates the cluster is added to the Kubernetes RBAC authorization table as the administrator (with <code>system:masters</code> permissions). Initially, only that IAM user can make calls to the Kubernetes API server using <code>kubectl</code>. For more information, see Managing users or IAM roles for your cluster (p. 285). If you use the console to create the cluster, you must ensure that the same IAM user credentials are in the AWS SDK credential chain when you are running <code>kubectl</code> commands on your cluster.

If you install and configure the AWS CLI, you can configure the IAM credentials for your user. For more information, see Configuring the AWS CLI in the AWS Command Line Interface User Guide.

If you assumed a role to create the Amazon EKS cluster, you must ensure that kubectl is configured to assume the same role. Use the following command to update your kubeconfig file to use an IAM role. For more information, see Create a kubeconfig for Amazon EKS (p. 281).

```
aws --region <region-code> eks update-kubeconfig --name <cluster_name> --role-arn
arn:aws:iam::<aws_account_id>:role/<role_name>
```

To map an IAM user to a Kubernetes RBAC user, see Managing users or IAM roles for your cluster (p. 285) or watch a video about how to map a user.

aws-iam-authenticator Not found

If you receive the error "aws-iam-authenticator": executable file not found in \$PATH, then your kubectl is not configured for Amazon EKS. For more information, see Installing aws-iam-authenticator (p. 277).

Note

The aws-iam-authenticator is not required if you have the AWS CLI version 1.16.156 or higher installed.

hostname doesn't match

Your system's Python version must be 2.7.9 or later. Otherwise, you receive hostname doesn't match errors with AWS CLI calls to Amazon EKS. For more information, see What are "hostname doesn't match" errors? in the Python Requests FAQ.

getsockopt: no route to host

Docker runs in the 172.17.0.0/16 CIDR range in Amazon EKS clusters. We recommend that your cluster's VPC subnets do not overlap this range. Otherwise, you will receive the following error:

```
Error: : error upgrading connection: error dialing backend: dial tcp 172.17.<nn>:10250: getsockopt: no route to host
```

Managed node group errors

If you receive the error "Instances failed to join the kubernetes cluster" in the AWS Management Console, ensure that either the cluster's private endpoint access is enabled, or that you have correctly configured CIDR blocks for public endpoint access. For more information, see Amazon EKS cluster endpoint access control (p. 56).

If your managed node group encounters a health issue, Amazon EKS returns an error message to help you to diagnose the issue. The following error messages and their associated descriptions are shown below.

- AccessDenied: Amazon EKS or one or more of your managed nodes is failing to authenticate or authorize with your Kubernetes cluster API server. For more information about resolving this error, see Fixing AccessDenied errors for managed node groups (p. 368).
- AutoScalingGroupNotFound: We couldn't find the Auto Scaling group associated with the managed node group. You may be able to recreate an Auto Scaling group with the same settings to recover.
- ClusterUnreachable: Amazon EKS or one or more of your managed nodes is unable to to communicate with your Kubernetes cluster API server. This can happen if there are network disruptions or if API servers are timing out processing requests.
- **Ec2SecurityGroupNotFound**: We couldn't find the cluster security group for the cluster. You must recreate your cluster.
- **Ec2SecurityGroupDeletionFailure**: We could not delete the remote access security group for your managed node group. Remove any dependencies from the security group.
- **Ec2LaunchTemplateNotFound**: We couldn't find the Amazon EC2 launch template for your managed node group. You may be able to recreate a launch template with the same settings to recover.
- Ec2LaunchTemplateVersionMismatch: The Amazon EC2 launch template version for your managed node group does not match the version that Amazon EKS created. You may be able to revert to the version that Amazon EKS created to recover.
- **IamInstanceProfileNotFound**: We couldn't find the IAM instance profile for your managed node group. You may be able to recreate an instance profile with the same settings to recover.
- **IamNodeRoleNotFound**: We couldn't find the IAM role for your managed node group. You may be able to recreate an IAM role with the same settings to recover.
- AsgInstanceLaunchFailures: Your Auto Scaling group is experiencing failures while attempting to launch instances.
- NodeCreationFailure: Your launched instances are unable to register with your Amazon EKS cluster.
 Common causes of this failure are insufficient node IAM role (p. 332) permissions or lack of outbound internet access for the nodes. Your nodes must be able to access the internet using a public IP address to function properly. For more information, see VPC IP addressing (p. 202). Your nodes must also have ports open to the internet. For more information, see Amazon EKS security group considerations (p. 204).
- InstanceLimitExceeded: Your AWS account is unable to launch any more instances of the specified instance type. You may be able to request an Amazon EC2 instance limit increase to recover.

- InsufficientFreeAddresses: One or more of the subnets associated with your managed node group does not have enough available IP addresses for new nodes.
- InternalFailure: These errors are usually caused by an Amazon EKS server-side issue.

Fixing AccessDenied errors for managed node groups

The most common cause of AccessDenied errors when performing operations on managed node groups is missing the eks:node-manager ClusterRole or ClusterRoleBinding. Amazon EKS sets up these resources in your cluster as part of onboarding with managed node groups, and these are required for managing the node groups.

The ClusterRole may change over time, but it should look similar to the following example:

```
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRole
metadata:
 name: eks:node-manager
rules:
- apiGroups:
  resources:
  - pods
  verbs:
  - aet
  - list
  - watch
  - delete
apiGroups:
  resources:
  - nodes
  verbs:
  - get
  - list
  - watch
  - patch
- apiGroups:
  resources:
  - pods/eviction
  verbs:
  - create
```

The ClusterRoleBinding may change over time, but it should look similar to the following example:

```
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
  name: eks:node-manager
roleRef:
  apiGroup: rbac.authorization.k8s.io
  kind: ClusterRole
  name: eks:node-manager
subjects:
  apiGroup: rbac.authorization.k8s.io
  kind: User
  name: eks:node-manager
```

Verify that the eks:node-manager ClusterRole exists.

Amazon EKS User Guide Managed node group errors

```
kubectl describe clusterrole eks:node-manager
```

If present, compare the output to the previous ClusterRole example.

Verify that the eks:node-manager ClusterRoleBinding exists.

```
kubectl describe clusterrolebinding eks:node-manager
```

If present, compare the output to the previous ClusterRoleBinding example.

If you've identified a missing or broken ClusterRole or ClusterRoleBinding as the cause of an AcessDenied error while requesting managed node group operations, you can restore them. Save the following contents to a file named eks-node-manager-role.yaml.

```
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRole
metadata:
 name: eks:node-manager
rules:
- apiGroups:
 resources:
  - pods
  verbs:
  - get
  - list
  - watch
  - delete
- apiGroups:
  resources:
  - nodes
 verbs:
  - get
 - list
  - watch
  - patch
- apiGroups:
  resources:
  - pods/eviction
 verbs:
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
 name: eks:node-manager
roleRef:
 apiGroup: rbac.authorization.k8s.io
  kind: ClusterRole
 name: eks:node-manager
subjects:
- apiGroup: rbac.authorization.k8s.io
  kind: User
  name: eks:node-manager
```

Apply the file.

```
kubectl apply -f eks-node-manager-role.yaml
```

Retry the node group operation to see if that resolved your issue.

CNI log collection tool

The Amazon VPC CNI plugin for Kubernetes has its own troubleshooting script (which is available on nodes at /opt/cni/bin/aws-cni-support.sh) that you can use to collect diagnostic logs for support cases and general troubleshooting.

Use the following command to run the script on your node:

```
sudo bash /opt/cni/bin/aws-cni-support.sh
```

Note

If the script is not present at that location, then the CNI container failed to run. You can manually download and run the script with the following command:

```
curl -0 https://raw.githubusercontent.com/awslabs/amazon-eks-ami/master/log-
collector-script/linux/eks-log-collector.sh
sudo bash eks-log-collector.sh
```

The script collects the following diagnostic information. The CNI version that you have deployed can be earlier than the script version.

```
This is version 0.6.1. New versions can be found at https://github.com/awslabs/
amazon-eks-ami
Trying to collect common operating system logs...
Trying to collect kernel logs...
Trying to collect mount points and volume information...
Trying to collect SELinux status...
Trying to collect iptables information...
Trying to collect installed packages...
Trying to collect active system services...
Trying to collect Docker daemon information...
Trying to collect kubelet information...
Trying to collect L-IPAMD information...
Trying to collect sysctls information...
Trying to collect networking information...
Trying to collect CNI configuration information...
Trying to collect running Docker containers and gather container data...
Trying to collect Docker daemon logs...
Trying to archive gathered information...
Done... your bundled logs are located in /var/log/eks i-0717c9d54b6cfaa19 2020-03-24 0103-
UTC_0.6.1.tar.gz
```

The diagnostic information is collected and stored at

```
/var/log/eks_i-0717c9d54b6cfaa19_2020-03-24_0103-UTC_0.6.1.tar.gz
```

Container runtime network not ready

You may receive a Container runtime network not ready error and authorization errors similar to the following:

Amazon EKS User Guide TLS handshake timeout

```
4191 kubelet.go:2130] Container runtime network not ready: NetworkReady=false reason:NetworkPluginNotReady message:docker: network plugin is not ready: cni config uninitialized
4191 reflector.go:205] k8s.io/kubernetes/pkg/kubelet/kubelet.go:452: Failed to list
*v1.Service: Unauthorized
4191 kubelet_node_status.go:106] Unable to register node "ip-10-40-175-122.ec2.internal"
with API server: Unauthorized
4191 reflector.go:205] k8s.io/kubernetes/pkg/kubelet/kubelet.go:452: Failed to list
*v1.Service: Unauthorized
```

The errors are most likely related to the AWS IAM Authenticator configuration map not being applied to the nodes. The configuration map provides the <code>system:bootstrappers</code> and <code>system:nodes</code> Kubernetes RBAC permissions for nodes to register to the cluster. For more information, see **To enable nodes to join your cluster** on the **Self-managed nodes** tab of Launching self-managed Amazon Linux nodes (p. 116). Ensure that you specify the **Role ARN** of the instance role in the configuration map, not the **Instance Profile ARN**.

The authenticator does not recognize a **Role ARN** if it includes a path other than /, such as the following example:

```
arn:aws:iam::<111122223333>:role/<development/apps/prod-iam-role-
NodeInstanceRole-621LVEXAMPLE>
```

When specifying a **Role ARN** in the configuration map that includes a path other than /, you must drop the path. The ARN above would be specified as the following:

```
arn:aws:iam::<111122223333>:role/cprod-iam-role-NodeInstanceRole-621LVEXAMPLE>
```

TLS handshake timeout

When a node is unable to establish a connection to the public API server endpoint, you may an error similar to the following error.

```
server.go:233] failed to run Kubelet: could not init cloud provider "aws": error finding instance i-1111f2222f333e44c: "error listing AWS instances: \"RequestError: send request failed\\ncaused by: Post net/http: TLS handshake timeout\""
```

The kubelet process will continually respawn and test the API server endpoint. The error can also occur temporarily during any procedure that performs a rolling update of the cluster in the control plane, such as a configuration change or version update.

To resolve the issue, check the route table and security groups to ensure that traffic from the nodes can reach the public endpoint.

InvalidClientTokenId

If you're using IAM roles for service accounts for a pod or daemonset deployed to a cluster in a China Region, and haven't set the AWS_DEFAULT_REGION environment variable in the spec, the pod or daemonset may receive the following error:

An error occurred (InvalidClientTokenId) when calling the GetCallerIdentity operation: The security token included in the request is invalid

To resolve the issue, you need to add the AWS_DEFAULT_REGION environment variable to your pod or daemonset spec, as shown in the following example pod spec.

Troubleshooting IAM

This topic covers some common errors that you may see while using Amazon EKS with IAM and how to work around them.

AccessDeniedException

If you receive an AccessDeniedException when calling an AWS API operation, then the AWS Identity and Access Management (IAM) user or role credentials that you are using do not have the required permissions to make that call.

```
An error occurred (AccessDeniedException) when calling the DescribeCluster operation:
User: arn:aws:iam::<111122223333>:user/<user_name> is not authorized to perform:
eks:DescribeCluster on resource: arn:aws:eks<:region>:<111122223333>:cluster/<cluster_name>
```

In the above example message, the user does not have permissions to call the Amazon EKS DescribeCluster API operation. To provide Amazon EKS admin permissions to a user, see Amazon EKS identity-based policy examples (p. 322).

For more general information about IAM, see Controlling access using policies in the IAM User Guide.

Can't see workloads or nodes and receive an error in the AWS Management Console

You may see a console error message that says Your current user or role does not have access to Kubernetes objects on this EKS cluster. Make sure that the IAM entity (user or role) that you're signed into the AWS Management Console with meets all of the following requirements:

- Has an IAM policy attached to it that includes the eks:AccessKubernetesApi action. For an example IAM policy, see View nodes and workloads for all clusters in the AWS Management Console (p. 324). If you're using the IAM policy visual editor in the AWS Management Console and you don't see the eks:AccessKubernetesApi Permission listed, edit the policy's JSON and add eks:AccessKubernetesApi to the list of Actions in the JSON.
- Has a mapping to a Kubernetes user or group in the aws-auth configmap. For more information
 about adding IAM users or roles to the aws-auth configmap, see Managing users or IAM roles for your

cluster (p. 285). If the user or role isn't mapped, the console error may include **Unauthorized: Verify** you have access to the Kubernetes cluster.

- The Kubernetes user or group that the IAM account or role is mapped to in the configmap must be a subject in a rolebinding or clusterrolebinding that is bound to a Kubernetes role or clusterrole that has the necessary permissions to view the Kubernetes resources. If the user or group doesn't have the necessary permissions, the console error may include Unauthorized:

 Verify you have access to the Kubernetes cluster. To create roles and bindings, see Using RBAC Authorization in the Kubernetes documentation. You can download the following example manifests that create a clusterrole and clusterrolebinding or a role and rolebinding:
 - View Kubernetes resources in all namespaces The group name in the file is eks-console-dashboard-full-access-group, which is the group that your IAM user or role needs to be mapped to in the aws-auth configmap. You can change the name of the group before applying it to your cluster, if desired, and then map your IAM user or role to that group in the configmap. To download the file, select the appropriate link for the Region that your cluster is in.
 - All Regions other than Beijing and Ningxia China
 - · Beijing and Ningxia China Regions
 - View Kubernetes resources in a specific namespace The namespace in this file is default, so if you want to specify a different namespace, edit the file before applying it to your cluster. The group name in the file is eks-console-dashboard-restricted-access-group, which is the group that your IAM user or role needs to be mapped to in the aws-auth configmap. You can change the name of the group before applying it to your cluster, if desired, and then map your IAM user or role to that group in the configmap. To download the file, select the appropriate link for the Region that your cluster is in.
 - · All Regions other than Beijing and Ningxia China
 - · Beijing and Ningxia China Regions

aws-auth ConfigMap does not grant access to the cluster

AWS IAM authenticator does not permit a path in the role ARN used in the configuration map. Therefore, before you specify rolearn, remove the path. For example, change arn:aws:iam::<123456789012>:role/<team>/<developers>/<eks-admin> to arn:aws:iam::<123456789012>:role/<eks-admin>.

I Am not authorized to perform iam:PassRole

If you receive an error that you're not authorized to perform the iam: PassRole action, then you must contact your administrator for assistance. Your administrator is the person that provided you with your user name and password. Ask that person to update your policies to allow you to pass a role to Amazon EKS.

Some AWS services allow you to pass an existing role to that service, instead of creating a new service role or service-linked role. To do this, you must have permissions to pass the role to the service.

The following example error occurs when an IAM user named marymajor tries to use the console to perform an action in Amazon EKS. However, the action requires the service to have permissions granted by a service role. Mary does not have permissions to pass the role to the service.

User: arn:aws:iam::123456789012:user/marymajor is not authorized to perform: iam:PassRole

In this case, Mary asks her administrator to update her policies to allow her to perform the iam: PassRole action.

I want to view my access keys

After you create your IAM user access keys, you can view your access key ID at any time. However, you can't view your secret access key again. If you lose your secret key, you must create a new access key pair.

Access keys consist of two parts: an access key ID (for example, AKIAIOSFODNN7EXAMPLE) and a secret access key (for example, wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY). Like a user name and password, you must use both the access key ID and secret access key together to authenticate your requests. Manage your access keys as securely as you do your user name and password.

Important

Do not provide your access keys to a third party, even to help find your canonical user ID. By doing this, you might give someone permanent access to your account.

When you create an access key pair, you are prompted to save the access key ID and secret access key in a secure location. The secret access key is available only at the time you create it. If you lose your secret access key, you must add new access keys to your IAM user. You can have a maximum of two access keys. If you already have two, you must delete one key pair before creating a new one. To view instructions, see Managing access keys in the IAM User Guide.

I'm an administrator and want to allow others to access Amazon EKS

To allow others to access Amazon EKS, you must create an IAM entity (user or role) for the person or application that needs access. They will use the credentials for that entity to access AWS. You must then attach a policy to the entity that grants them the correct permissions in Amazon EKS.

To get started right away, see Creating your first IAM delegated user and group in the IAM User Guide.

I want to allow people outside of my AWS account to access my Amazon EKS resources

You can create a role that users in other accounts or people outside of your organization can use to access your resources. You can specify who is trusted to assume the role. For services that support resource-based policies or access control lists (ACLs), you can use those policies to grant people access to your resources.

To learn more, consult the following:

- To learn whether Amazon EKS supports these features, see How Amazon EKS works with IAM (p. 319).
- To learn how to provide access to your resources across AWS accounts that you own, see Providing access to an IAM user in another AWS account that you own in the IAM User Guide.
- To learn how to provide access to your resources to third-party AWS accounts, see Providing access to AWS accounts owned by third parties in the IAM User Guide.
- To learn how to provide access through identity federation, see Providing access to externally authenticated users (identity federation) in the IAM User Guide.
- To learn the difference between using roles and resource-based policies for cross-account access, see How IAM roles differ from resource-based policies in the IAM User Guide.

Amazon EKS Distro

Amazon EKS Distro is a distribution of the same open source Kubernetes software and dependencies deployed by Amazon EKS in the cloud. With Amazon EKS Distro, you can create reliable and secure clusters wherever your applications are deployed. You can rely on the same versions of Kubernetes deployed by Amazon EKS, etcd, CoreDNS, upstream CNI, and CSI sidecars with the latest updates and extended security patching support. Amazon EKS Distro follows the same Kubernetes version release cycle as Amazon EKS and is provided as an open-source project.

Note

The source code for the Amazon EKS Distro is available on GitHub. The latest documentation is available on the Amazon EKS Distro website. If you find any issues, you can report them with Amazon EKS Distro by connecting with us on GitHub. There you can open issues, provide feedback, and report bugs.

Related projects

These open-source projects extend the functionality of Kubernetes clusters running on or outside of AWS, including clusters managed by Amazon EKS.

Management tools

Related management tools for Amazon EKS and Kubernetes clusters.

eksctl

eksctl is a simple CLI tool for creating clusters on Amazon EKS.

- Project URL: https://eksctl.io/
- Project documentation: https://eksctl.io/
- · AWS open source blog: eksctl: Amazon EKS cluster with one command

AWS controllers for Kubernetes

With AWS Controllers for Kubernetes, you can create and manage AWS resources directly from your Kubernetes cluster.

- Project URL: https://aws.github.io/aws-controllers-k8s/
- AWS open-source blog: AWS service operator for Kubernetes now available

Flux CD

Flux is a tool that you can use to manage your cluster configuration using Git. It uses an operator in the cluster to trigger deployments inside of Kubernetes. For more information about operators, see Awesome Operators in the Wild on GitHub.

- Project URL: https://fluxcd.io/
- Project documentation: https://docs.fluxcd.io/

CDK for Kubernetes

With the CDK for Kubernetes (cdk8s), you can define Kubernetes apps and components using familiar programming languages. cdk8s apps synthesize into standard Kubernetes manifests, which can be applied to any Kubernetes cluster.

- Project URL: https://cdk8s.io/
- Project documentation: https://github.com/awslabs/cdk8s/tree/master/docs/getting-started
- AWS containers blog: Introducing cdk8s+: Intent-driven APIs for Kubernetes objects

Networking

Related networking projects for Amazon EKS and Kubernetes clusters.

Amazon VPC CNI plugin for Kubernetes

Amazon EKS supports native VPC networking through the Amazon VPC CNI plugin for Kubernetes. Using this CNI plugin allows Kubernetes pods to have the same IP address inside the pod as they do on the VPC network. For more information, see Pod networking (CNI) (p. 208) and CNI configuration variables (p. 229).

- Project URL: https://github.com/aws/amazon-vpc-cni-k8s
- Project documentation: https://github.com/aws/amazon-vpc-cni-k8s/blob/master/README.md

AWS Application Load Balancer (ALB) ingress controller for Kubernetes

The AWS ALB Ingress Controller satisfies Kubernetes ingress resources by provisioning Application Load Balancers.

- Project URL: https://github.com/kubernetes-sigs/aws-alb-ingress-controller
- Project documentation: https://github.com/kubernetes-sigs/aws-alb-ingress-controller/tree/master/docs
- AWS open-source blog: Kubernetes ingress with AWS ALB ingress controller

External DNS

External DNS synchronizes exposed Kubernetes services and ingresses with DNS providers including Amazon Route 53 and AWS Service Discovery.

- Project URL: https://github.com/kubernetes-incubator/external-dns
- Project documentation: https://github.com/kubernetes-incubator/external-dns/blob/master/docs/tutorials/aws.md

App Mesh Controller

The App Mesh Controller for Kubernetes helps to manage App Mesh for your cluster. With the controller, you can manage the service mesh using custom resources within your cluster. The controller manages the injection of networking proxy sidecars to pods to enable the mesh.

- Project URL: https://github.com/aws/aws-app-mesh-controller-for-k8s
- Project documentation: https://docs.aws.amazon.com/app-mesh/latest/userguide/mesh-k8s-integration.html
- AWS blog: Getting started with App Mesh and Amazon EKS

Security

Related security projects for Amazon EKS and Kubernetes clusters.

AWS IAM authenticator

A tool to use AWS IAM credentials to authenticate to a Kubernetes cluster if you're not using the AWS CLI version 1.16.156 or higher. For more information, see Installing aws-iam-authenticator (p. 277).

- Project URL: https://github.com/kubernetes-sigs/aws-iam-authenticator
- Project documentation: https://github.com/kubernetes-sigs/aws-iam-authenticator/blob/master/ README.md
- AWS open source blog: Deploying the AWS IAM authenticator to kops

Machine learning

Related machine learning projects for Amazon EKS and Kubernetes clusters.

Kubeflow

A machine learning toolkit for Kubernetes.

- Project URL: https://www.kubeflow.org/
- Project documentation: https://www.kubeflow.org/docs/
- AWS open source blog: Kubeflow on Amazon EKS

Auto Scaling

Related auto scaling projects for Amazon EKS and Kubernetes clusters.

Cluster autoscaler

Cluster Autoscaler is a tool that automatically adjusts the size of the Kubernetes cluster based on CPU and memory pressure.

- Project URL: https://github.com/kubernetes/autoscaler/tree/master/cluster-autoscaler
- Project documentation: https://github.com/kubernetes/autoscaler/blob/master/cluster-autoscaler/ cloudprovider/aws/README.md
- Amazon EKS workshop: https://eksworkshop.com/scaling/deploy_ca/

Escalator

Escalator is a batch or job optimized horizontal autoscaler for Kubernetes.

- Project URL: https://github.com/atlassian/escalator
- Project documentation: https://github.com/atlassian/escalator/blob/master/docs/README.md

Monitoring

Related monitoring projects for Amazon EKS and Kubernetes clusters.

Prometheus

Prometheus is an open-source systems monitoring and alerting toolkit.

- Project URL: https://prometheus.io/
- Project documentation: https://prometheus.io/docs/introduction/overview/
- Amazon EKS workshop: https://eksworkshop.com/intermediate/240_monitoring/

Continuous integration / continuous deployment

Related CI/CD projects for Amazon EKS and Kubernetes clusters.

Jenkins X

CI/CD solution for modern cloud applications on Amazon EKS and Kubernetes clusters.

- Project URL: https://jenkins-x.io/
- Project documentation: https://jenkins-x.io/docs/

Document history for Amazon EKS

The following table describes the major updates and new features for the Amazon EKS User Guide. We also update the documentation frequently to address the feedback that you send us.

update-history-change	update-history-description	update-history-date
View node and workload resources in the AWS Management Console	You can now view details about your managed, self-managed, and Fargate nodes and your deployed Kubernetes workloads in the AWS Management Console.	December 1, 2020
Deploy Spot Instance types in a managed node group	You can now deploy multiple Spot or On-Demand Instance types to a managed node group.	December 1, 2020
Amazon EKS can now manage specific add-ons for your cluster	You can manage add-ons yourself, or let Amazon EKS control the launch and version of an add-on through the Amazon EKS API for clusters running Kubernetes version 1.18 with platform version eks.3 or later.	December 1, 2020
Share an ALB across multiple Ingresses	You can now share an AWS Application Load Balancer across multiple Kubernetes Ingresses. In the past, you had to deploy a separate Application Load Balancer for each Ingress.	October 23, 2020
NLB IP target support	You can now deploy a network load balancer (NLB) with IP targets. This enables you to use an NLB to load balance network traffic to Fargate pods and directly to pods running on Amazon EC2 nodes.	October 23, 2020
Kubernetes version 1.18	Added Kubernetes version 1.18 support for new clusters and version upgrades.	October 13, 2020
Specify a custom CIDR block for Kubernetes service IP address assignment.	You can now specify a custom CIDR block that Kubernetes will assign service IP addresses from.	September 29, 2020
Assign security groups to individual pods	You can now associate different security groups to some of the individual pods running on many Amazon EC2 instance types.	September 9, 2020
Deploy Bottlerocket on your nodes	You can now deploy nodes running Bottlerocket.	August 31, 2020

The ability to launch Arm nodes is generally available	You can now launch Arm nodes in managed and self-managed node groups.	August 17, 2020
Managed node group launch templates and custom AMI	You can now deploy a managed node group using an Amazon EC2 launch template. The launch template can specify a custom AMI, if you choose.	August 17, 2020
EFS support for AWS Fargate	You can now use Amazon EFS with AWS Fargate.	August 17, 2020
Amazon EKS platform version update	New platform version with security fixes and enhancements, including UDP support for services of type LoadBalancer when using NLB with Kubernetes 1.15 or later. For more information, see the Allow UDP for AWS NLB issue on GitHub.	August 12, 2020
Amazon EKS Region expansion (p. 380)	Amazon EKS is now available in the Africa (Cape Town) (afsouth-1) and Europe (Milan) (eu-south-1) Regions.	August 6, 2020
Fargate usage metrics	AWS Fargate provides CloudWatch usage metrics which provide visibility into your accounts usage of Fargate On- Demand resources.	August 3, 2020
Kubernetes version 1.17	Added Kubernetes version 1.17 support for new clusters and version upgrades.	July 10, 2020
Create and manage App Mesh resources from within Kubernetes with the App Mesh controller for Kubernetes	You can create and manage App Mesh resources from within Kubernetes. The controller also automatically injects the Envoy proxy and init containers into pods that you deploy.	June 18, 2020
Amazon EKS now supports Amazon EC2 Inf1 nodes	You can add Amazon EC2 Inf1 nodes to your cluster.	June 4, 2020
Amazon EKS Region expansion (p. 380)	Amazon EKS is now available in the AWS GovCloud (US-East) (us-gov-east-1) and AWS GovCloud (US-West) (us-gov-west-1) Regions.	May 13, 2020
Kubernetes 1.12 deprecated on Amazon EKS	Kubernetes version 1.12 is no longer supported on Amazon EKS. Please update any 1.12 clusters to version 1.13 or higher in order to avoid service interruption.	May 12, 2020

Kubernetes version 1.16	Added Kubernetes version 1.16 support for new clusters and version upgrades.	April 30, 2020
Added the AWSServiceRoleForAmazonEKS service-linked role	Added the AWSServiceRoleForAmazonEKS service-linked role.	April 16, 2020
Kubernetes version 1.15	Added Kubernetes version 1.15 support for new clusters and version upgrades.	March 10, 2020
Amazon EKS Region expansion (p. 380)	Amazon EKS is now available in the Beijing (cn-north-1) and Ningxia (cn-northwest-1) Regions.	February 26, 2020
Amazon FSx for Lustre CSI driver	Added topic for installing the Amazon FSx for Lustre CSI Driver on Kubernetes 1.14 Amazon EKS clusters.	December 23, 2019
Restrict network access to the public access endpoint of a cluster	Amazon EKS now enables you to restrict the CIDR ranges that can communicate to the public access endpoint of the Kubernetes API server.	December 20, 2019
Resolve the private access endpoint address for a cluster from outside of a VPC	Amazon EKS now enables you to resolve the private access endpoint of the Kubernetes API server from outside of a VPC.	December 13, 2019
(Beta) Amazon EC2 A1 Amazon EC2 instance nodes	Launch Amazon EC2 A1 Amazon EC2 instance nodes that register with your Amazon EKS cluster.	December 4, 2019
Creating a cluster on AWS Outposts	Amazon EKS now supports creating clusters on an AWS Outpost.	December 3, 2019
AWS Fargate on Amazon EKS	Amazon EKS Kubernetes clusters now support running pods on Fargate.	December 3, 2019
Amazon EKS Region expansion (p. 380)	Amazon EKS is now available in the Canada (Central) (cacentral-1) Region.	November 21, 2019
Managed node groups	Amazon EKS managed node groups automate the provisioning and lifecycle management of nodes (Amazon EC2 instances) for Amazon EKS Kubernetes clusters.	November 18, 2019
Amazon EKS platform version update	New platform versions to address CVE-2019-11253.	November 6, 2019

Kubernetes 1.11 de Amazon EKS	precated on	Kubernetes version 1.11 is no longer supported on Amazon EKS. Please update any 1.11 clusters to version 1.12 or higher in order to avoid service interruption.	November 4, 2019
Amazon EKS Region expansion (p. 380)	า	Amazon EKS is now available in the South America (São Paulo) (sa-east-1) Region.	October 16, 2019
Windows support		Amazon EKS clusters running Kubernetes version 1.14 now support Windows workloads.	October 7, 2019
Autoscaling		Added a chapter to cover some of the different types of Kubernetes autoscaling that are supported on Amazon EKS clusters.	September 30, 2019
Kubernetes Dashbo	ard update	Updated topic for installing the Kubernetes Dashboard on Amazon EKS clusters to use the beta 2.0 version.	September 28, 2019
Amazon EFS CSI dri	iver	Added topic for installing the Amazon EFS CSI Driver on Kubernetes 1.14 Amazon EKS clusters.	September 19, 2019
Amazon EC2 Syster parameter for Ama optimized AMI ID		Added topic for retrieving the Amazon EKS optimized AMI ID using an Amazon EC2 Systems Manager parameter. The parameter eliminates the need for you to look up AMI IDs.	September 18, 2019
Amazon EKS resour	ce tagging	Manage tagging of your Amazon EKS clusters.	September 16, 2019
Amazon EBS CSI dr	iver	Added topic for installing the Amazon EBS CSI driver on Kubernetes 1.14 Amazon EKS clusters.	September 9, 2019
New Amazon EKS of patched for CVE-2019-9514		Amazon EKS has updated the Amazon EKS optimized AMI to address CVE-2019-9512 and CVE-2019-9514.	September 6, 2019

Announcing deprecation of Kubernetes 1.11 in Amazon EKS	Amazon EKS will deprecate Kubernetes version 1.11 on November 4, 2019. On this day, you will no longer be able to create new 1.11 clusters and all Amazon EKS clusters running Kubernetes version 1.11 will be updated to the latest available platform version of Kubernetes version 1.12.	September 4, 2019
Kubernetes version 1.14	Added Kubernetes version 1.14 support for new clusters and version upgrades.	September 3, 2019
IAM roles for service accounts	With IAM roles for service accounts on Amazon EKS clusters, you can associate an IAM role with a Kubernetes service account. With this feature, you no longer need to provide extended permissions to the node IAM role so that pods on that node can call AWS APIs.	September 3, 2019
Amazon EKS Region expansion (p. 380)	Amazon EKS is now available in the Middle East (Bahrain) (mesouth-1) Region.	August 29, 2019
Amazon EKS platform version update	New platform versions to address CVE-2019-9512 and CVE-2019-9514.	August 28, 2019
Amazon EKS platform version update	New platform versions to address CVE-2019-11247 and CVE-2019-11249.	August 5, 2019
Amazon EKS Region expansion (p. 380)	Amazon EKS is now available in the Asia Pacific (Hong Kong) (ap-east-1) Region.	July 31, 2019
Kubernetes 1.10 deprecated on Amazon EKS	Kubernetes version 1.10 is no longer supported on Amazon EKS. Please update any 1.10 clusters to version 1.11 or higher in order to avoid service interruption.	July 30, 2019
Added topic on ALB ingress controller	The AWS ALB Ingress Controller for Kubernetes is a controller that triggers the creation of an Application Load Balancer when ingress resources are created.	July 11, 2019
New Amazon EKS optimized AMI	Removing unnecessary kubectl binary from AMIs.	July 3, 2019

Kubernetes version 1.13	Added Kubernetes version 1.13 support for new clusters and version upgrades.	June 18, 2019
New Amazon EKS optimized AMI patched for AWS-2019-005	Amazon EKS has updated the Amazon EKS optimized AMI to address the vulnerabilities described in AWS-2019-005.	June 17, 2019
Announcing deprecation of Kubernetes 1.10 in Amazon EKS	Amazon EKS will deprecate Kubernetes version 1.10 on July 22, 2019. On this day, you will no longer be able to create new 1.10 clusters and all Amazon EKS clusters running Kubernetes version 1.10 will be updated to the latest available platform version of Kubernetes version 1.11.	May 21, 2019
Amazon EKS platform version update	New platform version for Kubernetes 1.11 and 1.10 clusters to support custom DNS names in the Kubelet certificate and improve etcd performance.	May 21, 2019
Getting started with eksctl	This getting started guide helps you to install all of the required resources to get started with Amazon EKS using eksctl, a simple command line utility for creating and managing Kubernetes clusters on Amazon EKS.	May 10, 2019
AWS CLI get-token command (p. 380)	The aws eks get-token command was added to the AWS CLI so that you no longer need to install the AWS IAM Authenticator for Kubernetes to create client security tokens for cluster API server communication. Upgrade your AWS CLI installation to the latest version to take advantage of this new functionality. For more information, see Installing the AWS command line interface in the AWS Command Line Interface User Guide.	May 10, 2019

Amazon EKS platform version update	New platform version for Kubernetes 1.12 clusters to support custom DNS names in the Kubelet certificate and improve etcd performance. This fixes a bug that caused node Kubelet daemons to request a new certificate every few seconds.	May 8, 2019
Prometheus tutorial	Added topic for deploying Prometheus to your Amazon EKS cluster.	April 5, 2019
Amazon EKS control plane logging	Amazon EKS control plane logging makes it easy for you to secure and run your clusters by providing audit and diagnostic logs directly from the Amazon EKS control plane to CloudWatch Logs in your account.	April 4, 2019
Kubernetes version 1.12 (p. 380)	Added Kubernetes version 1.12 support for new clusters and version upgrades.	March 28, 2019
Added App Mesh getting started guide	Added documentation for getting started with App Mesh and Kubernetes.	March 27, 2019
Amazon EKS API server endpoint private access	Added documentation for disabling public access for your Amazon EKS cluster's Kubernetes API server endpoint.	March 19, 2019
Added topic for installing the Kubernetes Metrics Server	The Kubernetes Metrics Server is an aggregator of resource usage data in your cluster.	March 18, 2019
Added list of related open source projects	These open source projects extend the functionality of Kubernetes clusters running on AWS, including clusters managed by Amazon EKS.	March 15, 2019
Added topic for installing Helm locally	The helm package manager for Kubernetes helps you install and manage applications on your Kubernetes cluster. This topic helps you install and run the helm and tiller binaries locally so that you can install and manage charts using the helm CLI on your local system.	March 11, 2019

Amazon EKS platform version update	New platform version updating Amazon EKS Kubernetes 1.11 clusters to patch level 1.11.8 to address CVE-2019-1002100.	March 8, 2019
Increased cluster limit	Amazon EKS has increased the number of clusters that you can create in a Region from 3 to 50.	February 13, 2019
Amazon EKS Region expansion (p. 380)	Amazon EKS is now available in the Europe (London) (eu-west-2), Europe (Paris) (eu-west-3), and Asia Pacific (Mumbai) (ap-south-1) Regions.	February 13, 2019
New Amazon EKS optimized AMI patched for ALAS-2019-1156	Amazon EKS has updated the Amazon EKS optimized AMI to address the vulnerability described in ALAS-2019-1156.	February 11, 2019
New Amazon EKS optimized AMI patched for ALAS2-2019-1141	Amazon EKS has updated the Amazon EKS optimized AMI to address the CVEs referenced in ALAS2-2019-1141.	January 9, 2019
Amazon EKS Region expansion (p. 380)	Amazon EKS is now available in the Asia Pacific (Seoul) (apnortheast-2) Region.	January 9, 2019
Amazon EKS region expansion (p. 380)	Amazon EKS is now available in the following additional regions: Europe (Frankfurt) (eucentral-1), Asia Pacific (Tokyo) (ap-northeast-1), Asia Pacific (Singapore) (ap-southeast-1), and Asia Pacific (Sydney) (apsoutheast-2).	December 19, 2018
Amazon EKS cluster updates	Added documentation for Amazon EKS cluster Kubernetes version updates and node replacement.	December 12, 2018
Amazon EKS Region expansion (p. 380)	Amazon EKS is now available in the Europe (Stockholm) (eunorth-1) Region.	December 11, 2018
Amazon EKS platform version update	New platform version updating Kubernetes to patch level 1.10.11 to address CVE-2018-1002105.	December 4, 2018
Added version 1.0.0 support for the Application Load Balancer ingress controller	The Application Load Balancer ingress controller releases version 1.0.0 with formal support from AWS.	November 20, 2018

Added support for CNI network	The Amazon VPC CNI plugin	October 16, 2018
configuration	for Kubernetes version 1.2.1 now supports custom network configuration for secondary pod network interfaces.	
Added support for MutatingAdmissionWebhook and ValidatingAdmissionWebhook	Amazon EKS platform version 1.10-eks.2 now supports MutatingAdmissionWebhook and ValidatingAdmissionWebhook admission controllers.	October 10, 2018
Added partner AMI information	Canonical has partnered with Amazon EKS to create node AMIs that you can use in your clusters.	October 3, 2018
Added instructions for AWS CLI update-kubeconfig command	Amazon EKS has added the update-kubeconfig to the AWS CLI to simplify the process of creating a kubeconfig file for accessing your cluster.	September 21, 2018
New Amazon EKS optimized AMIs	Amazon EKS has updated the Amazon EKS optimized AMIs (with and without GPU support) to provide various security fixes and AMI optimizations.	September 13, 2018
Amazon EKS Region expansion (p. 380)	Amazon EKS is now available in the Europe (Ireland) (eu-west-1) region.	September 5, 2018
Amazon EKS platform version update	New platform version with support for Kubernetes aggregation layer and the Horizontal Pod Autoscaler(HPA).	August 31, 2018
New Amazon EKS optimized AMIs and GPU support	Amazon EKS has updated the Amazon EKS optimized AMI to use a new AWS CloudFormation node template and bootstrap script. In addition, a new Amazon EKS optimized AMI with GPU support is available.	August 22, 2018
New Amazon EKS optimized AMI patched for ALAS2-2018-1058	Amazon EKS has updated the Amazon EKS optimized AMI to address the CVEs referenced in ALAS2-2018-1058.	August 14, 2018
Amazon EKS optimized AMI build scripts	Amazon EKS has open-sourced the build scripts that are used to build the Amazon EKS optimized AMI. These build scripts are now available on GitHub.	July 10, 2018
Amazon EKS initial release (p. 380)	Initial documentation for service launch	June 5, 2018