11.2.7 Creating a FlashCopy Consistency Group

To create a FlashCopy Consistency Group in the GUI, complete the following steps:

 Open the Consistency Groups window by clicking Copy Services → Consistency Groups. Click Create Consistency Group, as shown in Figure 11-38.




Figure 11-38 Creating a consistency group

2. Enter the FlashCopy Consistency Group name that you want to use and click **Create**, as shown in Figure 11-39.



Figure 11-39 Enter the name of new consistency group

Consistency Group name: You can use the letters A - Z and a - z, the numbers 0 - 9, and the underscore (_) character. The volume name can be 1 - 63 characters.

11.2.8 Creating FlashCopy mappings in a Consistency Group

To create a FlashCopy Consistency Group in the GUI, complete the following steps:

- Open the Consistency Groups window by clicking Copy Services → Consistency Groups. This example assumes that source and target volumes were previously created.
- Select the Consistency Group that you want to create the FlashCopy mapping in. If you prefer not to create a FlashCopy mapping in a Consistency Group, select Not in a Group, and right-click the selected consistency group or click Actions → Create FlashCopy Mapping, as shown in Figure 11-40 on page 511.