```
//SYSUT2 DD DSN=&USERHLQ..&SITE..&VTSID..BVIRPHY,MGMTCLAS=&MC,
//
              UNIT=&UNIT, LABEL=(,SL), DISP=(NEW, CATLG),
//
              DCB=(RECFM=FB,BLKSIZE=80,LRECL=80,TRTCH=NOCOMP)
//SYSIN
          DD DUMMY
//*
//STEP3
          EXEC PGM=IEBGENER
//SYSPRINT DD SYSOUT=*
//SYSUT1 DD DSN=&USERHLQ..&SITE..&VTSID..BVIRPHY,DISP=(OLD,DELETE),
          DCB=(DSORG=PS, RECFM=U, BLKSIZE=320)
//SYSUT2 DD DSN=&USERHLQ..&SITE..&VTSID..PHYFILE,
//
          UNIT=SYSDA, SPACE=(320, (500000, 200000), RLSE),
//
          DISP=(,CATLG),DCB=(DSORG=PS,RECFM=U,BLKSIZE=320)
//SYSIN
          DD DUMMY
// PEND
//*
//GETVOLS EXEC BVIRPHY, VTSID=CLO, MC=
//*
```

## **Physical Volume Pool Status report**

For a formatted report of the physical volume pool status, use BVIRPLNN (see Example E-10). The output of BVIRPLNN can then be processed by using BVIRPRPT (see "Physical Volume and Pool Status Report Writer" on page 866) to produce a fully formatted report.

Example E-10 Sample JCL for BVIRPLNN

```
//ITS01
            JOB CONSOLE,
         MSGCLASS=H, MSGLEVEL=(1,1), CLASS=B,
//
//
         TIME=1440, REGION=2M
//*
//*
//*
   THIS JOB ISSUES THE BULK VOLUME INFORMATION (BVIR) REQUEST FOR
//* MEDIA POOLING STATISTICS FROM THE VE ASSOCIATED WITH THE VIRTUAL
//* DRIVE ADDRESS USED.
//*
//* TO ENSURE THAT BVIR REQUESTS ARE SATISFIED FROM THE PROPER
//* CLUSTER, YOU SHOULD HAVE MANAGEMENT CLASSES FOR RNN(CLO), NRN(CL1)
//* AND NNR(CL2) SO THAT ONLY THE TARGET CLUSTER WILL HAVE A COPY OF
//* THE BVIR VOLUME. YOU CAN'T CONTROL WHERE THE INITIAL SCRATCH
//* MOUNT IS SATISFIED, BUT YOU CAN CONTROL WHICH TVC THE VOLUME WILL
//* BE IN WHEN THE SUBSEQUENT SPECIFIC MOUNT IS DONE. THE SPECIFIC
//* MOUNT COLLECTS THE BVIR INFORMATION, NOT THE INTIIAL SCRATCH MOUNT.
//*
//* IF YOU HAVE MULTIPLE TS7740 GRIDS, YOU MUST HAVE A SEPARATE
//* STORAGE GROUP DEFINED FOR EACH GRID to ALLOCATE ON THE
//* DESIRED GRID. USE AN ACS ROUTINE TO SELECT THE TARGET GRID.
//*
//* IF YOU ARE RUNNING JES3, YOU MUST RUN STEP3 AS A SEPARATE JOB
    to FORCE THE DISMOUNT OF THE TAPE IN STEP2. BVIR DATA
//* WILL ONLY BE WRITTEN TO A TAPE AFTER THE INITIAL DISMOUNT AND
//* RE-MOUNT FOR READ.
//*
//BVIRPOOL PROC USERHLQ=USERID,
                                    HI-LEVEL FOR USER DATA FILES
         TOOLHLQ=TOOLID,
                                 HLQ FOR LOAD AND CNTL
//
         SITE=SITENAME,
//
                                 2ND LEVEL OUALIFIER
//
         VTSID=CLO, USE CLO, CL1, CL2, ETC TO BE PART OF DSN
         POOL=, TWO DIGIT POOL NUMBER REQUESTED
//
                                 DIRECT TO SPECIFIC CLUSTER IN GRID
//
         MC=,
         UNIT=VTAPE
                                 UNITNAME ON THIS VE
//
```