Note: For non-Linux systems, values greater than or equal to 600 seconds (10 minutes) will be ignored by mongod and mongos. For Linux, values greater than 300 seconds (5 minutes) will be overridden on the mongod and mongos sockets with a maximum of 300 seconds.

On Linux systems:

• To view the keep alive setting, you can use one of the following commands:

```
sysctl net.ipv4.tcp_keepalive_time
Or:
cat /proc/sys/net/ipv4/tcp_keepalive_time
```

The value is measured in seconds.

• To change the tcp_keepalive_time value, you can use one of the following command:

```
sudo sysctl -w net.ipv4.tcp_keepalive_time=<value>
Or:
echo <value> | sudo tee /proc/sys/net/ipv4/tcp_keepalive_time
```

These operations do not persist across system reboots. To persist the setting, add the following line to /etc/sysctl.conf:

```
net.ipv4.tcp_keepalive_time = <value>
```

On Linux, mongod and mongos processes limit the keepalive to a maximum of 300 seconds (5 minutes) on their own sockets by overriding keepalive values greater than 5 minutes.

For OS X systems:

• To view the keep alive setting, issue the following command:

```
sysctl net.inet.tcp.keepinit
```

• To change the net.inet.tcp.keepinit value, you can use the following command:

```
sysctl -w net.inet.tcp.keepinit=<value>
```

The above method for setting the TCP keepalive is not persistent; you will need to reset the value each time you reboot or restart a system. See your operating system's documentation for instructions on setting the TCP keepalive value persistently.

For Windows systems:

• To view the keep alive setting, issue the following command:

```
reg query HKLM\SYSTEM\CurrentControlSet\Services\Tcpip\Parameters /v KeepAliveTime
```

The registry value is not present by default. The system default, used if the value is absent, is 7200000 *milliseconds* or 0x6ddd00 in hexadecimal.

• To change the KeepAliveTime value, use the following command in an Administrator *Command Prompt*, where <value> is expressed in hexadecimal (e.g. 0x0124c0 is 120000):

```
reg add HKLM\SYSTEM\CurrentControlSet\Services\Tcpip\Parameters\ /v KeepAliveTime /d <value>
```

Windows users should consider the Windows Server Technet Article on KeepAliveTime³⁰ for more information on setting keep alive for MongoDB deployments on Windows systems.

³⁰https://technet.microsoft.com/en-us/library/cc957549.aspx