authenticate as. To create or modify a login path file, use the mysql_config_editor utility. See Section 4.6.7, "mysql config editor — MySQL Configuration Utility".

For additional information about this and other option-file options, see Section 4.2.2.3, "Command-Line Options that Affect Option-File Handling".

• --low-priority

Use LOW_PRIORITY when loading the table. This affects only storage engines that use only table-level locking (such as MyISAM, MEMORY, and MERGE).

• --no-defaults

Do not read any option files. If program startup fails due to reading unknown options from an option file, --no-defaults can be used to prevent them from being read.

The exception is that the <code>.mylogin.cnf</code> file is read in all cases, if it exists. This permits passwords to be specified in a safer way than on the command line even when <code>--no-defaults</code> is used. To create <code>.mylogin.cnf</code>, use the <code>mysql_config_editor</code> utility. See Section 4.6.7, "<code>mysql_config_editor</code>—MySQL Configuration Utility".

For additional information about this and other option-file options, see Section 4.2.2.3, "Command-Line Options that Affect Option-File Handling".

• --password[=password], -p[password]

The password of the MySQL account used for connecting to the server. The password value is optional. If not given, mysqlimport prompts for one. If given, there must be *no space* between --password= or -p and the password following it. If no password option is specified, the default is to send no password.

Specifying a password on the command line should be considered insecure. To avoid giving the password on the command line, use an option file. See Section 6.1.2.1, "End-User Guidelines for Password Security".

To explicitly specify that there is no password and that mysqlimport should not prompt for one, use the --skip-password option.

• --pipe, -W

On Windows, connect to the server using a named pipe. This option applies only if the server was started with the named_pipe system variable enabled to support named-pipe connections. In addition, the user making the connection must be a member of the Windows group specified by the named_pipe_full_access_group system variable.

• --plugin-dir=dir_name

The directory in which to look for plugins. Specify this option if the --default-auth option is used to specify an authentication plugin but mysqlimport does not find it. See Section 6.2.17, "Pluggable Authentication".

• --port=port_num, -P port_num

For TCP/IP connections, the port number to use.