- ceph tell \$type.\$id config get gets a specific runtime setting for a daemon.
- ceph tell *\$type.\$id* config set sets a specific runtime setting for a daemon. When the daemon restarts, these temporary settings revert to their original values.

The ceph tell \$type.\$id config command can also accept wildcards to get or set the value on all daemons of the same type. For example, ceph tell osd.* config get debug_ms displays the value of that setting for all OSD daemons in the cluster.

You can use the ceph daemon *\$type.\$id* config command to temporarily override a configuration setting. Run this command on the cluster node where the setting is required.

The ceph daemon does not need to connect through the MONs. The ceph daemon command will still function even when the MONs are not running, which can be useful for troubleshooting.

- ceph daemon \$type.\$id config get gets a specific runtime setting for a daemon.
- ceph daemon *\$type.\$id* config set sets a specific runtime setting for a daemon. Temporary settings revert to their original values when their daemon restarts.

References For more information, refer to the Red Hat Ceph Storage 5 Configuration Guide at https://access.redhat.com/documentation/en-us/red_hat_ceph_storage/5/html-single/configuration_guide/index#the-basics-of-ceph-configuration