```
                "api_name": "classroom",
                "is_master": "true",
                "endpoints": [
                    "http://serverc:80"
                ],
                "hostnames": [],
                "hostnames_s3website": [],
                "master_zone": "4f1863ca-1fca-4c2d-a7b0-f693ddd14882",
                "zones": [
                    {
                        "id": "3879a186-cc0c-4b42-8db1-7624d74951b0",
                        "name": "us-east-2",
                        "endpoints": [
                            "http://serverf:80"
                        ],
...output omitted...
                    },
                    {
                        "id": "4f1863ca-1fca-4c2d-a7b0-f693ddd14882",
                        "name": "us-east-1",
                        "endpoints": [
                            "http://serverc:80"
                        ],
...output omitted...
    "master_zonegroup": "d3524ffb-8a3c-45f1-ac18-23db1bc99071",
    "master_zone": "4f1863ca-1fca-4c2d-a7b0-f693ddd14882",
...output omitted...
    "realm_id": "9eef2ff2-5fb1-4398-a69b-eeb3d9610638",
    "realm_name": "cl260",
    "realm_epoch": 2
}
```

5.4. Update the zone name in the configuration database.

```
[ceph: root@serverf /]# ceph config set client.rgw rgw_zone us-east-2
```

6. Create a new RADOS Gateway service called `cl260-2` in the `cl260` realm and `us-east-2` zone, and with a single RGW daemon on the `serverf` node. Verify that the RGW daemon is up and running. View the period associated with the current configuration. Verify the sync status of the site.

6.1. Create the RADOS Gateway service on the `serverf` node.

```
[ceph: root@serverf /]# ceph orch apply rgw cl260-2 --realm=cl260 \
  --zone=us-east-2 --placement="1 se rverf.lab.example.com"
Scheduled rgw.east update...
[ceph: root@serverf /]# ceph orch ps --daemon-type rgw
NAME                     HOST                     STATUS         REFRESHED  AGE
 PORTS  ...
rgw.east.serverf.zgkgem  serverf.lab.example.com  running (37m)  6m ago     37m
 *:80   ...
```

6.2. View the period associated with the current configuration.