

0. MySQL的安装 - Windows

1. 本节目标

- 掌握在Windows系统下使用Installer安装MySQL数据库
- 掌握在Windows系统下安装MySQL历史版本

MySQL版本：8.0.x

安装之前先确保没有MySQL服务正在运行，建议在没有安装过MySQL的机器上进行全新的安装。

2. 使用Installer安装

2.1 下载最新版本Installer

- 官网下载8.0.X的最新版本，网址：<https://dev.mysql.com/downloads/installer/>

MySQL Community Downloads

MySQL Installer

最新发布版本

General Availability (GA) Releases Archives

MySQL Installer 8.0.39

Note: MySQL 8.0 is the final series with MySQL Installer. As of MySQL 8.1, use a MySQL product's MSI or Zip archive for installation. MySQL Server 8.1 and higher also bundle MySQL Configurator, a tool that helps configure MySQL Server.

Select Version:
8.0.39

Select Operating System:
Microsoft Windows

Windows (x86, 32-bit), MSI Installer (mysql-installer-web-community-8.0.39.0.msi)	8.0.39	2.1M	Download
Windows (x86, 32-bit), MSI Installer (mysql-installer-community-8.0.39.0.msi)	8.0.39	303.6M	Download

We suggest that you use the MD5 checksums and GnuPG signatures to verify the integrity of the packages you download.

当前最新是8.0.39

Windows系统


下载这个完事安装包

8.0.X中的X是小版本号，每发布一个小版本就会累加一次，选最新即可。


下载的过程中需要登录，如果没有Oracle的账户，注册一个即可。

2.2 运行安装程序


1. 点击Edit并设置过滤器



2. 确保所有组件都显示在左侧列表中




3. 依次展开每个组件，选择要安装的版本，通常选最新的即可




4. 点击向右的箭头，将选择的版本移至待安装区，依次选中组件出现高级选项


一般只选择MySQL Server 和MySQL Workbench 这两个组件，其他的现在用不到，课件中为了完整演示安装过程选择了所有组件




5. 设置自定义安装路径，建议安装在非系统盘，点击OK后，再点击Next




6. 点击执行按钮



7. 数据库安装完成，点击下一步




8. 点击下一步配置MySQL服务器




2.3 配置MySQL数据库服务


1. 在配置页面确认MySQL服务器的相着配置
 - a. Config Type选择 Development Computer
 - b. 勾选 TCP/IP
 - c. Port: 3306
 - d. X Protocol Port: 33060
 - e. 勾选 Open Windows Firewall ports for network access



2. 密码加密策略



3. 设置密码



The screenshot shows the 'Accounts and Roles' step of the MySQL Installer. The left sidebar lists the installation steps: Type and Networking, Authentication Method, Accounts and Roles (selected), Windows Service, Server File Permissions, and Apply Configuration. The main area is titled 'Accounts and Roles' and contains two sections. The first section, 'Root Account Password', prompts the user to enter a password for the root account. It includes two input fields: 'MySQL Root Password:' and 'Repeat Password:'. Both fields contain six dots. Below these fields, the text 'Password strength: Weak' is displayed. The second section, 'MySQL User Accounts', prompts the user to create MySQL user accounts. It features a table with columns 'MySQL User Name', 'Host', and 'User Role'. To the right of the table are three buttons: 'Add User', 'Edit User', and 'Delete'. At the bottom of the window, there are three buttons: '< Back', 'Next >', and 'Cancel'. The 'Next >' button is highlighted with a red rectangle. A red box also highlights the password input fields. A large blue watermark '数据库' is visible across the center of the window.

MySQL. Installer
MySQL Server 8.0.39

Type and Networking
Authentication Method
Accounts and Roles
Windows Service
Server File Permissions
Apply Configuration

Accounts and Roles

Root Account Password
Enter the password for the root account. Please remember to store this password in a secure place.

MySQL Root Password:

Repeat Password:

Password strength: **Weak**

MySQL User Accounts
Create MySQL user accounts for your users and applications. Assign a role to the user that consists of a set of privileges.

MySQL User Name	Host	User Role
-----------------	------	-----------

[Add User](#)
[Edit User](#)
[Delete](#)

< Back **Next >** Cancel

输入密码和确认密码

下一步

4. 设置Windows服务名和开机自启动

MySQL. Installer
MySQL Server 8.0.39

Type and Networking
Authentication Method
Accounts and Roles
Windows Service
Server File Permissions
Apply Configuration

Windows Service

☒ Configure MySQL Server as a Windows Service

Windows Service Details
Please specify a Windows Service name to be used for this MySQL Server instance. A unique name is required for each instance.

Windows Service Name:

☒ Start the MySQL Server at System Startup

Run Windows Service as ...
The MySQL Server needs to run under a given user account. Based on the security requirements of your system you need to pick one of the options below.


☒ Standard System Account
Recommended for most scenarios.

☐ Custom User
An existing user account can be selected for advanced scenarios.


下一步

< Back Next > Cancel


5. 设置数据目录的访问权限，默认即可



6. 执行配置



7. 配置成功



8. MySQL Server配置完成

MySQL. Installer

Adding Community

Select Products

Installation

Product Configuration

Installation Complete

Product Configuration

We'll now walk through a configuration wizard for each of the following products.

You can cancel at any point if you wish to leave this wizard without configuring all the products.

Product	Status
MySQL Server 8.0.39	Configuration complete.
MySQL Router 8.0.39	Ready to configure
Samples and Examples 8.0.39	Ready to configure

下一步

Next >

Cancel

9. MySQL Router组件配置页面，直接点Finish

MySQL. Installer
MySQL Router 8.0.39

MySQL Router Configuration

MySQL Router Configuration

☐ Bootstrap MySQL Router for use with InnoDB Cluster

This wizard can bootstrap MySQL Router to direct traffic between MySQL applications and InnoDB Cluster. Applications that connect to the router will be automatically directed to an available read/write or read-only member of the cluster.

The bootstrapping process requires a connection to InnoDB Cluster. In order to register the MySQL Router for monitoring, use the current Read/Write instance of the cluster.

Hostname:

Port:

Management User:

Password:

MySQL Router requires specification of a base port (between 80 and 65532). The first port is used for classic read/write connections. The other ports are computed sequentially after the first port. If any port is indicated to be in use, please change the base port.

Classic MySQL protocol connections to InnoDB Cluster:

Read/Write:

Read Only:


X Protocol connections to InnoDB Cluster:

Read/Write:

Read Only:

不用配置直接点完成

10. MySQL Router组件配置完成，点击下一步



11. 配置Samples and Examples，输入密码，校验数据库连接

MySQL[®] Installer

Samples and Examples

Connect To Server

Apply Configuration

Connect To Server

Select the MySQL server instances from the list to receive sample schemas and data.

	Server	Port	Archi...	Type	Status
☒	MySQL Server 8.0.39	3306	X64	Stand-alone Server	Connection succeeded.

Provide the credentials that should be used (requires root privileges).
Click "Check" to ensure they work.

User name: Credentials provided in Server configuration
Password:

Check 


输入密码点Check

下一步


Next >

Cancel

12. 执行配置



13. Samples and Examples配置完成，点击下一步



14. 所有组件配置完成

MySQL® Installer

Adding Community

Select Products

Installation

Product Configuration

Installation Complete

Product Configuration

We'll now walk through a configuration wizard for each of the following products.

You can cancel at any point if you wish to leave this wizard without configuring all the products.

Product	Status
MySQL Server 8.0.39	Configuration complete.
MySQL Router 8.0.39	Configuration not needed.
Samples and Examples 8.0.39	Configuration complete.


三个组件都配置完成

下一步

Next >


Cancel

15. 安装完成




2.4 查看服务

1. 服务列表中MySQL80的服务状态应该是**正在运行**，启动类型应该是**自动**



2.5 连接数据库

1. 检查环境变量的PATH中是否配置了MySQL的bin目录，如果没有自动配置，手动配置即可



2. 打开CMD输入 `mysql -uroot -p`，回车后输入密码，测试连接，出现如下所示，表示MySQL正常运行


```
1 C:\Users\bit>mysql -uroot -p
2 Enter password: ***** #输入密码
3 Welcome to the MySQL monitor.  Commands end with ; or \g.
4 Your MySQL connection id is 18
5 Server version: 8.0.39 MySQL Community Server - GPL # 显示MySQL的版本号
6
7 Copyright (c) 2000, 2024, Oracle and/or its affiliates.
8
9 Oracle is a registered trademark of Oracle Corporation and/or its
10 affiliates. Other names may be trademarks of their respective
11 owners.
12
```

```
13 Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.
14
15 mysql>
```


3. 卸载

3.1 卸载MySQL数据库服务

1. 运行Installer并点击Remove




1. 选择要卸载的组件，然后点击下一步




2. 同时卸载数据目录，根据实际需要选项，如果勾选数据目录将被删除



3. 确认卸载，点击执行



4. 卸载完成



3.2 检查服务

1. 在Windows服务列表中检查之前的MySQL80服务已被删除

3.3 手动删除目录

1. 删除安装目录
2. 备份数据目录并删除，否则下次安装会读取数据目录中的配置

一般情况不要手动修改注册表