实验 利用三层交换机实现 VLAN 间路由

【实验名称】

利用三层交换机实现 VLAN 间路由。

【实验目的】

掌握如何在三层交换机上配置 SVI 端口,实现 VLAN 间的路由。

【背景描述】

假设某企业有两个主要部门:销售部和技术部,其中销售部门的个人计算机系统分散连接在两台交换机上,他们之间需要相互进行通信,销售部和技术部也需要进行相互通信,现要在交换机上做适当配置来实现这一目标。

【需求分析】

需要在网络内所有的交换机上配置 VLAN, 然后在三层交换机上给相应的 VLAN 设置 IP 地址, 以实现 VLAN 间的路由。

【实验拓扑】




图 3-10 实验拓扑图

【实验设备】

三层交换机 1台

二层交换机 1台

【预备知识】

交换机的基本配置方法, VLAN 的工作原理和配置方法, Trunk 的工作原理和配置方法, 三层交换的工作原理和配置方法

【实验原理】

在交换网络中,通过 VLAN 对一个物理网络进行了逻辑划分,不同的 VLAN 之间是无法直接访问的,必须通过三层的路由设备进行连接。一般利用路由器或三层交换机来实现不同 VLAN 之间的互相访问。三层交换机和路由器具备网络层的功能,能够根据数据的 IP 包头信息,进行选路和转发,从而实现不同网段之间的访问。

直连路由是指:为三层设备的接口配置 IP 地址,并且激活该端口,三层设备会自动产生该接口 IP 所在网段的直连路由信息。

三层交换机实现 VLAN 互访的原理是,利用三层交换机的路由功能,通过识别数据包的 IP 地址,查找路由表进行选路转发。三层交换机利用直连路由可以实现不同 VLAN 之间的互相访问。三层交换机给接口配置 IP 地址,采用 SVI(交换虚拟接口)的方式实现 VLAN间互连。SVI 是指为交换机中的 VLAN 创建虚拟接口,并且配置 IP 地址。

【实验步骤】

第一步: 配置两台交换机的主机名

Switch#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Switch(config)#hostname L2-SW

L2-SW(config)#

S3750#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

S3750(config)#hostname L3-SW

L3-SW(config)#

第二步: 在三层交换机上划分 VLAN 添加端口,并设置 Trunk

- L3-SW(config)#vlan 10
- L3-SW(config-vlan)#name xiaoshou
- L3-SW(config-vlan)#vlan 20
- L3-SW(config-vlan)#name jishu
- L3-SW(config-vlan)#exit
- L3-SW(config)#
- L3-SW(config)#interface range fastEthernet 0/6-10
- L3-SW(config-if-range)#switchport mode access
- L3-SW(config-if-range)#switchport access vlan 10
- L3-SW(config-if-range)#exit
- L3-SW(config)#interface range fastEthernet 0/11-15
- L3-SW(config-if-range)#switchport mode access
- L3-SW(config-if-range)#switchport access vlan 20
- L3-SW(config-if-range)#exit
- L3-SW(config)#
- L3-SW(config)#interface fastEthernet 0/1
- L3-SW(config-if)#switchport mode trunk
- L3-SW(config-if)#exit
- L3-SW(config)#

第三步: 在二层交换机上划分 VLAN 添加端口,并设置 Trunk

- L2-SW(config)#vlan 10
- L2-SW(config-vlan)#name xiaoshou

- L2-SW(config-vlan)#vlan 20
- L2-SW(config-vlan)#name jishu
- L2-SW(config-vlan)#exit
- L2-SW(config)#
- L2-SW(config)#interface range fastEthernet 0/6-10
- L2-SW(config-if-range)#switchport mode access
- L2-SW(config-if-range)#switchport access vlan 10
- L2-SW(config-if-range)#exit
- L2-SW(config)#
- L2-SW(config)#interface fastEthernet 0/1
- L2-SW(config-if)#switchport mode trunk
- L2-SW(config-if)#exit
- L2-SW(config)#

第四步: 查看 VLAN 和 Trunk 的配置

L2-SW#show vlan

VLAN Name		Status	s Ports			
1	default	active	Fa0/1 ,Fa0/2 ,Fa0/3 Fa0/4 ,Fa0/5 ,Fa0/11 Fa0/12,Fa0/13,Fa0/14 Fa0/15,Fa0/16,Fa0/17 Fa0/18,Fa0/19,Fa0/20 Fa0/21,Fa0/22,Fa0/23 Fa0/24			
10	xiaoshou	active	Fa0/1 ,Fa0/6 ,Fa0/7			
20	jishu	active	Fa0/8 ,Fa0/9 ,Fa0/10 Fa0/1			
L2-SW# L2-SW#show interfaces fastEthernet 0/1 switchport						

Interface	Switchport N	/lode	Access	Native	Protected VLAN lists
Fa0/1	Enabled	Trunk	1	1	Disabled All

L3-SW#show vlan

VLAN Name	Status	Ports
1 VLAN0001	STATIC	 Fa0/1, Fa0/2, Fa0/3, Fa0/4
	F	Fa0/5, Fa0/16, Fa0/17, Fa0/18
	F	Fa0/19, Fa0/20, Fa0/21, Fa0/22
	F	Fa0/23, Fa0/24, Gi0/25, Gi0/26
	G	Gi0/27, Gi0/28
10 xiaoshou	STATIC I	Fa0/1, Fa0/6, Fa0/7, Fa0/8

Fa0/9, Fa0/10

20 jishu STATIC Fa0/1, Fa0/11, Fa0/12, Fa0/13

Fa0/14, Fa0/15

L3-SW#

L3-SW#show interfaces fastEthernet 0/1 switchport

PC3 和 PC2 是不能 ping 通的,如错误!未找到引用源。所示。

Interface Switchport Mode Access Native Protected VLAN lists
----FastEthernet 0/1 enabled TRUNK 1 1 Disabled ALL

第五步:验证配置

PC3 和 PC1 都属于 VLAN 10, 它们的 IP 地址都在 C 类网络 192.168.10.0/24 内, PC2 属于 VLAN 20, 它的 IP 地址在 C 类网络 192.168.20.0/24 内,此时,不同 VLAN 之间的

C:\VINDOVS\system32\cmd.exe

C:\>
C:\>
C:\>
ping 192.168.20.172

Pinging 192.168.20.172 with 32 bytes of data:

Request timed out.
Request timed out.
Request timed out.
Request timed out.
Ping statistics for 192.168.20.172:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

图 3-11 从 PC3 不能 ping 通 PC2

第六步: 在三层交换机上配置 SVI 端口

L3-SW#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

L3-SW(config)#interface vlan 10

!激活 VLAN 10 的 SVI 端口并配置 IP 地址

L3-SW(config-if)#Dec 2 18:59:30 L3-SW %7:%LINE PROTOCOL CHANGE:

Interface VLAN 10, changed state to UP

L3-SW(config-if)#ip address 192.168.10.1 255.255.255.0

L3-SW(config-if)#no shutdown

L3-SW(config-if)#exit

L3-SW(config)#

L3-SW(config)#interface vlan 20

! 激活 VLAN 20 的 SVI 端口并配置 IP 地址

L3-SW(config-if)#Dec 2 19:00:05 L3-SW %7:%LINE PROTOCOL CHANGE:

Interface VLAN 20, changed state to UP

L3-SW(config-if)#ip address 192.168.20.1 255.255.255.0

- L3-SW(config-if)#no shutdown
- L3-SW(config-if)#exit
- L3-SW(config)#

第七步: 查看 SVI 端口的配置

L3-SW#show ip route

Codes: C - connected, S - static, R - RIP B - BGP

O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default

Gateway of last resort is no set

- C 192.168.10.0/24 is directly connected, VLAN 10
- C 192.168.10.1/32 is local host.
- C 192.168.20.0/24 is directly connected, VLAN 20
- C 192.168.20.1/32 is local host.

L3-SW#

从中可以看到, VLAN 的虚拟端口上配置的 IP 地址, 其网段成为了三层交换机的直连路由。

L3-SW#show interfaces vlan 10

Index(dec):4106 (hex):100a

VLAN 10 is UP , line protocol is UP

Hardware is VLAN, address is 00d0.f821.a543 (bia 00d0.f821.a543)

Interface address is: 192.168.10.1/24

ARP type: ARPA, ARP Timeout: 3600 seconds

MTU 1500 bytes, BW 1000000 Kbit

Encapsulation protocol is Ethernet-II, loopback not set

Keepalive interval is 10 sec, set

Carrier delay is 2 sec RXload is 1 ,Txload is 1 Queueing strategy: WFQ

L3-SW#

L3-SW#show interfaces vlan 20

Index(dec):4116 (hex):1014

VLAN 20 is UP , line protocol is UP

Hardware is VLAN, address is 00d0.f821.a543 (bia 00d0.f821.a543)

Interface address is: 192.168.20.1/24

ARP type: ARPA,ARP Timeout: 3600 seconds

MTU 1500 bytes, BW 1000000 Kbit

Encapsulation protocol is Ethernet-II, loopback not set

Keepalive interval is 10 sec, set Carrier delay is 2 sec RXload is 1,Txload is 1 Queueing strategy: WFQ L3-SW#

第八步:验证配置

给 PC3 添加网关 192.168.10.1,如错误!未找到引用源。所示,此时再从 PC3 去 ping 不同 VLAN 的主机 PC2,是可以 ping 通的,如错误!未找到引用源。所示。

```
_ 🗆 ×
C:\WINDOWS\system32\cmd.exe
C:\>ipconfig
Windows IP Configuration
Ethernet adapter UMware Network Adapter UMnet8:
      Connection-specific DNS Suffix .:
      IP Address. . . . . . . . . . : 192.168.145.1
      Default Gateway . . . . . . . :
Ethernet adapter UMware Network Adapter UMnet1:
      Connection-specific DNS Suffix .:
      IP Address. . . . . . . . . . . : 192.168.126.1
      Default Gateway . . . . . . . :
Ethernet adapter 本地连接:
      Connection-specific DNS Suffix .:
      IP Address. . . . . . . . . . : 192.168.10.98
      Subnet Mask . . . . . . . . . : 255.255.255.0
      Default Gateway . . . . . . . : 192.168.10.1
C: \>
```

图 3-12 为 PC3 设置网关

图 3-13 设置三层交换机后, PC3 可以 ping 通 PC2

【注意事项】

- 1、两台交换机之间相连的端口应该设置为 tag vlan 模式。
- 2、给 SVI 端口设置完 IP 地址后,一定要使用 **no** shutdown 命令进行激活,否则无法 正常使用。
 - 3、如果 VLAN 内没有激活的端口,相应 VLAN 的 SVI 端口将无法被激活。
 - 4、需要设置 PC 的网关为相应 VLAN 的 SVI 接口地址。

【参考配置】

L3-SW#show running-config

```
Building configuration...
Current configuration: 1605 bytes
version RGNOS 10.1.00(4), Release(18443)(Tue Jul 17 19:51:54 CST 2007 -ubu6server)
hostname L3-SW
vlan 1
vlan 10
 name xiaoshou
!
vlan 20
 name jishu
!
interface FastEthernet 0/1
 switchport mode trunk
interface FastEthernet 0/2
interface FastEthernet 0/3
interface FastEthernet 0/4
interface FastEthernet 0/5
interface FastEthernet 0/6
 switchport access vlan 10
!
interface FastEthernet 0/7
 switchport access vlan 10
```

```
!
interface FastEthernet 0/8
 switchport access vlan 10
interface FastEthernet 0/9
 switchport access vlan 10
interface FastEthernet 0/10
 switchport access vlan 10
!
interface FastEthernet 0/11
 switchport access vlan 20
interface FastEthernet 0/12
 switchport access vlan 20
interface FastEthernet 0/13
 switchport access vlan 20
!
interface FastEthernet 0/14
 switchport access vlan 20
interface FastEthernet 0/15
 switchport access vlan 20
interface FastEthernet 0/16
interface FastEthernet 0/17
interface FastEthernet 0/18
interface FastEthernet 0/19
interface FastEthernet 0/20
interface FastEthernet 0/21
interface FastEthernet 0/22
interface FastEthernet 0/23
```

```
!
interface FastEthernet 0/24
interface GigabitEthernet 0/25
interface GigabitEthernet 0/26
interface GigabitEthernet 0/27
interface GigabitEthernet 0/28
interface VLAN 10
 ip address 192.168.10.1 255.255.255.0
interface VLAN 20
 ip address 192.168.20.1 255.255.255.0
!
line con 0
line vty 04
 login
end
L2-SW#show running-config
System software version: 1.68 Build Apr 25 2007 Release
Building configuration...
Current configuration: 457 bytes
!
version 1.0
hostname L2-SW
vlan 1
!
vlan 10
 name xiaoshou
```

```
vlan 20
 name jishu
interface fastEthernet 0/1
 switchport mode trunk
!
interface fastEthernet 0/6
 switchport access vlan 10
interface fastEthernet 0/7
 switchport access vlan 10
interface fastEthernet 0/8
 switchport access vlan 10
!
interface fastEthernet 0/9
 switchport access vlan 10
interface fastEthernet 0/10
 switchport access vlan 10
!
end
```