

How does Windows set the %SystemRoot% variable?

Asked 1 year, 9 months ago Modified 1 year, 9 months ago Viewed 4k times



The MSystemRoot% environment variable contains the path to the Windows directory. (e.g. c:\windows)



SystemRoot is not configured in Computer\HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\Session Manager\Environment, it is automagically set.



Now, typically on Windows 10 this directory has the caseing C:\Windows on NTFS disk.



After a script test(*) broke, we noticed:



- With same OS version Windows 10 (LTSC 1809 17763.3887)
- Some boxes use %SystemRoot% == C:\WINDOWS (all uppercase, despite the directory on-disk being C:\Windows)
- Some boxes use %SystemRoot% == C:\Windows (case of dir on disk)
- We cross checked with ProcessExplorer: The casing difference is already present in the environment block of the wininit.exe process, so it's not overridden somewhere.

Q:

Is the base for the value of SystemRoot read from any specific registry key?

What could explain this difference?

^{(*):} To be clear, the test was broken anyway - thou shall not rely on path casing on Windows.

windows-registry

Share Improve this question Follow



One explanation for the difference is it really doesn't matter. Windows in general and paths specifically are not case sensitive, so there is no impact to the operating system or native commands. – Greg Askew Mar 2, 2023 at 18:53

The OS and filesystem case-AWARE but not case-SENSITIVE. Of course, anyone could choose to make a given script be case-sensitive, which as OP said, appears to be what they accidentally did. – mfinni Mar 2, 2023 at 23:32

1 Answer

Sorted by: Highest score (default)

4



It's set in the boot process. It's not set in the registry, because the OS boot process needs to know where to find the registry files (and other OS files) before it can read them from the registry.

3

https://learn.microsoft.com/en-us/windows-hardware/drivers/devtest/boot-options-in-windows



Windows boot options are stored in the Boot Configuration Data (BCD) store on BIOS-based and EFI-based computers.





PS C:\> bcdedit.exe /enum | select-string "device|root"

device partition=\Device\HarddiskVolume1

device partition=C:
osdevice partition=C:
systemroot \WINDOWS

PS C:\> \$env:systemroot

C:\WINDOWS

On older Windows OS, it's probably in boot.ini

Share Improve this answer Follow

edited Mar 2, 2023 at 17:09

answered Mar 2, 2023 at 16:36



1 Thanks. This is exactly it. One machine reports systemroot \WINDOWS and the other \Windows. Doesn't make a whole lot sense to me, but there it is.

- Martin Mar 3, 2023 at 7:41