ReadProcessMemory函数的分析



ReadProcessMemory 函数 用于读取其他进程的数据。我们知道自远古时代结束后,user模式下的进程都有自己的地址空间,进程与进程间互不干扰,这叫私有财产神圣不可侵犯。但windows 卫里还真就提供了那么一个机制,让你可以合法的获取别人的私有财产,这就是ReadProcessMemory和WriteProcessMemory。为什么一个进程居然可以访问另一个进程的地址空间呢?因为独立的只是低2G的用户态空间,高2G的内核态空间是所有进程共享的。一段执行中的线程进入内核态后,它可以拿到别人的cr3寄存器,用该cr3替换自己的cr3便完成了地址空间的转换。理论说明完毕,下面来看实现细节:

```
BOOL
STDCALL
ReadProcessMemory (
       HANDLE hProcess,
       LPCVOID lpBaseAddress,
       LPVOID lpBuffer,
       DWORD
               nSize,
       LPDWORD lpNumberOfBytesRead
       NTSTATUS Status;
       Status = NtReadVirtualMemory( hProcess, (PVOID)lpBaseAddress,lpBuffer, nSize,
                (PULONG)1pNumberOfBytesRead
               );
       if (!NT_SUCCESS(Status))
                SetLastErrorByStatus (Status);
                return FALSE;
       }
```

```
return TRUE;
}
```

这是用户态ReadProcessMemory的实现,它只做了一件事那就是调用NtReadVirtualMemory。NtReadVirtualMemory函数位于ntdll中,属于所谓的桩函数,

作用就是把用户态的函数调用翻译成相应的系统调用,进入内核态。内核中一般有一个相同名字的处理函数,接收到该类型的系统调用后做实际的工作。系统调用

的细节按下不表,让我们来看NtReadVirtualMemory到底在做什么事情:

```
NTSTATUS STDCALL
NtReadVirtualMemory(IN HANDLE ProcessHandle,
                    IN PVOID BaseAddress,
                    OUT PVOID Buffer,
                    IN ULONG NumberOfBytesToRead,
                    OUT PULONG NumberOfBytesRead)
   NTSTATUS Status;
   PMDL Mdl;
   PVOID SystemAddress;
   PEPROCESS Process;
   DPRINT("NtReadVirtualMemory(ProcessHandle %x, BaseAddress %x, "
          "Buffer %x, NumberOfBytesToRead %d)\n",ProcessHandle,BaseAddress,
          Buffer,NumberOfBytesToRead);
   Status = ObReferenceObjectByHandle(ProcessHandle,
                                      PROCESS_VM_WRITE,
                                      NULL,
```

ObReferenceObjectByHandle函数从代表目标进程的handle里获取EPROCESS类型的指针,存放在变量Process中。EPROCESS结构保存了能代表一个进程的

几乎所有关键数据,包括我们这里急需的cr3。

```
typedef struct _KPROCESS
{
```

```
/* So it's possible to wait for the process to terminate */
 DISPATCHER HEADER
                    DispatcherHeader;
                                               /* 000 */
  * Presumably a list of profile objects associated with this process,
  * currently unused.
  */
                    ProfileListHead;
                                      /* 010 */
 LIST ENTRY
 /*
  * We use the first member of this array to hold the physical address of
  * the page directory for this process.
  */
                  DirectoryTableBase; /* 018 这是cr3*/
 PHYSICAL_ADDRESS
。。。/*其他*/
```

接下来是从目标地址里创建一个MDL并将其锁定在主存里:

为什么要创建这个MDL?等会儿再说。

然后是最关键的一步, 当前线程要当逃兵, 叛逃至目标进程里了。。。

```
KeAttachProcess(Process);
```

执行完KeAttachProcess后,当前线程就成了Process进程所属的线程了,悲剧啊。怎么着咱们就被策反了呢?细节我们等下再看,让我们完成主逻辑先。

```
SystemAddress = MmGetSystemAddressForMdl(Mdl);
memcpy(SystemAddress, BaseAddress, NumberOfBytesToRead);
```

```
KeDetachProcess();
```

```
if (Mdl->MappedSystemVa != NULL)
{
         MmUnmapLockedPages(Mdl->MappedSystemVa, Mdl);
}
MmUnlockPages(Mdl);
ExFreePool(Mdl);

ObDereferenceObject(Process);

*NumberOfBytesRead = NumberOfBytesToRead;
return(STATUS_SUCCESS);
}
```

attach到目标进程里之后,我们又从之前生成好的MDL里获取一个虚拟地址映射,然后执行memcpy操作。这下为什么要创建MDL的秘密就清楚了,假如我们直接这样

写memcpy:

```
memcpy(Buffer, BaseAddress, NumberOfBytesToRead);
```

过去的数据,其实位于错误的内存里,等KeDetachProcess执行完切回原来的进程空间后,这些数据就全丢了,找都没地方找去。所以我们应该先从Buffer里

看着好像没什么问题,其实问题很大。Buffer所代表的地址应该是前一个进程空间里的,但现在确实新进程空间里的,根本不是一回事。我们费劲拷贝

生成一个MDL,切换进程完成后再从该MDL里反生成一个Virtual Address,然后memcpy就可以正确的将数据拷贝到该去的地方了。

完成内存拷贝后,KeDetachProcess函数又将我们的线程从Process进程转回原来的进程,这下好,数据也偷到了,组织也回归了,原来这家伙是个间谍啊。。。

现在我们可以来看看KeAttachProcess函数到底做了什么事情了。核心行为很明确,那就是替换cr3,但是细节到底如何呢:

```
VOID STDCALL
KeAttachProcess (PEPROCESS Process)
{
    KIRQL oldlvl;
    PETHREAD CurrentThread;
    PULONG AttachedProcessPageDir;
    ULONG PageDir;

    DPRINT("KeAttachProcess(Process %x)\n",Process);

CurrentThread = PsGetCurrentThread();
```

```
if (CurrentThread->OldProcess != NULL)
{
    DbgPrint("Invalid attach (thread is already attached)\n");
    KEBUGCHECK(0);
}

KeRaiseIrql(DISPATCH_LEVEL, &oldlv1);

KiSwapApcEnvironment(&CurrentThread->Tcb, &Process->Pcb);
```

这里我们把当前的IRQL提升到了DPC level,为的就是防止线程切换。然后调用KiSwapApcEnvironment把当前的apc队列也贴到目标进程里,按下不表。

```
/* The stack of the current process may be located in a page which is
not present in the page directory of the process we're attaching to.
That would lead to a page fault when this function returns. However,
since the processor can't call the page fault handler 'cause it can't
push EIP on the stack, this will show up as a stack fault which will
crash the entire system.
To prevent this, make sure the page directory of the process we're
attaching to is up-to-date. */

AttachedProcessPageDir = ExAllocatePageWithPhysPage(Process->Pcb.DirectoryTableBase);
MmUpdateStackPageDir(AttachedProcessPageDir, &CurrentThread->Tcb);
ExUnmapPage(AttachedProcessPageDir);
```

接下来如注释所说,Process->Pcb.DirectoryTableBase所代表的数据很有可能正在硬盘里的,物理如何也要保证它在内存里,因为函数返回时要做栈操作,

如果Process->Pcb.DirectoryTableBase在硬盘上,栈操作就会引起page fault,而处理page fault前又必须要push eip,悲剧就要发生了。同样的,

stack base 和 stack top这两哥们也一定得在内存里,MmUpdateStackPageDir做的就是这个事情。

```
CurrentThread->OldProcess = PsGetCurrentProcess();
CurrentThread->ThreadsProcess = Process;
PageDir = Process->Pcb.DirectoryTableBase.u.LowPart;
DPRINT("Switching process context to %x\n",PageDir);
Ke386SetPageTableDirectory(PageDir);
KeLowerIrql(oldlv1);
}
```

最后做的事情就简单了,把当前线程的ThreadsProcess换成新的,再把当前的cr3换成Process->Pcb.DirectoryTableBase.u.LowPart。一番梳妆打扮后,

敌人就分不清咱的身份了。

至此为止,ReadProcessMemory函数分析完毕。个人觉得有几个细节是需要注意的:第一呢,lpBaseAddress和lpBuffer所在的进程空间是不同的。第二呢,

KeRaiseIrql和KeLowerIrql这两个函数一定要限制在进程空间切换的函数内,绝对不能把memcpy放在它们中间,因为KeRaiseIrql之后page fault就没法处理

了,而memcpy不产生page fault那是不可能的,想都不要想。