

SCALPBOT - Scalp Deck

Complete guide to the live scalping dashboard for **BTCUSDT**, **XAUUSDT**, **BNBUSDT** and **SOLUSDT**: momentum meter, Bollinger / MA chart, live per-second graph, liquidation map, order book heatmap, pressure meter, big trades, TradingView window with the Sniper Indicator, footprint, the AI Agent widget, alerts and music — what every part measures, how to use it and how far to trust it.



Version 30 September 2026 · v4 · English

Execution platform: Exness

Educational tool · not investment advice

Contents

1	What the dashboard is · trust levels	10	Order book heatmap
2	Layout · desktop split view & phone	11	Big trades
3	Header · market, timeframe, price, alert, contact	12	TradingView window · controls & auto tools
4	Alerts · soft beep and loud siren	13	Sniper Indicator
5	Momentum meter (overbought / oversold)	14	Footprint · volume profile · entry timing
6	Bollinger · MA chart & 1H squeeze strategy	15	AI Agent widget · sniper plan
7	Live per-second graph · open-price momentum	16	Music widget
8	Liquidation map & heatmaps	17	Multi-market notes
9	Pressure meter	18	Daily workflow, glossary & risk notice

Quick start

1. Open liemyo.github.io/btcusdt, enter your password, then choose the **Market** and **Timeframe** in the header — every window follows them.
2. Click **ALERT: OFF** once so it reads **ALERT: ON**. From now on strong signals sound a loud siren with a spoken message; small events give a short beep.
3. Read the context: momentum meter, Bollinger chart, liquidation clusters, order book walls, pressure meter and big trades.
4. Read the **AI Agent** bar in the header (click it for details): it summarises every indicator and, when they agree, gives one plan — **open price, take profit 1–3 and cut loss**.
5. Execute manually on Exness ([EXNESS ↗](#)), always with the cut loss shown. Questions? **CONTACT CS** opens WhatsApp.

1 What the dashboard is

The Scalp Deck reads live **Binance spot** data (candles, every trade, the full order book, one-second prices) and **Gate.io futures** data (liquidations). Bybit, OKX and Coinbase are added to the big-trades tape automatically when your network can reach them.

It is a set of instruments that show where momentum, liquidity, liquidations and aggressive orders are, plus a few rule-based trade plans with stop and targets. **It never places trades for you.**

How much to trust each part

PART	STATUS	HOW TO USE IT
1H Bollinger squeeze breakout (section 6)	Backtested 12 months BTCUSDT	74 trades · win 46 % · profit factor 1.61 (1.47 first half / 1.87 second half) after a 15-point cost. The only rule on screen with a measured edge. About 1–2 trades a week.
Sniper Indicator, AI Agent plan, footprint price action, TradingView auto tools	Chart aids · not backtested	Structured levels with a stop and targets. Use small size and prefer moments when several of them agree.
Momentum meter, live graph, pressure meter, heatmaps, big trades, liquidations	Measurements	Context and short-term pressure. Not signals on their own.


TESTED AND REJECTED

Bollinger band bounces on 5m / 15m, SMA 20 pull-backs, SMA 20 open-crosses and fading overbought / oversold on low timeframes were tested on 12 months of data and **lost money after costs**. That is why the momentum meter warns but never triggers a trade on its own.

IMPORTANT

No indicator wins every trade. Expect losing streaks (4–6 in a row are normal even for the tested rule), never move a stop further away and risk only 0.5–1 % of capital per trade.

2 Layout · desktop split view & phone



Desktop split view (1920 × 1080): every window on one screen, no scrolling. The AI Agent bar sits in the header.

On a computer screen of at least 1280 × 680 pixels the dashboard fills the window like a trading terminal:

AREA	WINDOW
Top	Header (market, timeframe, user guide, AI Agent bar, live price, alert, Exness, Contact CS, clock)
Strip under the header	Momentum meter · Bollinger / MA candle chart · live per-second graph
Middle-left	Liquidation map (3 days) + liquidation heatmaps 1 month / 1 week / 12 hours
Middle-right	TradingView window with auto tools and the Sniper Indicator
Bottom-left	Pressure meter · order book heatmap · big trades
Bottom-right	Footprint: entry timing · footprint chart with volume profile
Floating	Music button (bottom-right) only

Phones and tablets

Windows are stacked and the page scrolls in this order: header, momentum meter, Bollinger chart, live graph, liquidation map and heatmaps, pressure meter, order book heatmap, big trades, TradingView window, footprint.

On a phone the AI Agent bar takes a full row in the header; tap it to open the summary, tap outside to close it.

The  button on the order book heatmap and on the TradingView window opens that window full-screen; **X** or **Esc** closes it.



3 Header · market, timeframe, price, alert, contact



CONTROL	WHAT IT DOES
Market	BTCUSDT · XAUUSDT (gold) · BNBUSDT · SOLUSDT. The page reloads and every window and widget switches to the chosen pair.
Timeframe	1M · 5M · 15M · 1H · 4H · 1D — one timeframe for every instrument : Bollinger / MA chart and momentum meter, the OPEN reference of the live graph, the TradingView window with the Sniper Indicator, the AI Agent, and the footprint (1M and 5M; for 15M and higher the footprint uses 5M). Liquidation map, order book heatmap and big trades use fixed windows. Each window still has its own TF box if you want a different view there.
USER GUIDE · PDF	Downloads this guide.
AI AGENT bar	Fixed in the header top row. Shows the current verdict at a glance (e.g. BUY @ price · TP1 · CL or WAIT · agreement %); click it or + to drop down the full summary (section 15).
Live price box (top-right)	Current price of the chosen market, 24-hour change in % and points, green dot = live stream connected. On every tick the border and the price flash green (up) or red (down). It is fixed in the header — it no longer floats.
ALERT: ON / OFF	Master switch for every sound on the page (section 4). Your choice is remembered.
EXNESS ↗	Opens Exness web trading to execute manually.
CONTACT CS	Green WhatsApp button: opens a chat with customer service (wa.me/6282299774825) for access, passwords or questions.
Clock	UTC time and data latency; the strap line shows WIB (Jakarta) time and the active timeframe.



Live price, ALERT, EXNESS and CONTACT CS.

4 Alerts • soft beep and loud siren

Turn **ALERT: ON** in the header. Browsers only allow sound after you have clicked the page once, so click anywhere after opening it.

TYPE	SOUND	TRIGGERED BY
Strong signal	Loud siren: three rising/falling pulses, four times, repeated three times (≈ 9 s) plus a spoken message such as “Sniper buy BTC”. Higher pitch = BUY, lower pitch = SELL.	• AI Agent changes to BUY or SELL • New Sniper Indicator BUY / SELL / RE-BUY / RE-SELL • New footprint price-action setup • 1H Bollinger squeeze trade opened
Weak event	One short beep	• Momentum meter enters overbought or oversold • Strong open drive on the live graph ($z \geq 2$ in the first minute of a candle) • Pressure meter reaches STRONG BUY / STRONG SELL • Big trade $\geq 5\times$ the chosen minimum


SILENCING AND REPEATS

Click anywhere on the page or press any key to stop the siren. The same signal does not sound again within 60 seconds. Turning ALERT off also stops it.

BACKGROUND TAB

While ALERT is on, the AI Agent and the TradingView window keep updating when the tab is in the background, so the siren can still wake you up. Keep the tab open (it may be in another window or behind other tabs).

5 Momentum meter - overbought / oversold



The box in the top-left corner of the Bollinger panel. The needle (0–100) is the average of three oscillators calculated on the selected timeframe, updated live:

- **RSI 14** — strength of recent closes.
- **Stochastic 14 · 3** — where the close sits in the 14-candle high–low range.
- **Bollinger %B** — where price sits between the lower (0) and upper (100) band.

The three bars below show each component (green zone ≤ 20, red zone ≥ 80). The four boxes show the same meter on **1M, 5M, 15M and 1H**; a box turns red when that timeframe is overbought and green when oversold.

READING	BORDER	MEANING
≥ 80 OVERBOUGHT	red, blinking	Stretched up — late to buy
70–80 NEAR OVERBOUGHT	yellow, slow blink	Approaching the top
30–70 NEUTRAL	grey	No extreme
20–30 NEAR OVERSOLD	yellow, slow blink	Approaching the bottom
≤ 20 OVERSOLD	green, blinking	Stretched down — late to sell

The arrow text (momentum rising ↑ / falling ↓) compares the meter with three candles ago. When the meter **turns back** out of an extreme, the blinking becomes faster. The bottom line shows the 1H squeeze status (section 6).

HOW TO USE IT

Use it as a “do not chase” filter: avoid new longs when it is overbought on your timeframe and higher ones, and avoid new shorts when it is oversold. On its own it is not an entry — fading extremes lost money in the 12-month test.

6 Bollinger · MA chart & 1H squeeze strategy



Momentum meter (left), Bollinger / MA candle chart (right) and the live per-second graph (bottom).

Real-time candles (Binance stream) with **Bollinger Bands 20 · 2σ** (blue upper / lower band), **SMA 20** (yellow dotted middle band), **EMA 50** (pink) and **EMA 200** (purple). The TF box changes the timeframe of this chart (1m ... D); it also follows the header. The line at the top shows %B (position inside the bands), band width and whether price is above or below SMA 20. Scroll and zoom with the mouse; double-click to reset.

The tested rule: 1H open-price squeeze breakout

- Squeeze** — the last closed 1H candle has a band width at most 1.15× the lowest width of the last 120 hours (the bands are unusually tight).
- Trigger** — the next 1H candle **closes** outside the band: above the upper band = BUY, below the lower band = SELL.
- Entry** — market order at the **open price** of the following 1H candle. Do not enter in the middle of the candle.
- Exit** — stop loss 1 × ATR 14 (1H), take profit 2 × ATR (2R), close after 48 hours if neither is hit. One position at a time.


BACKTEST (12 MONTHS BTCUSD, STOP CHECKED FIRST IN EVERY 1-MINUTE BAR)	RESULT
Trades · win rate	74 · 46 %
Profit factor, 15-point cost / 25-point cost	1.61 / 1.54
First half / second half (unseen)	1.47 / 1.87
Nine neighbouring settings	all profitable (1.34–1.88)

When the rule is active the entry, SL and TP lines are drawn on this chart, arrows mark past signals on the 1H chart, the momentum box footer shows **BUY / SELL active** or **ARMED** (squeeze on, waiting for the close) and the AI Agent uses it as a strong vote. A new squeeze trade sounds the siren.

EMA 50 / 200

The moving averages show the trend (EMA 50 above EMA 200 and price above EMA 200 = up). They are context only: as a filter they cut trades without improving the result.

7 Live per-second graph · open-price momentum



A glowing line of the price **every second** (Binance trade stream), scrolling smoothly. The fill is green while price is above the candle open and red below it.

ELEMENT	MEANING
Open selector	Which candle open is the reference line: 1m · 5m · 15m · 1h · 4h · 1D (follows the header timeframe).
Win selector	Time shown: 1, 2 or 5 minutes.
Yellow dashed line “OPEN”	Open price of the current candle. If it is off-screen an arrow shows where it is.
Yellow dots · dotted verticals	Start of every new minute (each minute open).
Thin gold line	10-second EMA — the very short-term direction.
H / L	High and low of the visible window.
Stats row	Price · Δ from the open · speed (points per second over 10 s) · momentum 30 s and 60 s · share of aggressive buying in the last 30 s.

Open drive badge


Measures how strong the move since the open is compared with the normal per-second noise: $z = \Delta \text{ since open} \div (1\text{-second volatility} \times \sqrt{\text{seconds}})$.

- **OPEN DRIVE** ↑ / ↓ ($|z| \geq 2$ in the opening phase) — a strong push right after the open; glowing border. A short beep sounds when ALERT is on.
- **STRONG TREND** — the same strength later in the candle.
- **LEANING** ($|z|$ 1-2) — a mild bias. **NO DRIVE** — noise.

HOW TO USE IT

Use it for timing: enter a planned trade when the drive is in your direction, wait when it pushes against you. It is a measurement, not a tested rule.

8 Liquidation map & heatmaps




- **Liquidation map • 3 days** — estimated liquidation volume per price for 10x, 25x, 50x and 100x leverage. **Cum Long** (red) = total long liquidations below price, **Cum Short** (green) = total short liquidations above. Big bars near price act as magnets: price often runs into them.
- **Heatmaps 1 month (4H candles) • 1 week (1H) • 12 hours (5M)** — the same estimate through time. A band disappears once price trades through it; brighter = more positions at risk.

HOW TO USE IT

Targets just before a big cluster are reached more often; stops inside a cluster on the other side are hunted more often. The pressure meter uses the nearest clusters automatically.

9 Pressure meter



A needle from -100 (sell) to +100 (buy) for the next minutes, weighted from:


COMPONENT	WEIGHT
Taker flow, last 60 s	35 %
Order book imbalance ±0.1 %	25 %
Order book imbalance ±0.5 %	15 %
Momentum 60 s	15 %
Liquidation magnet pull	10 %

Labels: STRONG SELL ≤ -45 · SELL ≤ -15 · NEUTRAL · BUY ≥ +15 · STRONG BUY ≥ +45. The border glows green on BUY, red on SELL, yellow when neutral. STRONG readings give a beep.

Leaning toward is the price the pressure is heading to: the biggest wall (±0.5 %) or liquidation magnet on the dominant side.

Short-term pressure only — the AI Agent counts it as one vote.

10 Order book heatmap



Pressure meter · order book heatmap · big trades.

A live copy of the Binance order book (up to 5000 levels, updated every 100 ms) drawn through time. Each column is a moment, each row a price; colour shows how much is resting there (dark blue = little, yellow / orange / red = large walls).


ELEMENT	MEANING
Green / red stepped line	Best bid / best ask
Bubbles	Trades (green buy, red sell); size = value; minimum set with BUBBLES
Yellow ring	A liquidation
Labels “x BTC · price”	Top 3 walls per side
Right histogram	Current depth per price (green bids, red asks)

WINDOW sets the time shown (1–20 min), **RANGE** the price span (±40 ... ±640 points). Hover for exact size and time. = full screen. History starts when the page opens.

READING WALLS

A wall that stays while price approaches often holds (bounce); a wall pulled just before price arrives, or eaten by aggressive trades, usually leads to a breakout through that level.

11 Big trades



Taker volume boxes

Rows 5m · 30m · 4h · 1d: aggressive buy volume (green, left) against aggressive sell volume (red, right) in USD from Binance spot. The AI Agent uses the 30-minute balance as a vote.


Big prints tape

Every aggressive trade above the chosen minimum (≥ \$50K / \$100K / \$250K / \$500K) with exchange icon, price, size and time. Fills from the same exchange and side within 150 ms are merged into one print (a sweep). Green = taker buy, red = taker sell; brighter = bigger. A print of 5× the minimum beeps.

ICON	SOURCE
B	Binance spot
G	Gate futures
Y	Bybit futures
O	OKX swap
C	Coinbase

The footer shows which sources are connected. Some networks block Bybit, OKX or Coinbase; the tape then uses the sources that work.

12 TradingView window · controls & auto tools



15M with Auto Fibonacci, Auto Breakout Retracement, RSI Swing and Auto TP & SL switched on.

A TradingView-style chart with its own Binance candles (up to 1000 bars, updated every 3 seconds). Drag to scroll, mouse wheel to zoom, double-click to return to the latest candles.

CONTROL	WHAT IT DOES
TF dropdown	1m · 5m · 15m · 30m · 1h · 4h · D · W. The header timeframe sets it too.
TOOLS	Switch every tool on or off (the pink number = how many are on) and set swing sensitivity (Low = major swings, High = minor swings).
RESET · BLANK	Removes every drawing — plain candles.
	Full-screen window; X or Esc closes it.

Timeframe, tools and sensitivity are remembered in your browser. Under the chart each tool has a card; the **Auto TP & SL** card is always first with a glowing border (green LONG, red SHORT, yellow no setup).

12 TradingView window - the tools



The TOOLS dropdown.

TOOL	WHAT IT DRAWS
Auto Fibonacci	Latest major swing (ATR zigzag): 0.236 · 0.382 · 0.5 · 0.618 · 0.786 retracements and 1.272 / 1.618 extension targets. The card shows the leg and how deep price has retraced.
Auto Breakout Retracement	Most recent close through a swing level (dashed yellow) or a two-point trendline (solid yellow), marked BO ▲ / ▼, with the blue 38.2–61.8 % retest zone and the red 78.6 % line. Status: EXTENDING → WAITING RETEST → RETEST IN ZONE → DEEP RETRACE / FAILED.
Auto Take Profit & Stop Loss	A position box with entry, SL and TP1–TP3 in R, from the switched-on tools in the order N Strategy › Breakout retest › Fibonacci (EMA 50 trend if none).
Auto N Strategy	A-B-C N wave; entry on the break of B; targets V, N, E, NT (below).
Sniper Indicator	Complete sniper overlay with signals, entry, SL, TP1–TP4 and a status table — section 13.
RSI Swing Indicator	RSI(7) 70/30 pane; swing highs / lows between overbought and oversold labelled HH / LH / HL / LL.

N strategy targets

TARGET	FORMULA	MEANING
V	$B + (B - C)$	mirror of the pullback
N	$C + (B - A)$	classic N target (gold line)
E	$B + (B - A)$	extended target
NT	$C + (C - A)$	conservative target

13 Sniper Indicator



TradingView window full screen, 15M, TOOLS → Sniper Indicator.

Switch it on in **TOOLS** → **Sniper Indicator**. It is always calculated in the background (the AI Agent reads it) but only drawn when switched on.

ELEMENT	RULE / MEANING
Yellow + blue ribbon	EMA 9 (yellow) and EMA 21 (blue).
BUY / SELL tag	EMA 9 crosses EMA 21 in the direction of the EMA 50 / 200 trend (EMA 50 above 200 and price above 200 = up trend).
RE-BUY / RE-SELL	After a signal, price pulls back to EMA 21, is rejected and closes back beyond EMA 9 — a second entry in the same direction.
Entry / SL / TP box	Entry = close of the signal candle. SL beyond the 10-candle swing + 0.2 ATR (limited to 0.8–2.5 ATR). TP1 0.5R · TP2 1.5R · TP3 3R · TP4 open runner (trail with EMA 21). After TP1 the stop moves to the entry (“SL → BE”). Labels show distance in points and price.
TOKYO / LONDON / NEW YORK HIGH & LOW	Session ranges (UTC 00–09, 07–16, 13–22), “live” while the session runs. Shown on 1m–1h.
BSL / SSL	Buy-side / sell-side liquidity: swing highs above and swing lows below price that have not been taken yet, on the chart timeframe and on 15M. Price often sweeps them.
1H BULL / BEAR OB	Order blocks: last opposite candle before a strong 1-hour move (≥ 1.5 ATR in 3 candles) that price has not closed through yet.
UNTESTED DEMAND / SUPPLY	Same idea on the chart timeframe, zones not yet revisited.
Status table (top-right)	Market TRENDING / BUILDING / RANGING ($ADX\ 14 \geq 25$ / $18-25$ / < 18) · Trend BULLISH / BEARISH / MIXED · Status LONG / SHORT ACTIVE, TP HIT, STOPPED, WAITING SETUP · Entry · SL · TP1–TP4.


CHART AID, NOT BACKTESTED

Best used when Market = TRENDING, the signal is in the direction of the higher timeframe, and the entry is not right under a BSL (for longs) or above an SSL (for shorts). A new signal sounds the siren when ALERT is on.

14 Footprint · volume profile · entry timing



Title bar: **TF** 1m / 3m / 5m (follows the header; 15M and higher use 5m) and **Candles** 20 / 30 / 45 / 60. The status on the right reads e.g. **WAIT · TIMING 77 NO SETUP · READY**. The panel border glows green on BUY, red on SELL, yellow while waiting.



PART	MEANING
Left strip · order book	Liquidity resting at each price now: lavender = bids, grey = asks.
Candles + profile inside	Grey = up, navy = down. For candles recorded live: volume per price inside the candle (lavender taker buy, grey taker sell), magenta tick = that candle's POC.
Pattern tags	Short codes (3S, IB, NS, E ▲ ...) for candle patterns, coloured by their measured odds.
Right profile · VPVR	Volume per price for all visible candles.
POC · VAH · VAL	Point of control (most volume) and value area high / low (70 % of volume).
VOL pane	Volume per candle, buy/sell stacked, yellow 20-candle average; spikes $\geq 2\times$ outlined.
CVD pane	Cumulative volume delta: rising = aggressive buyers in control.
Signal lines	White dashed entry, red stop, green TP1 / TP2 when a setup is live.

14 Footprint · entry timing & setups



A score from 0 to 100 that tells you **when** conditions are good to act — never whether a setup is right. The inner ring is the progress of the current candle; the centre shows the time to close.

COMPONENT	GOOD WHEN
Candle clock	With a setup: early in a fresh candle
Activity	Volume pace ≥ normal
Delta 60 s	Aggressive flow in the trade direction
Book ±0.1 %	Imbalance in the trade direction
Distance to entry	Price still close to the entry (< ~1 ATR)
Volatility	ATR normal
Session	EU / US hours (07–21 UTC)

States: **ENTER NOW** (≥ 70 with a setup) · **GET READY** (50–69) · **WAIT** (< 50) · **NO SETUP** · **READY** / **WAIT**.

Price-action setups (checked on every closed candle)

- **Sweep & reclaim** — wick through VAL / swing low / bid wall (long) or VAH / swing high / ask wall (short), close back inside with delta.
- **VAH / VAL breakout retest** — accepted outside the value area, retest holds.
- **POC engulfing** — engulfing candle at the POC with delta.

A new setup draws its lines, turns the border green / red, sounds the siren and is passed to the AI Agent. Not backtested.

15 AI Agent - summary & sniper plan



The AI Agent bar in the header with its summary dropped down.

The AI Agent is fixed in the **header top row**, between USER GUIDE and the live price. It reads **every instrument on the page every second** and concludes one plan.

- **The bar** shows the verdict at a glance: **BUY @ price · TP1 · CL**, **SELL @ ...** or **WAIT · agreement %**. Its border glows green on BUY, red on SELL, purple while waiting.
- **Click the bar or +** to drop the full summary down over the page; **–** closes it. The open / closed choice is remembered. On phones, tapping outside closes it.

Votes

INSTRUMENT	WEIGHT
Sniper Indicator active trade	3
1H Bollinger squeeze trade	3
Footprint setup	2
Trend EMA 50/200 · pressure meter · momentum 60 s · taker flow 30 m	1 each
Momentum meter (only at overbought / oversold, against chasing)	1

Verdict

Agreement = weighted votes ÷ total weight. When it is at least 20 % to one side **and** an instrument on that side has a plan, the verdict is BUY or SELL. Plan source priority: Sniper Indicator › footprint setup › 1H squeeze › Auto TP & SL. Otherwise **WAIT** with the nearest liquidity above and below.

Each row of the list shows ▲ (buy), ▼ (sell) or · (neutral) for one instrument with its reading. A change to BUY or SELL sounds the siren.

The plan

FIELD	MEANING
Open price	Where to open. If price has already moved more than half the risk away, it reads Open (limit) : place a limit order there instead of chasing.
Take profit 1 · 2 · 3	Targets from the plan source.
Cut loss	Stop loss. Move it to the open price after TP1.
Risk / reward · Price now	Reward to TP2 in R, and the live price.

USE WITH CARE

The agent combines chart aids; only the 1H squeeze part is backtested. Treat its plan as a checklist and keep the size small.

16 Music widget



The **MUSIC** button (bottom-right) plays or pauses a background YouTube playlist — audio only, the video is hidden and requested in low quality (240p) to save power and data. When the playlist ends it starts again. Your play / pause choice is remembered.

Browsers start sound only after you click the page once. The tiny • button next to it hides or shows the music button. Music is silent while the password screen is shown.

17 Multi-market notes

- **Gold (XAUUSD)** uses Binance spot PAXG/USDT (1 PAXG = 1 troy ounce) as the price; Gate.io XAU_USDT futures supply liquidations. Exness XAUUSD may differ by a few dollars.
- Point settings (row sizes, distances, costs) scale with each market's volatility; dollar thresholds (big trades, bubbles) scale with market size.
- Prices use the right decimals (SOL 3, others 2).
- The 1H squeeze backtest was done on BTCUSD. On other markets the panel marks it as unconfirmed.

18 Daily workflow, glossary & risk notice

A simple routine

1. Choose market and timeframe, turn **ALERT: ON**, click the page once.
2. Check the momentum meter on several timeframes and the Bollinger chart: is the market stretched or squeezed?
3. Read the context: liquidation clusters, order book walls, pressure meter, big trades, Sniper Indicator status table (TRENDING or RANGING).
4. Wait for the siren: AI Agent BUY / SELL, a Sniper signal, a footprint setup or a 1H squeeze trade. Prefer moments where several agree and the live graph shows an open drive in the same direction.
5. Open on Exness at the open price (limit if price ran away), place the cut loss immediately, take partial profit at TP1 and move the stop to entry.
6. Never move a stop further away. Stop after 3 losses in a row or -3R in a day.

Glossary

ATR	Average True Range — typical candle size; used for stops and targets.
R	Result in units of the initial risk (1R = the stop distance).
Bollinger squeeze	Unusually narrow bands — low volatility that often precedes a strong move.
%B	Position of price between the lower (0) and upper (100) Bollinger band.
BSL / SSL	Buy-side / sell-side liquidity: stops resting above swing highs / below swing lows.
Order block (OB)	Last opposite candle before a strong move; often revisited.
POC / VAH / VAL	Point of control, value area high / low of the volume profile.
CVD / delta	Aggressive buys minus aggressive sells.
Taker	The side that crosses the spread (market order).
Sweep	A quick run through a level (stops / liquidations) followed by a return.
Points (pts)	Price units of the selected market (BTC: \$1).

RISK NOTICE

This dashboard is an educational technical-analysis tool. It does not execute trades and is not investment advice. Leveraged CFD and crypto trading carries a high risk of losing money quickly. Past or backtested results do not guarantee future results; data feeds can be delayed or unavailable. Only trade with money you can afford to lose and always use a stop loss. Support: CONTACT CS (WhatsApp).