8.13 实现数据模型的类型约束 ¶

问题¶

你想定义某些在属性赋值上面有限制的数据结构。

解决方案¶

在这个问题中,你需要在对某些实例属性赋值时进行检查。 所以你要自定义属性赋值函数,这种情况下最好使用描述器。

下面的代码使用描述器实现了一个系统类型和赋值验证框架:

```
# Base class. Uses a descriptor to set a value
class Descriptor:
  def __init__(self, name=None, **opts):
    self.name = name
    for key, value in opts.items():
      setattr(self, key, value)
  def set (self, instance, value):
    instance. dict [self.name] = value
# Descriptor for enforcing types
class Typed(Descriptor):
  expected_type = type(None)
  def set (self, instance, value):
    if not isinstance(value, self.expected type):
      raise TypeError('expected ' + str(self.expected type))
    super(). set (instance, value)
# Descriptor for enforcing values
class Unsigned(Descriptor):
  def set (self, instance, value):
    if value < 0:
      raise ValueError('Expected >= 0')
    super().__set__(instance, value)
class MaxSized(Descriptor):
  def init (self, name=None, **opts):
    if 'size' not in opts:
      raise TypeError('missing size option')
    super().__init__(name, **opts)
  def __set__(self, instance, value):
    if len(value) >= self.size:
      raise ValueError('size must be < ' + str(self.size))
    super(). set (instance, value)
这些类就是你要创建的数据模型或类型系统的基础构建模块。 下面就是我们实际定义的各种不同的数据类型:
```

```
class Integer(Typed):
  expected type = int
class UnsignedInteger(Integer, Unsigned):
  pass
class Float(Typed):
  expected_type = float
class UnsignedFloat(Float, Unsigned):
  pass
class String(Typed):
  expected_type = str
class SizedString(String, MaxSized):
  pass
然后使用这些自定义数据类型,我们定义一个类:
class Stock:
  # Specify constraints
  name = SizedString('name', size=8)
  shares = UnsignedInteger('shares')
  price = UnsignedFloat('price')
  def __init__(self, name, shares, price):
    self.name = name
    self.shares = shares
    self.price = price
然后测试这个类的属性赋值约束,可发现对某些属性的赋值违法了约束是不合法的:
>>> s.name
'ACME'
>>> s.shares = 75
>>> s.shares = -10
Traceback (most recent call last):
  File "<stdin>", line 1, in <module>
  File "example.py", line 17, in __set_
    super(). set (instance, value)
  File "example.py", line 23, in __set_
    raise ValueError('Expected >= 0')
ValueError: Expected >= 0
>>> s.price = 'a lot'
Traceback (most recent call last):
  File "<stdin>", line 1, in <module>
  File "example.py", line 16, in __set_
    raise TypeError('expected ' + str(self.expected type))
TypeError: expected <class 'float'>
>>> s.name = 'ABRACADABRA'
Traceback (most recent call last):
  File "<stdin>", line 1, in <module>
  File "example.py", line 17, in __set_
    super(). set (instance, value)
  File "example.py", line 35, in __set_
    raise ValueError('size must be < ' + str(self.size))
```

```
ValueError: size must be < 8
还有一些技术可以简化上面的代码,其中一种是使用类装饰器:
# Class decorator to apply constraints
def check_attributes(**kwargs):
 def decorate(cls):
   for key, value in kwargs.items():
     if isinstance(value, Descriptor):
       value.name = key
       setattr(cls, key, value)
       setattr(cls, key, value(key))
   return cls
 return decorate
# Example
@check_attributes(name=SizedString(size=8),
        shares=UnsignedInteger,
        price=UnsignedFloat)
class Stock:
 def __init__(self, name, shares, price):
   self.name = name
   self.shares = shares
   self.price = price
另外一种方式是使用元类:
# A metaclass that applies checking
class checkedmeta(type):
 def __new__(cls, clsname, bases, methods):
   # Attach attribute names to the descriptors
   for key, value in methods.items():
     if isinstance(value, Descriptor):
       value.name = key
   return type.__new__(cls, clsname, bases, methods)
# Example
class Stock2(metaclass=checkedmeta):
 name = SizedString(size=8)
 shares = UnsignedInteger()
 price = UnsignedFloat()
 def __init__(self, name, shares, price):
   self.name = name
   self.shares = shares
   self.price = price
讨论¶
本节使用了很多高级技术,包括描述器、混入类、 super() 的使用、类装饰器和元类。 不可能在这里一一详细展开来
讲,但是可以在8.9、8.18、9.19小节找到更多例子。 但是,我在这里还是要提一下几个需要注意的点。
首先,在 Descriptor 基类中你会看到有个 __set_() 方法,却没有相应的 __get_() 方法。 如果一个描述仅仅是从底层实
```

四字事中等原在区面医院的法 电区分别分单十分分

所有描述器类都是基于混入类来实现的。比如 Unsigned 和 MaxSized 要跟其他继承自 Typed 类混入。 这里利用多继承来实现相应的功能。

混入类的一个比较难理解的地方是,调用 super() 函数时,你并不知道究竟要调用哪个具体类。 你需要跟其他类结合后才能正确的使用,也就是必须合作才能产生效果。

使用类装饰器和元类通常可以简化代码。上面两个例子中你会发现你只需要输入一次属性名即可了。

Normal

class Point:

x = Integer('x')

y = Integer('y')

Metaclass

class Point(metaclass=checkedmeta):

x = Integer()
y = Integer()

所有方法中,类装饰器方案应该是最灵活和最高明的。 首先,它并不依赖任何其他新的技术,比如元类。其次,装饰器可以很容易的添加或删除。

最后,装饰器还能作为混入类的替代技术来实现同样的效果;

```
# Decorator for applying type checking
```

```
def Typed(expected_type, cls=None):
   if cls is None:
       return lambda cls: Typed(expected_type, cls)
       super_set = cls.__set__

def __set__(self, instance, value):
       if not isinstance(value, expected_type):
           raise TypeError('expected ' + str(expected_type))
           super_set(self, instance, value)

cls.__set__ = __set__
       return cls
```

Decorator for unsigned values

```
def Unsigned(cls):
    super_set = cls.__set__

def __set__(self, instance, value):
    if value < 0:
        raise ValueError('Expected >= 0')
        super_set(self, instance, value)

cls.__set__ = __set__
    return cls
```

Decorator for allowing sized values

def MaxSized(cls):

Carman tuta "ata" tuta

```
super_init = cis.__init__
 def __init__(self, name=None, **opts):
    if 'size' not in opts:
      raise TypeError('missing size option')
    super_init(self, name, **opts)
 cls.__init__ = __init__
 super_set = cls.__set__
 def __set__(self, instance, value):
    if len(value) >= self.size:
      raise ValueError('size must be < ' + str(self.size))
    super_set(self, instance, value)
 cls.__set__ = __set__
 return cls
# Specialized descriptors
@Typed(int)
class Integer(Descriptor):
 pass
@Unsigned
class UnsignedInteger(Integer):
 pass
@Typed(float)
class Float(Descriptor):
 pass
@Unsigned
class UnsignedFloat(Float):
 pass
@Typed(str)
class String(Descriptor):
 pass
@MaxSized
class SizedString(String):
 pass
这种方式定义的类跟之前的效果一样,而且执行速度会更快。 设置一个简单的类型属性的值,装饰器方式要比之前的混
```

入类的方式几乎快100%。 现在你应该庆幸自己读完了本节全部内容了吧? ^_^