一、环境

xmjmaster: 192.168.238.160 xmjslave1: 192.168.238.161 xmjslave2: 192.168.238.162

二、zookeeper集群安装部署

1.下载zookeeper

```
https://zookeeper.apache.org/releases.html
zookeeper-3.4.14.tar.gz
```

2.上传到linux并解压缩

```
tar -zxvf zookeeper-3.4.14.tar.gz -C /usr/local/
```

3.进入zookeeper目录,创建data和logs目录

```
cd /usr/local/zookeeper-3.4.14
mkdir data
cd data
mkdir logs
```

4.修改配置文件zoo.cfg

```
cd /usr/local/zookeeper-3.4.14/conf
mv zoo_sample.cfg zoo.cfg

vim zoo.cfg

dataDir=/usr/local/zookeeper-3.4.14/data
dataLogDir=/usr/local/zookeeper-3.4.14/data/logs
```

5.集群配置: myid

```
cd /usr/local/zookeeper-3.4.14/data touch myid vim myid ##记录每个服务器的id,内容分别为1、2、3
```

6.集群配置:修改配置文件zoo.cfg

```
cd /usr/local/zookeeper-3.4.14/conf
vim zoo.cfg
server.1=192.168.238.160:2881:3881
server.2=192.168.238.161:2881:3881
server.3=192.168.238.162:2881:3881
```

7.分发zookeeper目录到其他节点(注意修改对应的myid)

```
cd /usr/local/
scp -r zookeeper-3.4.14 192.168.238.161:/usr/local/
scp -r zookeeper-3.4.14 192.168.238.162:/usr/local/
```

8.启动

```
cd /usr/local/zookeeper-3.4.14/bin
./zkServer.sh start
```

三、hbase集群安装部署

1.下载hbase

```
http://archive.apache.org/dist/
hbase-1.3.1-bin.tar.gz
```

2.上传到linux并解压缩

```
tar -zxvf hbase-1.3.1-bin.tar.gz -C /usr/local/
```

3.修改配置文件

1) 把hadoop中的配置core-site.xml 、hdfs-site.xml拷贝到hbase安装目录下的conf文件夹中

```
cd /usr/local/hadoop-2.7.2/etc/hadoop/
cp core-site.xml hdfs-site.xml /usr/local/hbase-1.3.1/conf/
```

2)修改 hbase-env.sh

```
cd /usr/local/hbase-1.3.1/conf/
vim hbase-env.sh

#添加java环境变量
export JAVA_HOME=/usr/java/jdk1.8.0_251-amd64

#指定使用外部的zk集群
export HBASE_MANAGES_ZK=FALSE
```

3)修改 hbase-site.xml

4)修改regionservers

```
vim regionservers

xmjmaster

xmjslave1

xmjslave2
```

5)hbase的conf目录下创建文件backup-masters

```
vim backup-masters
xmjslave1
```

4.配置hbase环境变量

```
vim /etc/profile

export HBASE_HOME=/usr/local/hbase-1.3.1
export PATH=$PATH:$HBASE_HOME/bin

source /etc/profile
```

5. 分发hbase目录和环境变量到其他节点

```
cd /usr/local/
scp -r hbase-1.3.1 192.168.238.161:/usr/local/
scp -r hbase-1.3.1 192.168.238.162:/usr/local/
```

四、hbase集群的启动和停止

```
##前提条件: 先启动hadoop和zk集群
cd /usr/local/hbase-1.3.1/bin/
./start-hbase.sh
```

访问hbase集群的web管理界面: HMaster的主机名:16010

http://xmjmaster:16010

Master xmjmaster

Region Servers

Base Stats Memory Requests Storefiles Compactions						
ServerName			Start time	Version	Requests Per Second	Num. Regions
xmjmaster,16020,15953856	394385		Wed Jul 22 10:41:34 CST 2020	1.3.1	0	1
xmjslave1,16020,15953857	09407		Wed Jul 22 10:41:49 CST 2020	1.3.1	0	1
xmjslave2,16020,15953857	03950		Wed Jul 22 10:41:43 CST 2020	1.3.1	0	0
Total:3					0	2

Backup Masters

ServerName	Port	Start Time
xmjslave1	16000	Wed Jul 22 10:41:49 CST 2020