Transport Layer

our goals:

- understand

 principles behind
 transport layer
 services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control

- learn about Internet transport layer protocols:
 - UDP: connectionless transport
 - TCP: connectionoriented reliable transport
 - TCP congestion control

Outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

3.5 connection-oriented transport: TCP


- segment structure
- reliable data transfer
- flow control
- connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP: Overview RFCs: 793,1122,1323, 2018, 2581

- point-to-point:
 - one sender, one receiver
- reliable, in-order byte steam:
 - no "message boundaries"
- * pipelined:
 - TCP congestion and flow control set window size

- full duplex data:
 - bi-directional data flow in same connection
 - MSS: maximum segment size
- * connection-oriented:
 - handshaking (exchange of control msgs) inits sender, receiver state before data exchange
- flow controlled:
 - sender will not overwhelm receiver

TCP segment structure




TCP seq. numbers, ACKs

sequence numbers:


•byte stream "number" of first byte in segment's data

acknowledgements:

- seq # of next byte
 expected from other
 side
- cumulative ACK
- Q: how receiver handles out-of-order segments
 - A: TCP spec doesn't say, - up to implementor



TCP seq. numbers, ACKs



simple telnet scenario

TCP round trip time, timeout


- Q: how to set TCP timeout value?
- longer than RTT
 - but RTT varies
- too short:
 premature timeout,
 unnecessary
 retransmissions
- too long: slow reaction to segment loss

- Q: how to estimate RTT?
- * SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT

TCP round trip time, timeout

EstimatedRTT = $(1-\alpha)$ *EstimatedRTT + α *SampleRTT

- exponential weighted moving average
- influence of past sample decreases exponentially fast
- * typical value: $\alpha = 0.125$



TCP round trip time, timeout

- * timeout interval: EstimatedRTT plus "safety margin"
 - large variation in EstimatedRTT -> larger safety margin
- estimate SampleRTT deviation from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT +

\beta*|SampleRTT-EstimatedRTT|

(typically, \beta = 0.25)
```

TimeoutInterval = EstimatedRTT + 4*DevRTT



estimated RTT "safety margin"

Outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP reliable data transfer

- TCP creates rdt service on top of IP's unreliable service
 - pipelined segments
 - cumulative acks
 - single retransmission timer
- retransmissions triggered by:
 - timeout events
 - duplicate acks

let's initially consider simplified TCP sender:

- ignore duplicate acks
- ignore flow control, congestion control

TCP sender events:

data rcvd from app:

- create segment with seq #
- seq # is bytestream number of first data byte in segment
- start timer if not already running
 - think of timer as for oldest unacked segment
 - expiration interval:TimeOutInterval


timeout:

- retransmit segment that caused timeout
- * restart timer


ack rcvd:

- if ack acknowledges previously unacked segments
 - update what is known to be ACKed
 - start timer if there are still unacked segments


TCP sender (simplified)



TCP: retransmission scenarios



TCP: retransmission scenarios



cumulative ACK

TCP ACK generation [RFC 1122, RFC 2581]

event at receiver	TCP receiver action
arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
arrival of in-order segment with expected seq #. One other segment has ACK pending	immediately send single cumulative ACK, ACKing both in-order segments
arrival of out-of-order segment higher-than-expect seq. # . Gap detected	immediately send duplicate ACK, indicating seq. # of next expected byte
arrival of segment that partially or completely fills gap	immediate send ACK, provided that segment starts at lower end of gap

TCP fast retransmit


- time-out period often relatively long:
 - long delay before resending lost packet
- detect lost segments via duplicate ACKs.
 - sender often sends many segments backto-back
 - if segment is lost, there will likely be many duplicate ACKs.

TCP fast retransmit

if sender receives 3
ACKs for same data
("triple duplicate ACKs"),
resend unacked
segment with smallest
seq #

 likely that unacked segment lost, so don't wait for timeout

TCP fast retransmit



receipt of triple duplicate ACK

Outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

3.5 connection-oriented transport: TCP

- segment structure
- reliable data transfer
- flow control
- connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP flow control

application may remove data from TCP socket buffers

... slower than TCP receiver is delivering (sender is sending)

application process application OS TCP socket receiver buffers **TCP** code code from sender


receiver protocol stack

flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast

TCP flow control

- receiver "advertises"
 free buffer space by
 including rwnd value in
 TCP header of receiver to-sender segments
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust RcvBuffer
- sender limits amount of unacked ("in-flight") data to receiver's rwnd value
- guarantees receive buffer will not overflow



receiver-side buffering

Outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Connection Management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters



```
Socket clientSocket =
  newSocket("hostname","port
  number");
```

```
application


connection state: ESTAB
connection Variables:
  seq # client-to-server
      server-to-client
  rcvBuffer size
  at server,client


network
```

```
Socket connectionSocket =
  welcomeSocket.accept();
```

Agreeing to establish a connection

2-way handshake:







Q: will 2-way handshake always work in network?

- variable delays
- retransmitted messages
 (e.g. req_conn(x)) due to
 message loss
- message reordering
- * can't "see" other side


Agreeing to establish a connection



TCP 3-way handshake




TCP 3-way handshake: FSM



TCP: closing a connection

- client, server each close their side of connection
 - send TCP segment with FIN bit = 1
- * respond to received FIN with ACK
 - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

TCP: closing a connection



Outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer


- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Principles of congestion control

congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- * manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- * a top-10 problem!

Recall: Packet Switching, Queue of packets




Sequence of A & B packets does not have fixed pattern, shared on demand \Rightarrow statistical multiplexing.


two senders, two receivers

one router, infinite buffers


output link capacity: R

* no retransmission





maximum per-connection throughput: R/2




 large delays as arrival rate, λ_{in}, approaches capacity

- * one router, finite buffers
- * sender retransmission of timed-out packet
 - application-layer input = application-layer output:


$$\lambda_{\text{in}} = \lambda_{\text{out}}$$


• transport-layer input includes retransmissions: $\lambda'_{in} \geq \lambda_{out}$



idealization: perfect knowledge


 sender sends only when router buffers available






Idealization: known loss packets can be lost, dropped at router due to full buffers


 sender only resends if packet known to be lost



Idealization: known loss packets can be lost, dropped at router due to full buffers

 sender only resends if packet known to be lost







Realistic: duplicates

 packets can be lost, dropped at router due to full buffers


* sender times out prematurely, sending two copies, both of which are delivered





Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- * sender times out prematurely, sending two copies, both of which are delivered




"costs" of congestion:


- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt
 - decreasing goodput

- * four senders
- multihop paths
- * timeout/retransmit

 $\frac{Q:}{\lambda_{in}}$ what happens as λ_{in} and λ_{in} increase ?

A: as red λ_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput $\rightarrow 0$





another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

Approaches towards congestion control

two broad approaches towards congestion control:

end-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

network-assisted – congestion control:

- routers provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
 - explicit rate for sender to send at

Case study: ATM ABR congestion control


ABR: available bit rate:

- "elastic service"
- if sender's path "underloaded":
 - sender should use available bandwidth
- if sender's path congested:
 - sender throttled to minimum guaranteed rate

RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("networkassisted")
 - NI bit: no increase in rate (mild congestion)
 - CI bit: congestion indication
- RM cells returned to sender by receiver, with bits intact

Case study: ATM ABR congestion control



- * two-byte ER (explicit rate) field in RM cell
 - congested switch may lower ER value in cell
 - senders' send rate thus max supportable rate on path
- EFCI bit in data cells: set to 1 in congested switch
 - if data cell preceding RM cell has EFCI set, receiver sets CI bit in returned RM cell

Outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control


TCP congestion control: additive increase multiplicative decrease

- * approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
 - additive increase: increase cwnd by 1 MSS every RTT until loss detected
 - multiplicative decrease: cut cwnd in half after loss

AIMD saw tooth behavior: probing for bandwidth cwnd: TCP sender



TCP Congestion Control: details



* sender limits transmission:

LastByteSent-
$$\leq$$
 cwnd LastByteAcked

 cwnd is dynamic, function of perceived network congestion


TCP sending rate:

 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

TCP Slow Start

- * when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = 1 MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- * <u>summary</u>: initial rate is slow but ramps up exponentially fast



TCP: detecting, reacting to loss

- * loss indicated by timeout:
 - cwnd set to 1 MSS;
 - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - dup ACKs indicate network capable of delivering some segments
 - cwnd is cut in half window then grows linearly
- * TCP Tahoe always sets cwnd to 1 (timeout or 3 duplicate acks)


TCP: switching from slow start to CA

Q: when should the exponential increase switch to linear?


A: when cwnd gets to 1/2 of its value before timeout.

Implementation:

- variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event




Summary: TCP Congestion Control



TCP throughput

- avg. TCP thruput as function of window size, RTT?
 - ignore slow start, assume always data to send
- * W: window size (measured in bytes) where loss occurs
 - avg. window size (# in-flight bytes) is $\frac{3}{4}$ W
 - avg. thruput is 3/4W per RTT

avg TCP thruput =
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec



TCP Futures: TCP over "long, fat pipes"


- example: 1500 byte segments, 100ms RTT, want 10 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

TCP throughput =
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- → to achieve 10 Gbps throughput, need a loss rate of $L = 2.10^{-10}$ a very small loss rate!
- new versions of TCP for high-speed

TCP Fairness

fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K




Why is TCP fair?

two competing sessions:

additive increase gives slope of 1, as throughout increases

* multiplicative decrease decreases throughput



Fairness (more)

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- * instead use UDP:
 - send audio/video at constant rate, tolerate packet loss

Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- * web browsers do this
- e.g., link of rate R with 9 existing connections:
 - new app asks for 1 TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2

summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control
- instantiation, implementation in the Internet
 - UDP
 - TCP

next:

- leaving the network "edge" (application, transport layers)
- into the network
 "core"