

Fancy Banjo Chords

and Their Voicings

(G) D G B D



<https://github.com/linenoise/voicings>

Movable Shapes

Banjo closed, so they move

shape root on bottom example

major

0000	G	5	1111 = Ab
2012	B	3	3123 = Db
2102	D	R	3213 = F
0234	D	R	1345 = Eb

minor

1011	B	b3	2122 = Dbm
1101	G	5	2212 = Am
2002	D	R	3113 = Fm

seventh

0003	G	5	1114 = Ab7
0102	D	b7	1213 = F7
2100	D	R	3211 = F7

- Shape is the fingering above its lowest fret.
- Slide it one fret, the chord rises a semitone.
- Bottom is the degree on the lowest string.

Banjo

Bb / A#

- Drone spike: 9, tune down → Bb

Bb	3333	Bb7b5	2336
Bbm	3323	Bb7#5	4336
Bb5	x36x		
Bb+	0334	Bb9	0110 ^r
Bb°	2322	Bbmaj9	0210 ^r
Bbsus2	331x	Bbm9	3526 ^r
Bbsus4	1341	Bbadd9	0310
		Bbmadd9	866 ^[10]
Bb6	0335	Bb7b9	0100 ^r
Bbm6	3325	Bb7#9	0120 ^r
Bb6/9	0010 ^r	Bbm11	1121 ^r

Bb7	3336	Bbm/Db	x668
Bbmaj7	0337	Bb/D	0330
Bbm7	3326	Bb7/D	0336
Bb°7	2325	Bbsus2/D	0310
Bbm7b5	2326	Bb/F	3330
Bb7sus4	1346	Bbm/F	332x

Banjo

C

- Drone spike: open g → G

C	2012	C7b5	2314
Cm	1011	C7#5	6558
C5	x58x		
C+	2112	C9	0312
C°	1514	Cmaj9	0002 ^r
Csus2	0010	Cm9	0311
Csus4	3013	Cadd9	0012
		Cmadd9	0011
C6	2215	C7b9	2322 ^r
Cm6	1211	C7#9	1312
C6/9	0210	Cm11	1333 ^r

C7	2312	Cm/Eb	1511
Cmaj7	5502	C/E	2012
Cm7	1311	C7/E	2312
C°7	1214	Csus2/E	2010
Cm7b5	1314	C/G	5012
C7sus4	3315	Cm/G	5011

Banjo


A

Drone spike: 7 → A

A	2222	A7b5	1225
Am	2212	A7#5	3225
A5	x25x		
A+	3223	A9	2425 ^r
A°	1211	Amaj9	6602 ^r
Asus2	220x	Am9	5502 ^r
Asus4	0230	Aadd9	7602
		Amadd9	7502
A6	2224	A7b9	2325 ^r
Am6	2214	A7#9	5522 ^r
A6/9	2204	Am11	0010 ^r
A7	2225	Am/C	x557
Amaj7	2226	A/C#	x657
Am7	2215	A7/C#	[11]087
A°7	1214	Asus2/C#	x607
Am7b5	1215	A/E	2222
A7sus4	0255	Am/E	221x

Banjo

Circle of Fifths



Outer ring: major.

Inner ring: relative minor.

Spike the drone as shown on the banjo pages.

Banjo

Db / C#

Drone spike: 7, tune down → Ab

Db	3123	Db7b5	3425
Dbm	2122	Db7#5	3607
Db5	x69x		
Db+	3223	Db9	1103 ^r
Db°	5022	Dbmaj9	1113 ^r
Dbsus2	1121	Dbm9	1102 ^r
Dbsus4	4124	Dbadd9	1123
		Dbmadd9	1122
Db6	3326	Db7b9	0103 ^r
Dbm6	2322	Db7#9	2103 ^r
Db6/9	1321	Dbm11	2104 ^r
Db7	3423	Dbm/E	2622
Dbmaj7	3523	Db/F	3123
Dbm7	2422	Db7/F	3423
Db°7	2325	Dbsus2/F	3121
Dbm7b5	2425	Db/Ab	6623
Db7sus4	4426	Dbm/Ab	6622

Banjo

B / Cb

Drone spike: 9 → B

B	4444	B7b5	1203
Bm	4434	B7#5	1007
B5	x47x		
B+	1001	B9	1221 ^r
B°	0403	Bmaj9	1321 ^r
Bsus2	442x	Bm9	0220 ^r
Bsus4	4402	Badd9	1421
		Bmadd9	0420
B6	1104	B7b9	1211 ^r
Bm6	0100	B7#9	0201
B6/9	1121 ^r	Bm11	0222 ^r
B7	1201	Bm/D	0x00
Bmaj7	1301	B/D#	1441
Bm7	0200	B7/D#	1201
B°7	0103	Bsus2/D#	1421
Bm7b5	0203	B/F#	4401
B7sus4	2204	Bm/F#	4430

Banjo

D

- Drone spike: 7 → A

D	0234	D7b5	0114
Dm	0233	D7#5	0314
D5	023x		
D+	0334	D9	2214 ^r
D°	0133	Dmaj9	2224 ^r
Dsus2	0232	Dm9	2213 ^r
Dsus4	00xx	Dadd9	0254

D6	0204	Dmadd9	0262
Dm6	0203	D7b9	1214 ^r
D6/9	xx00	D7#9	3214 ^r
		Dm11	0013

D7	0214	Dm/F	3230
Dmaj7	0224	D/F#	4230
Dm7	0213	D7/F#	4210
D°7	0103	Dsus2/F#	4232
Dm7b5	0113	D/A	7734
D7sus4	0010	Dm/A	7733

○

○

Banjo

E

- Drone spike: major 9 → B
minor open g → G

E	2102	E7b5	2336
Em	2002	E7#5	2110
E5	245x		
E+	2112	E9	0104 ^r
E°	2355	Emaj9	1104 ^r
Esus2	4402	Em9	2034
Esus4	2252	Eadd9	2104

E6	6602	Emadd9	2004
Em6	5022	E7b9	0103 ^r
E6/9	4122	E7#9	0105 ^r
		Em11	0205 ^r

E7	2100	Em/G	5002
Emaj7	1102	E/G#	x102
Em7	2000	E7/G#	x150
E°7	2325	Esus2/G#	x154
Em7b5	2335	E/B	9956
E7sus4	2200	Em/B	9055

○

○

Banjo

Gb / F#

- Drone spike: major 5, tune down → Gb
minor 7 → A

Gb	4324	Gb7b5	4312
Gbm	4224	Gb7#5	4332
Gb5	467x		
Gb+	4330	Gb9	2326 ^r
Gb°	4214	Gbmaj9	3326 ^r
Gbsus2	4124	Gbm9	2226 ^r
Gbsus4	442x	Gbadd9	4326

Gb6	1344	Gbmadd9	4226
Gbm6	4221	Gb7b9	2325 ^r
Gb6/9	1121 ^r	Gb7#9	2357 ^r
		Gbm11	2204

Gb7	4322	Gb/Db	[11][11]78
Gbmaj7	3324	Gbm/Db	[11][11]77
Gbm7	4222	Gbm/A	x224
Gb°7	4211	Gb/Bb	x324
Gbm7b5	2214	Gb7/Bb	x354
Gb7sus4	4402	Gbsus2/Bb	x376

○

○

Banjo

Ab / G#

- Drone spike: major 7, tune down → Ab
minor 9 → B

Ab	1111	Ab7b5	0114
Abm	1101	Ab7#5	2114
Ab5	x14x		
Ab+	2112	Ab9	1314 ^r
Ab°	0100	Abmaj9	1315 ^r
Absus2	1346	Abm9	1304 ^r
Absus4	1121	Abadd9	6548

Ab6	1113	Abmadd9	1306
Abm6	1103	Ab7b9	1214 ^r
Ab6/9	1113	Ab7#9	4411 ^r
		Abm11	4421 ^r

Ab7	1114	Ab/C	x546
Abmaj7	1115	Ab7/C	x576
Abm7	1104	Absus2/C	x598
Ab°7	0103	Ab/Eb	1111
Abm7b5	0104	Abm/Eb	110x
Ab7sus4	1124	Abm/B	x406

○

○

Banjo

F

Drone spike: major **7** → **A**
 minor **7**, tune down → **Ab**

F	3213	F7b5	3201
Fm	3113	F7#5	3221
F5	356x		
F+	3223	F9	1215^r
F°	3103	Fmaj9	2215^r
Fsus2	3013	Fm9	1115^r
Fsus4	331x	Fadd9	3215
		Fmadd9	3115
F6	3210	F7b9	1214^r
Fm6	3110	F7#9	1246^r
F6/9	0010^r	Fm11	1346^r
F7	3211	F/C	[10][10]67
Fmaj7	2213	Fm/C	[10][10]66
Fm7	3111	Fm/Ab	x113
F°7	3100	F/A	x213
Fm7b5	1103	F7/A	x243
F7sus4	3311	Fsus2/A	7063

Banjo

Eb / D#

Drone spike: major **open g** → **G**
 minor **9**, tune down → **Bb**

Eb	5345	Eb7b5	1225
Ebm	4344	Eb7#5	1425
Eb5	134x		
Eb+	1001	Eb9	1023
Eb°	1244	Ebmaj9	1033
Ebsus2	3341	Ebm9	3324^r
Ebsus4	1141	Ebadd9	1043
		Ebmadd9	3344
Eb6	5011	Eb7b9	1022
Ebm6	1314	Eb7#9	1024
Eb6/9	1311	Ebm11	1124
Eb7	1325	Ebm/Gb	4341
Ebmaj7	1030	Eb/G	5041
Ebm7	1324	Eb7/G	5021
Eb°7	1214	Ebsus2/G	5043
Ebm7b5	1224	Eb/Bb	8045
Eb7sus4	1121	Ebm/Bb	8844

Tunings

Banjo (G) D G B D

Open G (gDGBD). Numbers cover the four long strings; the 5th is a drone, spiked rather than fretted.

Fret numbers read from the lowest string.

x means don't play that string.

r means rootless: for rhythm, not for soloing.

Banjo

G

Drone spike: **open g** → **G**

G	0000	G7b5	5423
Gm	0335	G7#5	1003
G5	x03x		
G+	5001	G9	0203^r
G°	5325	Gmaj9	0204^r
Gsus2	5230	Gm9	3337^r
Gsus4	0010	Gadd9	5200
		Gmadd9	5337
G6	0002	G7b9	0103^r
Gm6	5332	G7#9	3300^r
G6/9	0002	Gm11	3310^r
G7	0003	G/D	0000
Gmaj7	0004	Gm/D	0335
Gm7	5333	Gm/Bb	x335
G°7	5322	G/B	9005
Gm7b5	3325	G7/B	9003
G7sus4	0013	Gsus2/B	x487

Fancy Banjo Chords and Their Voicings

Danne Stayskal

danne@stayskal.com

<http://danne.stayskal.com/>

Source, corrections and a printable copy:

<https://github.com/linenoise/voicings>

MIT licensed. Print it, cut it, sew it, give it away.