


Fancy  
**Ukulele**  
**Chords**  
and Their Voicings


---

**G C E A**



<https://github.com/linenoise/voicings>

# Circle of Fifths



Outer ring: major.

Inner ring: relative minor.

Both show the most common voicing.

# Movable Shapes

Ukulele closed, so they move

shape root on bottom example

## major

0003 C 5 1114 = Db

2010 E 3 3121 = Gb

2100 G R 3211 = Bb

2013 E 3 3124 = Gb

## minor

2000 G R 3111 = Bbm

1013 E b3 2124 = Gbm

2003 G R 3114 = Bbm

## seventh

0001 C 5 1112 = Db7

0100 A b7 1211 = Bb7

0212 G R 1323 = Ab7

Shape is the fingering above its lowest fret.

Slide it one fret, the chord rises a semitone.

Bottom is the degree on the lowest string.

## Ukulele

## A

|       |      |
|-------|------|
| A     | 2100 |
| Am    | 2000 |
| A5    | xx00 |
| A+    | 2110 |
| A°    | 2056 |
| Asus2 | 4400 |
| Asus4 | 2200 |

|      |      |
|------|------|
| A6   | 2120 |
| Am6  | 2020 |
| A6/9 | 2120 |

|        |      |
|--------|------|
| A7     | 0100 |
| Amaj7  | 1100 |
| Am7    | 0000 |
| A°7    | 2323 |
| Am7b5  | 2333 |
| A7sus4 | 0200 |

|      |      |
|------|------|
| A7b5 | 2334 |
| A7#5 | 0110 |

|        |                   |
|--------|-------------------|
| A9     | 2132              |
| Amaj9  | 1102 <sup>r</sup> |
| Am9    | 0002 <sup>r</sup> |
| Aadd9  | 4100              |
| Amadd9 | 2002              |
| A7b9   | 0101 <sup>r</sup> |
| A7#9   | 0103 <sup>r</sup> |
| Am11   | 2233              |

|          |      |
|----------|------|
| Am/C     | x000 |
| A/C#     | x100 |
| A7/C#    | x130 |
| Asus2/C# | x152 |
| A/E      | x454 |
| Am/E     | 9053 |

|   |                |             |                 |                         |
|---|----------------|-------------|-----------------|-------------------------|
| ○ | <b>Bb</b>      | <b>3211</b> | <b>Bb7b5</b>    | <b>1201</b>             |
|   | <b>Bbm</b>     | <b>3111</b> | <b>Bb7#5</b>    | <b>1221</b>             |
|   | <b>Bb5</b>     | <b>3511</b> |                 |                         |
|   | <b>Bb+</b>     | <b>3221</b> | <b>Bb9</b>      | <b>3243</b>             |
|   | <b>Bb°</b>     | <b>3101</b> | <b>Bbmaj9</b>   | <b>2213<sup>r</sup></b> |
|   | <b>Bbsus2</b>  | <b>3011</b> | <b>Bbm9</b>     | <b>1113<sup>r</sup></b> |
| ○ | <b>Bbsus4</b>  | <b>3311</b> | <b>Bbadd9</b>   | <b>3015</b>             |
|   |                |             | <b>Bbmadd9</b>  | <b>5111</b>             |
|   | <b>Bb6</b>     | <b>0211</b> | <b>Bb7b9</b>    | <b>1212<sup>r</sup></b> |
|   | <b>Bbm6</b>    | <b>0111</b> | <b>Bb7#9</b>    | <b>1115<sup>r</sup></b> |
|   | <b>Bb6/9</b>   | <b>0011</b> | <b>Bbm11</b>    | <b>1314<sup>r</sup></b> |
|   |                |             |                 |                         |
| ○ | <b>Bb7</b>     | <b>1211</b> | <b>Bbm/Db</b>   | <b>x111</b>             |
|   | <b>Bbmaj7</b>  | <b>3210</b> | <b>Bb/D</b>     | <b>x211</b>             |
|   | <b>Bbm7</b>    | <b>1111</b> | <b>Bb7/D</b>    | <b>x241</b>             |
|   | <b>Bb°7</b>    | <b>0101</b> | <b>Bbsus2/D</b> | <b>7063</b>             |
|   | <b>Bbm7b5</b>  | <b>1101</b> | <b>Bb/F</b>     | <b>x565</b>             |
|   | <b>Bb7sus4</b> | <b>1311</b> | <b>Bbm/F</b>    | <b>x564</b>             |
|   |                |             |                 |                         |
| ○ |                |             |                 |                         |
|   |                |             |                 |                         |
| ○ |                |             |                 |                         |

## Ukulele

B / C<sup>b</sup>

|       |      |
|-------|------|
| B     | 4322 |
| Bm    | 4222 |
| B5    | 4622 |
| B+    | 4332 |
| B°    | 4212 |
| Bsus2 | 4122 |
| Bsus4 | 4422 |

|      |      |
|------|------|
| B6   | 1322 |
| Bm6  | 1222 |
| B6/9 | 1122 |

|        |      |
|--------|------|
| B7     | 2322 |
| Bmaj7  | 4321 |
| Bm7    | 2222 |
| B°7    | 1212 |
| Bm7b5  | 4210 |
| B7sus4 | 4420 |

|      |      |
|------|------|
| B7b5 | 4310 |
| B7#5 | 2332 |

|        |                   |
|--------|-------------------|
| B9     | 6352              |
| Bmaj9  | 3324 <sup>r</sup> |
| Bm9    | 4155              |
| Badd9  | 6322              |
| Bmadd9 | 6222              |
| B7b9   | 2323 <sup>r</sup> |
| B7#9   | 2226 <sup>r</sup> |
| Bm11   | 2200 <sup>r</sup> |

|          |      |
|----------|------|
| Bm/D     | x222 |
| B/D#     | x322 |
| B7/D#    | x352 |
| Bsus2/D# | x374 |
| B/F#     | x676 |
| Bm/F#    | x675 |

# Ukulele

## C

|         |      |         |                   |
|---------|------|---------|-------------------|
| ○ C     | 0003 | C7b5    | 5421              |
| Cm      | 0333 | C7#5    | 1001              |
| C5      | 00xx |         |                   |
| C+      | 1003 | C9      | 0201 <sup>r</sup> |
| C°      | 5026 | Cmaj9   | 0202 <sup>r</sup> |
| Csus2   | 0233 | Cm9     | 0266 <sup>r</sup> |
| Csus4   | 0013 | Cadd9   | 0203              |
|         |      | Cmadd9  | 7333              |
| C6      | 0000 | C7b9    | 0101 <sup>r</sup> |
| Cm6     | 2333 | C7#9    | 0301 <sup>r</sup> |
| C6/9    | 0000 | Cm11    | 0311 <sup>r</sup> |
|         |      |         |                   |
| C7      | 0001 | Cm/Eb   | x333              |
| ○ Cmaj7 | 0002 | C/E     | 9003              |
| Cm7     | 3333 | C7/E    | x463              |
| C°7     | 2323 | Csus2/E | 9005              |
| Cm7b5   | 5321 | C/G     | 000x              |
| C7sus4  | 0011 | Cm/G    | 0333              |

○

○

## Ukulele

## Db / C#

|        |      |
|--------|------|
| Db     | 1114 |
| Dbm    | 1104 |
| Db5    | 1144 |
| Db+    | 2110 |
| Db°    | 0104 |
| Dbsus2 | 1344 |
| Dbsus4 | 1124 |

|       |      |
|-------|------|
| Db6   | 1111 |
| Dbm6  | 3444 |
| Db6/9 | 1111 |

|         |      |
|---------|------|
| Db7     | 1112 |
| Dbmaj7  | 1113 |
| Dbm7    | 4444 |
| Db°7    | 0101 |
| Dbm7b5  | 0102 |
| Db7sus4 | 1122 |

|       |      |
|-------|------|
| Db7b5 | 0112 |
| Db7#5 | 4110 |

|         |                   |
|---------|-------------------|
| Db9     | 1312 <sup>r</sup> |
| Dbmaj9  | 1313 <sup>r</sup> |
| Dbm9    | 1302 <sup>r</sup> |
| Dbadd9  | 1314              |
| Dbmadd9 | 1304              |
| Db7b9   | 1212 <sup>r</sup> |
| Db7#9   | 1412 <sup>r</sup> |
| Dbm11   | 1422 <sup>r</sup> |

|          |      |
|----------|------|
| Dbm/E    | x444 |
| Db/F     | x514 |
| Db7/F    | x574 |
| Dbsus2/F | x596 |
| Db/Ab    | 1114 |
| Dbm/Ab   | 1104 |

## Ukulele

## D

|   |        |      |          |                   |
|---|--------|------|----------|-------------------|
| ○ | D      | 2220 | D7b5     | 1223              |
|   | Dm     | 2210 | D7#5     | 5221              |
|   | D5     | 2250 |          |                   |
|   | D+     | 3221 | D9       | 2423 <sup>r</sup> |
|   | D°     | 1215 | Dmaj9    | 2424 <sup>r</sup> |
|   | Dsus2  | 2200 | Dm9      | 5410 <sup>r</sup> |
| ○ | Dsus4  | 0230 | Dadd9    | 2425              |
|   |        |      | Dmadd9   | 2415              |
|   | D6     | 2222 | D7b9     | 2323 <sup>r</sup> |
|   | Dm6    | 2212 | D7#9     | 5520 <sup>r</sup> |
|   | D6/9   | 2222 | Dm11     | 0010 <sup>r</sup> |
|   |        |      |          |                   |
| ○ | D7     | 2223 | Dm/F     | x515              |
|   | Dmaj7  | 2224 | D/F#     | x625              |
|   | Dm7    | 2213 | D7/F#    | x685              |
|   | D°7    | 1212 | Dsus2/F# | [11]905           |
|   | Dm7b5  | 1213 | D/A      | 2220              |
|   | D7sus4 | 0233 | Dm/A     | 2210              |
|   |        |      |          |                   |
| ○ |        |      |          |                   |
|   |        |      |          |                   |
| ○ |        |      |          |                   |

## Ukulele

## Eb / D#

|        |      |
|--------|------|
| Eb     | 0331 |
| Ebm    | 3321 |
| Eb5    | 3366 |
| Eb+    | 4332 |
| Eb°    | 2320 |
| Ebsus2 | 3311 |
| Ebsus4 | 1341 |

|       |                   |
|-------|-------------------|
| Eb6   | 3333              |
| Ebm6  | 3323              |
| Eb6/9 | 0011 <sup>r</sup> |

|         |                   |
|---------|-------------------|
| Eb7     | 3334              |
| Ebmaj7  | 3231 <sup>r</sup> |
| Ebm7    | 3324              |
| Eb°7    | 2323              |
| Ebm7b5  | 2324              |
| Eb7sus4 | 1344              |

|       |      |
|-------|------|
| Eb7b5 | 2334 |
| Eb7#5 | 6332 |

|         |                   |
|---------|-------------------|
| Eb9     | 0111 <sup>r</sup> |
| Ebmaj9  | 0211 <sup>r</sup> |
| Ebm9    | 3524 <sup>r</sup> |
| Ebadd9  | 0311              |
| Ebmadd9 | 3526              |
| Eb7b9   | 0101 <sup>r</sup> |
| Eb7#9   | 0121 <sup>r</sup> |
| Ebm11   | 1121 <sup>r</sup> |

|          |      |
|----------|------|
| Ebm/Gb   | x626 |
| Eb/G     | 0331 |
| Eb7/G    | 0334 |
| Ebsus2/G | 0311 |
| Eb/Bb    | 3331 |
| Ebm/Bb   | 3321 |

# Ukulele

# E

|   |               |                         |                 |                         |
|---|---------------|-------------------------|-----------------|-------------------------|
| ○ | <b>E</b>      | <b>4442</b>             | <b>E7b5</b>     | <b>1201</b>             |
|   | <b>Em</b>     | <b>0432</b>             | <b>E7#5</b>     | <b>1005</b>             |
|   | <b>E5</b>     | <b>4402</b>             |                 |                         |
|   | <b>E+</b>     | <b>1003</b>             | <b>E9</b>       | <b>1222<sup>r</sup></b> |
|   | <b>E°</b>     | <b>0401</b>             | <b>Emaj9</b>    | <b>1322<sup>r</sup></b> |
|   | <b>Esus2</b>  | <b>4422</b>             | <b>Em9</b>      | <b>0222<sup>r</sup></b> |
| ○ | <b>Esus4</b>  | <b>2402</b>             | <b>Eadd9</b>    | <b>1422</b>             |
|   |               |                         | <b>Emadd9</b>   | <b>0422</b>             |
|   | <b>E6</b>     | <b>4444</b>             | <b>E7b9</b>     | <b>1212<sup>r</sup></b> |
|   | <b>Em6</b>    | <b>0102</b>             | <b>E7#9</b>     | <b>0242<sup>r</sup></b> |
|   | <b>E6/9</b>   | <b>1102</b>             | <b>Em11</b>     | <b>0200</b>             |
|   |               |                         |                 |                         |
| ○ | <b>E7</b>     | <b>1202</b>             | <b>Em/G</b>     | <b>0402</b>             |
|   | <b>Emaj7</b>  | <b>4342<sup>r</sup></b> | <b>E/G#</b>     | <b>1402</b>             |
|   | <b>Em7</b>    | <b>0202</b>             | <b>E7/G#</b>    | <b>1202</b>             |
|   | <b>E°7</b>    | <b>0101</b>             | <b>Esus2/G#</b> | <b>1422</b>             |
|   | <b>Em7b5</b>  | <b>0201</b>             | <b>E/B</b>      | <b>4442</b>             |
|   | <b>E7sus4</b> | <b>2200</b>             | <b>Em/B</b>     | <b>4432</b>             |
|   |               |                         |                 |                         |
| ○ |               |                         |                 |                         |
|   |               |                         |                 |                         |
| ○ |               |                         |                 |                         |

## Ukulele

## F

|       |      |
|-------|------|
| F     | 2010 |
| Fm    | 1013 |
| F5    | 5013 |
| F+    | 2110 |
| F°    | 1512 |
| Fsus2 | 0533 |
| Fsus4 | 3011 |

|      |      |
|------|------|
| F6   | 2213 |
| Fm6  | 1213 |
| F6/9 | 0210 |

|        |                   |
|--------|-------------------|
| F7     | 2310              |
| Fmaj7  | 2400 <sup>r</sup> |
| Fm7    | 1313              |
| F°7    | 1212              |
| Fm7b5  | 1312              |
| F7sus4 | 3311              |

|      |      |
|------|------|
| F7b5 | 4310 |
| F7#5 | 2314 |

|        |                   |
|--------|-------------------|
| F9     | 2333 <sup>r</sup> |
| Fmaj9  | 0000 <sup>r</sup> |
| Fm9    | 1333 <sup>r</sup> |
| Fadd9  | 0010              |
| Fmadd9 | 1533              |
| F7b9   | 2320 <sup>r</sup> |
| F7#9   | 1310              |
| Fm11   | 1311              |

|         |      |
|---------|------|
| F/C     | 5010 |
| Fm/C    | 5543 |
| Fm/Ab   | 1013 |
| F/A     | 2010 |
| F7/A    | 2310 |
| Fsus2/A | 2530 |

|   |         |                   |           |                   |
|---|---------|-------------------|-----------|-------------------|
| ○ | Gb      | 3121              | Gb7b5     | 5421              |
|   | Gbm     | 2120              | Gb7#5     | 3425              |
|   | Gb5     | 6624              |           |                   |
|   | Gb+     | 3221              | Gb9       | 3444 <sup>r</sup> |
|   | Gb°     | 2020              | Gbmaj9    | 1111 <sup>r</sup> |
|   | Gbsus2  | 1124              | Gbm9      | 1100 <sup>r</sup> |
| ○ | Gbsus4  | 4122              | Gbadd9    | 1121              |
|   |         |                   | Gbmadd9   | 1120              |
|   | Gb6     | 3324              | Gb7b9     | 0101 <sup>r</sup> |
|   | Gbm6    | 2324              | Gb7#9     | 3100 <sup>r</sup> |
|   | Gb6/9   | 1321              | Gbm11     | 4100 <sup>r</sup> |
|   |         |                   |           |                   |
| ○ | Gb7     | 3424              | Gb/Db     | x121              |
|   | Gbmaj7  | 3111 <sup>r</sup> | Gbm/Db    | 6620              |
|   | Gbm7    | 2424              | Gbm/A     | 2120              |
|   | Gb°7    | 2323              | Gb/Bb     | 3121              |
|   | Gbm7b5  | 2423              | Gb7/Bb    | 3421              |
|   | Gb7sus4 | 4422              | Gbsus2/Bb | 3644              |
|   |         |                   |           |                   |
| ○ |         |                   |           |                   |
|   |         |                   |           |                   |
| ○ |         |                   |           |                   |

## Ukulele

## G

|       |      |
|-------|------|
| G     | 0232 |
| Gm    | 0231 |
| G5    | 0235 |
| G+    | 4332 |
| G°    | 0131 |
| Gsus2 | 0230 |
| Gsus4 | 0233 |

|      |                   |
|------|-------------------|
| G6   | 0202              |
| Gm6  | 0201              |
| G6/9 | xx00 <sup>r</sup> |

|        |      |
|--------|------|
| G7     | 0212 |
| Gmaj7  | 0222 |
| Gm7    | 0211 |
| G°7    | 0101 |
| Gm7b5  | 0111 |
| G7sus4 | 0013 |

|      |      |
|------|------|
| G7b5 | 0112 |
| G7#5 | 0312 |

|        |                   |
|--------|-------------------|
| G9     | 4210 <sup>r</sup> |
| Gmaj9  | 2222 <sup>r</sup> |
| Gm9    | 0551              |
| Gadd9  | 0252              |
| Gmadd9 | 0251              |
| G7b9   | 1212 <sup>r</sup> |
| G7#9   | 4211 <sup>r</sup> |
| Gm11   | 0011              |

|         |      |
|---------|------|
| G/D     | x232 |
| Gm/D    | x231 |
| Gm/Bb   | 3231 |
| G/B     | 4232 |
| G7/B    | 4532 |
| Gsus2/B | 4230 |

## Ukulele

## Ab / G#

|   |         |      |          |                   |
|---|---------|------|----------|-------------------|
| ○ | Ab      | 5343 | Ab7b5    | 1223              |
|   | Abm     | 4342 | Ab7#5    | 1423              |
|   | Ab5     | 1346 |          |                   |
|   | Ab+     | 1003 | Ab9      | 1021              |
|   | Ab°     | 1242 | Abmaj9   | 0031 <sup>r</sup> |
|   | Absus2  | 3346 | Abm9     | 3322 <sup>r</sup> |
| ○ | Absus4  | 1344 | Abadd9   | 1041              |
|   |         |      | Abmadd9  | 4341              |
|   | Ab6     | 1313 | Ab7b9    | 1020              |
|   | Abm6    | 1312 | Ab7#9    | 1022              |
|   | Ab6/9   | 1311 | Abm11    | 1122              |
|   |         |      |          |                   |
| ○ | Ab7     | 1323 | Ab/C     | 5043              |
|   | Abmaj7  | 1333 | Ab7/C    | 5643              |
|   | Abm7    | 1322 | Absus2/C | 5041              |
|   | Ab°7    | 1212 | Ab/Eb    | 8043              |
|   | Abm7b5  | 1222 | Abm/Eb   | x342              |
|   | Ab7sus4 | 1124 | Abm/B    | 4342              |
|   |         |      |          |                   |
| ○ |         |      |          |                   |
|   |         |      |          |                   |
| ○ |         |      |          |                   |

# Tunings

---

## Ukulele **G C E A**

Soprano, concert and tenor. Re-entrant: the 4th sounds above the 3rd, so "lowest first" means leftmost. Low-G is the same.

---

Fret numbers read from the lowest string.

**x** means don't play that string.

**r** means rootless: for rhythm, not for soloing.

---

## Fancy Ukulele Chords and Their Voicings

Danne Stayskal

danne@stayskal.com

<http://danne.stayskal.com/>

Source, corrections and a printable copy:

<https://github.com/linenoise/voicings>

MIT licensed. Print it, cut it, sew it, give it away.