


# Fancy Ukulele Chords and Their Voicings



<https://github.com/linenoise/voicings>

## Ukulele Circle of Fifths



Outer ring: major.  
Inner ring: relative minor.  
Both show the most common voicing.

## Movable Shapes

Ukulele closed, so they move

shape root on bottom example

### major

0003 C 5 1114 = Db

2010 E 3 3121 = Gb

2100 G R 3211 = Bb

2013 E 3 3124 = Gb

### minor

2000 G R 3111 = Bbm

1013 E b3 2124 = Gbm

2003 G R 3114 = Bbm

### seventh

0001 C 5 1112 = Db7

0100 A b7 1211 = Bb7

0212 G R 1323 = Ab7

## Ukulele

## Bb / A#

Bb 3211 Bb7b5 1201  
Bbm 3111 Bb7#5 1221

Bb5 3511  
Bb+ 3221  
Bb° 3101  
Bbsus2 3011  
Bbsus4 3311

Bb6 0211  
Bbm6 0111  
Bb6/9 0011

Bb7 1211 Bbm/Db x111  
Bbmaj7 3210 Bb/D x211  
Bbm7 1111 Bb7/D x241  
Bb°7 0101 Bbsus2/D 7063  
Bbm7b5 1101 Bb/F x565  
Bb7sus4 1311 Bbm/F x564

Shape is the fingering above its lowest fret.  
Slide it one fret, the chord rises a semitone.

Bottom is the degree on the lowest string. The page before gives the fret.

## Root Positions

Ukulele

|           | G  | C  | E  | A  |
|-----------|----|----|----|----|
| <b>C</b>  | 5  | 0  | 8  | 3  |
| <b>Db</b> | 6  | 1  | 9  | 4  |
| <b>D</b>  | 7  | 2  | 10 | 5  |
| <b>Eb</b> | 8  | 3  | 11 | 6  |
| <b>E</b>  | 9  | 4  | 0  | 7  |
| <b>F</b>  | 10 | 5  | 1  | 8  |
| <b>Gb</b> | 11 | 6  | 2  | 9  |
| <b>G</b>  | 0  | 7  | 3  | 10 |
| <b>Ab</b> | 1  | 8  | 4  | 11 |
| <b>A</b>  | 2  | 9  | 5  | 0  |
| <b>Bb</b> | 3  | 10 | 6  | 1  |
| <b>B</b>  | 4  | 11 | 7  | 2  |

Fret for the root of each key on each string.  
Everything else is measured from there.

## Ukulele Chords

G C E A

### Ukulele **B / C<sup>b</sup>**

|               |             |                 |                         |
|---------------|-------------|-----------------|-------------------------|
| <b>B</b>      | <b>4322</b> | <b>B7b5</b>     | <b>4310</b>             |
| <b>Bm</b>     | <b>4222</b> | <b>B7#5</b>     | <b>2332</b>             |
| <b>B5</b>     | <b>4622</b> |                 |                         |
| <b>B+</b>     | <b>4332</b> | <b>B9</b>       | <b>6352</b>             |
| <b>B°</b>     | <b>4212</b> | <b>Bmaj9</b>    | <b>3324<sup>r</sup></b> |
| <b>Bsus2</b>  | <b>4122</b> | <b>Bm9</b>      | <b>4155</b>             |
| <b>Bsus4</b>  | <b>4422</b> | <b>Badd9</b>    | <b>6322</b>             |
|               |             | <b>Bmadd9</b>   | <b>6222</b>             |
| <b>B6</b>     | <b>1322</b> | <b>B7b9</b>     | <b>2323<sup>r</sup></b> |
| <b>Bm6</b>    | <b>1222</b> | <b>B7#9</b>     | <b>2226<sup>r</sup></b> |
| <b>B6/9</b>   | <b>1122</b> | <b>Bm11</b>     | <b>2200<sup>r</sup></b> |
| <b>B7</b>     | <b>2322</b> | <b>Bm/D</b>     | <b>x222</b>             |
| <b>Bmaj7</b>  | <b>4321</b> | <b>B/D#</b>     | <b>x322</b>             |
| <b>Bm7</b>    | <b>2222</b> | <b>B7/D#</b>    | <b>x352</b>             |
| <b>B°7</b>    | <b>1212</b> | <b>Bsus2/D#</b> | <b>x374</b>             |
| <b>Bm7b5</b>  | <b>4210</b> | <b>B/F#</b>     | <b>x676</b>             |
| <b>B7sus4</b> | <b>4420</b> | <b>Bm/F#</b>    | <b>x675</b>             |

### Ukulele **A**

|               |             |                 |                         |
|---------------|-------------|-----------------|-------------------------|
| <b>A</b>      | <b>2100</b> | <b>A7b5</b>     | <b>2334</b>             |
| <b>Am</b>     | <b>2000</b> | <b>A7#5</b>     | <b>0110</b>             |
| <b>A5</b>     | <b>xx00</b> |                 |                         |
| <b>A+</b>     | <b>2110</b> | <b>A9</b>       | <b>2132</b>             |
| <b>A°</b>     | <b>2056</b> | <b>Amaj9</b>    | <b>1102<sup>r</sup></b> |
| <b>Asus2</b>  | <b>4400</b> | <b>Am9</b>      | <b>0002<sup>r</sup></b> |
| <b>Asus4</b>  | <b>2200</b> | <b>Aadd9</b>    | <b>4100</b>             |
|               |             | <b>Amadd9</b>   | <b>2002</b>             |
| <b>A6</b>     | <b>2120</b> | <b>A7b9</b>     | <b>0101<sup>r</sup></b> |
| <b>Am6</b>    | <b>2020</b> | <b>A7#9</b>     | <b>0103<sup>r</sup></b> |
| <b>A6/9</b>   | <b>2120</b> | <b>Am11</b>     | <b>2233</b>             |
| <b>A7</b>     | <b>0100</b> | <b>Am/C</b>     | <b>x000</b>             |
| <b>Amaj7</b>  | <b>1100</b> | <b>A/C#</b>     | <b>x100</b>             |
| <b>Am7</b>    | <b>0000</b> | <b>A7/C#</b>    | <b>x130</b>             |
| <b>A°7</b>    | <b>2323</b> | <b>Asus2/C#</b> | <b>x152</b>             |
| <b>Am7b5</b>  | <b>2333</b> | <b>A/E</b>      | <b>x454</b>             |
| <b>A7sus4</b> | <b>0200</b> | <b>Am/E</b>     | <b>9053</b>             |

## Ukulele

## C

|         |      |         |                   |
|---------|------|---------|-------------------|
| ○ C     | 0003 | C7b5    | 5421              |
| Cm      | 0333 | C7#5    | 1001              |
| C5      | 00xx |         |                   |
| C+      | 1003 | C9      | 0201 <sup>r</sup> |
| C°      | 5026 | Cmaj9   | 0202 <sup>r</sup> |
| Csus2   | 0233 | Cm9     | 0266 <sup>r</sup> |
| Csus4   | 0013 | Cadd9   | 0203              |
|         |      | Cmadd9  | 7333              |
| C6      | 0000 | C7b9    | 0101 <sup>r</sup> |
| Cm6     | 2333 | C7#9    | 0301 <sup>r</sup> |
| C6/9    | 0000 | Cm11    | 0311 <sup>r</sup> |
|         |      |         |                   |
| C7      | 0001 | Cm/Eb   | x333              |
| ○ Cmaj7 | 0002 | C/E     | 9003              |
| Cm7     | 3333 | C7/E    | x463              |
| C°7     | 2323 | Csus2/E | 9005              |
| Cm7b5   | 5321 | C/G     | 000x              |
| C7sus4  | 0011 | Cm/G    | 0333              |

○

○

## Ukulele

## E

|         |                   |          |                   |
|---------|-------------------|----------|-------------------|
| ○ E     | 4442              | E7b5     | 1201              |
| Em      | 0432              | E7#5     | 1005              |
| E5      | 4402              |          |                   |
| E+      | 1003              | E9       | 1222 <sup>r</sup> |
| E°      | 0401              | Emaj9    | 1322 <sup>r</sup> |
| Esus2   | 4422              | Em9      | 0222 <sup>r</sup> |
| Esus4   | 2402              | Eadd9    | 1422              |
|         |                   | Emadd9   | 0422              |
| E6      | 4444              | E7b9     | 1212 <sup>r</sup> |
| Em6     | 0102              | E7#9     | 0242 <sup>r</sup> |
| E6/9    | 1102              | Em11     | 0200              |
|         |                   |          |                   |
| E7      | 1202              | Em/G     | 0402              |
| ○ Emaj7 | 4342 <sup>r</sup> | E/G#     | 1402              |
| Em7     | 0202              | E7/G#    | 1202              |
| E°7     | 0101              | Esus2/G# | 1422              |
| Em7b5   | 0201              | E/B      | 4442              |
| E7sus4  | 2200              | Em/B     | 4432              |

○

○

## Ukulele

## D

|         |      |          |                   |
|---------|------|----------|-------------------|
| ○ D     | 2220 | D7b5     | 1223              |
| Dm      | 2210 | D7#5     | 5221              |
| D5      | 2250 |          |                   |
| D+      | 3221 | D9       | 2423 <sup>r</sup> |
| D°      | 1215 | Dmaj9    | 2424 <sup>r</sup> |
| Dsus2   | 2200 | Dm9      | 5410 <sup>r</sup> |
| Dsus4   | 0230 | Dadd9    | 2425              |
|         |      | Dmadd9   | 2415              |
| D6      | 2222 | D7b9     | 2323 <sup>r</sup> |
| Dm6     | 2212 | D7#9     | 5520 <sup>r</sup> |
| D6/9    | 2222 | Dm11     | 0010 <sup>r</sup> |
|         |      |          |                   |
| D7      | 2223 | Dm/F     | x515              |
| ○ Dmaj7 | 2224 | D/F#     | x625              |
| Dm7     | 2213 | D7/F#    | x685              |
| D°7     | 1212 | Dsus2/F# | [11]905           |
| Dm7b5   | 1213 | D/A      | 2220              |
| D7sus4  | 0233 | Dm/A     | 2210              |

○

○

## Ukulele

## Gb / F#

|          |                   |           |                   |
|----------|-------------------|-----------|-------------------|
| ○ Gb     | 3121              | Gb7b5     | 5421              |
| Gbm      | 2120              | Gb7#5     | 3425              |
| Gb5      | 6624              |           |                   |
| Gb+      | 3221              | Gb9       | 3444 <sup>r</sup> |
| Gb°      | 2020              | Gbmaj9    | 1111 <sup>r</sup> |
| Gbsus2   | 1124              | Gbm9      | 1100 <sup>r</sup> |
| Gbsus4   | 4122              | Gbadd9    | 1121              |
|          |                   | Gbmadd9   | 1120              |
| Gb6      | 3324              | Gb7b9     | 0101 <sup>r</sup> |
| Gbm6     | 2324              | Gb7#9     | 3100 <sup>r</sup> |
| Gb6/9    | 1321              | Gbm11     | 4100 <sup>r</sup> |
|          |                   |           |                   |
| Gb7      | 3424              | Gb/Db     | x121              |
| ○ Gbmaj7 | 3111 <sup>r</sup> | Gbm/Db    | 6620              |
| Gbm7     | 2424              | Gbm/A     | 2120              |
| Gb°7     | 2323              | Gb/Bb     | 3121              |
| Gbm7b5   | 2423              | Gb7/Bb    | 3421              |
| Gb7sus4  | 4422              | Gbsus2/Bb | 3644              |

○

○

## Ukulele

## Eb / D#

|        |      |        |                   |
|--------|------|--------|-------------------|
| Eb     | 0331 | Eb7b5  | 2334              |
| Ebm    | 3321 | Eb7#5  | 6332              |
| Eb5    | 3366 |        |                   |
| Eb+    | 4332 |        |                   |
| Eb°    | 2320 | Eb9    | 0111 <sup>r</sup> |
| Ebsus2 | 3311 | Ebmaj9 | 0211 <sup>r</sup> |
| Ebsus4 | 1341 | Ebm9   | 3524 <sup>r</sup> |
|        |      | Ebadd9 | 0311              |

|       |                   |         |                   |
|-------|-------------------|---------|-------------------|
| Eb6   | 3333              | Ebmadd9 | 3526              |
| Ebm6  | 3323              | Eb7b9   | 0101 <sup>r</sup> |
| Eb6/9 | 0011 <sup>r</sup> | Eb7#9   | 0121 <sup>r</sup> |
|       |                   | Ebm11   | 1121 <sup>r</sup> |

|         |                   |          |      |
|---------|-------------------|----------|------|
| Eb7     | 3334              | Ebm/Gb   | x626 |
| Ebmaj7  | 3231 <sup>r</sup> | Eb/G     | 0331 |
| Ebm7    | 3324              | Eb7/G    | 0334 |
| Eb°7    | 2323              | Ebsus2/G | 0311 |
| Ebm7b5  | 2324              | Eb/Bb    | 3331 |
| Eb7sus4 | 1344              | Ebm/Bb   | 3321 |

## Ukulele

## Db / C#

|        |      |        |                   |
|--------|------|--------|-------------------|
| Db     | 1114 | Db7b5  | 0112              |
| Dbm    | 1104 | Db7#5  | 4110              |
| Db5    | 1144 |        |                   |
| Db+    | 2110 |        |                   |
| Db°    | 0104 | Db9    | 1312 <sup>r</sup> |
| DbSus2 | 1344 | Dbmaj9 | 1313 <sup>r</sup> |
| DbSus4 | 1124 | Dbm9   | 1302 <sup>r</sup> |
|        |      | Dbadd9 | 1314              |

|       |      |         |                   |
|-------|------|---------|-------------------|
| Db6   | 1111 | Dbmadd9 | 1304              |
| Dbm6  | 3444 | Db7b9   | 1212 <sup>r</sup> |
| Db6/9 | 1111 | Db7#9   | 1412 <sup>r</sup> |
|       |      | Dbm11   | 1422 <sup>r</sup> |

|         |      |          |      |
|---------|------|----------|------|
| Db7     | 1112 | Dbm/E    | x444 |
| Dbmaj7  | 1113 | Db/F     | x514 |
| Dbm7    | 4444 | Db7/F    | x574 |
| Db°7    | 0101 | DbSus2/F | x596 |
| Dbm7b5  | 0102 | Db/Ab    | 1114 |
| Db7sus4 | 1122 | Dbm/Ab   | 1104 |

## Ukulele

## G

|       |      |       |                   |
|-------|------|-------|-------------------|
| G     | 0232 | G7b5  | 0112              |
| Gm    | 0231 | G7#5  | 0312              |
| G5    | 0235 |       |                   |
| G+    | 4332 |       |                   |
| G°    | 0131 | G9    | 4210 <sup>r</sup> |
| Gsus2 | 0230 | Gmaj9 | 2222 <sup>r</sup> |
| Gsus4 | 0233 | Gm9   | 0551              |
|       |      | Gadd9 | 0252              |

|      |                   |        |                   |
|------|-------------------|--------|-------------------|
| G6   | 0202              | Gmadd9 | 0251              |
| Gm6  | 0201              | G7b9   | 1212 <sup>r</sup> |
| G6/9 | xx00 <sup>r</sup> | G7#9   | 4211 <sup>r</sup> |
|      |                   | Gm11   | 0011              |

|        |      |         |      |
|--------|------|---------|------|
| G7     | 0212 | G/D     | x232 |
| Gmaj7  | 0222 | Gm/D    | x231 |
| Gm7    | 0211 | Gm/Bb   | 3231 |
| G°7    | 0101 | G/B     | 4232 |
| Gm7b5  | 0111 | G7/B    | 4532 |
| G7sus4 | 0013 | Gsus2/B | 4230 |

## Ukulele

## F

|       |      |       |                   |
|-------|------|-------|-------------------|
| F     | 2010 | F7b5  | 4310              |
| Fm    | 1013 | F7#5  | 2314              |
| F5    | 5013 |       |                   |
| F+    | 2110 |       |                   |
| F°    | 1512 | F9    | 2333 <sup>r</sup> |
| Fsus2 | 0533 | Fmaj9 | 0000 <sup>r</sup> |
| Fsus4 | 3011 | Fm9   | 1333 <sup>r</sup> |
|       |      | Fadd9 | 0010              |

|      |      |        |                   |
|------|------|--------|-------------------|
| F6   | 2213 | Fmadd9 | 1533              |
| Fm6  | 1213 | F7b9   | 2320 <sup>r</sup> |
| F6/9 | 0210 | F7#9   | 1310              |
|      |      | Fm11   | 1311              |

|        |                   |         |      |
|--------|-------------------|---------|------|
| F7     | 2310              | F/C     | 5010 |
| Fmaj7  | 2400 <sup>r</sup> | Fm/C    | 5543 |
| Fm7    | 1313              | Fm/Ab   | 1013 |
| F°7    | 1212              | F/A     | 2010 |
| Fm7b5  | 1312              | F7/A    | 2310 |
| F7sus4 | 3311              | Fsus2/A | 2530 |

|   |         |      |          |                   |
|---|---------|------|----------|-------------------|
| ○ | Ab      | 5343 | Ab7b5    | 1223              |
|   | Abm     | 4342 | Ab7#5    | 1423              |
|   | Ab5     | 1346 |          |                   |
|   | Ab+     | 1003 | Ab9      | 1021              |
|   | Ab°     | 1242 | Abmaj9   | 0031 <sup>r</sup> |
|   | Absus2  | 3346 | Abm9     | 3322 <sup>r</sup> |
| ○ | Absus4  | 1344 | Abadd9   | 1041              |
|   |         |      | Abmadd9  | 4341              |
|   | Ab6     | 1313 | Ab7b9    | 1020              |
|   | Abm6    | 1312 | Ab7#9    | 1022              |
|   | Ab6/9   | 1311 | Abm11    | 1122              |
|   |         |      |          |                   |
| ○ | Ab7     | 1323 | Ab/C     | 5043              |
| ○ | Abmaj7  | 1333 | Ab7/C    | 5643              |
|   | Abm7    | 1322 | Absus2/C | 5041              |
|   | Ab°7    | 1212 | Ab/Eb    | 8043              |
|   | Abm7b5  | 1222 | Abm/Eb   | x342              |
|   | Ab7sus4 | 1124 | Abm/B    | 4342              |

○

○

# Tunings

## Ukulele G C E A

Soprano, concert and tenor. Re-entrant: the 4th sounds above the 3rd, so "lowest first" means leftmost. Low-G is the same.

Fret numbers read from the lowest string.

x means don't play that string.

r means rootless: for rhythm, not for soloing.

## Fancy Ukulele Chords and Their Voicings

Danne Stayskal

danne@stayskal.com

<http://danne.stayskal.com/>

Source, corrections and a printable copy:

<https://github.com/linenoise/voicings>

MIT licensed. Print it, cut it, sew it, give it away.