# TCP performance

LinuxSA Adelaide 2003-09-16

Glen Turner glen.turner@aarnet.edu.au



aarnet

Australia's Academic & Research Network www.aarnet.edu.au

# Part 1 TCP performance

LinuxSA Adelaide 2003-09-16

Glen Turner glen.turner@aarnet.edu.au



aarnet

Australia's Academic & Research Network www.aarnet.edu.au

# Topics

TCP primer

Limits to TCP performance

Application program, equipment, and network design implications

Using Web100

Design of Web100

# TCP primer

## What is TCP?

"Transmission control protocol"

Specified in *RFC793* 

 Free online at http://www.ietf.org/rfc/rfc793.txt

RFCs are not like ISO standards

- Once issued RFCs are not updated, they are amended by other RFCs
- So IEEE802.3-2002 is the Ethernet standard
- But RFC793 amended by ..., is the TCP standard

## What does TCP do

#### Provides a connection which is

- Simple
- Multiplexed
- Bidirectional
- Reliable
- Flow controlled
- Multiplexed

# Simple connection

## TCP just provides a stream of bytes

- No record boundaries
- Says nothing about latency or jitter

## Only one feature

"Urgent" data for Ctrl+C

# Simple connection

# Some higher layer is responsible for implementing record boundaries

- Usually the application, the TCP/IP suite of protocols has no formal session or presentation layers
- Increasingly an XML library ("presentation") over HTTP or BEEP ("session")

# Multiplexed

One link can carry simultaneous connections

One host can have many connections, even to the same remote host

```
Connection is defined by 
(label_space, 
src_af, src_addr, src_port, 
dst_af, dst_addr, dst_port)
```

## Ports

## Ephemeral ports provide multiplexing

- Allocated on demand by operating system
- netstat -t -n

# Well-known ports provide application selection

- Web servers listen on src\_port = 80
- netstat -t -n -l

# Multiplexing example

10.1.0.1

10001

Web browser

(10.1.0.1, 10001, 10.2.0.1, 80)

10.1.0.2

10001

Web browser

10002

(10.1.0.2, 10001, 10.2.0.1, 80)

(10.1.0.2, 10002, 10.2.0.1, 80)

(10.1.0.1, 10001, 10.1.0.1, 80)

10.2.0.1

<sup>80</sup> Web server

Web browser

# Reliability

Lost or corrupted data is retransmitted

That's why there is nothing said about latency

Loss is detected by a late Ack for a packet

## Flow control

Do not over-run receiver's hardware or buffering

## TCP header

++   Source Port		Destination Port
Sequence Number		
Acknowledgment Number		
Data   Offset 	Res-	Window
+		Urgent Pointer
[ Options		Padding
[ data ]		
[		

# Header - simple connection

## Sequence number

Modulo index into byte stream

## Urgent pointer

- For a small amount of out-of-band data
- Not used much, as an early implementation error has lead to divergent interpretations

# Header - multiplexing

Source port
Destination port

# Header - reliability

#### Checksum

error detection

## Acknowledgement

Ack number

### Sequence and window

 Unacknowledged data which may need to be retransmitted if an Ack does not arrive in time.

## Header - flow control

#### Window

 Always less than amount of receive buffering available

# Limits to TCP performance

## **Sub-topics**

- Bandwidth-delay product
  - Buffers sizing
- Enhancements to TCP
  - Window scaling, timestamps, SACK, ECN
- Mathis' formula
  - Bit error rates, maximum transfer unit

# Bandwidth-delay product

Bits of data in transit between hosts is bandwidth × rtt

bandwidth is in bits per second
rtt is round-trip delay, in seconds
bdp is usually expressed in MB, so
convert formula from b to MB

•  $bdp = (bandwidth/8 \times 10^6) \times rtt$ 

# Example bandwidths

#### **Ethernet**

10Mbps-HD, 100Mbps, 1000Mbps

#### Leased line

128Kbps, 2Mbps, 34Mbps, 155Mbps

#### **ADSL**

Around 3000/256Kbps or 0.5Mbps

#### Modem

• 56/34Kbps

# Example delays

28ms Adelaide-Sydney

150ms Sydney-US east coast

200ms US east-west

500ms Sydney-Sydney via satelite

# Example bandwidth delay product

Take slowest link in path

Take computed round-trip time

Example: Glen's desk

- slowest link in path is fast ethernet
  - bandwidth = 100,000,000bps
- rtt to www.internet2.edu is 0.240s
  - measured with ping
- $bdp = (100,000,000/8,000,000) \times 0.240$ = 3MB

## TCP buffers

- To run at full speed TCP may need to buffer an entire window of unacknowledged data
  - that is, the value of the bandwidth-delay product
- Most operating systems are tuned for 10Mbps LANs "out of the box"
- eg: Windows XP has 17,520 bytes (12 packets)
  - rtt < 2ms at 100Mbps</li>

# Linux buffer tuning

## /proc/sys/net/core

- rmem\_default
  - Default receive window (64KB)
- rmem\_max
  - Maximum receive window (64KB)
- wmem\_default
  - Default send window (64KB)
- wmem\_max
  - Maximum send window (64KB)

## RTT with Linux 2.4 defaults

## 56Kbps modem, no wucking furries

• 
$$64 \times 2^{10} \times 8 = 56 \times 10^{3} \times rtt$$
  
 $rtt = 9s$ 

## 2Mbps leased line, uh oh

•  $64 \times 2^{10} \times 8 = 2 \times 10^{6} \times rtt$ rtt = 262 ms

## 10Mbps ethernet, OK for LAN, else bad

• 
$$64 \times 2^{10} \times 8 = 10 \times 10^{6} \times rtt$$
  
 $rtt = 52ms$ 

100Mbps rtt = 5.2ms, tuning time

## Let's go faster

#### AARNet3

- slowest link in path is 1Gbps
- but speed of light in fiber unchanged
- so 90% of traffic will have rtt > 200ms

Bandwidth product delay ≈ 40MB

So some tuning is needed :-)

# What if I ask Linux for a 40MB buffer per connection?

## Receiver buffer allocation algorithm

- Initially allocate receive buffer for 4 packets, advertise Window accordingly
- Increase by 2 packets per Ack
- Until rmem\_default is reached

## Caching

- TCP control information to a host is cached for 10 minutes
  - cwnd, rtt, rttvar, ssthresh, reorder

# What if I ask Linux for a 40MB buffer per connection?

Transmit buffer allocation

Application's problem :-)

Interface output buffer

Needs to be set accordingly

## Configuration

```
/etc/sysctl.conf
```

• net.core.rmem\_max = 41943040

## /sbin/ifup-local

```
• if [ "${1%[0-9]*}" = "eth" ]
  then
  /sbin/ifconfig "${1}" txqueuelen 1000
  fi
```

## Windows bigger than 64KB

Doesn't the TCP header have 16 bits for Window? Yes.

## TCP window scaling option

- Negotiated at connection startup
- Window is 32 bits at hosts, but 16 bits on packet
- Number of bits to right-shift the Window value in the packet
- RFC1323

# More configuration

```
sys.net.ipv4.tcp_timestamps=1
sys.net.ipv4.tcp_window_scaling=1
sys.net.ipv4.tcp_sack=1
```

# What are these timestamps

TCP samples one packet per round-trip, uses this to build estimate of RTT and the variance of the estimate

But fat pipes have thousands of packets, so far too few packets are measured for good RTT estimate

If we lose the "RTT sample" packet we are really stuffed

A timestamp allows every packet to contribute to the RTT estimate

# Why is an accurate RTT estimate important?

It is used to answer two questions:

- Is it time to send the next packet (assuming I'm facing an open window)
- Is the Ack late, and thus I've dropped a packet
  - and need to enter slow start

Variance of RTT is also maintained

So we can define "late" better

You can look at the back-flow of Acks as an "Ack clock" which maintains the RTT estimate

## What is this SACK

Selective Acknowledgement

We have thousands of packets in the pipe

We drop one

We want to retansmit that one, not the thousands of subsequent packets too

We want to acknowledge individual packets

Also works well for lossy media, WLAN

## What is ECN?

Explicit congestion control

Packet is dropped

- Is it congestion?
- Is it corruption/loss?

Re-transmission actions differ:

- Congestion: slow-start; halve data rate
- Loss: retain data rate

Must assume congestion to avoid congestion collapse of Internet

#### What is ECN?

But if loss if explicity signalled, then there is no ambiguity

Routers mark packets forwarded on a congested link

 Setting IP's ECN bits to a "congestion encountered" value

Receiver reflects this back to sender

TCP's ECN Echo set until CWR heard

Sender backs off

Setting TCP's Congestion Window Reduced

#### What is ECN?

A packet drop on an ECN path is loss Retransit immediately

- But without the IP "ECN enabled" value
- So if it too is dropped then back off

Some firewalls with stale software reject ECN traffic

www.news.com.au

#### Configuration

net.ipv4.tcp\_ecn=1

### Mathis' formula

## Mathis' formula TCP throughput

Upper bound on TCP transfer rate (bps)

$$rate \leq \frac{mss}{rtt} \times \frac{1}{\sqrt{p}}$$

Mathis, et al. The macroscopic behavior of the TCP congestion avoidance algorithm. CCR, 27 (3), July 1997.

#### Where

```
mss Maximum segment size (B), say 1460 B
```

rtt Round trip time (ms)

```
60ms Adelaide - Sydney
160ms Sydney – Seattle
```

p Loss probability (%), say 10 $^{ ext{-}11}$ %

## Mathis's formula Example

Ethernet file transfer from US east coast

- mss = 1460B, as ethernet MTU is 1500
- rtt = 220ms, Adelaide-Sydney-Seattle
- $p = 10^{-11}\%$ , as  $10^{-13}$  is typical fiber BER

#### Substituting

• *rate* ≤ 2.1Gbps

#### Formula for non-mathematicans

#### To increase rate, in priority order

- Decrease round-trip time
- Decrease loss probability
- Increase maximum segment size

## Decrease round-trip time

That is, increase the speed of light in fiber

 Happening, but <%5 improvement per decade

Using the speed of light in free space is limited by earth's curvature

 lasers or microwave radios need "line of sight"

## Decrease loss probability

SDH specifies a typical bit error rate of 10<sup>-13</sup>, flags an link down at 10<sup>-6</sup>

Can actually do better, by reducing phase errors, but this limits bandwidth

Need a new "typical" specification from ITU-T, this might take a decade from proposal to implementation

## Increase maximum segment size

TCP MSS is the link's maximum transmission unit minus the TCP/IP header

Increasing MTU requires a new generation of hosts and routers

#### Maximum MTU

IPv4 is 64KB

Ethernet MTU is 1500, changing this breaks 10/100 interoperability

### Summary

# Numbers which are reasonable at 10Mbps are large at 100Mbps and unreasonable at 1Gbps

Throughput (Mbps)	RTT between losses (sec)	Congestion window (packets)	Maximum packet loss (%)
1	5.5	8.3	0.02
10	55.5	83.3	0.0002
100	555.5	833.3	0.000002
1,000	5,555.5	8,333.3	0.00000002
10,000	55,555.5	83,333.3	0.0000000002

#### More unreasonable numbers

Back-to-back packets on gigabit ethernet

- Maximum size frames: 81,724fps
- Minimum size frames: 1,488,095fps

Not the worst case, as ethernet has a minimum frame size and an interpacket gap

An SDH interface could deliver

Even so, no host will cope with 1.5m interrupts per second

#### Better interface cards

Template and TCP segmentation offload

Also called "large send offload"

Implies checksum offload

Interrupt combining

 A burst of incoming packets causes only one interrupt

Fast, wider, better PCI bus

64-bit PCI-X

#### Better device drivers

Minimise data copying

Support features of better interface cards

e1000 does, tg3 doesn't

Dynamic selection of interrupt versus polling

- use interrupts when idle
- use polling when busy

## Consequences for application design

#### Sub-topics

- Nagle algorithm
- Transaction protocols and round-trips

## Nagle Algorithm

## Don't want a packet per keystoke Algorithm

- is an outgoing Ack likely?
- Yes
  - can we send a full packet?
    - no: try to piggy-back the data onto an Ack
    - yes: send data
- No: send data

## Nagle problems

Introduces delay in transaction protocols Fails for disk I/O on ethernet

- 4KB disk blocks leads to 3 1500B packets
- So an Ack is always pending
- So we always wait

### TCP\_CORK

New API to make boundaries of upperlayer protocol data unit known to TCP

- When TCP\_CORK set only full packets transmitted
- When TCP\_CORK unset the remaining data is send immediately

Can also do this by disabling Nagle and using a single write() to send the PDU

### sendfile()

#### New API to send a file over a connection

- Less copying of data than
  - bytes = read(file, buffer, sizeof(buffer));
     write(socket, buffer, bytes);
- No switching between kernel-user-kernel space
- Can reuse buffers (the disk I/O buffer gets reused as the network I/O buffer)

Compatible with TCP\_CORK

## Latency A fundamental limit

We can fit more packets onto a fiber, but we can't get the to the other end any faster

1ms per 200Km

In particular, crossing the Pacific is at least 70ms one-way

## Applications and latency

Lots of application protocols have too many round-trips.

#### HTTP GET

- Fetch HTML
- It refers to a CSS stylesheet, fetch it
- Can now start page render
- It refers to images, fetch them

Say 3 RTTs, roughly 420ms to render a US-hosted we page.

## User experience and latency

User interface people suggest 0.3s is the maximal time for a screen update

So an interactive protocol requiring more than two RTTs is bad news

# Additional criteria for network equipment

#### Mathis formula

- MTU
  - At least 9000, if not 64KB
  - Multiple MTU per subnet
- Bit error rate
  - 10<sup>-13</sup> isn't good enough
- Round-trip time
  - Latency is everything
    - SCCN versus Flag

# Consequences for network design

#### Decrease latency

- Take the direct path
- Versus traffic engineering

#### Wizard certificate

You are all now TCP tuning wizards Welcome to the few

- assuming your ISP will tell you about their network
- assuming you have administration access on your computers
- Hmmmm

## Wizard gap

But there are millions of computers on the Internet

So we need to reduce the Wizard Gap to mere mortals can get good performance

Web100

## Part 2 Web100 Project

LinuxSA Adelaide 2003-09-16

Glen Turner glen.turner@aarnet.edu.au



aarnet

Australia's Academic & Research Network www.aarnet.edu.au

#### Basic observation

Modern computers all have capable fast ethernet interfaces

- PC hardware has enough headroom to put a sustained 100Mbps through its fast ethernet interface
- Not so for 1,000Mbps

Yet most users don't come close to their theoretical throughput rates

## Some people are lucky

They have the expertise, time and connections to locate the performance bottlenecks and fix them

Web100 is for everyone else

# Stating the Web100 goal more formally

Provide the software and tools necessary for end-hosts to automatically and transparently achieve high bandwidth data rates (100 Mbps) over high performance research networks.

## Web100 organisation

## A NSF-funded project coordinated by Pittsburgh Supercomputer Center

#### Various other contributors

- National Center for Atmospheric Research
- Computer Science & Mathematics
   Oak Ridge National Labatory
- Data Intensive Distributed Computing Group Lawrence Berkeley National Laboratory

#### and a range of individuals

Such as the presenter

#### Net100

Same goals as Web100

But allowed to break the rules

- Be unfair to other network users
- Drive through congestion

Net100 is for "mission centric" networks

 The network is built for the application, so the application has every right to be unfair to other applications

Web100 is for the Internet

## Topics

## Instrumenting TCP performance APIs for instrumentation

- /proc/web100
- libweb100
- TCP-ESTATS-MIB
  - This is the area of the project I am responsible for implementing

#### **Applications**

## Instrumenting TCP performance



#### Where?

Most operating systems implement TCP entirely in the operating system kernel

- Unixen, VMS, Windows NT/2000/XP
- Not the only option: QNX

Add counters to kernel TCP data structures

#### Where?

#### Getting counters out of the kernel

- There is a lot of them
  - not ioctl() or other single-variable scheme
  - /proc, but not widely used
  - /dev/kmem, but ugly
- There is no single mechanism used by many operating systems

## All this had better be hidden from Web100 applications

libweb100

### What is counted? (1 of 3)

Connection state

Syn options

Traffic counts

Data sequence

Sender congestion triage

Congestion

## What is counted? (2 of 3) Sender

Loss

Path, not Ack clock

Reordering

Round-trip time

Segment size

Buffer size and use

## What is counted? (3 of 3) Local reciever

Packet counts
Buffer size and use
Window

## How much does all this counting cost

No effect in normal case

Up to 1% of file transfer rate in worst case

Lots of small packets on fast ethernet


Performance testing has been extensive

 A lot of the current Web100 users do massive file transfers and won't accept a performance hit

### APIs for instrumentation



### Overview



## /proc/web100

Linux has a filesystem for kernel-user interaction - /proc

Originally a text version of UNIX SystemV's /proc

## /proc/web100/header

Identifies kernel running Web100 and the variables collected

This allows some independence between kernel versions and library versions

For example, the kernel patch and library were extended to support IPv6.

- Previous library versions work with newer kernel code
- Newer library versions work with older kernel patches

## /proc/web100/<cid>

Most high performance computing people only want to tune a single connection

AARNet mirror an exception

Allow efficient access to a particular connection

 So all variables for a connection are under /proc/web100/connection\_identifer

## /proc/web100/<cid>/<group>

Web100 has a lot of variables

We want to pass these over in groups

- Not one at a time, as we want a snapshot of counters at a single moment
- Not all at once, as Web100 would do ridiculously large kernel/user I/O

Group design careful to collect related variables together, so all are snapshotted at same time

### libweb100

- Offers same application programing interface on all operating systems
  - Implemented using /proc/web100 on Linux
- Offers same build environment on all machines
  - Using web100-config command
- Portability a major aim so that analysis tools can be easily ported and widely used

### libweb100 data heirarchy

#### Variables access by following heirarchy

- agent, a machine
  - Usually local
  - Can also be remote, using SNMP
- connection, a TCP session
- group, a related set of variables
- variable, location of a instrument within a snapshot
  - Not it's value
- instrument, value of a TCP counter (only used wher "varaible" confusing)

## Why odd treatment of variables?

#### Allows parsing to be done once

 Convert variable name to offset within the snapshot

#### But used many times

Take a snapshot, ask for the value at the saved offset

## Applications can efficiently carry textual representations of variable names

Hardcoding these in a header reduces inter-version portability

### Snapshots

```
web100 snap()
```

- Take a snapshot of all variables for one (agent, connection, group) tuple
- All the instruments in a snapshot are collected in the same instant

```
web100_snap_read()
```

Parse a snapshot, returning variable values

### Read a variable for a connection

```
#include <web100/web100.h>
int connection id = argv[1];
char *variable name = argv[2];
agent = web100 attach(WEB100 AGENT TYPE LOCAL, NULL);
web100 find var and group(agent, variable name, &group, &variable p);
connection = web100 connection lookup(agent, connection id);
snap = web100 snapshot alloc(group, connection);
web100 snap(snap);
web100_snap read(variable p, snap, &variable value);
web100 snapshot free(snap);
return variable value;
```

# Other libweb100 features Snapshot logging

Can send a snapshot to a log file

And pull it back and parse it at convenience

Separate logging and analysis

 Easy to patch existing code (httpd, ftpd) to generate log records

Logged snapshots are architecturedependent

 Could fix, but log disk usage would double on 32b machines

# Other libweb100 features Snapshot deltas

Returns a snapshot with the changes between two snapshots

All nasty semantic issues dealt with by library

- Zero versus null values
- Counter wraps
- Quantisation

# Other libweb100 features Remote agents

agent is usually WEB100\_AGENT\_TYPE\_LOCAL Working on WEB100\_AGENT\_TYPE\_REMOTE

- Using SNMP to obtain variables of remote end
  - Access, athentication, authorisation, accounting issues are punted to SNMP
- Data transmitter carries more interesting set of TCP varaibles

### libweb100 environment

#### C library style error handling

- Functions return WEB100 ERROR
- web100 perror(), web100 strerror()

#### Application build environment

- cc `web100-config --cflags` -o example.o example.c
- cc `web100-config --libs` -o example example.o

#### Installation is easy (uses GNU automake)

./configure; make;
 su -c 'make install; ldconfig; makewhatis -u -w'

## TCP Extended Statistics MIB What is a MIB?

A "management information base" is a set of counters and tables

- Formally expressed in computer-parsable format
- Expression carries some semantic information
  - Data types, ranges, etc
- Each variable compiles into a Object Identifier

SNMP can read and write Object Identifier values

### TCP Extended Statistics MIB

## A standards-track management information base for TCP statistics

draft-ietf-tsvwg-tcp-mib-extension

#### Part of the Web100 project

- New variables propogate back through libweb100 library and /proc/web100 kernel patch
- Used within libweb100 for remote agents

### TCP-ESTATS contents

A reasonably direct correspondence between libweb100 and TCP-ESTATS-MIB

- cid becomes tcpEStatsConnectionIndex
- Groups become tables

Add SNMP-specific data

- Conformance
- Control

### Why use a ConnectionIndex?

SNMP presents data in a ascending order of MIB identifier

The identifier of a varaible in a table includes the index

So if we used (zone, src\_addr, src\_port, dst\_addr, dst\_port) as the index we would need to sort the data

- Maintain data structure to map kernel order into sorted order
- Kernels don't do a user-space callback when a conenction established

### Why use a ConnectionIndex?

Worse still, after all this work most SNMP applications don't care about order of table rows

They are doing a full table scan to collect statistics

#### Better to use the kernel identifier

- Kernel returns connections in this order
- libweb100 calls this cid
- TCP-ESTATS-MIB calls this tcpEStatsConnectionIndex

### Maintaining the MIB

SNMP MIB is automatically built from the Kernel Instrumentation Set documentation

- Avoids typos
- Records current alignment of Web100 and TCP-ESTATS-MIB

## Don't allow public to read these varaibles

#### Privacy

tcpEStatsConnectRemAddress

#### Connection hijaaking

 tcpEStatsDataSndUna, tcpEStatsDataSndNxt, tcpEStatsDataSndMax, tcpEStatsDataSendInitial, tcpEStatsDataRcvNxt, tcpEStatsDataRecInitial

## MIB tables are off by default

Easy way for vendors to ship *TCP- ESTATS* MIB in operating systems

Especially as many implementations ship allowing public to read all variables

MIB table off doesn't imply kernel stops counters

This might actually cost more CPU

## Applications



## gutil (1 of 4)

## A graphical tool to analyse connection performance

select a connection


Concline	PID	CID	Local addr	Fort	Remote addr	Port	CID	State
	4937	501	202,14,0,324	32801	192,42.62,3	21	62	ESTBLSH
	ō.	0	202,14,0,324	32824	192,42.62,3	60271	100	UNKNOWN
	0	0	127,0.0.1	32825	127,0,0,1	631	101	TMEWAIT
	u u	0	127,0.0.1	631	127,0,0,1	32835	102	UNKNOWN
	O .		202.140.224	32826	192,42.63.2	00274	103	UNKNOWN

explore variable values




## gutil (2 of 4)

graph changes over time




## gutil (3 of 4)

- find bottlenecks
  - triage: is the bottleneck sender, receiver or path



## gutil (4 of 4)

tune send and receive buffers





### WAD

"word-around daemon"

Patches TCP stack variables to improve goodput

- Allows longer-term flow tuning than can be done by kernel
- Allows TCP's fairness to be defeated
  - Good for mission-oriented networks (DoE, NASA)
  - Bad for wide deployment
- In effect, move TCP policy to user space

### WAD actions

Watch buffer usage and increase if this will improve throughput

On mission-centered networks

- Disable delayed Acks
- Faster slow-start
- Lessen multiplicative decrease

Implement alternative TCP policies

- Vegas
- Floyd's High Speed TCP

## WAD is really user-space TCP policy

Coding TCP policy in the kernel is a technical mistake but probably socially necessary

### webd

During and at close of socket, archive all Web100 variables

Allows a corpus of TCP performance to be built

## Existing tools

Tools like *ttcp* and *iperf* report basic statistics

Extended to include Web100 variables

# What we have learned about TCP performance



## Scaling TCP

# Numbers which are reasonable at 10Mbps get large at 100Mbps and unreasonable at 1Gbps

Throughput (Mbps)	RTT between losses (sec)	Congestion window (packets)	Maximum packet loss (%)
1	5.5	8.3	0.02
10	55.5	83.3	0.0002
100	555.5	833.3	0.000002
1,000	5,555.5	8,333.3	0.00000002
10,000	55,555.5	83,333.3	0.0000000002

## Quality of engineering Link layer bit error rates

Bit error rates for correctly configured microwave and fiber are around 10<sup>-13</sup>

PDH/SDH link layers will allow 10<sup>-6</sup> before declaring the link down

Common misconfigurations result in bit error rates of 10<sup>-3</sup> or more

- Synchronous link clocking
- Analogue power budgets
- Ethernet autoconfiguration not used

## Quality of engineering Transfer to USA

Every link is good

$$rate \leq \frac{1460}{260} \times \frac{1}{\sqrt{10^{-11}}}$$

 $rate \leq 1,776$ Mbps

Let's say one of the links has a bit error rate of 10<sup>-6</sup>

$$rate \leq \frac{1460}{260} \times \frac{1}{\sqrt{10^{-4}}}$$

 $rate \leq 0.56 Mbps$ 

## Quality of engineering Lessons

A single TCP session can't fill a AU-US 10Gbps link

TCP throughput is sensitive to the quality of network engineering

- Error rates of 0.001% are unacceptable
- But lots of real life links have 3% error rates, fortunately the longer the link the (usually) better the engineering
- A new design criteria for long-haul links

## TCP buffers

- The "current congestion window" is the amount of data the operating system transmits
- The optimal *buffer* size is 2 × *bandwidth* × *delay* 
  - which is bandwidth  $\times RTT$
- Take a fast ethernet (100Mbps) machine on a GbE WAN to Sydney (50ms)

 $buffer = (100,000 \div 8) \times 0.050 = 625KB$ 

A GbE-connected host needs 6.25MB!

## Congestion window and path loss

TCP congestion window  $cwnd \approx \frac{1.2}{\sqrt{p}}$ 10Gbps, ethernet MTU, 100ms RTT

- 83,333 segments in flight
- To retain performance, at most one congestion event per 5,000m packets (or 1h40m)

Even at 1Gbps the congestion window makes sustained use of gigabit wireless impossible

## Hardware for 100Mbps

Modern computers have no design bottlenecks at 100Mbps

Lots of bottlenecks at 1Gbps

Lucky to get 690Mbps

## Hardware for 16bps

### Hardware can help

- Simply more memory, starting at 10GB
- Bus bandwidth
- TCP checksumming in NIC
- Segmentation offload (SOE)
  - Pass NIC TCP template header and 64KB data
- Interrupt combining
- Page alignment on receive

### Quality of device driver counts a lot

Intel e1000 versus Broadcom 5700

## Consequnces for Web100

### Not interested in Gbps rates

- Protocols have problems doing 0.1Gbps
- Solution space is different

# Empower a user to discover common network engineering faults

- High bit error rates on WAN links
  - Clocking
  - Analogue power budget
- Ethernet autonegotiation misconfiguration

Automatically set buffer sizes

### The end

Glen Turner *glen.turner@aarnet.edu.au* 



aarnet

Australia's Academic & Research Network www.aarnet.edu.au

# Part 3 Ethernet misconfiguration

LinuxSA Adelaide 2003-09-16

Glen Turner glen.turner@aarnet.edu.au



aarnet

Australia's Academic & Research Network www.aarnet.edu.au

## Ethernet auto-negotiation



#### Do one of

- Set Speed and Duplex at both ends of ethernet link
- Set auto-negotiation at both ends of ethernet link

#### Do not

 Disable auto-negotiation, setting Speed and Duplex at one end of link and expect auto-negotiation to force those settings upn the remote port

### Example

- A-end config: Auto=off, Speed=100,
   Duplex=full
- B-end config: Auto=on
- B-end actual: Speed=100 (from clock on Rx), Duplex=half

### Link layer result

- B-end has packet
- Waits for A-end to finish Tx
- Sends packet
- But A-end doesn't listen for collisions and sends packet
- B-end detects collision, signals "late collision"
- B-end requeues packet, increments 16stage exponential backoff

#### IP result

- Ethernet layer eventually signals "delay drop" and drops packet
- IP queues may have backlogged and packets dropped

#### TCP result

- Hosts using this link face a varying roundtrip time, can't form good RTT estimate
- Packets drops signal congestion
- Performance dies as TCP rarely leaves congestion avoidance mode

# Part 4 Linux configuration in detail

LinuxSA Adelaide 2003-09-16

Glen Turner glen.turner@aarnet.edu.au



aarnet

Australia's Academic & Research Network www.aarnet.edu.au

## Setting buffer size



# TCP buffers Setting buffer

### Within an application

```
int buffer_size = 128 * 1024;
setsockopt(s, SOL_SOCKET, SO_SNDBUF,
    &buffer_size);
setsockopt(s, SOL_SOCKET, SO_RCVBUF,
    &buffer_size);
```

This can fail, as the operating system has limits to the size of buffer space

# TCP buffers Setting buffer in Linux

Linux uses 64KB by default

- $-64 = (1,000,000 \div 8) \times RTT$
- Fast ethernet users should worry when
   RTT > 5ms
- GbE users worry when RTT > 0.5ms
- Obviously room for considerable improvement

# TCP buffers Setting buffer in Linux

#### Increase buffer size

```
    net.core.rmem_max = 8388608
    net.core.wmem_max = 8388608
    net.core.rmem_default = 65536
    net.core.wmem_default = 65536
```

### Increase autotuning range

```
    net.ipv4.tcp_rmem = 4096 87380 8388608
    net.ipv4.tcp_wmem = 4096 65536 8388608
    net.ipv4.tcp_mem = 8388608 8388608 8388608
    net.ipv4.tcp_rmem = 4096 87380 8388608
```

# TCP buffers Interfaces also have buffering

Increase transmit queue

• ifconfig eth0 txqueuelen 1000

Increase receive queue

net.core.netdev\_max\_backlog=2500