


 Vote

1

I already have MinGW on my computer. How do I configure it to work with MATLAB?

 Asked by [MathWorks Support Team](#) **STAFF** on 21 Nov 2016

Latest activity Commented on by [Ling Smile](#) on 29 Sep 2017 at 8:45

 Accepted Answer by [MathWorks Support Team](#) **STAFF**

386 views (last 30 days)

I already have MinGW on my computer. How do I configure it to work with MATLAB?

Tags

[matlab](#) [mingw](#) [manual](#) [configure](#)

Products

[MATLAB](#)

1 Answer


 Vote

4

 Link

 Answer by [MathWorks Support Team](#) **STAFF** on 21 Sep 2017 at 4:00

 Edited by [MathWorks Support Team](#) **STAFF** on 21 Sep 2017 at 15:36

 Accepted Answer

[configuremingw.p](#)

MATLAB detects the MinGW compiler by reading the environment variable MW_MINGW64_LOC. When you install MinGW from the MATLAB Add-Ons menu, MATLAB sets this variable. The following instructions can be used to set this environment variable manually.

For MATLAB R2017b and later:

Verify you have installed MinGW-w64 version 5.3 before following these steps.

- 1) Download the attached MATLAB function 'configuremingw'.
- 2) Identify the full path to the MinGW installation directory containing the MinGW compiler binaries. This is identified as MINGWROOT.
- 3) In the MATLAB Command Window run:

```
>> configuremingw(MINGWROOT)
```

Related Content

MATLAB Answers

[Why do I receive "No supported compiler or SDK was found" although MinGW is installed and after restarting MATLAB?](#)

1 Answer

[Why does mex -setup fail to locate the MinGW-64 SDK that I just installed from the Add-On explorer in Matlab R2017a?](#)

1 Answer

[I try to use a proprietary Danfoss software development tool with Simulink s-function export. The tool opens Matlab and tries to...](#)

1 Answer

[Entire Website](#)

[MATLAB Support for MinGW-w64 C/C++ Compiler](#)

[File Exchange](#)

[Troubleshooting and Limitations Compiling C/C++ MEX Files with MinGW-w64](#)

[Documentation](#)
[MinGW-w64 Compiler](#)
[Documentation](#)


MATLAB and Simulink resources for Arduino, LEGO, and Raspberry Pi

» [Learn more](#)

Discover what MATLAB® can do for your career.

Opportunities for recent engineering grads.

» [Apply Today](#)

[MATLAB Academy](#)

Alternatively, run:

```
>> configuremingw
```

Then navigate to MINGWROOT.

For MATLAB R2015b through R2017a:

Verify you have installed MinGW-w64 version 4.9.2 before following these steps.

The MW_MINGW64_LOC environment variable can be (A) set for the entire system level or (B) set temporarily every time you open MATLAB. Administrative privileges are required to set MW_MINGW64_LOC as a system environment variable. No special privileges are required to set the environment variable temporarily.

(A) To set MW_MINGW64 as a system environment variable on Windows 7/8/10:

1. Make sure you have administrative privileges.
2. Select Computer from the Start menu.
3. Choose System properties from the context menu.
4. Click Advanced system settings > Advanced tab.
5. Click Environment Variables.
6. Under System variables, select New.
7. In the New System Variable dialog box, type MW_MINGW64_LOC in the Variable name field.
8. In the Variable value field, type the location of the MinGW-w64 compiler installation, for example, 'C:\TDM-GCC-64'.
9. Click "OK" to close the dialog boxes, then close the Control Panel dialog box.

(B) To set MW_MINGW64 as a temporary environment variable using MATLAB:

Run the following in the MATLAB Command Window:

```
>> setenv('MW_MINGW64_LOC', folder)
```

where 'folder' is the installation directory of MinGW. For example, 'C:\TDM-GCC-64'. This command will need to be run every time you start MATLAB for MATLAB to correctly use MinGW. You can consider adding the above command to your 'startup.m' file. This will execute the command every time MATLAB starts up.

To Verify:

After performing the above steps, you can verify if the compiler was recognized by MATLAB by running the following command:

```
>> mex -setup
```

New to MATLAB?

» [Learn MATLAB today!](#)

5 Comments

Show 2 older comments



Ji Tan on 25 Jul 2017

Hi Bassem, same problem here. Did you fix it?



Munawwar Sohul on 25 Sep 2017 at 18:11

Thank you for the instructions. It worked for me.



Ling Smile on 29 Sep 2017 at 8:45

Hi Bassem, follow your steps, I still got the same problem? Could you help me? Thanks! If possible, send me a email smilelingyong@hust.edu.cn. Thanks a lot!

>>mex -setup MEX configured to use 'MinGW64 Compiler (C)' for C language compilation. Warning: The MATLAB C and Fortran API has changed to support MATLAB variables with more than 2^32-1 elements. You will be required to update your code to utilize the new API. You can find more information about this at: http://www.mathworks.com/help/matlab/matlab_external/upgrading-mex-files-to-use-64-bit-api.html.

To choose a different language, select one from the following: mex -setup C++ mex -setup FORTRAN MEX configured to use 'MinGW64 Compiler (C++)' for C++ language compilation. Warning: The MATLAB C and Fortran API has changed to support MATLAB variables with more than $2^{32}-1$ elements. You will be required to update your code to utilize the new API. You can find more information about this at: http://www.mathworks.com/help/matlab/matlab_external/upgrading-mex-files-to-use-64-bit-api.html.

[Log in](#) to comment.

[Log in](#) to answer this question.

mathworks.com

© 1994-2017 The MathWorks, Inc. MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.