DROP A VOCAL. PLAY METAL.

RONE Iron

Drop any vocal and it becomes a metallic chop instrument: flattened to the note you pick, sliced onto your keys, rung through a comb tuned to that note and thrown from left to right. Play it from the piano roll, or let the GROOVE write the pattern.



VERSION 1.2 · VST3 · AU · STANDALONE

RONEAUDIO.COM

Contents

1	Welcome to RONE Iron	a whole vocal-chop chain in one instrument
2	Installation with the RONE Plugins Center	Center, account, file locations
3	Quick start	your first metal vocal
4	Interface tour	every element on screen
5	The vocal, the note and the metal	controls reference
6	LFO	the knobs move by themselves
7	ARP	a melody from one vocal
8	GROOVE	the automatic pattern
9	Presets, macros, locks and slots	the whole sound at once
10	ADVANCED	voice, flattening, sound and keys
11	Step-by-step workflows	recipes
12	Tips, tricks and troubleshooting	

1 Welcome to RONE Iron

RONE Iron does in one step what usually takes four plugins and an afternoon: it **flattens** a vocal to a single note (the formants stay, so it still sounds like a voice), **slices** it into one-shot chops on its transients and lays them out on your MIDI keys, rings every chop through a **comb tuned to that note** so the voice turns to metal, and **pans** each chop to its own side so the hits jump from one speaker to the other.

The result is the chopped, metallic, left-right vocal you hear in psytrance and festival drops - in tune with your track, from any acapella, in seconds.

Where it shines

- **Drop hooks** - a rhythmic metal vocal on the note of your bassline.
- **Build-ups** - ride the macros CHOP and MOTION up into the drop, or let the LFO open the metal by itself.
- **Leads from a voice** - ARP turns the chops into a melody over a chord.
- **Breaks and intros** - long rings and soft pans for a hypnotic bed.


The 10-second version

1. Insert Iron as an instrument on a MIDI track.
2. Drag a vocal onto the plugin.
3. Click the note of your track on the piano.
4. Press GROOVE and play the song - or play the keys.

> **YOUR VOCAL TRAVELS WITH THE PROJECT**
> Iron keeps the vocal you dropped inside your project (losslessly compressed), with its chops, pans and groove edits. Moving or deleting the original file never breaks a saved project.

2 Installation with the RONE Plugins Center

Every RONE product is installed, updated and licensed through one application: the **RONE Plugins Center**. You never download individual installers by hand, and you never enter serial numbers into the plugin itself.



RONE Plugins Center. 1 Navigation · 2 Your account and licence · 3 Sync status · 4 Search · 5 Refresh · 6 Settings · 7 Updates summary · 8 UPDATE ALL · 9 Filters · 10 Sort · 11 A plugin card · 12 Card menu (Details, Open, Manual) · 13 OPEN the standalone app · 14 INSTALL · 15 Your plan

Step by step

1. Download the Center from roneaudio.com and run the installer (Windows: `RONE_Plugins_Center_Installer.exe`, macOS: `RONE_Plugins_Center.dmg`). On Windows the installer also adds the Microsoft WebView2 runtime if your PC does not have it yet; it is required for the plugin interfaces. On macOS (10.15 Catalina or later, Intel and Apple Silicon) open the .dmg and drag the Center onto Applications. It is signed and notarized by Apple, so macOS only asks once whether you want to open an app downloaded from the internet: press **Open**.
2. Open the Center and sign in with your **roneaudio.com account** (the same e-mail and password you used on the website). Your licences and device slots are checked automatically: an active **ALL ACCESS** plan unlocks every plugin, and a **lifetime licence** unlocks the plugin it was bought for — so RONE Iron opens either way.
3. Find **RONE Iron** in the list and press **INSTALL**. The Center downloads the signed installer, verifies its checksum, installs it silently and registers the version.

4. When the card shows **INSTALLED**, start (or restart) your DAW and rescan plugins if it does not pick up new plugins automatically. All RONE plugins appear next to each other in your plugin list because every name starts with **RONE**.
5. Updates appear on the same card. Press **UPDATE** on one plugin or **UPDATE ALL** at the top. Close the standalone version of a plugin before updating it.

Where the files go

WINDOWS

FILE	LOCATION
VST3	`C:\Program Files\Common Files\VST3\RONE\RONE Iron.vst3`
Standalone app	`C:\Program Files\RONE Plugins\RONE Iron.exe`
This manual	`C:\Program Files\RONE Plugins\Manuals\`

MACOS

FILE	LOCATION
VST3	`/Library/Audio/Plug-Ins/VST3/RONE Iron.vst3`
Audio Unit	`/Library/Audio/Plug-Ins/Components/RONE Iron.component`
Standalone app	`/Applications/RONE Iron.app`
This manual	`/Users/Shared/RONE Plugins/Manuals/`

MANUAL INSIDE THE CENTER

Every installed plugin has a **Manual** entry in its card menu (the three dots on the card). It opens this PDF from the install folder, or from roneaudio.com if the local copy is missing.

Licence and activation

Licensing is tied to your account, not to a key. The plugin checks the licence file that the Center writes when you sign in. There are two ways to own it: an **ALL ACCESS** plan, which unlocks every RONE plugin for as long as it is active, or a **lifetime licence** for this plugin alone, which never expires. Either one opens RONE Iron, and buying the lifetime licence later does not disturb a plan you already have.

If a plugin ever shows a *RONE Bundle License Required* screen, open the Center, make sure you are signed in and the plugin shows as licensed, then reopen it. Two devices can be signed in at the same time on either kind of licence; sign out on an old machine from the Center's Account page to free a slot. A lifetime licence keeps working offline for far longer than a plan does — there is nothing for it to expire against — but the Center still needs to reach the internet occasionally to confirm it.

Uninstalling

Windows: Settings → Apps → *RONE Iron (RONE)*. macOS: delete the bundles listed above. Presets and settings in your user folder are kept.

3 Quick start



A fresh RONE Iron. Drop a vocal or any sample anywhere on the card, or press the folder button.

1. **Insert Iron** on an instrument (MIDI) track. In FL Studio: Channel rack, + , RONE Iron.
2. **Drop a vocal - or any sample** onto the card - WAV, AIFF, FLAC, MP3 or OGG, from your DAW's browser or from Explorer / Finder. The first 60 seconds are used. A few seconds later the chops are on the keys.
3. **Pick the note** of your track on the piano (A by default). The whole vocal is flattened to the octave of that note nearest the voice, and the comb follows it.
4. **Play.** Every chop has a key, starting at C5 (FL Studio's naming; middle C = C5). Click a chop on the screen to hear it.
5. **Or let it play itself:** press GROOVE and start your song. Iron plays a 16th-note pattern of chops on the host tempo. DRAG MIDI drops that pattern into your piano roll as notes.
6. **Try the presets** at the top and the four macros next to them. They change the whole sound, not one knob.

> **RIGHT-CLICK ANY CONTROL**
> Right-click a knob for the host's own menu - in FL Studio that is where you create an automation clip or link it to a controller.

4 Interface tour



The header and the vocal card.

1. **Header logo** — click to flip to the back panel (About, version, licence)
2. **Preset browser** — 38 presets in nine groups; arrows step through them, the name opens the list
3. **Macros** — METAL, CHOP, SPACE, MOTION - four knobs that move the whole sound
4. **MIDI / tempo** — the MIDI light flashes with incoming notes; the host tempo the GROOVE follows
5. **Vocal** — the file you dropped
6. **AUTO SLICE** — SMALL (fewer, longer chops), MEDIUM, LARGE (many more)
7. **THRESHOLD** — only the strong chops get a key; breaths and faint sounds join the chop before them
8. **NORMALIZE** — every chop at the same level
9. **Chops** — how many chops the vocal was cut into
10. **Chop readout** — the chop under the mouse or selected: its number and key
11. **BROWSE / EJECT** — open a file, or empty the plugin
12. **Chop note** — the selected chop's own note: - / + moves it in semitones
13. **Chop map** — the flattened vocal with every slice marked; click a chop to hear it
14. **Pan lane** — one bar per chop: up = left, down = right; drag a bar to pan by hand
15. **Chop keys** — the keyboard of chops; the lit key is the one playing



The middle: the note, the metal and the pans.

1. **NOTE** — the one note the whole vocal is flattened to
2. **OCTAVE** — move that note an octave down or up (0 = nearest the vocal)
3. **MIDI NOTE** — lets the octave under the chops on your keyboard choose the note
4. **ARP** — lets you light several notes; every chop then takes one of them
5. **ARP order** — UP, DOWN, UP-DOWN or FOLLOW, over 1 or 2 octaves
6. **Note readout** — the vocal's own pitch and the note it goes to
7. **IRON** — how much metal: the tuned comb's share of the sound
8. **FADE OUT** — shortens every chop
9. **RING** — how long the metal rings
10. **LFO** — moves IRON, FADE OUT and RING by themselves, in time with the song
11. **AUTO PAN** — a new left-right pattern for every chop
12. **PAN STYLE** — PING-PONG, SPREAD or WIDE
13. **RANGE** — how far to the sides the pans go
14. **Pan meter** — where the chop that plays sits right now



The footer.

1. **ADVANCED** — opens the voice, comb, flatten, sound and key settings
2. **GROOVE** — the automatic pattern on or off
3. **Step strip** — the pattern at a glance; EDIT opens the GROOVE panel
4. **DRAG MIDI** — drag the pattern into your piano roll as MIDI notes
5. **Pattern name** — the groove pattern that plays, or CUSTOM
6. **MIX** — from the full effect back towards the plain chops
7. **NOTE** — makes MIX keep the flattened note (only the metal fades)
8. **OUT** — output level
9. **SAFE** — the output ceiling; green while it is on
10. **Resize grip** — drag to resize the window

5 The vocal, the note and the metal



The vocal card. The slices on the waveform, the pan of every chop under it, and the keys they play from.

Drop / BROWSE

`WAV, AIFF, FLAC, MP3, OGG`
`up to 60 s`

Drop a file on the card or press the folder button. Iron reads the first 60 seconds from the first sound, finds the vocal's pitch, flattens it to your note, finds the transients and builds the chops - usually in well under a second per ten seconds of audio. EJECT empties the plugin. Breaths, S sounds and other noises stay on the keys, but the GROOVE and the ARP never pick them.

AUTO SLICE

`SMALL / MEDIUM / LARGE`
`default MEDIUM`

How finely the vocal is cut. SMALL gives fewer, longer chops (whole words); LARGE gives many more short ones (syllables). DETAIL in ADVANCED fine-tunes it between the three. At most 128 chops; when there are more chops than keys above ROOT, the key map moves down to the highest C where every chop has a key.

Tip: Clicking a chop on the waveform or on the keys plays it.

THRESHOLD

`OFF, -42 to -6 dB`
`default OFF`

Decides which sounds are loud enough to be a chop. With THRESHOLD on, a chop that is more than the shown number of dB quieter than the loudest chop - a breath, a faint in-between sound - gets no key: it joins the chop before it. Raise it until only the syllables you want are left. Changing it re-slices the vocal.

Tip: Drag the chip or use the mouse wheel. Double-click = OFF.

NORMALIZE

`on / off`
`default off`

Brings every chop to the same level, so quiet syllables hit as hard as loud ones. It is the LEVEL knob of ADVANCED at 100 %; use that knob for anything in between.

Chop note

`-24 to +24 semitones per chop`

Click a chop on the waveform or on the keys: a small - / + appears over it. It moves that one chop in semitones above or below the note the rest of the vocal is flattened to (or its ARP note), and the comb gets a tooth for it, so the chop stays in metal and in tune. Use it to put one syllable on the fifth, or to write a short melody inside a groove. A new vocal or a new slicing clears the chop notes.

Tip: The mouse wheel over the - / + steps it. Double-click = back to 0.

NOTE

```
C to B
default A
```

The note the whole vocal is flattened to, in the octave nearest the voice. Pick the key of your track (the root of your bassline). Changing it re-renders the vocal in the background; the old chops keep playing until the new ones are ready.

Tip: The mouse wheel over the piano steps the note.

OCTAVE

```
-2 to +2
default 0
```

Moves the target note whole octaves down or up from the octave nearest the vocal. Big jumps change the character - down is darker and more robotic.

MIDI NOTE

```
on / off
default off
automatable
```

With MIDI NOTE on, the twelve keys right below the first chop key (with the chops starting at C5, that is C4 to B4) choose the NOTE instead of playing chops. Hold a key with your left hand while the GROOVE runs and the whole vocal follows - you can play the groove like an instrument. The switch is instant: Iron prepares the other notes in the background.

IRON

```
0 to 100 %
default 34 %
automatable
```

The amount of metal. The comb sits on the note: its first notch is the note itself and its teeth repeat on the note's harmonics, so the ring is always in key. At 0 % you hear the flattened chops alone.

Tip: Drag, or use the mouse wheel (Shift = fine). Double-click = default.

RING

```
0.10 to 3.00 s
default 0.70 s
automatable
```

How long the comb rings after each chop - short for tight, clanking hits, long for a shimmering, bell-like tail.

FADE OUT

```
0 to 100 %
default off
automatable
```

Shortens every chop. At 0 each chop plays to its end; turning it up fades every chop out earlier, for tighter, more percussive hits. Automate it to open the chops up over a build.

AUTO PAN, PAN STYLE, RANGE

```
PING-PONG / SPREAD
/ WIDE
RANGE 0 to 100 %,
default 80 %
automatable
```

Every chop has its own pan. AUTO PAN rolls a new set; chops you panned by hand keep theirs. PING-PONG alternates hard left and right in the order the hits play (the classic left-right explosion), SPREAD places them at random but never three in a row on one side, WIDE pushes them hard and wide. RANGE scales how far out they go.

Tip: Drag a bar in the pan lane to pan one chop by hand. Double-click a bar to give it back to AUTO.

MIX and NOTE

```
MIX 0 to 100 %,
default 100 %
NOTE on / off
automatable
```

MIX blends from the full effect (100 %) towards the plain chops: at 0 % you hear the untouched vocal chops, with the same slices, pans and fades. Turn on **NOTE** and MIX only takes the metal away - at 0 % you hear the vocal flattened to your note, without the comb. Use MIX to bring back more of the original voice.

OUT and SAFE

```
OUT -24 to +12 dB
SAFE on by default
```

OUT sets the level. SAFE is a ceiling at -0.3 dBFS on the output: it never touches normal levels and only catches the peaks that a long ring or many voices can pile up. The lamp next to OUT is green while SAFE is on.

6 LFO



The LFO editor (the LFO key under the IRON knob). Here a pump shape, one bar long, opens IRON by 50 % and pulls FADE OUT down by 30 %.

1. **LFO** — opens the editor; lit while the LFO is on
2. **ON** — the LFO on or off
3. **Shape** — one cycle: drag a point, click an empty spot for a new point, double-click a point to remove it
4. **Ready shapes** — triangle, sine, ramp up, ramp down, square and pump
5. **Length** — how long one cycle is, from 4 bars to 1/32, locked to the host tempo
6. **Depths** — how far the LFO moves IRON, FADE OUT and RING; click a box to attach or detach it

The LFO does the automation for you. Draw one shape, pick its length, and give each of the three knobs a depth: the knob then opens and closes by itself, in time with your song. The ring around each knob shows where the LFO has taken it. A depth below 0 pulls the knob down instead of up, so one LFO can open the metal while it tightens the chops.

The LFO never moves the knobs themselves: it is added on top, exactly like the macros, so switching it off returns to your settings. While the DAW plays it follows the song position (a bounce is the same every time); while the DAW is stopped it runs on its own at the project tempo. It is saved with the project and with the presets that use it.

> **PUMP THE METAL LIKE A SIDECHAIN**
>
> IRON low (15 to 20 %), the pump shape, length 1/4 and an IRON depth of +40 %: the metal ducks on every kick and opens after it. The MOTION presets are built this way.

7 ARP



ARP on with A, C and E lit: the chops play a minor triad, with one comb per note. UP, DOWN, UP-DOWN, FOLLOW and the octaves show while ARP is on.

1. **ARP** — on / off
2. **Chord notes** — click keys to add or remove notes; the NOTE is always one of them
3. **Order** — UP, DOWN, UP-DOWN or FOLLOW
4. **Octaves** — the notes in one octave, or continued into a second
5. **Note readout** — the notes in use

With ARP on, every chop takes one of the lit notes. In **UP**, **DOWN** and **UP-DOWN** the chops walk through the notes in order - chop 1 on the first note, chop 2 on the next and so on - so a GROOVE or a run of keys becomes an arpeggio. **FOLLOW** works differently: each chop goes to the lit note nearest its own pitch, so the vocal keeps its melody but snaps to your chord or scale. The **x** clears the extra notes. 2 OCT continues the order an octave higher (FOLLOW ignores it).

> **LIGHT THE SCALE, USE FOLLOW**
> Light the notes of your track's scale and choose FOLLOW: the chops stay in key but keep the shape of the original singing - the best way to keep two different vocals sounding different.

8 GROOVE



The GROOVE panel (EDIT in the footer). Each card is a 16th note: the chop it plays and its marks. A hit longer than one 16th is drawn across the steps it sounds on, like a note in a piano roll.

1. **GROOVE** — on / off - it plays the moment it is on, and follows your song while the DAW plays
2. **BARS** — a 1-bar or 2-bar pattern
3. **REROLL** — a new pattern; locked steps keep theirs
4. **History** — back to an earlier roll and forward again (32 kept)
5. **LOCK STEPS** — freeze every hit as it plays now
6. **CLEAR EDITS** — every step back to the generator
7. **Pattern** — 20 researched patterns, or CUSTOM
8. **DRAG MIDI** — drag the pattern into your piano roll
9. **Steps** — 16 cards per bar; click a hit to edit it
10. **Density / chops / variation** — how many hits, how many different chops, how different bar 2 is
11. **Length / hold / flip / rolls** — how long the hits are, how many ring on, pan flips and 1/32 rolls



A step's editor. Click a hit: ROLL turns it into 2, 3 or 4 fast 1/32 hits, LENGTH sets how long it sounds, FLIP throws it to the other side, CHOP picks the chop. A step you set by hand is locked; RESET STEP gives it back to the generator.

Step editor

`ROLL off / x2 / x3 / x4`
`LENGTH 1/2, 1, 2, 4, HOLD`
`FLIP, CHOP`

Every step can be built by hand. The power button switches a step on or off (on an empty step it shows under the mouse), the lock freezes it. Click a hit to open its editor: **ROLL** makes the 1/32 ratchet, **LENGTH** is in 16th notes (HOLD rings to the next hit), **FLIP** sends the hit to the other side and **PREV / NEXT** choose its chop. Whatever you set by hand is locked, so REROLL and the knobs leave it alone.

Tip: Shift + mouse wheel over a hit steps its ROLL.

Patterns

`20 + CUSTOM`

RONE, HOOK, GALLOP, SYLLABLES, ROLLING, OFFBEAT, BACKBEAT, PROG STAB, TRESILLO, DOTTED, FLIPSIDE, CALL ANSWER, RATCHET, BUILDUP, HALFTIME and BREAKDOWN - patterns built around the kick and bass grid of psytrance, progressive and techno - and four built on the 1/32 ratchet: RIPPER, JITTER, SHRED and TRIPWIRE. A pattern fixes the steps; the knobs and the chop choice still apply. Edit the steps or REROLL and it becomes CUSTOM.

DENSITY

`0 to 100 %`
`automatable`

How many of the 16 steps play (the readout counts them).

CHOPS

`0 to 100 %`
`automatable`

How many different chops the pattern uses - a few for a hypnotic loop, many for a talking line. The GROOVE only picks strong, tonal chops.

VARIATION

`0 to 100 %`
`2 BARS only`

How much bar 2 differs from bar 1.

LENGTH, HOLD

`LENGTH in 16ths`
`HOLD 0 to 100 %`

LENGTH is how long each hit lasts, in 16th notes. HOLD lets a share of the hits ring on to the next one.

FLIP, ROLLS

`0 to 100 %`


FLIP sends some hits to the other side, on top of the chop's own pan. ROLLS turns some hits into quick 1/32 repeats (2 to 4 hits, each a little quieter).

DRAG MIDI (in the panel and in the footer) writes the pattern exactly as it plays, edits and rolls included, as a MIDI clip you drag into your piano roll. Turn GROOVE off and edit the notes like any other clip - Iron's keys play the same chops, so the clip sounds the same.

GROOVE PLAYS AT ONCE, THEN FOLLOWS THE HOST

Switch GROOVE on and the pattern plays straight away at your project's tempo, even with the DAW stopped. Press play and it locks to your song's bars; press stop and it stops with the song. The footer then reads STOPPED · RUN: click it to run the pattern on its own again. A project saved with GROOVE on stays quiet until you play or click. In the standalone app GROOVE is play / stop on its own clock.

9 Presets, macros, locks and slots



The preset list. The line under the list describes the preset under the mouse; MY SLOTS keep six sounds of your own.

1. **Preset browser** — arrows step through the presets; the name opens the list
2. **Preset list** — SIGNATURE, STABS, ARP, SOFT, SPACE, FX, MOTION, RATCHET and PHRYGIAN
3. **Description** — what the preset is for
4. **MY SLOTS** — hold a slot to store the current sound, tap to recall it
5. **INIT** — every control back to its default

A preset sets the whole IRON sound: the metal, the fades, the pans, the ARP notes, the groove and what the four macros do. It never changes your vocal, your NOTE, OCTAVE or ROOT, or the pans you set by hand. **SIGNATURE**: IRON (the signature sound for the main drop), FORGE (peak-time full-on) and SPINE. **STABS**: RAZOR, ANVIL, PISTON. **ARP**: TRIAD, ASCEND, MELODY, PHRYGIAN, HIJAZ, DESCENT, SPIRAL. **SOFT**: HUMAN, HALO, GLASS, VELVET. **SPACE**: MOLTEN, CATHEDRAL. **FX**: SHRAPNEL, IGNITION.

New in 1.2: **MOTION** - PULSE, BREATHE, TIDE, STAIRS and UNFOLD, where the LFO moves the sound for you. **RATCHET** - RATTLE, RIPPER, JITTER, SHRED, TRIPWIRE and BUZZSAW, built on 1/32 rips. **PHRYGIAN** - COBRA, SERPENT, ORACLE, RITUAL, MIRAGE and SANDSTORM, ARPs in the phrygian scale that psytrance melodies live in. Also SPINE (the signature groove dead centre) in SIGNATURE and HIJAZ, DESCENT and SPIRAL in ARP. Every ARP preset starts from the note you pick with NOTE, so it is always in the key of your track. A preset that uses the LFO brings its shape; a preset without it switches the LFO off and keeps what you drew.

Macros

METAL, CHOP, SPACE, MOTION
0 to 100 %
automatable

Each macro moves several controls at once, in the way the current preset defines: METAL adds metal and ring, CHOP tightens the hits, SPACE opens the rings and the stereo, MOTION adds pan movement, density and rolls. The macros never move the knobs themselves - the knobs show where a macro has taken them - so turning a macro back to 0 always returns exactly to the preset. Automate them into a drop.

Tip: Hover a macro to light the controls it moves.



Locks. The small locks next to IRON, RING and MIX: those controls keep their values when you switch presets.

Locks

12 lockable controls

Every lockable control has a small lock next to it, grey while it is open; click it to lock and it lights up. A locked control stays where it is when you switch presets, so you can audition presets around a metal amount or a groove you like. Lockable: IRON, RING, FADE OUT, MIX, LIFE, the pans, the ARP notes, the GROOVE and each of the four macros.

MY SLOTS

6 slots

Hold a slot button to store the current sound in it, tap it to recall. Slots are kept on your computer, so they are there in every project and every instance.

10 ADVANCED



ADVANCED open: the switches on top, three groups below.

1. **VOICE** — MONO: a new chop cuts the last one; POLY: up to 16 ring together
2. **COMB** — the metal on or off
3. **SAFE** — the -0.3 dBFS output ceiling on or off
4. **FLATTEN + SLICE** — LIFE, FINE, DETAIL - these re-render the vocal
5. **SOUND** — TONE, LEVEL, LOW CUT - live
6. **KEYS** — ROOT, STEAL, VEL - live

LIFE

`0 to 100 %`
`default 15 %`

How much of the vocal's own pitch movement survives the flattening. 0 % is a dead-straight robot note; more keeps the scoops and vibrato of the singer around the note.

FINE

`-50 to +50 cents`
`default 0`

Tunes the target note in cents, for tracks that are not at A = 440 Hz.

DETAIL

`-1 to +1`
`default 0`

Fine control over the slicing between the AUTO SLICE steps: right = more chops, left = fewer. The readout shows the new count.

TONE

```
0 to 100 %
default 0
automatable
```

Darkens the metal: higher values damp the comb's upper teeth, for a softer, warmer ring.

LEVEL

```
0 to 100 %
default 0
automatable
```

Evens out the chops' levels, so quiet syllables hit as hard as loud ones. NORMALIZE on the vocal card is this knob at 100 %.

LOW CUT

```
OFF, 20 to 400 Hz
default OFF
automatable
```

A high-pass on the output - useful when the vocal is flattened low (OCTAVE -1 or -2) and starts to fight the bass.

ROOT

```
MIDI 0 to 127
default C5 (60)
automatable
```

The key of the first chop. The others follow upward, one chop per key, black keys included.

STEAL

```
0 to 100 ms
default 20 ms
```

In MONO, how quickly a chop fades when the next one cuts it. Shorter is choppier; longer is smoother.

VEL

```
0 to 100 %
default 0
```

How much the MIDI velocity sets each chop's level. At 0 every note plays at full level.

11 Step-by-step workflows

The classic metal drop hook

IRON preset, GROOVE

1. Drop an acapella and pick the root note of your bassline.
2. Preset IRON. Press GROOVE and play the drop.
3. REROLL until the pattern talks; lock the steps you love and REROLL the rest.
4. DRAG MIDI the pattern into the piano roll if you want to edit it as notes.

Play it over a chord progression

MIDI NOTE

1. Turn on GROOVE and MIDI NOTE.
2. With the chops from C5, the keys C4 to B4 choose the note: hold the root of each chord while the groove runs.
3. Record that left hand into the piano roll with the rest of the part.

A lead from a vocal

ARP + FOLLOW

1. Turn on ARP and light the notes of your scale (or a triad).
2. FOLLOW keeps the singer's melody snapped to your notes; UP or UP-DOWN turns the chops into an arpeggio.
3. Try the ARP presets: TRIAD, ASCEND, MELODY, PHRYGIAN - and the PHRYGIAN group for dark psytrance lines.

A build with no automation

LFO

1. Preset TIDE, or open the LFO on any preset.
2. Shape: ramp up. Length: 4 BAR. IRON depth up, FADE OUT depth below 0.
3. Every 4 bars the sound opens from a dry gate into ringing metal and snaps shut on the downbeat.

Rips at the end of a phrase

ROLL

1. Open the GROOVE panel and click a hit near the end of the bar.
2. ROLL x4 turns it into a 1/32 rip over two 16ths; x2 and x3 are shorter.
3. Or start from the RATCHET presets and the patterns RIPPER, JITTER, SHRED and TRIPWIRE.

Build-up into the drop

Macros

1. Preset IGNITION, or any preset you like.
2. Automate CHOP and MOTION from 0 up over the last 8 bars, METAL up in the last two.
3. Snap them back to 0 on the drop: the sound returns exactly to the preset.

12 Tips, tricks and troubleshooting

Tips

- **Clean acapellas work best.** A dry vocal with little reverb slices into clearer chops and flattens more cleanly.
- **Every vocal sounding alike?** One note and one comb bring vocals closer together by design. Use ARP FOLLOW, pull MIX down a little, or raise LIFE.
- **Too low and muddy?** OCTAVE +1, or LOW CUT in ADVANCED.
- **Tighter hits:** FADE OUT and a shorter RING; MONO with a short STEAL.
- **Breaths on the keys?** Raise THRESHOLD until they are gone.
- **Bigger stereo:** PAN STYLE WIDE, RANGE 100 %, FLIP up in the GROOVE.

Troubleshooting

SYMPTOM	CAUSE	FIX
No sound from the keys	No vocal loaded, or you play below the first chop key	Drop a vocal; play from the ROOT key (C5 by default) upward
Some low keys change the note instead of playing	MIDI NOTE is on: the octave under the chops chooses the note	Turn MIDI NOTE off, or play the chops from the ROOT key up
The GROOVE is silent	GROOVE is off, or the DAW's stop ended it	Switch GROOVE on, press play in your DAW, or click STOPPED · RUN in the footer
Only the first part of my file is used	Iron loads up to 60 seconds	Trim the vocal to the part you want before dropping it
The file is refused	Not an audio file Iron can read, or no audio in it	Use WAV, AIFF, FLAC, MP3 or OGG
A short wait after changing NOTE, LIFE or the slicing	The vocal is re-rendered for the new setting	The old chops play until the new ones are ready
It sounds too much like a robot	LIFE is low and MIX is at 100 %	Raise LIFE, or pull MIX down (NOTE on keeps the note)
Peaks sound squashed	SAFE is catching overs (many voices, long rings)	Lower OUT, IRON or RING, or switch POLY to MONO
The window is white in Ableton Live, the standalone works (Windows)	Live's **Auto-Scale Plug-In Window** (seen with Windows display scaling such as 110 %)	In Live's browser open Plug-Ins, right-click the plugin and untick Auto-Scale Plug-In Window, then delete the plugin from the track and insert it again