

计算机网络原理实验

交换机的VLAN配置 --交换机Vlan的划分





交换机的VLAN配置

- ➤ 交换机是数据链路层的网络互连设备,使用交换机可以定义VLAN。
- ➤ 定义V1an可以有效地控制广播风暴,提高网络的安全可靠性,有效地进行网络监控和数据流量控制,实现不同地理位置的部门间的局域网通信,节省构建网络所需网络设备的费用。

(1) 交换机VLAN的划分

- (2) 交换机间相同VLAN的通信
- (3) 使用三层交换机实现跨VLAN的通信




(1) 交换机VLAN的划分

- ➤ 交换机VLAN的划分在全局配置模式下完成,主要包括创建 VLAN、端口分配、VLAN接口IP设置等。
- ➤ 交换机可以划分成多个VLAN,每个VLAN可以分配一个或 多个端口,在同一个Vlan中所有端口连接的计算机设置成 同网段的IP地址后可实现连网。



宣為人等(1)交换机VLAN的划分-网络拓扑构建

- ▶添加6台计算机,标签名为PC0-PC5:
- ➤ 添加1台二层交换机2960,标签名为Switch0;
- ➤ 交换机划分的Vlan及端口根据如下拓扑图,使用直通线连接好计 算机和交换机,并为每台计算机设置好相应的IP(Internet Protocol Address, IP地址)和SM(Subnet Mask,子网掩码)。
- ◆ 验证是否接入相 同Vlan的计算机 能相互通信,不 同Vlan的计算机 不能通信。



愛媛 (1) 交換机VLAN的划分

-计算机IP地址配置

按要求配置好每台计算机的IP(Internet Protocol Address, IP地址)、SM(Subnet Mask,子网掩码)。

PC0配置

IP地址: 192.168.0.11 PC2配置

子网掩码: 255.255.255.0 IP地址: 192.168.0.21

PC1配置 子网掩码: 255.255.255.0

IP地址: 192.168.0.12 PC3配置

子网掩码: 255.255.255.0 IP地址: 192.168.0.22

子网掩码: 255.255.255.0

PC4配置

IP地址: 192.168.0.31

子网掩码: 255.255.255.0

PC5配置

IP地址: 192.168.0.32

子网掩码: 255.255.255.0



由于分配的计算 机的IP地址都是 192.168.0.0/24 网段的IP地址, 所以所有计算机 之间都是相互连 通的, 因此可以 用任何一台计算 机使用Ping命令 去测试与其它计 算机的连通性。



Physical Config Desktop Programming Attributes

Command Prompt

```
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 12ms, Average = 3ms
C:\>ping 192.168.0.21
Pinging 192.168.0.21 with 32 bytes of data:
Reply from 192.168.0.21: bytes=32 time=1ms TTL=128
Reply from 192.168.0.21: bytes=32 time<1ms TTL=128
Reply from 192.168.0.21: bytes=32 time<1ms TTL=128
Reply from 192.168.0.21: bytes=32 time<1ms TTL=128
Ping statistics for 192.168.0.21:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 1ms, Average = 0ms
C:\>ping 192.168.0.22
Pinging 192.168.0.22 with 32 bytes of data:
Reply from 192.168.0.22: bytes=32 time=1ms TTL=128
Reply from 192.168.0.22: bytes=32 time=7ms TTL=128
Reply from 192.168.0.22: bytes=32 time<1ms TTL=128
Reply from 192.168.0.22: bytes=32 time<1ms TTL=128
Ping statistics for 192.168.0.22:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 7ms, Average = 2ms
```



(1) 交换机VLAN的划分- 创建Vlan

- ➤ 创建及删除Vlan
- ✓交换机Vlan的创建在全局配置模式下进行。
 - 创建Vlan Vlan [id](如Vlan 10)。
 - 删除Vlan no Vlan [id] (如no Vlan10)。
- ✓ 本实验创建3个Vlan,分别为Vlan10、Vlan20和Vlan30。

Switch>enable //进入特权模式

Switch#conf t //进入全局配置模式

Switch(config)#vlan 10 //创建vlan 10

Switch(config-vlan)#name vlan10 //命名vlan10

Switch(config-vlan)#exit //返回全局配置模式

Switch(config)#vlan 20

Switch(config-vlan)#name vlan20

Switch(config-vlan)#exit

Switch(config)#vlan 30

Switch(config-vlan)#name vlan30

愛妈人が(1)交換机VLAN的划分-分配Vlan端口

- ➤ 分配Vlan端口
- ✓ 把交换机端口分配到相应的Vlan, IOS提供了2种方法, 一种是逐一添加; 另一种是对连续数字的端口分组添加。
 - 逐一添加的方
 - -Switch(config)#interface fa0/1 //进入端口模式
 - -Switch(config-if)#switchport access vlan 10 //把fa0/1端口分配到vlan10
 - -Switch(config)#interface fa0/2 //进入端口模式
 - -Switch(config-if)#switchport access vlan 10 //把fa0/2端口分配到vlan10
 - 分组添加的方法
 - -Switch(config)#interface range fa0/3 -4 //进入端口组模式
 - -Switch(config-if-range)#switchport access vlan 20 //把fa0/3-4个端口分配到vlan 20
 - -Switch(config)#interface range fa0/5 -6 //进入端口组模式
 - -Switch(config-if-range)#switchport access vlan 30 //把fa0/5-6个端口分配到vlan 30



愛媛 (1) 交換机VLAN的划分-查看Vlan配置

- ➤ 查看Vlan配置
- ✓ 使用 "show vlan"命令可以查看发现端口已经重新分配了,还 可以检查一下配置是否正确。

```
Switch#show vlan
VLAN Name
                                      Status Ports
  default
                                     active Fa0/7, Fa0/8, Fa0/9, Fa0/10
                                               Fa0/11, Fa0/12, Fa0/13, Fa0/14
                                               Fa0/15, Fa0/16, Fa0/17, Fa0/18
                                               Fa0/19, Fa0/20, Fa0/21, Fa0/22
                                               Fa0/23, Fa0/24, Gig0/1, Gig0/2
                                     active Fa0/1, Fa0/2 active Fa0/3, Fa0/4
10 vlan10
20 vlan20
                                     active Fa0/5, Fa0/6
   vlan30
1002 fddi-default
                                     active
1003 token-ring-default
                                     active
1004 fddinet-default
                                      active
1005 trnet-default
                                      active
VLAN Type
          SAID
                     MTU
                           Parent RingNo BridgeNo Stp BrdgMode Trans1 Trans2
    enet 100001
                     1500 -
10
   enet 100010
                     1500 -
20
                     1500 -
   enet 100020
    enet 100030
                     1500 -
```

✓ 通过以上配置操作,在交换机上进行了Vlan的创建和端口的分 配,从而实现了交换机端口的广播隔离。



(1) 交换机VLAN的划分-验证实验

▶ 验证实验,使用 相同Vlan的计算 机进行Ping测试 和不同Vlan间的 计算机进行Ping 测试。分别用相 同Vlan的PC0和 PC1、不同Vlan 的PCO和PC2进 行Ping测试,结 果如图所示。

```
PC0
                         Programming
 Physical
          Confia
               Desktop
                                     Attributes
 Command Prompt
  Request timed out.
  Ping statistics for 192.168.0.21:
      Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
  C:\>ping 192.168.0.12
  Pinging 192.168.0.12 with 32 bytes of data:
  Reply from 192.168.0.12: bytes=32 time=2ms TTL=128
  Reply from 192.168.0.12: bytes=32 time=3ms TTL=128
  Reply from 192.168.0.12: bytes=32 time<1ms TTL=128
  Reply from 192.168.0.12: bytes=32 time<1ms TTL=128
  Ping statistics for 192.168.0.12:
      Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
  Approximate round trip times in milli-seconds:
      Minimum = 0ms, Maximum = 3ms, Average = 1ms
  C:\>ping 192.168.0.21
  Pinging 192.168.0.21 with 32 bytes of data:
  Request timed out.
  Request timed out.
  Request timed out.
  Request timed out.
  Ping statistics for 192.168.0.21:
```



可以 (1) 交换机 VLAN的划分-实验小结

- ▶ 在一个交换机中,划分了Vlan后,所有计算机设置了同 一个网段的地址,只有相同Vlan的计算机进行可以进行 相互通信,不同Vlan的计算机之间不能进行通信。
 - > 通过交换机进行Vlan的划分可以实现广播域的控制。