3 Sharding-JDBC读写分离

3.1 不使用Spring

引入Maven依赖

```
<dependency>
     <groupId>org.apache.shardingsphere</groupId>
     <artifactId>sharding-jdbc-core</artifactId>
           <version>${sharding-sphere.version}</version>
</dependency>
```

基于Java编码的规则配置

```
// 配置真实数据源
Map<String, DataSource> dataSourceMap = new HashMap<>();
// 配置主库
BasicDataSource masterDataSource = new BasicDataSource();
masterDataSource.setDriverClassName("com.mysql.jdbc.Driver");
masterDataSource.setUrl("jdbc:mysql://localhost:3306/ds_master");
masterDataSource.setUsername("root");
masterDataSource.setPassword("");
dataSourceMap.put("ds_master", masterDataSource);
// 配置第一个从库
BasicDataSource slaveDataSource1 = new BasicDataSource();
slaveDataSource1.setDriverClassName("com.mysql.jdbc.Driver");
slaveDataSource1.setUrl("jdbc:mysql://localhost:3306/ds_slave0");
slaveDataSource1.setUsername("root");
slaveDataSource1.setPassword("");
dataSourceMap.put("ds_slave0", slaveDataSource1);
// 配置第二个从库
BasicDataSource slaveDataSource2 = new BasicDataSource();
slaveDataSource2.setDriverClassName("com.mysql.jdbc.Driver");
slaveDataSource2.setUrl("jdbc:mysql://localhost:3306/ds_slave1");
```

```
slaveDataSource2.setUsername("root");
slaveDataSource2.setPassword("");
dataSourceMap.put("ds_slave1", slaveDataSource2);

// 配置读写分离规则

MasterSlaveRuleConfiguration masterSlaveRuleConfig = new

MasterSlaveRuleConfiguration("ds_master_slave", "ds_master",

Arrays.asList("ds_slave0", "ds_slave1"));

// 获取数据源对象

DataSource dataSource =

MasterSlaveDataSourceFactory.createDataSource(createDataSourceMap(),
masterSlaveRuleConfig, new HashMap<String, Object>(), new Properties());
```

基于Yaml的规则配置

或通过Yaml方式配置,与以上配置等价:

```
dataSources:
  ds_master: !!org.apache.commons.dbcp.BasicDataSource
    driverClassName: com.mysql.jdbc.Driver
    url: jdbc:mysql://localhost:3306/ds_master
    username: root
    password:
 ds_slave0: !!org.apache.commons.dbcp.BasicDataSource
    driverClassName: com.mysql.jdbc.Driver
    url: jdbc:mysql://localhost:3306/ds_slave0
    username: root
    password:
 ds_slave1: !!org.apache.commons.dbcp.BasicDataSource
    driverClassName: com.mysql.jdbc.Driver
    url: jdbc:mysql://localhost:3306/ds_slave1
    username: root
    password:
masterSlaveRule:
 name: ds_ms
 masterDataSourceName: ds_master
  slaveDataSourceNames: [ds_slave0, ds_slave1]
 props:
```

```
sql.show: true
configMap:
    key1: value1
    DataSource dataSource =
MasterSlaveDataSourceFactory.createDataSource(yamlFile);
```

使用原生JDBC

通过MasterSlaveDataSourceFactory工厂和规则配置对象获取MasterSlaveDataSource, MasterSlaveDataSource实现自JDBC的标准接口DataSource。然后可通过DataSource选择使用原生JDBC开发,或者使用JPA, MyBatis等ORM工具。以JDBC原生实现为例:

```
DataSource dataSource =
MasterSlaveDataSourceFactory.createDataSource(yamlFile);
String sql = "SELECT i.* FROM t_order o JOIN t_order_item i ON
o.order_id=i.order_id WHERE o.user_id=? AND o.order_id=?";
try (
        Connection conn = dataSource.getConnection();
        PreparedStatement preparedStatement = conn.prepareStatement(sql))
{
    preparedStatement.setInt(1, 10);
    preparedStatement.setInt(2, 1001);
    try (ResultSet rs = preparedStatement.executeQuery()) {
        while(rs.next()) {
            System.out.println(rs.getInt(1));
            System.out.println(rs.getInt(2));
        }
    }
}
```

3.2 使用Spring

引入Maven依赖

基于Spring boot的规则配置

```
sharding.jdbc.datasource.names=master,slave0,slave1
sharding.jdbc.datasource.master.type=org.apache.commons.dbcp.BasicDataSour
ce
sharding.jdbc.datasource.master.driver-class-name=com.mysql.jdbc.Driver
sharding.jdbc.datasource.master.url=jdbc:mysql://localhost:3306/master
sharding.jdbc.datasource.master.username=root
sharding.jdbc.datasource.master.password=
sharding.jdbc.datasource.slave0.type=org.apache.commons.dbcp.BasicDataSour
sharding.jdbc.datasource.slave0.driver-class-name=com.mysql.jdbc.Driver
sharding.jdbc.datasource.slave0.url=jdbc:mysql://localhost:3306/slave0
sharding.jdbc.datasource.slave0.username=root
sharding.jdbc.datasource.slave0.password=
sharding.jdbc.datasource.slave1.type=org.apache.commons.dbcp.BasicDataSour
ce
sharding.jdbc.datasource.slave1.driver-class-name=com.mysql.jdbc.Driver
sharding.jdbc.datasource.slave1.url=jdbc:mysql://localhost:3306/slave1
sharding.jdbc.datasource.slave1.username=root
sharding.jdbc.datasource.slave1.password=
sharding.jdbc.config.masterslave.name=ms
sharding.jdbc.config.masterslave.master-data-source-name=master
```

```
sharding.jdbc.config.masterslave.slave-data-source-names=slave0,slave1
sharding.jdbc.config.props.sql.show=true
```

基于Spring命名空间的规则配置

```
<?xml version="1.0" encoding="UTF-8"?>
<beans xmlns="http://www.springframework.org/schema/beans"</pre>
    xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
    xmlns:master-
slave="http://shardingsphere.io/schema/shardingsphere/masterslave"
    xsi:schemaLocation="http://www.springframework.org/schema/beans"
http://www.springframework.org/schema/beans/spring-beans.xsd
http://shardingsphere.io/schema/shardingsphere/masterslave
http://shardingsphere.io/schema/shardingsphere/masterslave/master-
slave.xsd
    <bean id="ds_master" class="org.apache.commons.dbcp.BasicDataSource"</pre>
destroy-method="close">
        cproperty name="driverClassName" value="com.mysql.jdbc.Driver" />
        cproperty name="url" value="jdbc:mysql://localhost:3306/ds_master"
/>
        roperty name="username" value="root" />
        cproperty name="password" value="" />
    </bean>
    <bean id="ds_slave0" class="org.apache.commons.dbcp.BasicDataSource"</pre>
destroy-method="close">
        cproperty name="driverClassName" value="com.mysql.jdbc.Driver" />
        cproperty name="url" value="jdbc:mysql://localhost:3306/ds_slave0"
/>
        roperty name="username" value="root" />
        cproperty name="password" value="" />
    </bean>
    <bean id="ds_slave1" class="org.apache.commons.dbcp.BasicDataSource"</pre>
destroy-method="close">
        roperty name="driverClassName" value="com.mysql.jdbc.Driver" />
        cproperty name="url" value="jdbc:mysql://localhost:3306/ds_slave1"
/>
```

在Spring中使用DataSource

直接通过注入的方式即可使用DataSource , 或者将DataSource配置在JPA、Hibernate或MyBatis中使用。

```
@Resource
private DataSource dataSource;
```

3.3 配置项说明

读写分离

```
masterSlaveRule:
    name: #读写分离数据源名称,自定义
    masterDataSourceName: #主库数据源名称,数据源处定义的数据源名
    slaveDataSourceNames: #从库数据源名称列表,数据源处定义的数据源名
    - <data_source_name1>
        - <data_source_name2>
        - <data_source_name_x>
    loadBalanceAlgorithmClassName: #从库负载均衡算法类名称。该类需实现
    MasterSlaveLoadBalanceAlgorithm接口且提供无参数构造器
    loadBalanceAlgorithmType: #从库负载均衡算法类型,可选值:ROUND_ROBIN,RANDOM。若`loadBalanceAlgorithmClassName`存在则忽略该配置
```

props: #属性配置

sql.show: #是否开启SQL显示,默认值: false

executor.size: #工作线程数量,默认值: CPU核数

check.table.metadata.enabled: #是否在启动时检查分表元数据一致性,默认值: false

configMap: #用户自定义配置

key1: value1
key2: value2
keyx: valuex