# **PanWorld-Net GateWay Guide** Genenral Manual(v1.0) Dept. PanWorld-Net Lab 2009-03-04

### 1. What is the PWN GateWay

### 1. Introduction


- 1> PWN\_GateWay is a Client Side communication module provided by PanWorld-Net
- 2> PWN\_GateWay is TCP/IP based API to communicate with encrypted data between Client and Server
- 3> Merchant System <-- TCP/IP (Plain Text) --> PWN\_GateWay <-- TCP/IP (Encrypted Text) --> PWN\_PAYMENT

## 2. System Installation Requirments

- 1> PWN\_GateWay which is consisted of pureJAVA is able to install and operate with all the platforms using JVM, and also developed for various end-user interface (Unix, Linux, Windows)
- 2> PWN\_GateWay provides executive files (batch file, shell file) in Unix, Linux, and Windows system.
- 3> PWN\_GateWay operates under Java 1.5 system. For the stable user interface, it has to be upgraded to JVM version 1.5
- 4> For a compatability of client side developer, PWN\_GateWay provides daily or increment log as a file type.

# 2. System Configuration and Installation Guide

### 1. Network Flow



### 2. PWN\_GATEWAY Configuration

PWN\_GATEWAY

|- lib : library Directory

|- bin : Executable File (shell, batch file)

|- doc : Manual

|- logs : Log File Directory

| - conf : Configuration File Directory

### 3. JDK, JRE Installation Guide

- 1> J2SDK,JRE Download URL : <a href="http://java.sun.com">http://java.sun.com">http://java.sun.com</a> >> Downloads >> Java SE >> Previous Releases >> J2SE 5.0 Downloads >> JDK 5.0 Update 17 >>select Platform & Language
- 2> Parameter configuration
  - \* Windows

My computer properties >> Advanced (Tab) >> Environment Variable >> System Variable >> Add Path : ;C:\Program Files\Java\jdk1.5.0\_17\big|bin

\* Unix & Linux : vi /etc/profile

JAVA\_HOME=/usr/java/jdk1.5.0\_17

export JAVA\_HOME

PATH=\$PATH:\$JAVA\_HOME/bin

CLASSPATH=\$CLASSPATH:\$JAVA\_HOME/lib

3> Confirm Java installation interface

cmd >> java -version >> Enter

cmd >> java version "1.5.0\_17"

\* If it installed correctly, you can find version information.

### 4. PWN\_GateWay Installation Guide

- 1> Unzip "PWN\_GATEWAY.zip" in a preferred directory folder
- 2> Windows System

- \* Execute "PWN\_GATEWAY/bin/install.bat" with "NTService"
- \* It will drive correctly, when "PWN\_GATEWAY/bin/start.bat" is executed
- 3> Unix & Linux
  - \* move PWN GATEWAY/bin >> dos2unix \*.sh
  - \* PWN\_GATEWAY/bin/start.sh >> You can see PWN\_GATEWAY Started. ^^
- 4> Definition of each file of "bin"

\* start.sh,start.bat : Program Start

\* stop.sh,stop.bat : Program End

\* restart.sh,restart.bat : Program Restart

\* install.bat,uninstall.bat : Program Install and uninstall in NT platform

### 5. Definition of "service.xml" configuration file

- 1> PATH: PWN\_GATEWAY/conf/service.xml
- 2> It includes network configuration information between PWN\_GATEWAY and PW\_PAYMENT
- 3> PWN\_GATEWAY must be re-executed for normal system process when "Service.xml" was customized
- 4> Element Name of XML is unable to change. When it is changed, a module will not be executed

	Element Name	VALUE
1	serverPort	Default "20000"
		Port information for PWN_GATEWAY
		Able to change regarding to MERCHANT configuration
2	serverTimeout	TIMEOUT between PWN_GATEWAY and MERCHANT SYSTEM
	servernmeout	It consists of Millisecond
3	pwnServerIp	IP address of PW_PAYMENT Server
4	pwnServerPort	Port information of PW_PAYMENT server.
5	pwnTimeout	Timeout information of PW_PAYMENT server

### 6. Definition of "NTWrapper.conf", and "log4j.properties"

1> "NTWrapper.conf" and "log4j.properties" is optimized for PWN\_GATEWAY module \*Please do not change above configuration on the franchise.

### 3. Communication Packet Definition

### 1. Consist of Specification

- 1> Specification is consisted of HEADER Part and DATA Part
- 2> Method to specification construction

ENGTH HEADER Part	DATA Part
-------------------	-----------

3> Transmission Method

TCP/IP is formed of 1 HandShake, but Connection maintenance method is not supported.

- \* Steps to Transmission
- a> Construction and Socket Connect
- b> Send
- c> Receive
- d> Socket Close
- 4> PWN\_GATEWAY

For a normal data transmission, Company's encrypted communication with PW\_PAYMENT server is required.

### 2. Character Construction Formation

- 1> CHAR : C(20) : Character stands for "C", and "20" means length of 20 characters Not enough space for character length, you can put trailing Space (Filler) on the right of CHAR
  - Ex) C(20): [ABCDEFGHIJ
- 2> NUMBER: N(10): Numbers are described as "N", and "10" means 10 digits Not enough space for Number, you can put "0" at left prior to number Ex) N(10): [0001234567]

### 3. Symbols for Sending & Receiving Transmission

- 1> © : Essential Sending/Receiving Transmission Zone
- 2> Option Zone

# 4. Transmission Specification

# 1> Header Part

	NAME	DESC	TYPE	Sending	Receiving
1	SPEC_LENGTH	Total Length	N(4)	0	0
2	SPEC_TYPE	"CFIX": Fixed specification	C(4)	0	0
3	TRN_TYPE	"T001": Credit Card Payment "T002": Inquiry payment result "T003": Cancel payment	C(4)	©	0
4	MERCHANT_ID	ID for Each Merchant	C(20)	0	0
5	MALL_ID	ID for Low Level Merchant Mall	C(20)	0	0
6	SERVICE_TYPE	Connection Route Information for Merchant's Payment Ex) TERMINAL,MOBILE,WEB	C(8)	0	0
7	IP_ADDRESS	Customer's IP Information		0	0
8	TRN_DATE	Transaction Date ( YYYYMMDDHHMMSS )		0	0
9	TRN_RES_DATE	Transaction Response Date (YYYYMMDDHHMMSS)			0
10	PAY_NO	Merchant Order Number	C(50)	0	0
11	TRANSACTION_ID	Transaction Number (Accept Order / Cancel Order)	C(12)		0
12	RESULT_CD	Respond Code regarding Payment Request "0" : Transaction Completed "1" : Transaction Failed "2" : System Error	C(1)		0
13	RESULT_MSG	Respond Code regarding Payment	C(4)		0
14	EXTRA	Extra Space	C(25)	0	0
			C(200)		

### 2> Credit Card Approval (T001)

	NAME	DESC	TYPE	Symbol	Sending/Receiving
1	CARD_NUMBER	Credit Card Number	C(20)	0	0
2	CARD_EXPIRE	Credit Card Expiration Date (YYMM)	C(4)	0	0
3	CARD_CVV	Credit Card CVV number	C(3)	0	0
4	CARD_PASSWORD	Pin number	C(4)	0	0
5	CARD_EXTRA	Extra Parameter except for Credit Card.	C(10)	0	0
6	PAY_USERID	Merchant Membership ID (en-English)	C(50)	0	0
7	PAY_NAME	Name of Merchant Membership (en quad- English)	C(50)	0	0
8	PAY_TELNO	Member Telephone Number	C(20)	0	0
9	PAY_EMAIL	Member Email Address	C(100)	0	0
10	PRODUCT_TYPE	Type of Product ("0" :Goods "1":Contents)	C(2)	0	0
11	PRODUCT_NAME	Name of Product	C50)	0	0
12	AMOUNT	Amount of USD Ex) \$39.09 $\rightarrow$ "0000003909" Form of Amount x 100	N(10)	0	0
13	CUR_TYPE	Currency Type - "USD"	C(3)	0	0
14	APPROVAL_NO	Approval Number	C(8)		0
15	EXTRA	Merchant URL	C(66)	0	0
			C(400)		

<sup>\*</sup> SPACE is declared as "\_" for readability -REQ =[0596CFIXT001PANWORLD\_\_\_\_\_20010001\_\_\_\_\_WEB\_\_\_192.168.10.1\_\_\_\_20081224203347\_\_\_ \_\_\_\_\_PANWORLD\_20081224203347171\_\_\_\_\_\_\_4444 \_\_\_\_PAYUSERNAME\_\_\_\_ 555566667777\_\_\_1009\_\_\_\_\_\_PAYUSERID\_\_\_ \_\_\_\_\_PAYTELNUMBER\_\_\_\_\_PAYUSEREMAIL\_\_\_\_ \_\_\_\_\_1\_PRODUCTNAME\_\_\_\_\_\_\_0000050000JP -RES [0596CFIXT001PANWORLD\_\_\_\_\_20010001\_\_\_\_\_WEB\_\_\_192.168.10.1\_\_\_\_200812242033472008 1224203350PANWORLD\_20081224203347171\_\_\_\_\_\_08122400000300000\_\_\_ \_\_4444555566667777\_\_\_1009\_\_\_\_\_\_\_PAYUSERID\_\_\_\_\_\_\_\_\_PAYUSERNAME \_\_\_\_\_PAYTELNUMBER\_\_\_\_\_PAYUSEREMAIL\_\_\_\_ \_\_\_\_\_1\_PRODUCTNAME\_\_\_\_\_ 000005 0000JPY00203350\_\_\_\_\_

### 3> Credit Card Cancelation (T002)

	NAME	DESC	TYPE	Symbol	Sending/Receiving
1	VOID_TYPE	<ul><li>"1" : Transaction Number</li><li>"2" : Merchant Order Number</li></ul>	C(1)	0	0
2	APPROVAL_DAY	Date to Approve (YYYYMMDD)	C(8)	0	0
3	RAPPROVAL_NO	Initial Transaction Approval Number	C(8)	0	0
4	RPAY_NO	Initial Transaction Order Number	C(50)	0	0
5	RTRANSACTION_ID	Initial KTT Transaction Number	C(12)	0	0
6	CARD_NUMBER	Credit Card Number	C20)	0	0
7	CARD_EXPIRE	Credit Card Expiration Date	C(4)	0	0
8	AMOUNT	Amount of USD Ex) \$39.09 $\rightarrow$ "0000003909" Form of Amount x 100	N(10)	0	0
9	CUR_TYPE	Currency Type - "USD"	C(3)	0	0
10	APPRVAL_NO	Approval Number	C(8)	0	0
11	EXTRA	Extra Space	C(76)	0	0
			C(200)		

<sup>\*</sup> SPACE is declared as "\_" for readability

REQ=[0396CFIXT002PANWORLD20010001_	WEB	192.168.10.1	2008122420335
9PANWORLD_20081224203359140			
120081224			000000000
0		]	
-			
RES=[0396CFIXT002PANWORLD20010001	WEB	192.168.10.1	20081224203359
20081224203401PANWORLD_20081224203359140		0812240000040	0000
12008122400203401PANWORLD_200812242033	59140	0812	24000005
0000000000			]

<sup>\*</sup> In case of "VOID\_TYPE = 1", it needs to transmit "RTRANSACTION\_ID" only. For cancellation of a day after transaction, it transmits automatically to Card Company as a purchasing withdrawal level.

<sup>\*</sup> In case of "VOID\_TYPE = 2", it is essential to transmit all filed values. After it is referred by PanWord-net system, it will be withdrawn. It is highly recommended to customers to bring "TRANSACTION\_ID" using T003(조회) and transmit withdrawal data using "VOID\_TYPE =1" when communication error

# 4> Credit Card Transaction Reference (T003)

	NAME	DESC	TYPE	Symbol	Sending/Receiving
1	RPAY_NO	Initial Order Number	C(50)	0	0
2	TRN_TYPE	Transcation Type - T001	C(4)	0	0
3	RESULT_CD	Result of Type	C(1)		0
4	RESULT_MSG	Amount of Approval	C(4)		0
5	TRANSACTION_ID	Transaction Number	C(12)		0
6	APPROVAL_NO	Approval Number	C(8)		0
7	EXTRA	Extra Space	C(121)		
	_		C(200)		

<sup>\*</sup> SPACE is declared as "\_" for readability

-				
REQ=[0396CFIXT003PANWORLD	20010001	WEB	192.168.10.1	2008122420341
1PANWORLD_200812242	03411312			
PANWORLD_20081224203411312		000000	0000000	
				_]
-				
RES=[0396CFIXT003PANWORLD	20010001	WEB	192.168.10.1	20081224203411
20081224203414PANWORLD_2008122	0812240000600000			
PANWORLD_20081224203411312		T00100	0000812240000070	00203414
				1