

Developers



V

FlexQueue Methods



Apex Reference Guide / System Namespace / FlexQueue Class

FlexQueue Class

Contains methods that reorder batch jobs in the Apex flex queue.

Namespace

System

Usage

You can place up to 100 batch jobs in a holding status for future execution. When system resources become available, the jobs are taken from the top of the Apex flex queue and moved to the batch job queue. Up to five queued or active jobs can be processed simultaneously for each org. When a job is moved out of the flex queue for processing, its status changes from Holding to Queued. Queued jobs are executed when the system is ready to process new jobs.

Use this class's methods to reorder your Holding jobs in the flex queue. As best practice and for safe usage, a FlexQueue reorder method must be the final statement in a transaction.

Example

This example moves a job to the front of the flex queue so that it's executed immediately. The job is moved by calling the System.FlexQueue.moveJobToFront() method with the high priority job ID as the parameter.

ID highPriorityJobId = Database.executeBatch(new HighPriorityBatchClass(), 200);
boolean jobMovedToFrontOfQueue = FlexQueue.moveJobToFront(highPriorityJobId);

• FlexQueue Methods

See Also

- Monitoring the Apex Flex Queue
- Apex Developer Guide: Using Batch Apex

FlexQueue Methods

The following are methods for FlexQueue.

• moveAfterJob(jobToMoveId, jobInQueueId)

Moves the job with the ID *jobToMoveId* immediately after the job with the ID *jobInQueueId* in the flex queue. You can move *jobToMoveId* forward or backward in the queue. If either job isn't in the queue, it throws an element-not-found exception. Returns true if the job is moved, or false if *jobToMoveId* is already immediately after *jobInQueueId*, so no change is made.

moveBeforeJob(jobToMoveId, jobInQueueId)
 Moves the job with the ID jobToMoveId immediately before the job with the ID jobInQueueId in the flex queue. You can move jobToMoveId forward or backward in the



~

invoves the specified job the end of the flex queue, to index position (size - 1). All jobs after the job's starting position move one spot forward. If the job isn't in the queue, it throws an element-not-found exception. Returns true if the job is moved, or false if the job is already at the end of the queue, so no change is made.

moveJobToFront(jobId)

Moves the specified job to the front of the flex queue, to index position \emptyset . All other jobs move back one spot. If the job isn't in the queue, it throws an element-not-found exception. Returns true if the job is moved, or false if the job is already at the front of the queue, so no change is made.

moveAfterJob(jobToMoveld, jobInQueueld)

Moves the job with the ID *jobToMoveId* immediately after the job with the ID *jobInQueueId* in the flex queue. You can move *jobToMoveId* forward or backward in the queue. If either job isn't in the queue, it throws an element-not-found exception. Returns true if the job is moved, or false if *jobToMoveId* is already immediately after *jobInQueueId*, so no change is made.

Signature

public static Boolean moveAfterJob(Id jobToMoveId, Id jobInQueueId)

Parameters

jobToMoveld

Type: Id

The ID of the job to move.

joblnQueueld

Type: Id

The ID of the job to move after.

Return Value

Type: Boolean

moveBeforeJob(jobToMoveld, jobInQueueld)

Moves the job with the ID *jobToMoveId* immediately before the job with the ID *jobInQueueId* in the flex queue. You can move *jobToMoveId* forward or backward in the queue. If either job isn't in the queue, it throws an element-not-found exception. Returns true if the job is moved, or false if *jobToMoveId* is already immediately before *jobInQueueId*, so no change is made.

Signature

public static Boolean moveBeforeJob(Id jobToMoveId, Id jobInQueueId)

Parameters

jobToMoveld

Type: Id

The ID of the job to move.

joblnQueueld

Type: Id

The ID of the job to use as a reference point.

Return Value



V

wioves the specified job the end of the flex queue, to index position (size - 1). All jobs after the job's starting position move one spot forward. If the job isn't in the queue, it throws an element-not-found exception. Returns true if the job is moved, or false if the job is already at the end of the queue, so no change is made.

Signature

public static Boolean moveJobToEnd(Id jobId)

Parameters

jobld

Type: Id

The ID of the job to move.

Return Value

Type: Boolean

moveJobToFront(jobId)

Moves the specified job to the front of the flex queue, to index position 0. All other jobs move back one spot. If the job isn't in the queue, it throws an element-not-found exception. Returns true if the job is moved, or false if the job is already at the front of the queue, so no change is made.

Signature

public static Boolean moveJobToFront(Id jobId)

Parameters

jobld

Type: Id

The ID of the job to move.

Return Value

Type: Boolean

DID THIS ARTICLE SOLVE YOUR ISSUE?

Let us know so we can improve!

Share your feedback







DEVELOPER CENTERS

Heroku MuleSoft

Tableau

Commerce Cloud

POPULAR RESOURCES

Documentation
Component Library

APIs

Trailhead

COMMUNITY

Trailblazer Community
Events and Calendar
Partner Community

Blog





© Copyright 2025 Salesforce, Inc. All rights reserved. Various trademarks held by their respective owners. Salesforce, Inc. Salesforce Tower, 415 Mission Street, 3rd Floor, San Francisco, CA 94105, United States

<u>Privacy Information</u> <u>Terms of Service</u> <u>Legal</u> <u>Use of Cookies</u> <u>Trust</u> <u>Cookie Preferences</u>

Your Privacy Choices Responsible Disclosure Contact