



HttpResponse Class





Developers



Apex Reference Guide / System Namespace / HttpResponse Class

HttpResponse Class

Use the HttpResponse class to handle the HTTP response returned by the Http class.

Namespace

System

Usage

Use the XML classes or JSON Classes to parse XML or JSON content in the body of a response accessed by HttpResponse.

Example

In the following getXmlStreamReader example, content is retrieved via an HTTP callout, then the XML is parsed using the XmlStreamReader class.

```
public class ReaderFromCalloutSample {
   public void getAndParse() {
       // Get the XML document from the endpoint
       Http http = new Http();
       HttpRequest req = new HttpRequest();
       req.setEndpoint(URL.getOrgDomainUrl().toExternalForm() + '/services/data');
       req.setMethod('GET');
       req.setHeader('Accept', 'application/xml');
       HttpResponse res = http.send(req);
       // Log the XML content
       System.debug(res.getBody());
        // Generate the HTTP response as an XML stream
       XmlStreamReader reader = res.getXmlStreamReader();
        // Read through the XML
       while(reader.hasNext()) {
            System.debug('Event Type:' + reader.getEventType());
            if (reader.getEventType() == XmlTag.START_ELEMENT) {
            System.debug(reader.getLocalName());
        reader.next();
```

See Also

- Apex Developer Guide: JSON Support
- Apex Developer Guide: XML Support



Retrieves the body returned in the response.

getBodyAsBlob()

Retrieves the body returned in the response as a Blob.

• getBodyDocument()

Retrieves the body returned in the response as a DOM document.

• getHeader(key)

Retrieves the contents of the response header.

getHeaderKeys()

Retrieves an array of header keys returned in the response.

getStatus()

Retrieves the status message returned for the response.

getStatusCode()

Retrieves the value of the status code returned in the response.

• getXmlStreamReader()

Returns an XmlStreamReader that parses the body of the callout response.

setBody(body)

Specifies the body returned in the response.

setBodyAsBlob(body)

Specifies the body returned in the response using a Blob.

• setHeader(key, value)

Specifies the contents of the response header.

setStatus(status)

Specifies the status message returned in the response.

setStatusCode(statusCode)

Specifies the value of the status code returned in the response.

toString()

Returns the status message and status code returned in the response, for example:

getBody()

Retrieves the body returned in the response.

Signature

public String getBody()

Return Value

Type: String

Usage

Limit 6 MB for synchronous Apex or 12 MB for asynchronous Apex. The HTTP request and response sizes count towards the total heap size.

getBodyAsBlob()

Retrieves the body returned in the response as a Blob.

Signature

public Blob getBodyAsBlob()

Return Value

Type: Blob



getBodyDocument()

Retrieves the body returned in the response as a DOM document.

Signature

public Dom.Document getBodyDocument()

Return Value

Type: Dom.Document

Example

Use it as a shortcut for:

```
String xml = httpResponse.getBody();
Dom.Document domDoc = new Dom.Document(xml);
```

getHeader(key)

Retrieves the contents of the response header.

Signature

public String getHeader(String key)

Parameters

key

Type: String

Return Value

Type: String

getHeaderKeys()

Retrieves an array of header keys returned in the response.

Signature

public String[] getHeaderKeys()

Return Value

Type: String[]

getStatus()

Retrieves the status message returned for the response.

Signature

public String getStatus()

Return Value

Type: String



>

```
public Integer getStatusCode()
```

Return Value

Type: Integer

getXmlStreamReader()

Returns an XmlStreamReader that parses the body of the callout response.

Signature

public XmlStreamReader getXmlStreamReader()

Return Value

Type: System.XmlStreamReader

Usage

Use it as a shortcut for:

```
String xml = httpResponse.getBody();

XmlStreamReader xsr = new XmlStreamReader(xml);
```

setBody(body)

Specifies the body returned in the response.

Signature

public Void setBody(String body)

Parameters

body

Type: String

Return Value

Type: Void

setBodyAsBlob(body)

Specifies the body returned in the response using a Blob.

Signature

public Void setBodyAsBlob(Blob body)

Parameters

body

Type: Blob

Return Value

Type: Void



~

public Void setHeader(String key, String value)

Parameters

key

Type: String

value

Type: String

Return Value

Type: Void

setStatus(status)

Specifies the status message returned in the response.

Signature

public Void setStatus(String status)

Parameters

status

Type: String

Return Value

Type: Void

setStatusCode(statusCode)

Specifies the value of the status code returned in the response.

Signature

public Void setStatusCode(Integer statusCode)

Parameters

statusCode

Type: Integer

Return Value

Type: Void

toString()

Returns the status message and status code returned in the response, for example:

Signature

public String toString()

Return Value

Type: String

Example



DID THIS ARTICLE SOLVE YOUR ISSUE?

Let us know so we can improve!

Share your feedback











Heroku MuleSoft Tableau

Commerce Cloud Lightning Design System Einstein

Quip

POPULAR RESOURCES

Documentation Component Library APIs

Trailhead Sample Apps **Podcasts** AppExchange COMMUNITY

Trailblazer Community Events and Calendar Partner Community Blog

Salesforce Admins Salesforce Architects

© Copyright 2025 Salesforce, Inc. All rights reserved. Various trademarks held by their respective owners. Salesforce, Inc. Salesforce Tower, 415 Mission Street, 3rd Floor, San Francisco, CA 94105, United States

<u>Trust</u> <u>Cookie Preferences</u> <u>Privacy Information</u> <u>Terms of Service</u> <u>Legal</u> <u>Use of Cookies</u>



Your Privacy Choices Responsible Disclosure

Contact