



~





Apex Reference Guide / ApexPages Namespace / Message Class

Message Class

Contains validation errors that occur when the user saves the page that uses a standard controller.

Namespace

ApexPages

Usage

When using a standard controller, all validation errors, both custom and standard, that occur when the user saves the page are automatically added to the page error collections. If an <code>inputField</code> component is bound to the field with an error, the message is added to the component's error collection. All messages are added to the page's error collection. For more information, see Validation Rules and Standard Controllers in the Visualforce Developer's Guide.


If your application uses a custom controller or extension, you must use the message class for collecting errors.

Instantiation

In a custom controller or controller extension, you can instantiate a Message in one of these ways:



where ApexPages. severity is the enum that determines how severe a message is, and summary is the String used to summarize the message. For example:





where ApexPages. severity is the enum that determines how severe a message is, summary is the String used to summarize the message, and detail is the String used to provide more detailed information about the error.

ApexPages.Severity Enum

To specify the severity of the message, use the ApexPages.Severity enum values. The following are the valid values:

- CONFIRM
- ERROR
- FATAL



- iviessage constructors
- Message Methods

Message Constructors

The following are constructors for Message.

- Message(severity, summary)
 - Creates a new instance of the ApexPages.Message class using the specified message severity and summary.
- Message(severity, summary, detail)
 - Creates a new instance of the ApexPages.Message class using the specified message severity, summary, and message detail.
- Message(severity, summary, detail, id)
 Creates a new instance of the ApexPages.Message class using the specified severity, summary, detail, and component ID.

Message(severity, summary)

Creates a new instance of the ApexPages.Message class using the specified message severity and summary.

Signature

public Message(ApexPages.Severity severity, String summary)

Parameters

severity

Type: ApexPages.Severity

The severity of a Visualforce message.

summary

Type: String

The summary Visualforce message.

Message(severity, summary, detail)

Creates a new instance of the ApexPages.Message class using the specified message severity, summary, and message detail.

Signature

public Message(ApexPages.Severity severity, String summary, String detail)

Parameters

severity

Type: ApexPages.Severity

The severity of a Visualforce message.

summary

Type: String

The summary Visualforce message.

detail



ivicəsayetəeveiliy, sairiiriaiy, aeiaii, ia/

Creates a new instance of the ApexPages.Message class using the specified severity, summary, detail, and component ID.

Signature

public Message(ApexPages.Severity severity, String summary, String detail, String id)

Parameters

severity

Type: ApexPages.Severity

The severity of a Visualforce message.

summary

Type: String

The summary Visualforce message.

detail

Type: String

The detailed Visualforce message.

id

Type: String

The ID of the Visualforce component to associate with the message, for example, a form field with an error.

Message Methods

The following are methods for ${\tt Message}\,.$ All are instance methods.

• getComponentLabel()

Returns the label of the associated inputField component. If no label is defined, this method returns null.

getDetail()

Returns the value of the detail parameter used to create the message. If no detail String was specified, this method returns null.

getSeverity()

Returns the severity enum used to create the message.

getSummary()

Returns the summary String used to create the message.

getComponentLabel()

Returns the label of the associated inputField component. If no label is defined, this method returns null.

Signature

public String getComponentLabel()

Return Value

Type: String





Signature

public String getDetail()

Return Value

Type: String

getSeverity()

Returns the severity enum used to create the message.

Signature

public ApexPages.Severity getSeverity()

Return Value

Type: ApexPages.Severity

getSummary()

Returns the summary String used to create the message.

Signature

public String getSummary()

Return Value

Type: String

DID THIS ARTICLE SOLVE YOUR ISSUE?

Let us know so we can improve!

Share your feedback













Heroku MuleSoft

Tableau

Commerce Cloud

Lightning Design System

Einstein

Quip

POPULAR RESOURCES

Documentation Component Library

APIs

Trailhead

Sample Apps

Podcasts

AppExchange

COMMUNITY

Trailblazer Community

Events and Calendar

Partner Community

Blog

Salesforce Admins Salesforce Architects

© Copyright 2025 Salesforce, Inc. All rights reserved. Various trademarks held by their respective owners. Salesforce, Inc. Salesforce Tower, 415 Mission Street, 3rd Floor, San Francisco, CA 94105, United States



/