


Developers







Apex Reference Guide / Auth Namespace / AuthProviderPlugin Interface

AuthProviderPlugin Interface

This interface is deprecated. For new development, use the abstract class Auth.AuthProviderPluginClass to create a custom OAuth-based authentication provider plug-in for single sign-on in to Salesforce.

Namespace

Auth

Usage

Deprecated. Existing implementations that use Auth.AuthProviderPlugin still work. For new development, use Auth.AuthProviderPluginClass.

- AuthProviderPlugin Methods
- · AuthProviderPlugin Example Implementation

AuthProviderPlugin Methods

The following methods are for AuthProviderPlugin, which, as of API version 39.0, is deprecated. Use themethods in AuthProviderPluginClass instead.

getCustomMetadataType()

Deprecated as of API version 39.0. Use the corresponding method in ${\tt Auth.AuthProviderPluginClass}\,.$

• getUserInfo(authProviderConfiguration, response)

Deprecated as of API version 39.0. Use the corresponding method in Auth-AuthProviderPluginClass.

• handleCallback(authProviderConfiguration, callbackState)

Deprecated as of API version 39.0. Use the corresponding method in Auth-AuthProviderPluginClass.

• initiate(authProviderConfiguration, stateToPropagate)

Deprecated as of API version 39.0. Use the corresponding method in Auth-Auth-Provider-PluginClass.

See Also

• Salesforce Help: Create a Custom External Authentication Provider

getCustomMetadataType()

Deprecated as of API version 39.0. Use the corresponding method in Auth.AuthProviderPluginClass.

Signature

public String getCustomMetadataType()

Return Value





Returns the custom metadata type API name for a custom OAuth-based authentication provider for single sign-on to Salesforce. The <code>getCustomMetatadaType()</code> method returns only custom metadata type names. It does not return custom metadata record names.

getUserInfo(authProviderConfiguration, response)

Deprecated as of API version 39.0. Use the corresponding method in Auth.AuthProviderPluginClass.

Signature

public Auth.UserData getUserInfo(Map<String,String> authProviderConfiguration, Auth.AuthProviderTokenResponse response)

Parameters

authProviderConfiguration

Type: Map<String,String>

The configuration for the custom authentication provider. When you create a custom metadata type in Salesforce, the configuration populates with the custom metadata type default values. Or you can set the configuration with values you enter when you create the custom provider in Auth. Providers in Setup.

response

Type: Auth.AuthProviderTokenResponse

The OAuth access token, OAuth secret or refresh token, and state provided by the authentication provider to authenticate the current user.

Return Value

Type: Auth.UserData

Creates a new instance of the Auth. UserData class.

Usage

Returns information from the custom authentication provider about the current user. The registration handler and other authentication provider flows use this information.

handleCallback(authProviderConfiguration, callbackState)

Deprecated as of API version 39.0. Use the corresponding method in Auth-Auth-Provider-PluginClass.

Signature

public Auth.AuthProviderTokenResponse handleCallback(Map<String,String> authProviderConfiguration, Auth.AuthProviderCallbackState callbackState)

Parameters

authProviderConfiguration

Type: Map<StringString>

The configuration for the custom authentication provider. When you create a custom metadata type in Salesforce, the configuration populates with the custom metadata type default values. Or you can set the configuration with values you enter when you create the custom provider in Auth. Providers in Setup.

callbackState





Type: Auth.AuthProviderTokenResponse

Creates an instance of the AuthProviderTokenResponse class.

Usage

Uses the authentication provider's supported authentication protocol to return an OAuth access token, OAuth secret or refresh token, and the state passed in when the request for the current user was initiated.

initiate(authProviderConfiguration, stateToPropagate)

Deprecated as of API version 39.0. Use the corresponding method in Auth.AuthProviderPluginClass.

Signature

public System.PageReference initiate(Map<String,String> authProviderConfiguration, String stateToPropagate)

Parameters

authProviderConfiguration

Type: Map<StringString>

The configuration for the custom authentication provider. When you create a custom metadata type in Salesforce, the configuration populates with the custom metadata type default values. Or you can set the configuration with values you enter when you create the custom provider in Auth. Providers in Setup.

stateToPropagate

Type: String

The state passed in to initiate the authentication request for the user.

Return Value

Type: System.PageReference

The URL of the page where the user is redirected for authentication.

Usage

Returns the URL where the user is redirected for authentication.

AuthProviderPlugin Example Implementation

We've removed the example implementation for the Auth.AuthProviderPlugin interface because we've deprecated the interface and replaced it with an abstract class. See AuthProviderPluginClass Class.

DID THIS ARTICLE SOLVE YOUR ISSUE?

Let us know so we can improve!

Share your feedback







MuleSoft Tableau Commerce Cloud Lightning Design System Einstein

APIs Trailhead Sample Apps Podcasts Quip AppExchange

Component Library

Events and Calendar Partner Community Blog Salesforce Admins Salesforce Architects

© Copyright 2025 Salesforce, Inc. All rights reserved. Various trademarks held by their respective owners. Salesforce, Inc. Salesforce Tower, 415 Mission Street, 3rd Floor, San Francisco, CA 94105, United States

Privacy Information Terms of Service Legal Use of Cookies <u>Trust</u> <u>Cookie Preferences</u>

Your Privacy Choices Responsible Disclosure Contact