

SETUP WIZARD

ONBOARDING GUIDELINES

CONTENTS

3 INTRODUCTION

4

DESIGN

Color palette
End-to-end flow
Welcome screen

8 SPEC

Headers

Illustration & imagery

Typography

Navigation

Inputs

Modal dialogs

Dark theme

Progress & indication

Transitions


INTRODUCTION


WELCOME TO THE SETUP WIZARD DESIGN GUIDE

This guide will help you create a simple setup flow. There are two separate tools, which can be used individually or together.

- 1. Wizard Library helps you implement individual screens. If you use the Wizard Library, you'll get most of the design seen in this guide automatically.
- **2. Wizard Manager** helps you construct a complete setup experience from a sequence of screens.

Don't want to use the Wizard Library? This design guide can still show you how to provide a harmonious setup experience as the user moves between carrier, OEM, and Google screens.





DESIGN

Color palette
End-to-end flow
Welcome screen

COLOR PALETTE

Choose colors that work well with the Setup Wizard screens required by Google. Don't use colors that are close to the Google Blue.


Primary color

The background color you choose for your header will be the primary color of your section of Setup Wizard. Use a neutral background color to ensure visual harmony throughout setup.*

Secondary color

Use one secondary color for interactive elements in the content area, like text links or raised buttons.

Colors to avoid



Don't use any shades or tints of Indigo, Blue, Light Blue, or Cyan. This will help avoid confusion with the Google Blue used in the required Setup Wizard screens.

^{*} Please refer to the Color section in the Material Design guidelines

END-TO-END FLOW

Full screen layouts

After the Welcome screen, stick to small header layouts.

Adding screens

As illustrated by the dark gray screens in this flow, additional screens can be added in a few specific places throughout Setup Wizard. Moving users between screens that are branded differently can be jarring, so don't add screens anywhere else in the Setup Wizard flow.

Note:

Google Account setup MUST be the first account setup to be presented to users after network connection.

If a user doesn't connect to a Wi-Fi or cellular network, they'll go through offline setup. Restore, Google Account and some other features will not be shown.

- Required
- Can't be removed or customized
- Customizable
- Required but can be customized
- Optional
 Can be removed, but don't customize
- Customizable & optional
 Can be customized or removed entirely




WELCOME SCREEN

Brand customization

Creating an illustration on the Welcome screen is an eye-catching way to express your brand.

The default elements are centered aligned or at 50% of the screen width.

Center line



50%

SPEC

Headers

Illustration & imagery

Typography

Navigation

Inputs

Modal dialogs

Dark theme

Progress & indication

Transitions

HEADER


PHONE

Status bar

Use the status bar header on every page, as an anchoring element.

Title icon

Each page will also have a title icon. This icon should relate to the content on screen.




HEADER

TABLET

Portrait

Tablet layouts should be used for screens wider than 600dp.




11

HEADER

TABLET


Landscape

Tablet layouts should be used for screens wider than 600dp.



SPECS

PHONE




SPECS

TABLET CARD SPACING

Internal spacing for tablet in portrait orientation.

Card is centered within overall dimensions.




14

SPECS

TABLET, PORTRAIT

External spacing for tablet in portrait orientation.

Card is centered within overall dimensions.




SPECS

TABLET, LANDSCAPE


External spacing for tablet in landscape orientation.

Card is centered within overall dimensions.




ILLUSTRATIONS & IMAGERY

Keep illustrations and other imagery below the section title. This will help keep the hierarchy structure consistent throughout Setup Wizard.




PHONE, LIST ITEMS

Use these standard type styles to keep consistent hierarchy throughout Setup Wizard.



PHONE, BUTTONS

Use these standard type styles to keep consistent hierarchy throughout Setup Wizard.




TABLET, LIST ITEMS

Use these standard type styles to keep consistent hierarchy throughout Setup Wizard.

Body copy
Roboto Regular
14/20sp
(for 360x640 and below)

16/24sp (for 412x732 and above)

#000000,87%



TABLET, BUTTONS

Use these standard type styles to keep consistent hierarchy throughout Setup Wizard.

Body copy

14/20sp

16/24sp

#000000,87%

Roboto Regular

(for 360x640 and below)


(for 412x732 and above)

\$946 Headline Roboto Regular 34 sp, Accent color Link text Headline Roboto Regular Accent color Lorem ipsum dolor sit amet, consectetur adipiscing elit. Etiam nec euismod dui. Sed fringilla urna eget libero aliquet pharetra. Nulla id neque et quam iaculis mollis sit amet eget arcu. Click here . CONTINUE Cancel Raised button Roboto Medium 16sp, #ffffff, 100% \triangleleft

NAVIGATION

LIST ITEMS

Use a list item to advance when the user isn't modifying content on screen. The majority of screens use list items.




SPECS

LIST ITEMS


Single list item, with icon



Two list item, with icon




Multiple line list item



Single list item, no icon



Two list item, no icon




SPECS

LIST ITEMS


Single list item, with icon



Two list item, with icon



Multiple line list item



Single list item, no icon



Two list item, no icon



NAVIGATION


BUTTONS

Use a right-aligned raised button to advance when:

- -The user is modifying content on screen
- -There is a positive/negative interaction (such as "Next" and "Skip")
- -There is one action item (such as "Next")

Use a raised button on screens with switches and text input fields.

Use a left-aligned text button and a rightaligned raised button for two-action screens.




INPUTS

INPUT FIELDS

When necessary, use input fields to allow the user to modify content on screen. Add a raised button to advance to the next page.


Enter your email or phone number aubreybrooks@gmail.com



INPUTS

SWITCHES


When necessary, use switches to allow the user to modify content on screen. Add a raised button to advance to the next page.




INPUTS

DO'S AND DON'TS

Use switches when giving users the option to opt in or out.



Don't




MODAL DIALOGS


TERTIARY ACTIONS

For subtasks, such as entering a Wi-Fi password or reading Terms of Service, display a modal dialog.


For new tasks, such as a creating a new account or entering credit card information, fork the flow.



DARK THEME



PROGRESS & INDICATION




TRANSITIONS

LEFT TO RIGHT SLIDE

Use the left-to-right slide transition when moving between screens that do not require loading.

The transition should be 300ms long and gradually slow down as the screens move into place.*




^{*} Consider using Decelerate Interpolator provided in the Android SDK to implement the transition curve.

TRANSITIONS

FADE IN / FADE OUT

Fade in and out of screens of screens that are loading interstitials or have an indeterminate loading indicator.





THANKS