JNI 字符串操作



1. NewString

```
1 | jstring NewString(const jchar* unicodeChars, jsize len)
2 | { return functions->NewString(this, unicodeChars, len); }
```

该方法会利用(Unicode) char 数组生成并返回 java String对象;

```
jstring stringFromJNI(JNIEnv *env, jobject thiz){
       __android_log_print(ANDROID_LOG_INFO, "native", "stringFromJNI");
2
3
       jchar* data = new jchar[5];
4
      data[0] = 'h';
5
       data[1] = 'e';
       data[2] = '1';
7
       data[3] = '1';
8
       data[4] = 'o';
       return env->NewString(data, 5);
10
11
```

2. GetStringLength

返回 java 字符串的长度(Unicode)

```
jstring stringFromJNI(JNIEnv *env, jobject thiz, jstring s){
    __android_log_print(ANDROID_LOG_INFO, "native", "stringFromJNI");

jint length = env->GetStringLength(s);
    __android_log_print(ANDROID_LOG_INFO, "native", "string length:%d", length);
    return s;
}
```

3. GetStringChars 与 ReleaseStringChars

```
const jchar* GetStringChars(jstring string, jboolean* isCopy)
{ return functions->GetStringChars(this, string, isCopy); }

void ReleaseStringChars(jstring string, const jchar* chars)
{ functions->ReleaseStringChars(this, string, chars); }
```

GetStringChars 方法用于返回一个对应 java String 对象的(Unicode) char 数组指针,返回的指针可能指向 java String 对象,也可能是指向 jni 中的拷贝,参数 isCopy 用于返回是否是拷贝;

ReleaseStringChars 方法用于释放与 java String 对象绑定的(Unicode) char 数组指针;

因为 GetStringChars 方法的返回值用 const 修饰,所以获取的(Unicode) char 数组是不能被更改的;

```
jstring stringFromJNI(JNIEnv *env, jobject thiz, jstring s){
        __android_log_print(ANDROID_LOG_INFO, "native", "stringFromJNI");
3
       jboolean isCopy = JNI_FALSE;
4
       jsize length = env->GetStringLength(s);
5
        const jchar* chars = env->GetStringChars(s, &isCopy);
6
7
        for(int i = 0; i < length; i++){
            __android_log_print(ANDROID_LOG_INFO, "native", "char %c", chars[i]);
8
9
10
        env->ReleaseStringChars(s, chars);
        return s:
11
12
```

4. NewString(Unicode)

```
1 | jstring NewStringUTF(const char* bytes)
2 | { return functions->NewStringUTF(this, bytes); }
```

该方法会利用(UTF-8) char 数组生成并返回 java String对象;

```
jstring stringFromJNI(JNIEnv *env, jobject thiz, jstring s){
   __android_log_print(ANDROID_LOG_INFO, "native", "stringFromJNI");

std::string hello = "Hello from C++";
   return env->NewStringUTF(hello.c_str());
}
```

5. GetStringUTFLength

返回 java String 的长度(UTF-8);

```
jstring stringFromJNI(JNIEnv *env, jobject thiz, jstring s){
    __android_log_print(ANDROID_LOG_INFO, "native", "stringFromJNI");
    jint length = env->GetStringUTFLength(s);
    __android_log_print(ANDROID_LOG_INFO, "native", "length: %d", length);
    return s;
}
```

6. GetStringUTFChars = ReleaseStringUTFChars

```
const char* GetStringUTFChars(jstring string, jboolean* isCopy)
{ return functions->GetStringUTFChars(this, string, isCopy); }

void ReleaseStringUTFChars(jstring string, const char* utf)
{ functions->ReleaseStringUTFChars(this, string, utf); }
```

GetStringChars 方法用于返回一个对应 java String 对象的(UTF-8) char 数组指针,返回的指针可能指向 java String 对象,也可能是指向 jni 中的拷贝,参数 isCopy 用于返回是否是拷

贝;

ReleaseStringChars 方法用于释放与 java String 对象绑定的(UTF-8) char 数组指针;

因为 GetStringChars 方法的返回值用 const 修饰,所以获取的(UTF-8) char 数组是不能被更改的;

```
jstring stringFromJNI(JNIEnv *env, jobject thiz, jstring s){
        __android_log_print(ANDROID_LOG_INFO, "native", "stringFromJNI");
3
        jboolean isCopy = JNI_FALSE;
4
       jsize length = env->GetStringUTFLength(s);
        const char* chars = env->GetStringUTFChars(s, &isCopy);
6
        for(int i = 0; i < length; i++){
7
8
            __android_log_print(ANDROID_LOG_INFO, "native", "char %c", chars[i]);
9
        env->ReleaseStringUTFChars(s, chars);
10
11
        return s;
12
```

7. GetStringRegion

```
void GetStringRegion(jstring str, jsize start, jsize len, jchar* buf)
functions->GetStringRegion(this, str, start, len, buf);}
```

拷贝 java String 指定范围的字符至 jni 本地(Unicode);

```
jstring stringFromJNI(JNIEnv *env, jobject thiz, jstring s){
   __android_log_print(ANDROID_LOG_INFO, "native", "stringFromJNI");

jchar* chars = new jchar[5];
env->GetStringRegion(s, 0, 5, chars);
return env->NewString(chars, 5);
}
```

8. GetStringUTFRegion

```
void GetStringUTFRegion(jstring str, jsize start, jsize len, char* buf)
treturn functions->GetStringUTFRegion(this, str, start, len, buf);}
```

拷贝 java String 指定范围的字符至 jni 本地(UTF-8);

```
jstring stringFromJNI(JNIEnv *env, jobject thiz, jstring s){
    __android_log_print(ANDROID_LOG_INFO, "native", "stringFromJNI");

char* chars = new char[5];
    env->GetStringUTFRegion(s, 0, 5, chars);
    return env->NewStringUTF(chars);
}
```

9. GetStringCritical 与 ReleaseStringCritical

```
5 | void ReleasePrimitiveArrayCritical(jarray array, void* carray, jint mode)
      { functions->ReleasePrimitiveArrayCritical(this, array, carray, mode); }
```

GetStringCritical、ReleaseStringCritical 与 GetStringChars、ReleaseStringChars方法非常相似;区别在于前者更倾向于获取 java String 的指针,而不是进行拷贝;

GetStringCritical 方法用于返回一个对应 java String 对象的(Unicode) char 数组指针,返回的指针可能指向 java String 对象,也可能是指向 jni 中的拷贝,参数 isCopy 用于返回是否是拷贝;

ReleaseStringCritical 方法用于释放与 java String 对象绑定的(Unicode) char 数组指针;

因为 ReleaseStringCritical 方法的返回值用 const 修饰,所以获取的(Unicode) char 数组是不能被更改的;

```
jstring stringFromJNI(JNIEnv *env, jobject thiz, jstring s){
        __android_log_print(ANDROID_LOG_INFO, "native", "stringFromJNI");
3
       jboolean isCopy = JNI_FALSE;
        jsize length = env->GetStringLength(s);
5
       const jchar* chars = env->GetStringCritical(s, &isCopy);
6
        __android_log_print(ANDROID_LOG_INFO, "native", "isCopy %d", isCopy);
7
        for(int i = 0; i < length; i++){
8
            __android_log_print(ANDROID_LOG_INFO, "native", "char %c", chars[i]);
9
10
11
        env->ReleaseStringCritical(s, chars);
        return s;
12
13
```