## ECH 145B Lab 2 Memo

To: ECH 145B

From: Lucas Culverhouse

Date: May 10, 2023

**Subject:** Heat Transfer Through an Aluminum Cylinder

CC: TAs

Attachments: 3

## **Executive Summary**

Using a 6061-T6 aluminum cylinder, several flow conditions were tested to derive heat transfer coefficients. It was found that in general forced convection produced higher heat transfer coefficients that natural convection, meaning faster cooling. The heat transfer coefficients for the most accurate method used were: [number], [number], and [number] for forced convection on high fan speed, forced convection on low fan speed, and natural convection respectivly. Each of the methods used demonstrate different accuarcy when attempting to find the h-value from the data. The most accurate method used was a numerical approach with forward time and centered space; this had a maximum error on the h-value of [number]. The analytical approach also proved to be quite accurate with a maximum h-value error of [number]. This can be attributed to the low Biot number of all the flow conditions, with none having a Biot number larger than 0.005.

### Theory and Analysis

The geometry of our flow situation drastically simplifies the theoretical approach we must use to understand our system and solve for the h-values. We assume the following conditions are true of our system:

- 1. Cylindrical geometry  $\Rightarrow$  use radial coordinates, radial symmetry.
- 2. Insulated top and bottom of cylinder  $\Rightarrow$  1-D in r coordinate.
- 3. The ambient temperature outside the cylinder is a constant.
- 4. At time t = 0s the temperatue profile inside the cylinder is uniform at the inital temperature

These assumptions all give us the following governing equation for the temperature in the cylinder:

$$\rho C_p \frac{\partial T}{\partial t} = k \left[ \frac{1}{r} \frac{\partial}{\partial r} \left( r \frac{\partial T}{\partial r} \right) \right] \tag{1}$$

Where  $\rho$ ,  $C_p$ , and k are the density, heat capacity and thermal conductivity of the cylinder respectively. We also know that the total heat transfer at the surface of the cylinder must be zero; that is, any heat that moves to the surface through conduction must be removed thorugh convection at the surface, there will not be any accumulation. This can stated as:

$$q_{\text{conduction}} = q_{\text{convection}}$$
 (2)

If we use Newton's law of cooling the represent  $q_{
m convection}$  and (1) to represent  $q_{
m conduction}$  then we can write:

$$mC_{p}\frac{\partial T}{\partial t}\big|_{r=R} = -hA_{s}(T - T_{\infty}) \tag{3}$$

Equations (1) and (3) form our governing equations for each of the flow situations, where we want to find the heat transfer coefficient h for each flow condition.

There are three approaches that will be used to determine the h-value for each flow situation: analytical, emperical, and numerical.

The analytical approach assumes that the temperature we measure at the center-line of our cylinder is the same thorughout the cylinder, so we can simply integrate (3) to find:

$$\frac{T - T_{\infty}}{T_i - T_{\infty}} = \exp\left(-\frac{t}{\tau}\right) \tag{4}$$

Where  $\tau$  is the dimensionless time constant  $\tau = \frac{mC_p}{hA_s}$ . This will be used to find the h-value from the temperature data by fitting against the  $\tau$  parameter to find h. We can asses the quality of this assumption using the Biot number which compares conductive heat transfer to convective heat transfer, and is found using the following equation:

$$Bi = \frac{hk}{D} \tag{5}$$

Where D is the diameter of our cylinder, which is the characteristic length for this geometry.

The emperical approach simply uses known emperical statements of the Nusselt number to find the h-value, where we relate the Nusselt number and the h-value using the following

$$Nu = \frac{hD}{k} = CRe^{m}Pr^{\frac{1}{3}}$$
 (6)

Where Pr is the Prandtl number, Re is the Reynold's number with C and m being known parameters that vary with the value of the Reynold's number.

Finally we have the numerical approach, where we use a forward time and centered space equation to get both the time dependance of the temperature, but also the radial temperature profile in the cylinder. We will use the following equations to evaluate the temperature:

$$\frac{\partial T}{\partial t} = \frac{1}{\Delta t} \left( T^{t_{\text{new}}} - T^t \right) \tag{7}$$

$$\frac{\partial^2 T}{\partial r^2} = \frac{1}{\Delta r^2} \big(T_{r+1} - 2T_r + T_{r-1}\big) \tag{8} \label{eq:delta_total_total}$$

$$\frac{\partial T}{\partial r} = \frac{1}{2\Delta r} (T_{r+1} - T_{r-1}) \tag{9}$$

Where  $\Delta r$  and  $\Delta t$  are carefully chosen values for the spacing between radial and time values such that they meet the stability condition  $s=\alpha\frac{\Delta t}{\Delta r^2}<0.5$ , where  $\alpha$  is the thermal diffusivity of the cylinder. These parameters will be optimized using a brute force search to get the highest resolution numerical solution possible, while still maintaining stability.

Total heat transfer from the cylinder can be obtained using:

$$Q = mC_p \Delta T \tag{10}$$

#### **Results and Discussion**

Below are the graphs of each of the flow conditions along with the analytical and numerical solutions for each. These show, visually, the correlation between each solution method and the collected data




Figure 1: Temperature vs time for each of the flow conditions. The 'High' fan speed was 1.1 m/s, the 'Low' fan speed was 0.6 m/s. Each cylinder was insulated on the top and bottom with a piece of thick styrofoam. The temperature readings were taken at the center-line of each cylinder using a thermocouple

We can see from these graphs that the high fan setting forced convection cooled the fastest of all three, with the natural convection being much slower than the other two, taking about 1.5-2.5 times as long to get close to the ambient temperature. This is consistent with what we would intuitively expect and what we expect from heat transfer. Higher free stream velocites give thinner boundary layers, meaning higher heat transfer.

h-values were calculated for each of the flow conditions and each of the methods they are shown here, h has units of  $\frac{W}{m^2K}$ . Also shown are the biot numbers and total heat transfer from each cylinder:

	Forced High	Forced Low	Natural
Analytical	$29.71 \pm 0.61$	$23.60 \pm 0.73$	$10.97 \pm 0.82$
Emperical	$21.47 \pm 0.2$	$16.18 \pm 0.2$	-
Numerical	$29.74 \pm 0.15$	$23.58 \pm 0.17$	$11.01 \pm 0.12$
Biot Number	0.0044	0.0035	0.0016
Total Heat Transfer [J]	2821	3259	3176

We can see that the emperical solution does a poor job of prediciting the heat transfer coefficients while the analytical and numerical solutions are in close agreement. The error for the analytical and numerical solutions is found using the covariance of the fitting models used for each, while the emperical error is from the error of the velocity measurment taken, where all other values are assumed

to be exact. This close agreement can be explained by examining the Biot number for each, here we only use the h values found by the analytical solution to calculate it:

This shows that the effect of convection is 2-3 orders of magnitude larger than the effect of conduction. This allows us to use the lumped capacitance approximation for the analytical solution, without loss of much precision.

We can see from Fig. 1 that using a single h-value for the entire process of heat transfer produces fairly accurate results, however it does seem to become less accurate as the temperature approaches the ambient temperature.


For natural convection, using out analytical model, it would take  $2.79 \cdot 10^5$  s to reach 0.1 °C of the ambient temperature.

#### **Conclusions and Recommendations**

From the analysis we can see that the more velocity that fluid can be convected past an object with, the faster it will be cooled. This means that for any experiment where rapid cooling is desired, high fan speeds or pump speeds should be preferred. For future experiments, it would be beneficial to have a larger cylinder or other object with a different geometry in order to give a greater weight to the conductive effects. This would raise the Biot number.

Also, this larger geometry could be used to insert several thermocouples along the cylinder to find if the numerical predications of the temperature profile matched that of the real-world measured data. It would also be intresting to see the effects of a more viscous fluid, like water, and how a natural convection using it would be different. Using a rectangular geometry would also be beneficial to study as it would provide a different set of governing equations to use.

# Appendix



```
In [260... import numpy as np
         import matplotlib.pyplot as plt
         import scipy.optimize as opt
         import pandas as pd
          # Load in the data and get only the section from when after the thermocouple
          # was inserted into the cylinder, and define some useful constants.
         forced high data = np.loadtxt(
             "./Data/Lab2/forced high.csv", delimiter=",", skiprows=7, usecols=[1, 2, 3]
         max idx = forced high data[:, 1].argmax()
         forced high data[:, 0] -= forced high data[max idx, 0]
         forced high data = forced high data[max idx:, :]
         Ti high = forced high data[0, 1]
         Tinf high = forced high data[:, 2].mean()
         time high = forced high data[:, 0].max()
         forced low data = np.loadtxt(
             "./Data/Lab2/forced low.csv", delimiter=",", skiprows=7, usecols=[1, 2, 3]
         max idx = forced low data[:, 1].argmax()
         forced low data[:, 0] -= forced low data[max idx, 0]
         forced low data = forced low data[max idx:, :]
         Ti low = forced low data[0, 1]
         Tinf low = forced low data[:, 2].mean()
         time low = forced low data[:, 0].max()
         natural data = np.loadtxt(
             "./Data/Lab2/natural.csv", delimiter=",", skiprows=7, usecols=[1, 2, 3]
         max idx = natural data[:, 1].argmax()
         natural data[:, 0] -= natural data[max idx, 0]
         natural data = natural data[max idx:, :]
         Ti natural = natural data[0, 1]
         Tinf natural = natural data[:, 2].mean()
         time natural = natural data[:, 0].max()
In [274... # Analytical Solution
         def analyticalT dless(t, tau):
             return np.exp(-t / tau)
         def h analytical(tau, m, cp, surfA):
             return (m * cp) / (tau * surfA)
          # Aluminum 6061-T6 material properties from https://asm.matweb.com/search/SpecificMateri
         density = 2700 \# kg m^{-3}
         cp = 896 \# J kg^{-1} K^{-1}
         k = 167 \# W m^{-1} K^{-2}
         alpha = k / (density * cp)
          # Cylinder properties from Lab 2 Handout
         cylinder height = 0.075 # m
```

cylinder diameter = 0.025 # m

cylinder radius = cylinder diameter / 2

cylinder mass = cylinder volume \* density # kg

surface\_area = np.pi \* cylinder\_diameter \* cylinder\_height # m^2
cylinder\_volume = np.pi / 4 \* cylinder\_diameter\*\*2 \* cylinder\_height

dlessT high = (forced high data[:, 1] - forced high data[:, 2].mean()) / (

# Get the dimensionless temperatures for each type of flow

```
forced high data[0, 1] - forced high data[:, 2].mean()
         dlessT low = (forced low data[:, 1] - forced low data[:, 2].mean()) / (
              forced low data[0, 1] - forced low data[:, 2].mean()
          dlessT natural = (natural data[:, 1] - natural data[:, 2].mean()) / (
             natural data[0, 1] - natural data[:, 2].mean()
          # Optimize to find the tau value, then compute the h value
          tau high, pcov = opt.curve fit(
             analyticalT dless, forced high data[:, 0], dlessT high, p0=100
          tau high = tau high[0]
         perr = np.sqrt(np.diag(pcov))
         print(perr)
         h high = h analytical(tau high, cylinder mass, cp, surface area)
         print(h high)
          tau low, pcov = opt.curve fit(analyticalT dless, forced low data[:, 0], dlessT low, p0=1
         tau low = tau low[0]
         perr = np.sqrt(np.diag(pcov))
         print(perr)
         h low = h analytical(tau low, cylinder mass, cp, surface area)
         print(h low)
          tau natural, pcov = opt.curve fit(
              analyticalT dless, natural data[:, 0], dlessT natural, p0=100
          tau natural = tau natural[0]
         perr = np.sqrt(np.diag(pcov))
         print(perr)
         h natural = h analytical(tau natural, cylinder mass, cp, surface area)
         print(h natural)
         print()
         biot high = h high * cylinder diameter / k
         biot low = h low * cylinder diameter / k
         biot natural = h natural * cylinder diameter / k
         print("Biot Numbers:")
         print(biot high)
         print(biot low)
         print(biot natural)
         [0.61304113]
         29.711029137661274
         [0.73234186]
         23.601393292741434
         [0.81999177]
         10.96909190524705
         Biot Numbers:
         0.004447758852943305
         0.0035331427084942272
         0.0016420796265339895
In [262... | # Emperical Solution
          k = 2.623e-2 \# W m^{-1} K^{-1}
         density air = 1.225 \# kg m^{-3}
         visc air = 1.789e-5 # Pa s
         def h emperical(vel):
              reynolds = vel * density air * cylinder diameter / visc air
```

nusselt = 0.683 \* (reynolds\*\*0.466) \* (0.71 \*\* (1 / 3))

```
return nusselt * k air / cylinder diameter
         vel high = 1.1 # m s^{-1}
         print(h emperical(vel high))
         vel low = 0.6 # m s^{-1}
         print(h emperical(vel low))
         21.467549310046675
         16.184972302351355
In [263... # Numerical Solution
         # The following are from the optimization further down
         # High params:
         # (0.002, 0.008, 0.002, 0.15434053438507775)
         # ----
         # Low params:
         # (0.003, 0.014, 0.003, 0.17355170861815905)
         # Natural params:
         # (0.003, 0.014, 0.003, 0.11535986458049904)
         flow condition data = {
              "high": (Ti high, Tinf high, time_high, h_high, 0.002, 0.008),
             "low": (Ti low, Tinf low, time low, h low, 0.003, 0.014),
             "natural": (Ti natural, Tinf natural, time natural, h natural, 0.003, 0.014),
         }
         def numerical solution(Ti, Tinf, time, h, dr, dt):
             x steps = np.arange(0, cylinder radius, dr)
             t steps = np.arange(0, time, dt)
             n x = len(x steps)
             n t = len(t steps)
             s = alpha * dt / dr**2
             if s > 0.5:
                 print(f"S is too large {s}")
```

T[m, i] = a i \* T[m - 1, i - 1] + b i \* T[m - 1, i] + c i \* T[m - 1, i + 1]

 $H = -h * surface_area * dt / (cylinder_mass * cp)$  T[m, -1] = H \* (T[m - 1, -1] - Tinf) + T[m - 1, -1]

x steps high, t steps high, sol high = numerical solution(\*flow condition data["high"])

return

T[0] = Ti

T = np.zeros((n t, n x))

for m in range(1, n t):

for i in range(1,  $n_x - 1$ ): a i = s - s / (2 \* i)

ci = s + s / (2 \* i)

bi = 1 - 2 \* s

T[m, 0] = T[m, 1]


return x steps, t steps, T


```
x_steps_low, t_steps_low, sol_low = numerical_solution(*flow_condition_data["low"])
x_steps_natural, t_steps_natural, sol_natural = numerical_solution(*flow_condition_data[
```

```
def analyticalT(t, tau, Ti, Tinf):
             return (Ti - Tinf) * np.exp(-t / tau) + Tinf
         fig dpi = 100
         plt.figure(dpi=fig dpi)
         plt.plot(
             forced high data[:, 0],
             forced high data[:, 1],
             "bo",
             label="Experimental",
             markersize=2,
         plt.plot(
             forced high data[:, 0],
             analyticalT(forced high data[:, 0], tau high, Ti high, Tinf high),
             label="Analytical",
         plt.plot(t steps high, sol high[:, 0], "y-", label="Numerical")
         plt.ylabel("Temperature [$^\circ C$]")
         plt.xlabel("Time [s]")
         plt.title("Forced Convection (High)")
         plt.legend()
         plt.tight layout()
         plt.show()
         plt.figure(dpi=fig dpi)
         plt.plot(
             forced low data[:, 0],
             forced low data[:, 1],
             "bo",
             label="Experimental",
             markersize=2,
         plt.plot(
             forced low data[:, 0],
             analyticalT(forced low data[:, 0], tau low, Ti low, Tinf low),
             "r-",
             label="Analytical",
         plt.plot(t steps low, sol low[:, 0], "y-", label="Numerical")
         plt.ylabel("Temperature [$^\circ C$]")
         plt.xlabel("Time [s]")
         plt.title("Forced Convection (Low)")
         plt.legend()
         plt.tight layout()
         plt.show()
         plt.figure(dpi=fig dpi)
         plt.plot(
             natural data[:, 0],
             natural data[:, 1],
             "bo",
             label="Experimental",
             markersize=2,
         plt.plot(
             natural data[:, 0],
             analyticalT(natural data[:, 0], tau natural, Ti natural, Tinf natural),
```


```
label="Analytical",
plt.plot(t steps natural, sol natural[:, 0], "y-", label="Numerical")
plt.title("Natural Convection")
plt.ylabel("Temperature [$^\circ C$]")
plt.xlabel("Time [s]")
plt.legend()
plt.tight layout()
plt.show()
plt.figure(dpi=fig dpi)
plt.plot(forced high data[:, 0],dlessT high, "ro", label="Forced Convection (High)", mar
plt.plot(forced_low_data[:, 0],dlessT_low, "bo", label="Forced Convection (Low)", marker
plt.plot(natural data[:, 0], dlessT natural, "go", label="Natural Convection", markersiz
plt.title("Dimensionless Temperature For Each Flow Condition")
plt.xlabel("Time [s]")
plt.ylabel("Temperature")
plt.legend()
plt.show()
```

## Forced Convection (High)





## Dimensionless Temperature For Each Flow Condition



```
# This is run once for each flow condition and then the values are saved to variables
# higher up because this is very slow
def optimize steps(Tdata, Ti, Tinf, time, h):
    dr = np.arange(0, 0.015, 0.001)
    dt = np.arange(0, 0.015, 0.001)
    total time = time.max()
    def find rmse(exp time, t steps, Tdata, Tnum):
        residual = []
        for i in range(len(exp time)):
            time = exp time[i]
            idx = np.where(t steps == t)[0]
            error = (Tdata[i] - Tnum[idx])**2
            residual.append(error)
        rmse = np.sqrt(np.mean(residual))
        return rmse
    stability matrix = np.zeros(((len(dr)-1)*(len(dt)-1),3))
    for r in range(1, len(dr)):
        r idx = (r-1)*len(dr[1:])
        for t in range(1, len(dt)):
            idx = r idx + t -1
            stability matrix[idx, 0] = dr[r]
            stability_matrix[idx, 1] = dt[t]
            s = alpha * dt[t] / dr[r]**2
            stability matrix[idx, 2] = dr[r]
    all rmse = []
    for dr val in dr[1:]:
        for dt val in dt[1:]:
            x steps = np.arange(0, cylinder radius + dr val, dr val)
            t steps = np.arange(0, total_time + dt_val, dt_val)
            n x = len(x steps)
```

```
n t = len(t steps)
                    T = np.zeros((n t, n x))
                    T[0] = Ti
                    for m in range(1, n t):
                         for i in range (1, n \times -1):
                             a i = s - s / (2 * i)
                             bi = 1 - 2 * s
                             ci = s + s / (2 * i)
                             T[m, i] = a i * T[m - 1, i - 1] + b i * T[m - 1, i] + c i * T[m - 1,
                             T[m, 0] = T[m, 1]
                             H = -h * surface area * dt val / (cylinder mass * cp)
                             T[m, -1] = H * (T[m - 1, -1] - Tinf) + T[m - 1, -1]
                    rmse temp = find rmse(time, t steps, Tdata, T[:, 0])
                    all rmse.append(rmse temp)
                    df sr = pd.DataFrame(stability matrix, columns=["dr","dt","s"])
            def convertOtoFloat(df, column name):
                if str(df[column name].dtype) == 'object':
                         df[column name] = df[column name].as type(float)
                     except ValueError:
                         for j in range(len(df[column name])):
                             if len(df[column name]) == 0:
                                 df[column name][j] = np.nan
                             else:
                                 df[column name][j] = df[column name][j][0]
                return df
            df sr["RMSE"] = all rmse
            df sr = convertOtoFloat(df sr, "RMSE")
            df sr["RMSE"] = df sr["RMSE"].astype(float)
            \#df \ sr["RMSE"] = df \ sr['RMSE'].apply(lambda \ x: x.item() if len(x) == 1 else np.nan)
            df sr5 = df sr[df sr["s"]<0.5]
            min idx = df sr["RMSE"].idxmin()
            dr opt, dt opt, s opt, rmse opt = df sr.loc[min idx, :]
            return dr opt, dt opt, s opt, rmse opt
        print("High params:\n", optimize steps(forced high data[:, 1], Ti high, Tinf high, force
        print("----")
        print("Low params:\n", optimize steps(forced low data[:, 1], Ti low, Tinf low, forced lo
        print("----")
        print("Natural params:\n", optimize steps(natural data[:, 1], Ti natural, Tinf natural,
        print("----")
In [ ]: # These are the output values for the optimization, the output is otherwise
        # cluttered by warnings about the numerical instability of some solutions
        # which are filtered out in the last step.
        11 11 11
        High params:
         (0.002, 0.008, 0.002, 0.15434053438507775)
        Low params:
         (0.003, 0.014, 0.003, 0.17355170861815905)
        Natural params:
         (0.003, 0.014, 0.003, 0.11535986458049904)
```

```
----
-----
```

```
print(cylinder mass * cp * (forced high data[:, 1].max() - forced high data[:, 1].min()
In [290...
         print(cylinder mass * cp * (forced_low_data[:, 1].max() - forced_low_data[:, 1].min() ))
         print(cylinder mass * cp * (natural data[:, 1].max() - natural data[:, 1].min() ))
         time = np.linspace(0, 279 217, 1000)
         T = analyticalT(time, tau natural, Ti natural, Tinf natural)
         def T solve(time, a, b, c):
             return analyticalT(time, a, b, c) - 0.1 + Tinf natural
         plt.plot(time, T)
         plt.plot(time, time * 0 + 0.1 + Tinf natural)
         print(opt.fsolve(T solve,x0=7000, args=(tau_natural, Ti_natural, Tinf_natural)))
         print(T[-1])
         print(0.1 + Tinf natural)
         2820.6616852660013
         3259.480760836117
         3175.938586514062
         [279217.07357986]
         24.124923880597013
         24.224923880597014
```

/Users/lucas/anaconda3/envs/py10/lib/python3.10/site-packages/scipy/optimize/\_minpack\_p y.py:175: RuntimeWarning: The iteration is not making good progress, as measured by the improvement from the last ten iterations. warnings.warn(msg, RuntimeWarning)

